Tayyn Hyzmat

START HERE

Dispatcher dashboard and driver app

A practical guide for creating orders, managing a shift and following each trip.

Use this guide during the pilot. The diagrams explain the operating rules. They are not screenshots of the app.

Dispatcher
Creates the order and chooses its audience.

→

Driver
Confirms the offer and carries out the trip.

→

Shared state
Keeps assignments, balances and messages in sync.

Find the right instructions

Create and send an order

Use the map and manage drivers

Start a driver shift

Accept and complete a trip

Chat, reconnect and recover

Read daily figures and prepare a pilot

Cancel or complete a trip

> All prices are in TMT. The current pilot uses synthetic balances. Do not treat a displayed balance as a real payment.

Create an order

1. Sign in on the dispatcher page with your assigned phone number and password. The +993 prefix stays fixed. Enter the eight local digits.
2. Open **Заказы** and choose **Создать заказ**.
3. Choose the region, enter the customer phone number and a positive price in TMT. These fields are required.
4. Add an optional pickup, destination or note. On wide screens, use the large map beside the form. On smaller screens it sits below. Choose Откуда or Куда before placing a point; Убрать clears it.
5. Choose a public announcement or a private driver, then send the order. For a private offer, a selected driver is required.

Public announcement

First 20 seconds
Only drivers in the order’s saved region can claim.

→

Then all regions
If nobody claims, all eligible drivers can claim themselves.

→

First claim wins
The order disappears for everyone else.

Private offer

Select a driver
Online, free, fresh GPS, enough balance.

→

20-second offer
The selected driver must confirm.

→

Expiry choice
Open to all regions, or stop unassigned.

> Choose whether to offer the order to other drivers after the private deadline. When ON, all regions open at once. There is no second 20-second timer. When OFF, the order remains unassigned for the dispatcher to handle.

An early private decline returns the order to its original region until the original deadline. The expiry choice then applies. The customer phone is hidden until acceptance.

DISPATCHER · MONITORING

Find a driver and follow the trip

1. Open the monitoring map. Search the roster by name, phone or vehicle plate. Filter by region or status. On mobile, open the driver list as a bottom sheet.
2. Select a driver from a map marker or roster row. Check the location age, online state and whether the driver is free.
3. Use **Предложить заказ** for an eligible driver. Choose an existing waiting order or create a new private order.
4. Follow the assigned order through pickup, waiting and the trip. A last known point is not a live position.

What you see	What it means
Free	Online with fresh location and no active trip. Assignment still checks eligibility on the server.
In trip	The driver has an accepted, waiting or started trip and cannot receive a second assignment.
Check GPS	Coordinates are missing or stale. Ask the driver to check location and connectivity.
Offline	The driver is not available for new work. The map may still show a timestamped last location.

Drivers and balances

Create drivers in the driver list. Use a valid +993 phone number. A six-digit numeric password is allowed. When changing a phone or resetting a password, give the new credentials to the driver privately. Previous access is revoked and the driver signs in again.

Top up the pilot balance before assigning work. A driver needs the full order price to accept. For example, 15 TMT cannot cover a 30 TMT order. The app prevents a negative balance. If an adjustment response is uncertain, retry the same unchanged action. Refresh an old dashboard tab when asked; do not start a new adjustment until you check the balance history.

DRIVER · SHIFT

Get ready and go online

1. Open the driver app and sign in with your assigned phone number and password.
2. Allow precise location and notifications when asked. Android system location must also be switched on.
3. Check the location and connection indicator. If it is still checking, wait for a fresh position and dispatcher connection. If there is a warning, read its message.
4. Press the Online switch. The app confirms the shift with the dispatcher before showing that you are live.
5. Leave the app running during your shift. When finished, press Offline.

Location ready
Permission, system GPS and a fresh position.

→

Connection ready
The app can reach the dispatcher.

→

Online confirmed
The dispatcher can offer new work.

Situation	What to do
Location disabled	Enable location permission and Android system location, then return to the app.
No internet	Restore Wi-Fi or mobile data. GPS alone cannot send updates or accept work.
Outside every region	Your real location stays visible as outside region. You may claim orders once they are opened to all regions.
Address missing	Use the region and coordinates. An address lookup failure never blocks a shift.

> Offline can retain a last known position. During an active shift, the app sends fresh positions. Without internet, you cannot receive updates or confirm a claim. Server availability expires within 60 seconds. An accepted trip stays assigned.

On the target Android phone, background delivery must still be checked with the screen locked and battery restrictions enabled. A closed browser does not provide reliable background alerts.

From acceptance to completion

Accept
Choose arrival time and confirm. Price is charged once.

→

At pickup
Press Я на месте and wait for the customer.

→

Customer boarded
Press Начать поездку.

→

Trip finished
Press Завершить поездку.

1. The home grid shows every saved region. Each card counts cars and unfinished orders, including claimed trips. Open a region for orders still available to claim.
2. A new regional or private offer can appear automatically. A private offer has a fixed 20-second deadline. Decline it if you cannot take it.
3. Check the price and arrival time. Accept only when you can carry out the trip. A customer phone appears after acceptance; use it to confirm pickup.
4. Use the price, call and next-trip controls above the region grid. Open the trip details for extra information or permitted cancellation.
5. Complete the trip once it is finished. Completion does not charge the price again.

> If another driver claims first, the order disappears. If you try at the same moment, the app reports that it is already taken. Only one driver can own the order.

Balance and cancellation

You need enough balance for the full price. With 30 TMT, you can accept a 30 TMT order. With 15 TMT, a 30 TMT order can be visible but cannot be accepted.

You can cancel only while waiting for the customer, after Я на месте. You cannot cancel immediately after acceptance or once the trip starts. A permitted cancellation refunds the original charge once. Do not repeatedly accept and cancel to test a live customer order.

> If you lose internet, keep the accepted trip in mind and reconnect. Do not create another account or accept a second trip. If the trip cannot be completed in the app, contact the dispatcher.

BOTH ROLES · COMMUNICATION

Chat and recovery

1. Open the conversation with the dispatcher or selected driver. Type a message and press Send. Enter sends; Shift+Enter adds a line.
2. Read older messages inside the chat area. The app keeps your reading position when you scroll upward.
3. If a send fails, the draft stays available. Retry it. The same retry does not create a duplicate message.
4. After returning, let the app recover missed messages and the current order. If session verification fails, restore internet and press Повторить подключение; sign-in details stay saved.

Connection lost
The last displayed information may be old.

→

Reconnect
The app checks current server state.

→

Work continues
The accepted trip and balance remain consistent.

Question	Answer
The order vanished before I accepted	Another driver may have accepted it, or the dispatcher may have cancelled or changed the offer.
GPS works but I am not online	Location and shift availability are separate. Check internet, balance and the Online confirmation.
The address is missing or old	Street names are optional. The app hides stale names and keeps coordinates. Region matching uses saved boundaries.
I closed the app	An accepted trip stays assigned. Availability and background alerts depend on the Android shift service and connection. Reopen and check the current state.
I forgot to complete a trip	Complete it after reconnecting. If the controls fail, ask the dispatcher to resolve it with a recorded reason.

> Use chat while safely stopped. Phone lock-screen notifications hide the customer phone and message body.

DISPATCHER · DAILY VIEW

Read the pilot results

The Today panel follows Asia/Ashgabat time. It groups orders by the date they were created. Live waiting orders are counted separately, including orders left from yesterday.

Measure	How to read it
Waiting orders and oldest wait	The work still available now. Active private reservations are separate. Stopped private orders are not public waiting work.
Median / p90 acceptance time	Typical waiting time and the time within which 90% of measured orders were accepted. Check the sample count.
Completed / cancelled	Outcomes for orders created today. Unfinished orders are shown separately. Rates use completed plus cancelled orders.

Before the phone pilot

1. Use the freshly built APK and the matching deployed service. An older installed APK may show older screens.
2. Test one public order, one private acceptance, one expiry and two drivers claiming the same order. Confirm only one wins.
3. Check the price charge, permitted cancellation refund and normal trip completion.
4. Test GPS permission changes, screen lock, background delivery, Wi-Fi/mobile switching and a connection loss.
5. Keep the phone model, Android version and observed result with the test record.

> This is a pilot guide. Production signing, update distribution and physical Infinix Android 14 background reliability still need release verification.

Release notes for this edition

Current merged changes include the regional-first order audience, fixed private deadline and expiry choice, GPS readiness checks, trip resolution, safer balance handling and chat recovery. The compact driver feed, busy-driver monitoring guards and Today analytics are merged. Balance safeguards, safe adjustment retries and the restriction on cancelling started trips are merged. Session and device protections are merged and covered by the release checks.

Cancel or complete?

Cancellation means no drive took place. Completion means the drive was provided.

Accepted
The driver is on the way. The quoted price was charged.

→

Waiting
The driver arrived and is waiting for the customer.

→

Started
The customer boarded. Ordinary cancellation ends.

→

Completed
The drive was provided. No extra debit or refund.

Stage	Driver	Dispatcher
Unassigned	Accept an eligible offer	Cancel before acceptance. There is no charge to refund.
Accepted	Call the customer and go to pickup. No cancellation.	Cancel if the drive will not happen. Refund the recorded charge once.
Waiting	Start after boarding, or cancel if the drive will not happen.	Cancel before the trip starts. Refund the recorded charge once.
Started	Complete when the drive finishes. Cancellation is blocked.	If the completed drive is stuck, complete manually with a required reason. No refund or second debit.
Completed or cancelled	Review the result	Review the history. Do not repeat a terminal action.

When a trip needs completion

1. A started trip older than 15 minutes receives a warning. This is a reminder, not automatic completion.
2. Call the driver. Confirm whether the customer is still in the car or the drive is finished.
3. If the drive is finished and the driver cannot close it, choose Завершить вручную. Enter the actual reason.
4. Confirm the completed status. The record keeps the same driver, original charge, dispatcher identity and reason.

> Started trips cannot be cancelled. Exceptional refunds require a separate reviewed recovery process.