

17 NVMe

7.8.3 StorageVolumes

Property	Data type	Access	Description
DriveLetter	String	R	Current volume letter
Label	String	R	Volume label
FileSystem	String	R	NTFS, ReFS, FAT32 or CSVFS
FileSystemType	Int	R	File system type (see coding below)
ByteSize	ULong	R	Total size in bytes
ByteSizeRemaining	ULong	R	Free space in bytes
IsSystemVolume	Bool	R	Contains operating system
BitLockerVolumeData	BitLockerVolumeData	R	BitLocker data
VolumeID	String	R	Volume ID
PartitionType	String	R	Type of the partition

[FileSystemType]

- 0 Unknown
- 1 FAT
- 2 FAT32
- 3 NTFS
- 4 EXFAT
- 5 CSVFS
- 6 ReFS

7.8.4 BitLockerVolumeData

Property	Data type	Access	Description
ConversionStatus	Int	R	Conversion status (see coding below)
EncryptionPercentage	Int	R	Encryption progress in percent
SuspendCount	Int	R	Suspend BitLocker for <i>n</i> reboots
BitLockerVersion	Int	R	0 : Unknown 1 : Vista 2 : Win7+
ProtectionStatus	Int	R	0 : Unprotected 1 : Protected 2 : Unknown
LockStatus	Int	R	0 : Unknown 1 : Unlocked 2 : Locked

[ConversionStatus]

- 0 Fully decrypted
- 1 Fully encrypted
- 2 Encryption in progress
- 3 Decryption in progress
- 4 Encryption paused
- 5 Decryption paused
- 6 Unknown

7.8.5 Software

Property	Data type	Access	Description
Id	String	R	Unique ID of a software
Name	String	R	Name of a software
Version	String	R	Version of a software
Package	String	R	Identifier of a software
Manufacturer	String	R	Name of the manufacturer

7.8.6 SNMPDeviceData

Property	Data type	Access	Description
SNMPName	String	R	Name of a device
Description	String	R	Description of a device
VendorId	Int	R	SNMP ID of a vendor
UpTime	String	R	The time since a device has been running. Format: days.hours:minutes:sec.millisec
PrimaryMAC	String	R	Primary MAC address of a device
LastContact	DateTime	R	Date and time of last successful communication with a device
Comment	String	R	Freely editable text field
PrimaryIP	String	R	Primary IP address of a device
DetectionRules	List of < DetectionRule >	R	Detection Rules that apply for a device

7.8.6.1 DetectionRule

Property	Data type	Access	Description
TypeId	String	R	Id of a rule
Name	String	R	Name of a rule

7.8.7 IndustrialData

Property	Data type	Access	Description
GatewayType	String	R/C	Gateway type
Url	String	R/C/U	Web interface URL
Port	int	R/C/U	Communication port
SnmpConfiguration	SnmpConfiguration	R/C/U	SNMP configuration
LastInventory	DateTime	R	Last inventory date
ModelType	String	R	Model type
IndustrialCPU	String	R	CPU description
FirmwareVersion	String	R	Firmware version
HardwareVersion	String	R	Hardware version
OrderNumber	String	R	Order number
UpTime	Long	R	Uptime
Contact	String	R	Contact person
Location	String	R	Location

[GatewayType]
SiemensSimaticS7

7.8.8 MicrosoftDefenderData

Property	Data type	Access	Description
AntimalwareEngineVersion	String	R	Engine version
AntimalwareProductVersion	String	R	Product version
AntimalwareRunningMode	String	R	Running mode
AntimalwareServiceActive	Bool	R	Antimalware status
AntimalwareServiceVersion	String	R	Service version
AntispywareActive	Bool	R	Antispyware status
AntispywareDefinitionCreation	DateTime	R	Antispyware definition creation
AntispywareDefinitionVersion	String	R	Antispyware definition version
AntivirusActive	Bool	R	Antivirus status
AntivirusDefinitionCreation	DateTime	R	Antivirus definition creation
AntivirusDefinitionVersion	String	R	Antivirus definition version
BehaviorMonitoringActive	Bool	R	Behavior monitoring status
LastFullScanEndTime	DateTime	R	Last full scan
IoavProtectionActive	Bool	R	IOAV protection status
TamperProtectionActive	Bool	R	Tamper protection status
NetworkInspectionSystemActive	Bool	R	Network inspection system status
NetworkInspectionSystemEngineVersion	String	R	Network inspection system engine version
NetworkInspectionSystemDefinitionCreation	DateTime	R	Network inspection system definition creation
NetworkInspectionSystemDefinitionVersion	String	R	Network inspection system definition version
OnAccessProtectionActive	Bool	R	On-access protection status
LastQuickScanEndTime	DateTime	R	Last quick scan
RealTimeProtectionActive	Bool	R	Real-time protection status
RealTimeScanDirection	String	R	Real-time scan direction
HighestSeverity	String	R	Severity of highest active threat
ActiveThreats	Int	R	Number of active threats
ResolvedThreats	Int	R	Number of resolved threats

[HighestSeverity]

None,
Low,
Moderate,
High,
Severe

[RealTimeScanDirection]

ScanIncomingAndOutgoingFiles,
ScanIncomingFilesOnly,
ScanOutgoingFilesOnly

7.8.9 SnmpConfiguration

Property	Data type	Access	Description
Version	Int	R/C/U	SNMP version 1: V1 2: V2c 3: V3
Community	String	R/C/U	Community Required for V1 and V2c
Username	String	R/C/U	Username Required for V3
Authentication	String	R/C/U	Authentication Type Required for V3
AuthenticationPassword	String	C/U	Authentication password Required for Authentication other than 'NoAuth'
Encryption	String	R/C/U	Encryption algorithm
EncryptionPassword	String	C/U	Encryption password Required for Encryption other than 'NoEncrypt'
ContextName	String	R/C/U	Name of SNMP context (only for V.3)
ContextEngineId	String	R/C/U	Id of SNMP context engine (only for V.3)

[Authentication]

NoAuth

MD5

MD5 (96 bit)

SHA

SHA (96 bit)

SHA256

SHA (196 or 256 bit)

[Encryption]

NoEncrypt

DES

AES

TDES

AES192

AES256

7.8.10 WindowsModernManagementData

Property	Data type	Access	Description
IsAutopilotDevice	bool	R	True if the device is an autopilot device
ModernManagementState	String	R	The modern management state of the device. One of: <i>NotManaged,</i> <i>Managed,</i> <i>ManagedAndBaramundiAgentInstalling,</i> <i>ManagedAndBaramundiAgentInstalled</i>

7.9 NewEndpoint

Property	Data type	Access	Description
EnrollmentToken	String	R	Token for enrollment (<i>null</i> for endpoints of type WindowsEndpoints)
TokenValidUntil	DateTime	R	Validity time for created token (<i>null</i> for endpoints of type WindowsEndpoints)
Endpoint	Endpoint	R	Newly created endpoint object

7.10 Job

Property	Data type	Access	Description
Id	String	R/C ¹	Unique ID of a job
ParentId	String	R/C ¹ /U	ID of a superior org unit
Name	String	R/C ¹ /U	Name of a job
DisplayName	String	R/C ¹ /U ⁴	Display name of a job. Visible in the bMA TrayNotifier and Kiosk.
Type	String	R/C	Job type: Windows, Mobile, Universal
Initiator	String	R	User, who had created the job.
Category	String	R/C ¹ /U ⁴	The job's category.
Description	String	R/C ¹ /U ⁴	The job's description
Comments	String	R/C ¹ /U	Admin's comment
IconId	String	R/C ¹ /U ⁴	The id of the job's icon, which is visible in the Kiosk.
Destructive	Bool	R	True if the job is destructive (for example if it contains a wipe job step)
JobExecutionTimeout	Int	R/C ¹ /U ⁴	The execution timeout of the job
AbortOnError	Bool	R/C ¹ /U ⁴	If set to true the job aborts after an erroneous job step.
RemoveInstanceAfterCompletion	Bool	R/C ¹ /U ¹	If set to true the job assignment will be deleted after successful execution.
Steps	List< JobStep >	R/C ² /U ²	The job steps which the job will execute.
WindowsProperties	WindowsProperties	R ¹ /C ¹ /U ¹	The windows properties of the job. Must not be null if job is for windows endpoints. Must be null if job is for mobile or mac endpoints.
MobileAndMacProperties	MobileAndMacProperties	R ³ /C ³ /U ³	The mobile and mac properties of the job. Must not be null if job is for mobile or mac endpoints. Must be null if the job is for windows endpoints.
UniversalProperties	UniversalProperties	R ⁵ /C ⁵ /U ⁵	The properties of a universal job. Must be null if the job is for windows or mobile endpoints.

(1) Only possible if the job is a job for Windows endpoints

(2) Only supported for 'Deploy' and 'SoftwareDeployUninstall' (Windows endpoints) or 'HardwareInventory' (Industrial endpoints)

(3) Only possible if the job is a job for mobile or macOS endpoints

(4) Not for universal jobs

(5) Only possible if the job is a universal job

7.10.1 Step (Common)

Property	Data type	Access	Description
Sequence	Int	R	Sequence number of the step beginning with 1
Type	String	R	Type of the Step (see Type)
Properties	List of <Key, Value>	R	Additional properties

7.10.2 Step (Deploy)

Property	Data type	Access	Description
Sequence	Int	R	Sequence number of the step beginning with 1
Type	String	R	Step type (see Step Types)
Applications	List< Application Entry >	R	The applications which the step will install or uninstall. If the job step is an uninstall job step there must be exactly one application in the list.

7.10.3 Step Types

Windows jobs:

CloningBackup
 SoftwareDeploy
 SoftwareDeployUninstall
 InventoryScan
 PatchScan
 ManagedSoftwareScan
 PXEBoot
 OSInstall
 CloningImaging
 CloningSysprep
 WipeDisk
 PersonalBackup
 PersonalRestore
 DisasterBackup
 DisasterRestore
 Citrix_AppConfig_ServerConfig
 Citrix_Publish
 Citrix_Retract
 Citrix_ServerInstallation
 ApplyEnergyPolicy
 ServerSideAction
 ComplianceScan
 VirtualizationControlVM
 VirtualizationCreateVMFromProfile
 PatchManagement
 Deploy

ManagedSoftware
NetworkScan
MicrosoftUpdateInventory
UpdateMicrosoftDefenderDefinitions
RunMicrosoftDefenderScan
MicrosoftUpgradeInstallation

Mobile and mac jobs:

ApplicationExecuteJobStep
ApplicationInstallJobStep
ApplicationUninstallJobStep
ApplicationConfigureJobStep
ApplicationRemoveConfigurationJobStep
ExecuteCommandJobStep
HardwareInventoryJobStep
SoftwareInventoryJobStep
LockJobStep
UnlockJobStep
ProfileInstallJobStep
ProfileJobStep
ProfileUninstallJobStep
ServerSideActionJobStep
SSHExecutionJobStep
OSUpdateJobStep
WaitJobStep
WipeJobStep

Universal jobs:

HardwareInventory

7.10.4 ApplicationEntry

Property	Data type	Access	Description
Id	String	R	The id of the application
Name	String	R	The name of the application
Parameters	List< ParameterInstance >	R	The configured install/uninstall parameters
IsBundle	bool	R	If <i>true</i> , the application entry is a bundle (Readonly)

7.10.5 ParameterInstance

Property	Data type	Access	Description
ParameterName	String	R	The name of the parameter
ParameterValue	String	R	The value of the parameter
ApplicationId	String	R	Only set this property if the parameter is used in a bundle. The application id of the parameter

7.10.6 MobileAndMacProperties

Property	Data type	Access	Description
ShowInKiosk	Bool	R/C/U	If true the job will be accessible in the mobile kiosk.
CanRunOnMobileDevice	Bool	R	If true this job can be executed on a mobile device (does not include macOS endpoints)
CanRunOnMac	Bool	R	If true this job can be executed on a macOS device
RequiredComplianceLevel	String	R/C/U	The job will only be executed if the target's compliance state is better or equal to this. See RequiredComplianceLevel for possible values.
Repetition	Int	R/C/U	The job will be repeated after 'Repetition' seconds expired. Must be 0 or greater than 3600 (1 hour) and less than 31449600 (52 weeks)
RescheduleOnError	Bool	R/C/U	The job will be rescheduled, even if the previous execution wasn't successful
AssignOnEndpointCreation	Bool	R/C/U	If true, the job will be assigned to new endpoints. Requires the special OU right 'Edit AutoAssign'

[RequiredComplianceLevel]

Unknown,
 Compliant,
 NotCompliant_Info,
 NotCompliant_Warning,
 NotCompliant_Severe,
 ComplianceInactive

7.10.7 Windows Properties

Property	Data type	Access	Description
Priority	Int	R/C/U	The priority of the job. Higher priority jobs will be executed first.
MaxConcurrentTargets	Int	R/C/U	Determines the max. count of clients which will execute the job concurrently.
Unlocksequence	String	R/C/U	The sequence of characters required to enter for unlocking the endpoint's input devices during job execution.
MinBandwidth	Long	R/C/U	The job will only be executed if the available bandwidth is greater than this.
CustomTrayInfo	String	R/C/U	The custom information shown to the user in the tray notifier.
CustomTrayInfoShutdown	String	R/C/U	The custom information shown to the user when shutting down.
MandatoryTime	DateTime	R/C/U	The latest date when the job must be executed on the client. The user can not delay or deny the job if this date is exceeded.
MaxDelayMinutes	Long	R/C/U	The maximum time in minutes during which the user is able to delay the job.
RemindInterval	String	R/C/U	The remind interval type. See RemindInterval for possible values.
UserActionType	String	R/C/U	Determines if the user is allowed to deny/delay the job. See UserActionType for possible values.
KeyMouseLockType	String	R/C/U	Determines if the input device's should be locked during job execution. See KeyMouseLockType for possible values.
PrePostInstallType	String	R/C/U	Determines if the job should add pre and/or post install steps. See PrePostInstallType for possible values.
JobStartType	String	R/C/U	Determines the start type of the job. See JobStartType for possible values.
AtEndOfJobAction	String	R/C/U	Determines the end of job action. See AtEndOfJobAction for possible values.
InfoWindowType	String	R/C/U	Determines if the user is able to see the info window. See InfoWindowType for possible values.
AutoAssignment	String	R/C/U	The auto assignment XML of the job. When updating this property to an own sql statement you must only provide the sql statement's where clause. For example (WHERE machine.name = 'Computer'). If you want to use this property for other jobs, you can use the retrieved AutoAssignment-String without editing it, including the xml tags.

Prerequisites	String	R/C/U	The prerequisites XML of the job. When updating this property to an own SQL statement you must only provide the SQL statement's where clause. For example (WHERE machine.name = 'Computer'). If you want to use this property for other jobs, you can use the retrieved AutoAssignment-String without editing it, including the xml tags.
Options	WindowsJobOptions	R/C/U	The job's windows options.
Validity	JobValidity	R/C/U	The time during which the job is valid (will be executed)
Interval	JobInterval	R/C/U	The job interval
RetryInterval	JobRetryInterval	R/C/U	The job's retry interval

[RemindInterval]

None,
 FiveMinutes,
 TenMinutes,
 FifteenMinutes,
 ThirtyMinutes,
 OneHour,
 TwoHours,
 FourHours,
 Degressive

[UserActionType]

CanNotInfluence,
 CanDelay,
 CanDenyOrDelay,
 UserConsentRequired

[KeyMouseLockType]

DetermineAutomatically,
 LockAccordingToSoftwareConfiguration,
 Lock,
 DoNotLock

[PrePostInstallType]

ExecutePreAndPostInstallSteps,
 DoNotExecutePreAndPostInstallSteps,
 ExecuteOnlyPreInstallSteps,
 ExecuteOnlyPostInstallSteps

[JobStartType]

Active,
Passive,
ActiveWol,
ActiveOnline,
ActiveShutdown,
ActiveShutdownAndOnline

[AtEndOfJobAction]

NoAdditionalAction,
ShutdownSystem,
ShutdownSystemIfStartedWithWoL,
RestartSystem

[InfoWindowType]

DetermineAutomatically,
ShowAlways,
ShowNever,
ShowOnlyWhenBooting

7.10.8 WindowsJobOptions

Property	Data type	Access	Description
LatestLogOff	Bool	R/C/U	If true the user will be logged off as late as possible.
LatestLogon	Bool	R/C/U	If true the user will be logged on as late as possible.
LogoffUserBeforeJobStart	Bool	R/C/U	If true the user will be logged off before job start.
UserDelayShutdown	Bool	R/C/U	If true the user is able to delay shutdowns.
UseForceLogoff	Bool	R/C/U	If true the user will be logged off even if there are unsaved changes.
UsersettingsPerUser	Bool	R/C/U	If true, the user settings will be executed per user during software deployment.
WillReinstall	Bool	R/C/U	If true, the job will reinstall the client.
IgnoreBandwidth	Bool	R/C/U	If true, the job will be executed ignoring the configured MinBandwidth
IgnoreBITS	Bool	R/C/U	If true, the job will not support baramundi background transfer
SupportEndpointsInInternetMode	Bool	R/C/U	If true, the job will also be executed on clients which are currently roaming.
RespectUserNotificationState	Bool	R/C/U	If true, the job is automatically delayed without displaying the info window for active full screen/presentation applications

7.10.9 JobValidity

Property	Data type	Access	Description
StartDate	DateTime	R/C/U	The job will be valid after StartDate
EndDate	DateTime	R/C/U	The job is only valid before EndDate
Days	List< JobValidityDay >	R/C/U	The list of days during which the job is valid. Day types in the list must be unique. Day type "EveryDay" must not be combined with other day types. Day types "Weekday" and "WeekendDay" can only be combined together.

7.10.10 JobValidityDay

Property	Data type	Access	Description
DayType	String	R	The type of the day. See DayType for possible values.
Timeboxes	List< Timebox >	R	The list of timeboxes during which the job is valid.

[DayType]

EveryDay,
 Sunday,
 Monday,
 Tuesday,
 Wednesday,
 Thursday,
 Friday,
 Saturday,
 WeekDay,
 WeekendDay,

7.10.11 Timebox

Property	Data type	Access	Description
Start	Time	R	The start time of the timebox.
End	Time	R	The end time of the timebox.

7.10.12 Time

Property	Data type	Access	Description
Hour	Int	R/C/U	The hour of the time (from 0 – 23)
Minute	Int	R/C/U	The minute of the time (from 0 - 59)

7.10.13 JobInterval

Property	Data type	Access	Description
IntervalType	String	R/C/U	The type of the interval. See IntervalType for possible values.
Days	List<string >	R/C/U	The list of valid days when specifying IntervalType "Weekdays". Must be empty otherwise. For valid values see JobIntervalDays
Multiplicator	Int	R/C/U	The hour/day/minute multiplicator. Can only be used when specifying IntervalTypes 'EveryXDays', 'EveryXHours' or 'EveryXMinutes'
StartTime	Time	R/C/U	The time the job will be started.
Repetitions	Int	R/C/U	The number of job repetitions
RescheduleOnError	Bool	R/C/U	The job will be rescheduled, even if the previous execution wasn't successful

[IntervalType]

Weekdays,
Every1stOfMonth,
Every15thOfMonth,
EveryXHours,
EveryXDays,
EveryXMinutes

[JobIntervalDays]

Monday,
Tuesday,
Wednesday,
Thursday,
Friday,
Saturday,
Sunday

7.10.14 JobRetryInterval

Property	Data type	Access	Description
IntervalType	String	R/C/U	The type of the retry interval. See RetryIntervalType for possible values.
Multiplicator	Int	R/C/U	The hour/minute/day multiplicator
Retries	Long	R/C/U	The number of retries in case of an error
RetryAction	String	R/C/U	The type of the retry action. See RetryAction for possible values.

[RetryIntervalType]

EveryXDays,
EveryXHours,
EveryXMinutes

[RetryAction]

NoAction,
Continue,
Restart

7.10.15 UniversalProperties

Property	Data type	Access	Description
RepeatedExecution	RepeatedExecution	R/C/U	Configuration for repeated job execution.

7.10.16 RepeatedExecution

Property	Data type	Access	Description
IsActive	Bool	R/C/U	Determines if repeated execution is used.
RepetitionEntries	List< RepetitionItem >	R/C/U	The list of configured repeated executions.
ErrorBehavior	String	R/C/U	The behavior on job error. Abort is the default. (See ErrorBehavior)

[ErrorBehavior]

Abort,
PlanNew

7.10.17 RepetitionItem (TimeInterval)

Property	Data type	Access	Description
Type	String	R/C/U	The type of the repetition. (See RepetitionItemType)
Minutes	Long	R/C/U	The number of minutes between two executions.

7.10.18 ReptitionItem (Daily)

Property	Data type	Access	Description
Type	String	R/C/U	The type of the repetition. (See RepetitionItemType)
Time	Time	R/C/U	The time the job will be started. Specified time is the server time.

7.10.19 RepetitionItem (Weekly)

Property	Data type	Access	Description
Type	String	R/C/U	The type of the repetition. (See RepetitionItemType)
Time	Time	R/C/U	The time the job will be started. Specified time is the server time.
Weekdays	List<String>	R/C/U	Days of the week on which the job should be executed. For valid values see JobIntervalDays .

7.10.20 RepetitionItem (Monthly)

Property	Data type	Access	Description
Type	String	R/C/U	The type of the repetition. (See RepetitionItemType)
Time	Time	R/C/U	The time the job will be started. Specified time is the server time.
MonthlyRepetitionMode	String	R/C/U	Mode of the monthly repetition. (See MonthlyRepetitionMode)
DaysOfMonth	List<Int>	R/C/U	The specific days of a month on which the job should be executed. Only used when MonthlyRepetitionMode is SpecificDays. For valid values see JobIntervalDays .
Weekdays	List<String>	R/C/U	Days of the week on which the job should be executed. Only used when MonthlyRepetitionMode is not SpecificDays

7.10.21 RepetitionItem (Yearly)

Property	Data type	Access	Description
Type	String	R/C/U	The type of the repetition. (See RepetitionItemType)
Time	Time	R/C/U	The time the job will be started. Specified time is the server time.
Month	Int	R/C/U	Number of the month in which to execute the job.
Day	Int	R/C/U	The day in the month on which to execute the job.

[RepetitionItemType]

TimeInterval,
 Daily
 Weekly,
 Monthly,
 Yearly

[MonthlyRepetitionMode]

First,
 Second,
 Third,
 Fourth,
 Last,
 SpecificDays

7.11 JobInstance

For bMS 2014 R2 the *JobInstance* object has been extended to expose properties for mobile (Android, iOS) and Mac devices too.

Property	Data type	Access	Description
Id	String (*)	R	Unique ID of a job instance
EndpointId	String (*)	R	Unique ID of an endpoint
EndpointName	String	R	Name of the corresponding endpoint
JobDefinitionId	String (*)	R	Unique ID of a job
JobDefinitionName	String	R	Name of the corresponding job
TimeStart	DateTime	R	Starting time of execution
TimeNext	DateTime	R	Time of the next execution
TimeLastAction	DateTime	R	Time last action occurred
Executed	Int	R	Number of executions
Retried	Int	R	Number, how many times a job execution was tried
HasDenied	Int	R	Number, how many times a job was denied
State DEPRECATED (use BmsNetState instead)	UInt (**)	R	State of a job instance (see coding below)
StateText	String	R	The state of a job instance as text (for all endpoint types)
Properties	List of <Key, Value>	R	Additional properties
Created	DateTime	R	Creation time of a job instance
ExecutionCountError	Int	R	Number, how many times a job execution failed
ExecutionCountSuccess	Int	R	Number, how many times a job execution succeeded
ExecutionDate	DateTime	R	Time of the next execution
Initiator	String	R	User context the job instance was created with
BmsNetState	Int	R	State of job instance for BmsNet endpoint (see coding below)
EndpointCategory	Int	R	Endpoint category of a job instance
Steps	List of <Step>	R	Step can be type of ApplicationInstance or CommonInstance
JobDefinitionDisplayName	String	R	DisplayName of the corresponding job
JobDefinition	Job	R	The Job object the Instance belongs to

(*) must not be null for reading access
(**) applies for WindowsJobInstance only

Codings:

[EndpointCategory]

- 1 Any
- 0 Unknown
- 1 MicrosoftWindows
- 2 GoogleAndroid
- 3 AppleIOS,
- 4 AppleMac

- 6 Network
- 7 Industrial

[State] DEPRECATED (use BmsNetState instead)

A job instance state consists of a status (lower 8 bits) and a so-called state flag (upper 24 bits). The mask of job instance states is 0x000000FF. That means, just the below 8 bits can be used for coding the state.

- 0 Unknown
- 1 Inactive
- 2 Active
- 5 Running
- 6 Paused
- 7 Finished

0x00000100 Resume	Job steps will not be new created.
0x00000200 Warning	Cancel with warning
0x00000400 Error	Cancel with error
0x00000800 Rebooting	Client new start
0x00001000 RetryFailed	Retry failed
0x00002000 Waiting	Waiting for event to proceed
0x00004000 Connecting	Server connects to client
0x00008000 Delayed	Job on client is delayed (locked workstation)
0x00010000 Rescheduled	Job has been re-planned
0x00020000 Preparing	Job preparation phase
0x00040000 Initializing	Job initializing phase
0x00080000 Rebooted	Client rebooted
0x00100000 WaitingForBootClient	Job waits for a boot client connection.
0x00200000 OtherJobActive	Another Job is active for this client
0x00400000 ConnectFailed	Attempt to connect failed
0x00800000 PreconditionFailed	Set when Preconditions do not apply
0x01000000 DownloadsFinished	Job instance has finished downloading files via bBT
0x02000000 DownloadingFiles	Job instance is downloading files via bBT
0x04000000 UBDSExecuteOnEachLogin	UBDS Option ExecuteOnEachLogin is set
0x08000000 RescheduledForShutdown	Job rescheduled to time of the shutdown
0x10000000 ExecuteShutdownJob	Shutdown Job ready for execution

[BmsNetState]

- 1 Unknown
- 0 Assigned
- 1 Running
- 2 FinishedSuccess
- 3 FinishedError
- 4 FinishedCanceled
- 5 ReScheduled
- 6 ReScheduledError
- 7 WaitingForUser
- 8 RequirementsNotMet
- 9 Downloading
- 10 SkippedDueToIncompatibility
- 11 NonBlockingWaitingForUser

7.11.1 Step (CommonInstance)

Property	Data type	Access	Description
Sequence	Int	R	Sequence number of the step beginning with 1
Type	String	R	Type of the Step (see Type)
Properties	List of <Key, Value>	R	Additional properties
TimeLastAction	DateTime		Time, the last action was done
State	Int		Current state of the step (see State)
StateText	String		A text that has further information

7.11.2 Step (ApplicationInstance)

Property	Data type	Access	Description
Sequence	Int	R	Sequence number of the step beginning with 1
Type	String	R	Type of the Step (see Type)
Properties	List of <Key, list of < Property >>	R	Additional properties of Type <Key, list of < Property >>
TimeLastAction	DateTime		Time, the last action was done
State	Int		Current State of the step (see State)
StateText	String		A text that has further information

7.11.3 State

[State]

- 0 Assigned
- 1 Running
- 2 FinishedSuccess
- 3 FinishedError
- 4 FinishedCanceled
- 5 ReScheduled
- 6 ReScheduledError
- 7 WaitingForUser
- 8 RequirementsNotMet
- 9 Downloading
- 10 SkippedDueToIncompatibility

7.12 BootEnvironment

This object type applies for endpoints of type *WindowsEndpoint* only.

Property	Data type	Access	Description
Id	String	R	Unique ID of a boot environment
Name	String	R	Name of a boot environment
Bootpath	String	R	Path in which the Windows PE files will be placed
Comment	String	R	Freely editable text field
Architecture	String (*)	R	Processor architecture of the boot environment
Type	String	R	Defines the type of the boot environment (see coding below)
AutoConfirmStep	Bool	R	If <i>true</i> , the started image will not confirm this step
ShowInBootMenu	Bool	R	If <i>true</i> , the boot environment will be shown in the boot menu
ReinstallSystem	Bool	R	If <i>true</i> , the boot environment will reinstall the system
NetworkBootstrapProgram	String (**)	R	Selected network bootstrap program for the boot environment

(*) for other platforms than UEFI this value is *null*

(**) for UEFI platforms this value is *null*

Codings:

[Type]

Unknown

DOS

WinPE

WinPE_UEFI

Custom

7.13 HardwareProfile

This object type applies for endpoints of type *WindowsEndpoint* only.

Property	Data type	Access	Description
Id	String	R	ID of a hardware profile
CpuSpeed	String	R	Speed of the installed CPU in MHz
CpuType	String	R	Type of the installed CPU
Comment	String	R	Freely editable text field
IgnoreOnAutoDetect	Bool	R	If set, the hardware profile will be ignored on auto detection
Manufacturer	String	R	Hardware manufacturer
Memory	String	R	Size of available memory in MByte
Model	String	R	Hardware model
Name	String	R	Name of a hardware profile
UseManualDriverAssignment	Bool	R	If <i>true</i> , the driver package stored in the <i>DriverPath</i> will be used for drivers
DriverPath	String	R	Path to driver packages

7.14 ObjectVariables

Property	Data type	Access	Description
ObjectId	String	R	Unique ID of the object the variables belong to (e.g. an endpoint)
Scope	String	R	Scope of the variables (e.g. Device)
Variables	List of < Variable >	R	List of all variables of an object

Codings:

[Scope]

Device	Covers endpoints of type <i>WindowsEndpoint</i> and <i>MacEndpoint</i>
MobileDevice (DEPRECATED)	Covers endpoints of type <i>Android</i> and <i>iOSEndpoint</i>
Job	Covers jobs of type <i>WindowsJob</i>
OrgUnit	Covers org units in node <i>Logical Groups</i> only
Software	Covers software (applications) for Windows clients only
Hardwareprofile	Covers hardware profiles
ICDevice	Covers industrial control devices
NetworkDevice	Covers network devices
AndroidDevice	Covers Android devices
IOSDevice	Covers iOS devices

7.14.1 Variable

Property	Data type	Access	Description
Category	String	R	Category of a variable
Name	String	R	Name of a variable
Value	String	R/U	Value of a variable
UseDefault	Bool (*)	R/U	If <i>true</i> the default variable value (from variable definition) is used
Type	String	R	The type of a variable (see coding below)

(*) applies for BmsNetEndpoints only

Codings:

[Type]

Unknown
 Number
 String
 Date
 Checkbox
 Dropdownbox
 DropdownListbox
 Filelink
 Folder
 Password
 Certificate

7.15 App

This object type applies for endpoints of type *AndroidEndpoint* and *iOSEndpoint* only.

Property	Data type	Access	Description
Id	String	R	Unique ID of an app
Name	String	R	Name of an app
Version	String	R	Version of an app
Platform	String	R	Supported platforms of the app
Package	String	R	Identifier of the app
StoreId	String	R	Unique Store ID of an app
FileSize	Long	R	File size of an app
Account	String	R	Account of an app
VPPManagedOS	Bool (*)	R	If <i>true</i> , the app is managed by the bMS
VPPRedemptionCodes	Bool (*)	R	If <i>true</i> , there are redemption codes for the app available
Licenses	List of < AppLicenseCounter >	R	List of item properties with data type AppLicenseCounter
ParentId	String	R	Unique ID of a parent org unit

(*) if the platform does not support this property the value is *null*

7.15.1 AppLicenseCounter

Property	Data type	Access	Description
TotalInstalledOn	Int	R	Number of devices the app is installed on
InUse	Int	R	Number of devices where the app is in use
TotalLicense	Int	R	Number of available licenses
FreeLicense	Int	R	Number of free licenses

7.16 Icon

Property	Data type	Access	Description
Id	String	R	Unique ID of an app
Data	Array of Bytes	R	The apps binary icon data

7.17 Application

This object type applies for endpoints of type *WindowsEndpoint* only.

Property	Data type	Access	Description
Id	String	R/C	Unique ID of an application
Name	String	R/C/U	Name of an application
Comment	String	R/C/U	Freely editable text field
ParentId	String	R/C/U	ID of the parent org unit
Version	String	R/C/U	Version of an application
Vendor	String	R/C/U	Vendor of an application
Category	String	R/C/U	Category of an application
ValidForOS	List of String	R/C/U	List of all supported operating systems of an application (see coding below)
EnableAUT	Bool	R/C/U	If set, AUT is enabled for this application
Installation	InstallationData	R/C/U	Object of the type InstallationData
Uninstallation	UninstallationData	R/C/U	Object of the type UninstallationData
ConsistencyChecks	String	R/C/U	Consistency checks of an application
Files	List of ApplicationFile	R/C/U	List of ApplicationFile objects
Cost	Float	R/C/U	Purchase cost
SecurityContext	String	R/C/U	Context of the execution (see coding below)
Licenses	List of ApplicationLicense	R/C/U	List of ApplicationLicense objects
MSW	Bool	R	If <i>true</i> , the application is a managed software
AUT	List of AUTFileRule	R/C/U	Rules used for application usage tracking
SoftwareDependencies	List of SoftwareDependency	R/C/U	List of SoftwareDependency objects (Application must exist)
SoftwareLicenseActions	List of SoftwareLicenseAction	R/C/U	List of SoftwareLicenseAction objects
Parameters	List of Parameter	R/C/U	List of Parameter objects
Hashes	List of ApplicationHash	R/C/U	List of ApplicationHash objects

Codings:

[SecurityContext]

AnyUser
InstallUser
LocalInstallUser
LocalSystem
LoggedOnUser
RegisteredUser

SpecifiedUser

[ValidForOS]

NT4
 Windows2000
 WindowsXP
 WindowsServer2003
 WindowsVista
 WindowsServer2008
 Windows7
 WindowsServer2008R2
 WindowsXP_x64
 WindowsServer2003_x64
 WindowsVista_x64
 WindowsServer2008_x64
 Windows7_x64
 WindowsServer2008R2_x64
 Windows8
 Windows8_x64
 WindowsServer2012_x64
 Windows10
 Windows10_x64
 WindowsServer2016_x64
 WindowsServer2019_x64
 Windows11_x64
 WindowsServer2022_x64

7.17.1 ApplicationLicense

Property	Data type	Access	Description
Count	Int	R/C/U	Count of all available licenses
LicenseKey	String	R/C/U	Key of the license
Offline	Int	R/C/U	Count of all offline licenses
Online	Int	R	Count of all online licenses

7.17.2 ApplicationFile

Property	Data type	Access	Description
Source	String	R/C/U	Source of the file
Type	String	R/C/U	Type of the file (see coding below)

Codings:

[Type]

FolderWithSubFolders
 SingleFolder
 File

7.17.3 InstallationData

Property	Data type	Access	Description
Command	String	R/C/U	Installation / Uninstallation command
Parameter	String	R/C/U	Parameters for installation / uninstallation
Response File	String	R/C/U	Source of the response file after installation / uninstallation
Engine	String	R/C/U	Name of the installation / uninstallation engine
EngineFile	String	R/C/U	Source of the installation / uninstallation engine
Options	InstallApplicationOption	R/C/U	InstallApplicationOption
UserSettings	InstallUserSettings	R/C/U	InstallUserSettings

Codings:

[Engine]

baramundi Deploy Package
Rational Visual Test 6.5
baramundi Deploy Script

7.17.3.1 InstallApplicationOption

Property	Data type	Access	Description
RebootBehaviour	String	R/C/U	Behaviour after reboot (see coding below)
AllowReinstall	Bool	R/C/U	If set, reinstallation is allowed
UsebBT	Bool	R/C/U	If set, bBT is supported
VisibleExecution	String	R/C/U	Shows in which cases the execution of this software is visible (see coding below)
CopyLocally	Bool	R/C/U	If set, installation files should be copied to local filesystem
DisableInputDevices	Bool	R/C/U	If set, no input devices will be available during installation
DontSetAsInstalled	Bool	R/C/U	If set, this application shouldn't be shown as installed, after installation
MapShare	Bool	R/C/U	If set, installation share will be connected for installation
Target	String	R/C/U	Target file

Codings:

[RebootBehaviour]

NoReboot
Reboot
AppReboot
DeferrableReboot

[VisibleExecution]

Silent

NeedsDesktop

VisibleWhenUserLoggedIn

7.17.3.2 InstallUserSettings

Property	Data type	Access	Description
baramundiDeployScript	String	R/C/U	Path to the deploy script that needs to be executed during installation
ValidForInstallUser	Bool	R/C/U	If <i>true</i> , also valid for install user
RunbDSVisible	Bool	R/C/U	If <i>true</i> , bDS will be executed visible
CopyScriptToClient	Bool	R/C/U	If <i>true</i> , script will be copied to the client before execution
ExecuteAtEveryLogin	Bool	R/C/U	If <i>true</i> , script will be executed at every login

7.17.4 UninstallationData

Property	Data type	Access	Description
Command	String	R/C/U	Installation / Uninstallation command
Parameter	String	R/C/U	Parameters for installation / uninstallation
Response File	String	R/C/U	Source of the response file after installation / uninstallation
Engine	String	R/C/U	Name of the installation / uninstallation engine
EngineFile	String	R/C/U	Source of the installation / uninstallation engine
Options	UninstallApplicationOption	R/C/U	UninstallApplicationOption
UserSettings	UninstallUserSettings	R/C/U	UninstallUserSettings

Codings:

[Engine]

baramundi Deploy Package

Rational Visual Test 6.5

baramundi Deploy Script

7.17.4.1 UninstallApplicationOption

Property	Data type	Access	Description
RebootBehaviour	String	R/C/U	Behaviour after Reboot (see codings below)
RemoveUnknownSoftware	Bool	R/C/U	If <i>true</i> , unknown software will be uninstalled
UsebBT	Bool	R/C/U	If <i>true</i> , bBT is supported

VisibleExecution	String	R/C/U	Shows in which cases the execution of this software is visible (see coding below)
CopyLocally	Bool	R/C/U	If <i>true</i> , installation files are copied to local file system
DisableInputDevices	Bool	R/C/U	If <i>true</i> , no input devices will be available during installation

Codings:

[VisibleExecution]

Silent

NeedsDesktop

VisibleWhenUserLoggedIn

[RebootBehaviour]

NoReboot

Reboot

AppReboot

DeferrableReboot

7.17.4.2 UninstallUserSettings

Property	Data type	Access	Description
baramundiDeployScript	String	R/C/U	Path to the deploy script that needs to be executed during installation
ValidForInstallUser	Bool	R/C/U	If <i>true</i> , also valid for install user
RunbDSVisible	Bool	R/C/U	If <i>true</i> , bDS will be executed visible
CopyScriptToClient	Bool	R/C/U	If <i>true</i> , script will be copied to client before execution

7.17.5AUTFileRule

Property	Data type	Access	Description
FileName	String	R/C/U	Name of the file
FileSize	ULong	R/C/U	Size of the file
Date	String	R/C/U	Timestamp as Date of the file
CRC	ULong	R/C/U	Checksum of the file
Version	String	R/C/U	Version of the file
Company	String	R/C/U	Company of the file
ProductName	String	R/C/U	Product name of the file
InternalName	String	R/C/U	Internal name of the file
Language	String	R/C/U	Language of the file
ProductVersion	String	R/C/U	Product version of the file
FileDescription	String	R/C/U	File description of the file
FileVersionNumeric	String	R/C/U	Numerical file version
CommandLine	String	R/C/U	Command line parameters

7.17.6 SoftwareDependency

Property	Data type	Access	Description
DependencyId	String	R/C	Unique ID of the dependency (software Unique ID)
DependencyAppName	String	R	Name of the application
DependencyType	String	R/C	Type of the dependency
ValidForOS	List of Strings	R/C	List of all supported operating systems of the dependency (see coding below)

[DependencyType]

InstallBeforeIfNotInstalled
 AlwaysInstallAfterwards
 AlwaysInstallBefore
 DeinstallBeforeIfInstalled
 ErrorIfNotInstalled
 ErrorIfInstalled

[ValidForOS]

NT4
 Windows2000
 WindowsXP
 WindowsServer2003
 WindowsVista
 WindowsServer2008
 Windows7
 WindowsServer2008R2
 WindowsXP_x64
 WindowsServer2003_x64
 WindowsVista_x64
 WindowsServer2008_x64
 Windows7_x64
 WindowsServer2008R2_x64
 Windows8
 Windows8_x64
 WindowsServer2012_x64
 Windows10
 Windows10_x64
 WindowsServer2016_x64
 WindowsServer2019_x64
 Windows11_x64
 WindowsServer2022_x64

7.17.7 SoftwareLicenseAction

Property	Data type	Access	Description
AlarmCount	int	R/C	Count, when the alarm is executed.
AlarmAction	String	R/C	Action of the alarm
ContinueInstall	bool	R/C	If <i>false</i> , the application won't be installed, if less than ' <i>AlarmCount</i> ' licenses are available

[AlarmAction]

LogInfo

LogWarning

7.17.8 Parameters

Property	Data type	Access	Description
Name	String	R/C	Name of the parameter
Type	String	R/C	The type of the parameter
Value	String	R/C	The actual value of the parameter
DefaultValue	String	R/C	The default value of the parameter when <i>Value</i> is not set

[Type]

Unknown

Number

String

Date

Checkbox

Dropdownbox

DropdownListbox

Filelink

Folder

Password

Certificate

7.17.9 ApplicationHash

Currently only available if the application is a managed software (version or product line).

Property	Data type	Access	Description
FilePath	String	R/C	The path of the file
Sha256Hash	String	R/C/U	The sha256 hash of the file
IgnoreHashing	bool	R/C/U	If true, the hash for this file will not be checked on the clients. This is for cases where a file has different hashes on different DIPs

LastChangeBy	Int	R	Change source depending on how the hash was last updated or created.
LastChangeByUser	String	R	The user who last created or changed the hash. Empty if hash was created or updated automatically.
LastChanged	DateTime	R	The time at which the hash was last updated or created.

Code:

[LastChangeBy]

- 0 File Importer
- 1 User
- 2 Copy

7.18 Inventory

This object type applies for all endpoint types.

Property	Data type	Access	Description
EndpointId	String	R	Unique ID of the endpoint
Scans	List of InventoryScan	R	List of available inventory scans for an endpoint

7.18.1 InventoryScan

Property	Data type	Access	Description
Time	DateTime	R	Scan execution time (in UTC)
Template	String	R	Name of the template used for the inventory scan
Data	List of InventoryData>	R	Inventory data is one of following types: DataRegistry , DataFile , DataWMI , DataCustom and DataHardware

7.18.2 DataRegistry

Property	Data type	Access	Description
Name	String	R	Name of a scanned registry entry
Version	String	R	Version of a scanned registry entry
Company	String	R	Responsible Company
ProductName	String	R	Name of a product the entry is for

7.18.3 DataFile

Property	Data type	Access	Description
Name	String	R	Name of a scanned file

Path	String	R	Path of a scanned file
Size	Long	R	Size of a scanned file in Bytes
LastWriteTime	DateTime	R	Last time the file was modified
Version	String	R	Version of a scanned file
Company	String	R	Manufacturer of a scanned file
ProductName	String	R	Product a scanned file is part of
ProductVersion	String	R	Version of a product
OriginalName	String	R	Internal name of a scanned file
Description	String	R	Description of a scanned file

7.18.4 DataWMI

Property	Data type	Access	Description
ClassName	String	R	Corresponding WMI class name
Items	List of Item	R	List of found items with data type Item

7.18.4.1 Item

Property	Data type	Access	Description
Child	DataWMI	R	Possible child data
Properties	List of Property	R	List of item properties with data type Property .

7.18.5 DataCustom

Property	Data type	Access	Description
Name	String	R	Custom name of a root node
Properties	List of Property	R	List of custom node properties with type Property
SubNodes	List of DataCustom	R	List of SubNodes with data type DataCustom

7.18.6 DataHardware

Property	Data type	Access	Description
Name	String	R	Name of a root node
Properties	List of Property	R	List of node properties with type Property
SubNodes	List of DataHardware	R	List of SubNodes with data type DataHardware

7.18.6.1 Property

Property	Data type	Access	Description
Name	String	R	Property name

Value	String	R	Property value
-------	--------	---	----------------

7.18.7DataSnmpp

Property	Data type	Access	Description
Name	String	R	Name of a SNMP property
ObjectId	String	R	SNMP object identifier
PropertyId	String	R	Id of a SNMP property
Found	Bool	R	True if the object was found
Value	String	R	Value of a SNMP property

7.19 InventoryOverview

This object type applies for endpoints of type *WindowsEndpoint* only.

Property	Data type	Access	Description
EndpointId	String	R	ID of an endpoint
Scans	List of < Scan >	R	List of scan objects of an endpoint

7.19.1 Scan

Property	Data type	Access	Description
Template	String	R	Name of a used template
Time	DateTime	R	Date and time of a scan (in UTC)
Type	String	R	Inventory Type (see coding below)

Coding:

[Type]

Unknown

Custom

WMI

Hardware

7.20 InventoryApp

This object type applies for endpoints of type *AndroidEndpoint* and *iOSEndpoint* only.

Property	Data type	Access	Description
Id	String	R	Unique ID of an App
Name	String	R	Name of the App
Version	String	R	Version of the App
Build	String	R	Build number of the App
Platform	String	R	Supported platform for the App
Package	String	R	Identifier of the App
IsRunnable	Bool (*) (***)	R	If set, the App is runnable and whitelisted on the device
LocalPath	String (*) (**)	R	Local installation path of the app
VPPManagedOS	Bool (*) (***)	R	If set, the App is managed by the bMS
VPPRedemptionCodes	Bool (*) (***)	R	If set, there are redemption codes for the app available
Licenses	List of AppLicenseCounter	R	List of item properties with data type AppLicenseCounter

(*) if the platform does not support the property, the value is *null*.

(**) only supported on Mac OS X devices

(***) only supported on iOS and Mac OS X

7.21 SoftwareScanRule

Property	Data type	Access	Description
Id	String (*)	R	Unique ID of a software scan rule
SoftwareManufacturer	String (*)	R	Manufacturer of a software
SoftwareName	String (*)	R	Name of a software
SoftwareVersion	String (*)	R	Version of a software
Protected	Bool	R	<i>True</i> , if scan rule is protected
Comment	String	R	Freely editable text field
Rules DEPRECATED	String	R	The rule to detect a software
Category	String	R	Category of the software
IsMswRule	Bool	R	<i>True</i> , if scan rule is for ManagedSoftware product

(*) must not be null for reading access

7.22 SoftwareScanRuleCount

Property	Data type	Access	Description
SoftwareScanRule	SoftwareScanRule object	R	SoftwareScanRule object that a detection rule that identifies installed and deployed software
InstalledCount	String	R	Cumulated count of deployed and inventoried software
InstalledEndpoints	List of EndpointInfo objects	R	The Endpoints which match the scan rule

7.23 EndpointInvSoftware

Property	Data type	Access	Description
GuidEndpoint	String (*)	R	Unique ID of an endpoint
GuidRule	String (*)	R	Unique ID of a software scan rule
LastSeen	DateTime(*)	R	Last time a software was detected on an endpoint
InventoryPath	String	R	Inventory path
InventoryVersion	String	R	Inventory version
ConflictedRules DEPRECATED	String	R	List of IDs of conflicted scan rules

(*) must not be null for reading access

7.24 EndpointInfo

Property	Data type	Access	Description
Id	String	R	Unique ID of an endpoint
Name	String	R	Name of the endpoint

7.25 Image

Property	Data type	Access	Description
Id	String	R	Unique ID of an image
MimeType	String	R	Image Internet Media Type
Data	Array of Bytes	R	The binary icon data

7.26 VariableDefinition

Property	Data type	Access	Description
Id	String	R/C	Unique ID of a custom variable
Scope	String	R/C/U	Scope of a custom variable (e.g. Device). An update of the scope can only be performed on multiscope variables
Category	String	R/C/U	Category of a custom variable
Name	String	R/C/U	Name of a custom variable
Type	String	R/C/U	Type of a custom variable (see coding below)
Value	String	R/C/U	The default value of a custom variable
Comments	String	R/C/U	Freely editable text field

Codings:

[Type]

Unknown
 Number
 String
 Date
 Checkbox
 Dropdownbox
 DropdownListbox
 Filelink
 Folder
 Password
 Certificate

[Scope]

Device	Covers endpoints of type <i>WindowsEndpoint</i> and <i>MacEndpoint</i>
MobileDevice (DEPRECATED)	Covers endpoints of type <i>Android</i> and <i>iOSEndpoint</i>
Job	Covers jobs of type <i>WindowsJob</i>
OrgUnit	Covers org units in node <i>Logical Groups</i> only
Software	Covers software (applications) for Windows clients only
Hardwareprofile	Covers hardware profiles
AdObject	Covers Active Directory users and groups
Bulletin	Covers patch bulletins
Component	Covers hardware components
ICDevice	Covers industrial control devices
NetworkDevice	Covers network devices
AndroidDevice	Covers Android devices
IOSDevice	Covers iOS devices

7.27 KioskJob

Property	Data type	Access	Description
Id	long	R/D	Unique ID of the job release
AssignedObjectId	String	R/C	Unique Id of endpoint, group or user
AssignedObjectName	String	R	Name of endpoint, group or user
AssignedObjectType	String	R	Types: WindowsEndpoint MacEndpoint IOSEndpoint AndroidEndpoint Group (Logical Group) ADObject (User or AD-Group)
JobDefinitionId	String	R/C	Unique Id of the released job
JobDefinitionName	String	R	Name of the released job
JobDefinitionDisplayName	String	R	(Kiosk) Display name of the released job
JobDefinitionCategory	String	R	Category of the released job
JobDefinitionSupportedPlatforms	List of Strings	R	Supported device platforms of the released job

7.28 EndpointSecrets

Property	Data type	Access	Description
EndpointId	String	R	Unique ID of the endpoint
Pin	String	R/P	BitLocker unlock pin
VolumeSecretEntries	List of <VolumeSecretEntry>	R	Volume secrets

7.28.1 VolumeSecretEntry

Property	Data type	Access	Description
VolumId	String	R	Unique ID of the volume
VolumeName	String	R	Name of the volume
IsSystemVolume	Bool	R	Operation system on volume
GeneratedRecoveryKey	String	R	Generated recovery key sent to endpoint
InventoryRecoveryKey	String	R	Inventoried recovery key
InventoryTimestamp	DateTime	R	Last inventory time

7.29 EnrollmentData

Property	Data type	Access	Description
EndpointId	String	R	Unique ID of the endpoint
InstallCommand	String	R	Specific install command for the given endpoint
ValidUntil	String	R	Timestamp until the enrollment data is valid

7.30 ServerState

Property	Data type	Access	Description
Name	String	R	Name of the baramundi server
ExecutionState	ExecutionState	R	The current execution state of the baramundi server (see below)
Services	List of ServiceState	R	The states of the sub services of the server

[ExecutionState]

- 0 Unknown
- 1 Stopped
- 2 StoppedNotConfigured
- 3 Starting
- 4 Running
- 5 RunningNotConfigured
- 6 MaintenanceMode
- 7 Warning
- 8 Stopping
- 9 RestartRequired
- 10 NotLicensed
- 11 RunningNotLicensed

7.30.1 ServiceState

Property	Data type	Access	Description
Name	String	R	Name of the service (The name of the service may change in future releases.)
ExecutionState	ExecutionState	R	The current execution state of the service (see above)
StateText	List of String	R	The current state text of the service

7.31 VPPUser

Property	Data type	Access	Description
Id	String	R	Unique ID of the VPP user
Email	String	R/C	The email address of the VPP user
ManagedAppleId	String	R/C	The managed Apple ID of the VPP user
ItunesStoreHash	String	R	The hash of the user's iTunes Store ID
InviteUrl	String	R	The URL for VPP users to complete the registration process
Status	String	R	Status of a VPP user (see coding below)
UserId	String	R	An Id assigned by Apple upon user registration
IsManagedAppleId	Bool	R/C	<i>True</i> , if the VPP user is associated with a managed Apple Id
ADObjectId	String	R	The Id of the AD-User, if an AD-User has been attached to the VPP user

EmailLanguageId	String	R/C/U	The Identifier of the email template, which will be used for the email enrollment message sent to the Recipient email. Default available templates are "de-DE" and "en-US". Property can only be updated if IsManagedAppleId is false.
-----------------	--------	-------	--

Codings:

[Status]

Registered
Associated
Retired
Deleted

7.32 VPPLicenseAssociation

Property	Data type	Access	Description
Id	String	R	Unique ID of the VPP license association
ClientUserIdStr	String	R/C	The unique ID of the associated VPP user
LicenseIdStr	String	R	The identifier of the assigned license
BmsNetEndpoint	String	R	The unique ID of the associated Mobile Endpoint
SerialNumber	String	R	The serial number of the associated Mobile Endpoint
AdamId	String	R	The unique identifier for a product in the iTunes Store
ShouldBeDisassociated	Bool	R	<i>True</i> , if the VPP license is marked for disassociation, otherwise <i>False</i>
BundleId	String	R/C	The unique bundle ID of the associated app

7.33 MicrosoftUpdateInventories

Property	Data type	Access	Description
Endpoints	List of MicrosoftUpdateEndpointInventory	R	Inventoried Microsoft updates of Windows endpoints

7.34 MicrosoftUpdateEndpointInventory

Property	Data type	Access	Description
EndpointID	String	R	Unique ID of the Windows endpoint
UpdateInformation	List of MicrosoftUpdateInventoryInformation	R	Inventoried Microsoft updates of the Windows endpoint

7.35 MicrosoftUpdateInventoryInformation

Property	Data type	Access	Description
IsInstalled	Bool	R	Indicates whether the update is installed or not
UpdateId	String	R	Revision-independent identifier of the update
RevisionNumber	String	R	Revision number of the update
Classification	String	R	Classification of the update
Products	List of String	R	Collection of the product names that are associated with the update
Title	String	R	Title of the update
Type	String	R	Specifies the update type (see below)
SupportURL	String	R	Hyperlink to the support information for the update
InstallationDeadline	String	R	Date until an update classified as missing (taking into account the settings of an update profile) must be installed to avoid a negative effect on the update status (Noncompliant). The deadline can be extended by increasing the "missing update tolerance period".
LastDeploymentChangeTime	String	R	Last published date of the update on the server that deploys the update (in UTC)
MsrcSeverity	String	R	Microsoft Security Response Center severity rating of the update. Is <i>null</i> when not set.
KBArticleIDs	List of String	R	Collection of Microsoft Knowledge Base article IDs that are associated with the update
MoreInfoUrls	List of String	R	Collection of hyperlinks to more information about the update
SecurityBulletinIDs	List of String	R	Collection of the security bulletin IDs that are associated with the update
CveIDs	List of String	R	Collection of common vulnerabilities and exposures (CVE) IDs that are associated with the update
Description	String	R	Description of the update

[Type]

Software
Driver

[MsrcSeverity]

Low,
Medium,
High,
Critical

7.36 ComplianceViolation

Property	Data type	Access	Description
Cveld	String	R	The id of the associated cve rule
MdmComplianceRuleId	String	R	The id of the associated mobile devices compliance rule
EndpointId	String	R	The id of the associated endpoint
Endpoint	String	R	Name of the endpoint
Name	String	R	Name of the compliance rule
Products	String	R	Products that cause this compliance violation
CvssScore	Double	R	Cvss score of the compliance violation
Severity	String	R	Severity of the compliance violation
Description	String	R	Description of the compliance violation
ComplianceType	String	R	Type of the compliance depending on the OS
State	String	R	Sate of the compliance violation
MdmRuleType	String	R	Mobile Devices and macOS rule types

[Severity]

Unknown,
None,
Low,
Medium,
High,
Critical

[ComplianceType]

Windows
Mobile Devices & macOS
Industrial

[State]

Unknown,
Active,
Ignored,
Conditional Ignored,
Resolved

[MdmRuleType]

Unknown
Jailbreak
Blacklisted App
Whitelisted App
Missing App

Outdated Info
Operating System
Geo Fence
Invalid App Version

7.37 VulnerabilityExclusion

Property	Data type	Access	Description
CveName	String	R	The name of the associated cve rule
CvId	String	R	The id of the associated cve rule
OriginName	String	R	The origin of the vulnerability exclusion
OriginId	String	R	The id of the origin of the vulnerability exclusion
Initiator	String	R	User context the vulnerability exclusion was created with
Added	DateTime	R	Date and time the vulnerability exclusion was added
Reason	String	R	Entered reason why the vulnerability is excluded
Status	String	R	Exclusion: Exclusion is active Revoked exclusion: Exclusion is revoked

[Status]
Exclusion,
Revoked exclusion

7.38 MicrosoftUpdateProfile

Property	Data type	Access	Description
Id	string	R	Identifier of the Microsoft Update Profile
Name	String	R/C/U	Name of the Microsoft Update Profile. Must be unique (case-insensitive) among all Microsoft Update Profiles
Comment	String	R/C/U	A comment associated with the Microsoft Update Profile
UpdateDeferralPeriodInDays	int	R/C/U	The minimum age of an update relative to its LastDeploymentChangeTime before it is considered a candidate for update deployment. Value must be in the Range [0, 30]. Default value is 0.
BlockedUpdates	List of String	R/C/U	Collection of IDs of updates that must never be considered valid candidates for update deployment
BlockedClassifications	List of String	R/C/U	Collection of names of update classifications that must never be

			considered valid candidates for update deployment. If the property BlockedClassifications is not specified explicitly, the value ["Upgrades"] (in JSON, similarly in XML) is used as default.
BlockedProducts	List of String	R/C/U	Collection of names of update products that must never be considered valid candidates for update deployment

7.39 MicrosoftUpdateManagementSetting

Property	Data type	Access	Description
Key	String	R	The key of the setting
Value	String	R/U	The value of the setting

[Key]

InventoryValidityPeriod
MissingUpdateTolerancePeriod
DefaultUpdateProfileId

7.40 MicrosoftDefenderThreat

Property	Data type	Access	Description
Id	String	R	Identifier of detected threat
Name	String	R	Name of threat
IsActive	Bool	R	Indicates whether the threat is active or not
Severity	String	R	Specifies the threat severity (see below)
Category	String	R	Specifies the threat category (see below)
ThreatType	String	R	Type of threat (see below)
DomainUser	String	R	Domain user where threat was detected
ProcessName	String	R	Process name
FileNames	String	R	File names detected by Microsoft Defender Antivirus, separated by newline
ActionSuccess	Bool	R	Indicates whether threat could be resolved or not
ExecutionStatus	String	R	Execution status of threat (see below)
ThreatStatus	String	R	Threat status (see below)
DetectionSource	String	R	Detection source type (see below)
CleaningAction	String	R	Cleaning status (see below)
AdditionalActions	Int	R	Bit field for additional actions, combinations of two or three actions are possible (see below)
DetectionTime	DateTime	R	Detection time of the threat
RemediationTime	DateTime	R	Remediation time

LastStatusChangedTime	DateTime	R	Last time the status of threat changed
EndpointId	String	R	Id of endpoint where threat was detected
EndpointName	String	R	Name of endpoint where threat was detected

[Severity]

UnknownSeverity,
Low,
Moderate,
High,
Severe

[Category]

Invalid,
Adware,
Spyware,
PasswordStealer,
TrojanDownloader,
Worm,
Backdoor,
RemoteAccessTrojan,
Trojan,
EmailFlooder,
Keylogger,
Dialer,
MonitoringSoftware,
BrowserModifier,
Cookie,
BrowserPlugin,
AolExploit,
Nuker,
SecurityDisabler,
JokeProgram,
HostileActivexControl,
SoftwareBundler,
StealthNotifier,
SettingsModifier,
Toolbar,
Remotecontrolsoftware,
TrojanFtp,
PotentialUnwantedSoftware,
IcqExploit,
TrojanTelnet,
Exploit,
FilesharingProgram,
MalwareCreationTool,
RemoteControlSoftware,
Tool,
TrojanDenialofservice,
TrojanRopper,
TrojanMassmailer,
TrojanMonitoringsoftware,
TrojanProxyserver,
Virus,

Known,
Unknown,
Spp,
Behavior,
Vulnerabilty,
Policy

[ThreatType]

KnownBad,
BehaviorType,
UnknownType,
KnownGood,
NriType

[ExecutionStatus]

UnknownExecutionStatus,
BlockedExecutionStatus,
AllowedExecutionStatus,
Executing,
NotExecuting

[ThreatStatus]

UnknownStatus,
Detected,
Cleaned,
Quarantined,
Removed,
Allowed,
Blocked,
CleanFailed,
QuarantineFailed,
RemoveFailed,
AllowFailed,
Abandoned,
BlockedFailed

[DetectionSource]

UnknownDetectionSourceType,
User,
System,
RealTime,
Ioav,
Nri,
IeProtect,
Elam,
LocalAttestation,
RemoteAttestation

[CleaningAction]

UnknownCleaningAction,
Clean,
Quarantine,
Remove,
Allow,
Userdefined,
Noaction,

Block

[AdditionalActions]

0x00000000 None

0x00000002 Full scan required

0x00000008 Reboot required

0x00000010 Manual steps required

0x00008000 Offline scan required

7.41 ModernEnrollmentActivationResult

Property	Data type	Access	Description
EndpointId	String	R	The Id of the endpoint, which has been activated for native enrolment.
EnrollmentUrl	String	R	The URL where the native enrolment profile can be downloaded.
EnrollmentTokenValidUntilUTC	String	R	The timestamp until the enrolment profile can be downloaded as UTC time
ErrorSendingEmail	Bool	R	Indicates whether an error occurred or not while sending the enrolment mail. This property will only be shown if the sending of an email was requested.
ErrorDetail	String	R	Holds the detailed error message if an error has occurred while activating native enrolment. This property will only be shown in case of an error.

7.42 IpNetwork

Property	Data type	Access	Description
ID	String	R	The Id of the IP network.
Name	String	R/C/U	The name of the IP network.
Dips	String	R/C/U	The dips specified for this IP network.
WolRelay	String	R/C/U	Wake on lan relays set for this IP network.
BandwidthMode	Enum	R/C/U	The specified bandwidth mode for this IP network. Possible values are <i>AllowAll</i> (0), <i>BlockAll</i> (1) and <i>UseBandwidth</i> (2).
MaxBandwidthKbits	Long	R/C/U	The maximal bandwidth in Kbits specified for this IP network.
DuplicateWolToThisNetwork	Enum	R/C/U	States whether wake on lan should be duplicated to this IP network. Possible values are <i>True</i> and <i>False</i> .
Scopes	List of IpNetworkScope	R/C/U	The list of network scopes associated with this IpNetwork
VLMS	Enum	R/C/U	States whether VLMS is enabled. VLMS is enabled by default. Possible values are <i>True</i> and <i>False</i> .

7.43 IpNetworkScope

Property	Data type	Access	Description
NetworkAddress	String	R/C/U	The network address of the scope
SubnetMask	String	R/C/U	The subnet mask of the scope

7.44 PinnedBmaSetupFilesInformation

Property	Data type	Access	Description
----------	-----------	--------	-------------

PinnedBmaSetupFiles	List of PinnedBmaSetupFiles objects	R/U	A list of the installation sources protected by checksums.
---------------------	---	-----	--

7.45 PinnedBmaSetupFiles

Property	Data type	Access	Description
RelativeFilePath	String	R/U	Relative path to installation source
Hash	String	R/U	SHA-256 checksum of the installation source in the form of a lowercase hexadecimal string

7.46 EndpointSSHInfo

Property	Data type	Access	Description
EndpointId	String	R	Id of the corresponding Endpoint
Port	unit	R/U	Port of the SSH-Server on the Device (Possible values: 1- 65535 or null)
SshVersion	String	R	The Version reported by the SSH Server
DiscoveredOn	DateTime	R	The Time at which the SSH server was first discovered by the network scanner
HostKeys	List of SSHPublicKey	R/U	The SSH public keys for this device

7.46.1 SSHPublicKey

Property	Data type	Access	Description
KeyType	String	R/U	The type of key (e. g. ssh-rsa)
KeyData	String	R/U	The base64-encoded public key