

Electric Quadrupole Moments of Nuclei

The nuclear <u>electric quadrupole moment</u> is a parameter which describes the effective shape of the ellipsoid of nuclear charge distribution. A non-zero quadrupole moment Q indicates that the charge distribution is not spherically symmetric. By convention, the value of Q is taken to be positive if the ellipsoid is prolate and negative if it is oblate.



The quantity Q_0 is the classical form of the calculation represents the departure from spherical symmetry in the rest frame of the nucleus. The expression for Q is the quantum mechanical form which takes takes into account the <u>nuclear spin</u> I and the projection K in the z-direction.

One of the expectations of the **shell model** for the nucleus is that for closed shells the nuclear charge is spherically symmetric. If a nucleus is not spherically symmetric, it will have a nonzero electric quadrupole moment, so the measurement of the quadrupole moment is a test of the shell theory. Since the quadupole moment depends upon the size and charge of the nucleus, a better comparison is obtained by normalizing for those factors, giving what is called a "reduced quadrupole moment". A plot of measured values shows that magic numbers of neutrons or protons correlate with near-zero quadrupole moments.



Quadrupole measurements horizontal axis is either neutron number or proton

For a shell model, those nuclei with closed shells should be spherically symmetric and have no quadrupole moment.

for odd-A nuclei. The

number, whichever is odd.

<u>Index</u>

<u>Nuclear</u> **Structure** Concepts

References Booth & Combley

> **Krane** Ch 3

After Booth & Combley

Electric quadrupole moments of nuclei can be measured brom hyperfine splitting of atomic spectral lines, from quadrupole hyperfine splitting of molecular rotational spectra, and other spectroscopic techniques.

eb)
288
578
40
.09
03
.4
.0
37
03

The electric quadrupole moment has the units of Coulomb x meter². It is sometimes tabulated in units of e x 10^{-24} cm² where e is the electron charge. In <u>nuclear cross-section</u> measurements, the quantity 10⁻²⁴ cm² is called a "barn" and is represented by b. So sometimes the quadrupole unit is written "eb" for electron-barns. Usually the quadrupole moments will be a few tenths in these units until you reach mass numbers around 150. Then quadrupole moments around 2 are common and have been measured as high as 8.

Data from V. S. Shirley, Table of Isotopes, Wiley, New York, 1978, Appendix VII.

Evidence for nuclear shell structure "Magic numbers" of nucleons

<u>HyperPhysics</u>***** <u>Nuclear</u>

R Nave

Go Back