basil.js // typo() Cheatsheet

Structure:

typo(obj, 'property'); // get value
typo(obj, 'property', value); // set value

Full List:

http://jongware.mit.edu/iccs6js_html/iccs6js/pc_Text.html

Values:

string » 'text within quotes'
number » whole or decimal value, see (range) for limits
bool » true / false without quotes

» use color() or send variable of color()
» Copy + Paste, ie. Justification.LEFT ALIGN color

Examples:

typo(obj, 'appliedFont', 'Wingdings');
typo(obj, 'characterRotation', 45);
typo(obj, 'hyphenation', false);
typo(obj, 'fillColor', color(255,0,0));
typo(obj, 'justification', Justification.LEFT_ALIGN);

roperty	Value	Notes
ontents	string	contents of the text
ppliedFont	string	change font family
ontStyle	string	change font weight
ointSize	number	set pointsize (must be bigger than 0)
racking	number	loosen or tighten a block of text
eading	number	vertical space between lines of text
inimumLetterSpacing	number	required min letter spacing
aximumLetterSpacing	number	required max letter spacing
esiredLetterSpacing	number	set within range of min + max letter spacing
inimumWordSpacing	number	required min word spacing
aximumWordSpacing	number	required max word spacing
esiredWordSpacing	number	set within range of min + max word spacing
ustification	Justification.LEFT_ALIGN Justification.CENTER_ALIGN Justification.RIGHT_ALIGN Justification.LEFT_JUSTIFIED Justification.RIGHT_JUSTIFIED Justification.CENTER_JUSTIFIED Justification.FULLY_JUSTIFIED	set justification of paragraph
yphenation	bool	toggle hyphenation
yphenateLadderLimit	number (range: 0 - 25)	maximum number of hyphens appearing on consecutive lines
igatures	bool	toggle ligatures (e.g., fl, fi)
apitalization	Capitalization.NORMAL Capitalization.SMALL_CAPS Capitalization.ALL_CAPS Capitalization.CAP_TO_SMALL_CAP	shift text from baseline
aselineShift	number	shift text from baseline
irstLineIndent	number	amount to indent the first line
ropCapCharacters	number (range: 0 - 150)	number of characters to drop cap
ropCapLines	number (range: 0 - 25)	number of lines to drop cap
ropCapStyle	string / characterStyle	character style to apply to the drop cap
haracterRotation	number	angle (in degrees) of characters
kew	number	skew angle of the text
orizontalScale	number	horizontal scaling applied to the text
erticalScale	number	vertical scaling applied to the Text
illColor	string / color()	set fill color
illTint	number (0 - 100)	percentage of fill color
trokeColor	string / color()	set stroke color
trokeTint	number (0 - 100)	percentage of fill color
trokeWeight	number	stroke weight applied to the characters of the text
trokeAlignment	TextStrokeAlign.CENTER_ALIGNMENT TextStrokeAlign.OUTSIDE_ALIGNMENT	stroke alignment on text
nderline	bool	toggle underline
nderlineWeight	number	underline stroke weight
nderlineOffset	number	distance of underline to type
nderlineColor	string / color()	set color of underline
nderlineType	string	common name for strokestyle