

Cisco 642-648



Deploying Cisco ASA VPN Solutions (VPN v2.0)

Version: 6.0

QUESTION NO: 1

Which statement is correct concerning the trusted network detection (TND) feature?

- A.** The Cisco AnyConnect 3.0 Client supports TND on Windows, Mac, and Linux platforms.
- B.** With TND, one result of a Cisco Secure Desktop basic scan on an endpoint is to determine whether a device is a member of a trusted or an untrusted network.
- C.** If enabled, and a CSD scan determines that a host is a member of an untrusted network, an administrator can configure the TND feature to prohibit an end user from launching the Cisco AnyConnect VPN Client.
- D.** When the user is inside the corporate network, TND can be configured to automatically disconnect a Cisco AnyConnect session.

Answer: D

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect25/administration/guide/ac03features.html

Trusted Network Detection

Trusted Network Detection (TND) gives you the ability to have AnyConnect automatically disconnect a VPN connection when the user is inside the corporate network (the trusted network) and start the VPN connection when the user is outside the corporate network (the untrusted network). This feature encourages greater security awareness by initiating a VPN connection when the user is outside the trusted network.

If AnyConnect is also running Start Before Logon (SBL), and the user moves into the trusted network, the SBL window displayed on the computer automatically closes.

TND does not interfere with the ability of the user to manually establish a VPN connection. It does not disconnect a VPN connection that the user starts manually in the trusted network. TND only disconnects the VPN session if the user first connects in an untrusted network and moves into a trusted network. For example, TND disconnects the VPN session if the user makes a VPN connection at home and then moves into the corporate office.

Because the TND feature controls the AnyConnect GUI and automatically initiates connections, the GUI should run at all times. If the user exits the GUI, TND does not automatically start the VPN connection.

You configure TND in the AnyConnect profile. No changes are required to the ASA configuration.

QUESTION NO: 2

Refer to the exhibit.

VPN Client | Certificate Enrollment

Choose a certificate enrollment type: "*" denotes a required field:

☒ Online

Certificate Authority: <New>

CA URL*: http://ca.abc.com/certsrv/mscep/mscep.dll

CA Domain: abc.com

Challenge Password: xxxxxxxx

☐ File

File encoding: Binary

Filename*:

New Password:

Next Cancel

You are configuring a laptop with the Cisco VPN Client, which uses digital certificates for authentication.

Which protocol does the Cisco VPN Client use to retrieve the digital certificate from the CA server?

- A. FTP
- B. LDAP
- C. HTTPS
- D. SCEP
- E. OCSP

Answer: D

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa80/configuration/guide/cert_cfg.html

About CRLs

Certificate Revocation Lists provide the security appliance with one means of determining whether a certificate that is within its valid time range has been revoked by its issuing CA. CRL configuration is a part of the configuration of a trustpoint.

You can configure the security appliance to make CRL checks mandatory when authenticating a

certificate(revocation-check crl command). You can also make the CRL check optional by adding the none argument(revocation-check crl none command), which allows the certificate authentication to succeed when the CA is unavailable to provide updated CRL data. The security appliance can retrieve CRLs from CAs using HTTP, SCEP, or LDAP. CRLs retrieved for each trustpoint are cached for a length of time configurable for each trustpoint. When the security appliance has cached a CRL for more than the length of time it is configured to cache CRLs, the security appliance considers the CRL too old to be reliable, or "stale". The security appliance attempts to retrieve a newer version of the CRL the next time a certificate authentication requires checking the stale CRL.

QUESTION NO: 3

When using clientless SSL VPN, you might not want some applications or web resources to go through the Cisco ASA appliance. For these application and web resources, as a Cisco ASA administrator, which configuration should you use?

- A. Configure the Cisco ASA appliance for split tunneling.
- B. Configure network access exceptions in the SSL VPN customization editor.
- C. Configure the Cisco ASA appliance to disable content rewriting.
- D. Configure the Cisco ASA appliance to enable URL Entry bypass.
- E. Configure smart tunnel to bypass the Cisco ASA appliance proxy function.

Answer: C

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa80/asdm60/user/guide/vpn_web.html

Content Rewrite


The Content Rewrite pane lists all applications for which content rewrite is enabled or disabled. Clientless SSL VPN processes application traffic through a content transformation/rewriting engine that includes advanced elements such as JavaScript, VBScript, Java, and multi-byte characters to proxy HTTP traffic which may have different semantics and access control rules depending on whether the user is using an application within or independently of an SSL VPN device.

By default, the security appliance rewrites, or transforms, all clientless traffic. You might not want some applications and web resources (for example, public websites) to go through the security appliance. The security appliance therefore lets you create rewrite rules that let users browse certain sites and applications without going through the security appliance. This is similar to split-tunneling in an IPSec VPN connection.

You can create multiple rewrite rules. The rule number is important because the security appliance searches rewrite rules by order number, starting with the lowest, and applies the first rule that matches.

QUESTION NO: 4

Refer to the exhibit.



The "level_2" digital certificate was installed on a laptop.

What can cause an "invalid not active" status message?

- A. On first use, a CA server-supplied passphrase is entered to validate the certificate.
- B. A "newly installed" digital certificate does not become active until it is validated by the peer device upon its first usage.
- C. The user has not clicked the Verify button within the Cisco VPN Client.
- D. The CA server and laptop PC clocks are out of sync.

Answer: D

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa80/configuration/guide/cert_cfg.html

Certificates have a date and time that they become valid and that they expire. When the security appliance enrolls with a CA and gets a certificate, the security appliance checks that the current time is within the valid range for the certificate. If it is outside that range, enrollment fails. Same would apply to communication between ASA and PC

QUESTION NO: 5

Refer to the exhibit.

VPN Client | Create New VPN Connection Entry

Connection Entry:

Description:

Host:

Authentication | Transport | Backup Servers | Dial-Up

☒ Group Authentication ☐ Mutual Group Authentication

Name:

Password:

Confirm Password:

☐ Certificate Authentication

Name:

☐ Send CA Certificate Chain

A NOC engineer is in the process of entering information into the Create New VPN Connection Entry fields.

Which statement correctly describes how to do this?

- A.** In the Connection Entry field, enter the name of the connection profile as it is specified on the Cisco ASA appliance.
- B.** In the Host field, enter the IP address of the remote client device.

C. In the Authentication tab, click the Group Authentication or Mutual Group Authentication radio button to enable symmetrical pre-shared key authentication.

D. In the Name field, enter the name of the connection profile as it is specified on the Cisco ASA appliance.


Answer: D

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/cisco_vpn_client/vpn_client46/win/user/guide/vc4.html#wp1074766

Step 1 Start the VPN Client by choosing Start > Programs > Cisco Systems VPN Client > VPN Client.

Step 2 The VPN Client application starts and displays the advanced mode main window (Figure 4-1). If you are not already there, open the Options menu in simple mode and choose Advanced Mode or press Ctrl-M.



C:\Documents and Settings\user-nwz\Desktop\1.JPG

Step 3 Select New from the toolbar or the Connection Entries menu. The VPN Client displays a form



VPN Client | Properties for "10.86.194.173"

Connection Entry:

Description:

Host:

Authentication | Transport | Backup Servers | Dial-Up

☐ Group Authentication ☒ Mutual Group Authentication

Name:

Password:

Confirm Password:

☐ Certificate Authentication

Name:

☐ Send CA Certificate Chain

C:\Documents and Settings\user-nwz\Desktop\1.JPG

Step 4 Enter a unique name for this new connection. You can use any name to identify this connection; for example, Engineering. This name can contain spaces, and it is not case-sensitive.

Step 5 Enter a description of this connection. This field is optional, but it helps further identify this connection.

For example, Connection to Engineering remote server.

Step 6 Enter the hostname or IP address of the remote VPN device you want to access.

Group Authentication

Your network administrator usually configures group authentication for you. If this is not the case, use the following procedure:

Step 1 Click the Group Authentication radio button.


Step 2 In the Name field, enter the name of the IPsec group to which you belong. This entry is case-sensitive.

Step 3 In the Password field, enter the password (which is also case-sensitive) for your IPsec group. The field displays only asterisks.

Step 4 Verify your password by entering it again in the Confirm Password field.

QUESTION NO: 6

Refer to the exhibit.



A new NOC engineer is troubleshooting a VPN connection.

Which statement about the fields within the Cisco VPN Client Statistics screen is correct?

- A.** The ISP-assigned IP address of 10.0.21.1 is assigned to the VPN adapter of the PC.
- B.** The IP address of the security appliance to which the Cisco VPN Client is connected is 192.168.1.2.
- C.** CorpNet is the name of the Cisco ASA group policy whose tunnel parameters the connection is using.
- D.** The ability of the client to send packets transparently and unencrypted through the tunnel for test purposes is turned off.
- E.** With split tunneling enabled, the Cisco VPN Client registers no decrypted packets.

Answer: B

Explanation:

QUESTION NO: 7

An XYZ Corporation systems engineer, while making a sales call on the ABC Corporation headquarters, tried to access the XYZ sales demonstration folder to transfer a demonstration via FTP from an ABC conference room behind the firewall. The engineer could not reach XYZ through the remote-access VPN tunnel. From home the previous day, however, the engineer did connect to the XYZ sales demonstration folder and transferred the demonstration via IPsec over DSL.

To get the connection to work and transfer the demonstration, what should the engineer do?

- A.** Change the MTU size on the IPsec client to account for the change from DSL to cable transmission.
- B.** Enable the local LAN access option on the IPsec client.
- C.** Enable the IPsec over TCP option on the IPsec client.
- D.** Enable the clientless SSL VPN option on the PC.

Answer: C

Explanation:

IP Security (IPSec) over Transmission Control Protocol (TCP) enables a VPN Client to operate in an environment in which standard Encapsulating Security Protocol (ESP, Protocol 50) or Internet Key Exchange (IKE, User Datagram Protocol (UDP) 500) cannot function, or can function only with modification to existing firewall rules. IPSec over TCP encapsulates both the IKE and IPSec protocols within a TCP packet, and it enables secure tunneling through both Network Address Translation (NAT) and Port Address Translation (PAT) devices and firewalls.

QUESTION NO: 8

Refer to the exhibit.

Priority: 7

Perfect Forward Secrecy: ☒ Disable ☐ Enable
Diffie-Hellman Group: [Dropdown]

NAT-T: ☒ Enable

Reverse Route Injection: ☒ Enable

Security Association Lifetime

Time: 8 : 0 : 0 hh:mm:ss

Traffic Volume: 4608000 KBytes

Static Crypto Map Entry Parameters

Connection Type: originate-only (IKE v2 supports bidirectional only)

Pre-shared Key (for IKEv2): [Text Field]

Device Certificate: -- None --

☐ Send CA Certificate Chain

IKE Negotiation Mode: ☒ Main ☐ Aggressive (Only IKE v1 supports IKE Negotiation Mode)

Diffie-Hellman Group: [Dropdown]

While configuring a site-to-site VPN tunnel, a new NOC engineer encounters the Reverse Route Injection parameter.

Assuming that static routes are redistributed by the Cisco ASA to the IGP, what effect does enabling Reverse Route Injection on the local Cisco ASA have on a configuration?

- A. The local Cisco ASA advertises its default routes to the distant end of the site-to-site VPN tunnel.
- B. The local Cisco ASA advertises routes from the dynamic routing protocol that is running on the local Cisco ASA to the distant end of the site-to-site VPN tunnel.
- C. The local Cisco ASA advertises routes that are at the distant end of the site-to-site VPN tunnel.
- D. The local Cisco ASA advertises routes that are on its side of the site-to-site VPN tunnel to the distant end of the site-to-site VPN tunnel.

Answer: C

Explanation:

http://www.cisco.com/en/US/products/ps6120/products_configuration_example09186a00809d07de.shtml

QUESTION NO: 9

Refer to the exhibit.

```
ASA5520# show vpn-session anyconnect
Username       : engineer1           Index       : 76
Assigned IP    : 10.0.4.80           Public IP   : 172.26.26.15
Protocol       : Clientless SSL-Tunnel DTLS-Tunnel
License        : AnyConnect Premium
Encryption     : RC4 AES128          Hashing     : SHA1
Bytes Tx       : 63506               Bytes Rx    : 17216
Group Policy   : engineering         Tunnel Group : contractor
Login Time     : 11:35:57 UTC Thu Jul 1 2011
Duration       : 0h:01m:52s
Inactivity     : 0h:00m:00s
NAC Result     : Unknown
VLAN Mapping   : Static              VLAN        : 100
```

A NOC engineer needs to tune some prelogin parameters on an SSL VPN tunnel.

From the information that is shown, where should the engineer navigate to find the prelogin session attributes?

- A. "engineering" Group Policy
- B. "contractor" Connection Profile
- C. "engineer1" AAA/Local Users
- D. DfltGrpPolicy Group Policy

Answer: B

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect30/administration/guide/ac05hostscanposture.html#wp1039696

QUESTION NO: 10

Refer to the exhibit.


```
ASA5520# show vpn-session anyconnect
Username       : engineer1           Index       : 76
Assigned IP    : 10.0.4.80           Public IP    : 172.26.26.15
Protocol       : Clientless SSL-Tunnel DTLS-Tunnel
License        : AnyConnect Premium
Encryption     : RC4 AES128          Hashing      : SHA1
Bytes Tx       : 63506               Bytes Rx     : 17216
Group Policy   : engineering          Tunnel Group : contractor
Login Time     : 11:35:57 UTC Thu Jul 1 2011
Duration       : 0h:01m:52s
Inactivity     : 0h:00m:00s
NAC Result     : Unknown
VLAN Mapping   : Static              VLAN         : 100
```

A NOC engineer needs to tune some postlogin parameters on an SSL VPN tunnel.

From the information shown, where should the engineer navigate to, in order to find all the postlogin session parameters?

- A. "engineering" Group Policy
- B. "contractor" Connection Profile
- C. DefaultWEBVPNGroup Group Policy
- D. DefaultRAGroup Group Policy
- E. "engineer1" AAA/Local Users

Answer: A

Explanation:

http://www.cisco.com/en/US/docs/ios/12_4t/12_4t11/htwebvpn.html#wp1054618

The policy group is a container that defines the presentation of the portal and the permissions for resources that are configured for a group of remote users. Entering the policy group command places the router in webvpn group policy configuration mode. After it is configured, the group policy is attached to the SSL VPN context configuration by configuring the default-group-policy command.

The following tasks are accomplished in this configuration:

QUESTION NO: 11

Refer to the exhibit.

Login

Please enter your username and password.

GROUP: contractor ▼

USERNAME:

PASSWORD:

For the ABC Corporation, members of the NOC need the ability to select tunnel groups from a drop-down menu on the Cisco WebVPN login page.

As the Cisco ASA administrator, how would you accomplish this task?

- A.** Define a special identity certificate with multiple groups, which are defined in the certificate OU field, that will grant the certificate holder access to the named groups on the login page.
- B.** Under Group Policies, define a default group that encompasses the required individual groups that will appear on the login page.
- C.** Under Connection Profiles, define a NOC profile that encompasses the required individual profiles that will appear on the login page.
- D.** Under Connection Profiles, enable "Allow user to select connection profile."

Answer: D

Explanation:

Cisco ASDM User Guide Version 6.1

Add or Edit SSL VPN Connections > Advanced > SSL VPN

This dialog box lets you configure attributes that affect what the remote user sees upon login.

Fields • LoginPage Customization—Configures the look and feel of the user login page by specifying which predefined customization attributes to apply. The default is DfltCustomization. • Manage—Opens the Configure GUI Customization Objects window. • Connection Aliases—Lists in a table the existing connection aliases and their status and lets you add or delete items in that table. A connection alias appears on the user login page if the connection is configured to allow users to select a particular connection (tunnel group) at login. – Add—Opens the Add Connection Alias window, on which you can add and enable a connection alias. – Delete—Removes the selected row from the connection alias table. There is no confirmation or undo. • Group

URLs—Lists in a table the existing group URLs and their status and lets you add or delete items in that table. A group URL appears on the user login page if the connection is configured to allow users to select a particular group to login. – Add—Opens the Add Group URL window, on which you can add and enable a group URL. – Delete—Removes the selected row from the connection alias table. There is no confirmation or undo.

QUESTION NO: 12

Refer to the exhibit.

```
access-list temp_acl webtype permit url http://10.0.4.10
webvpn
enable outside
svc enable
tunnel-group-list enable
group-policy temp_worker internal
group-policy temp_worker attributes
banner value Welcome Temp Workers!
vpn-tunnel-protocol webvpn
vlan 100
webvpn
url-list value Corporate_Server
url-entry disable
group-policy Default attributes
vpn-tunnel-protocol IPSec svc webvpn
webvpn
url-list value Corporate_Server
filter value temp_acl
username temp1 password cisco
```

```
username temp1 attributes
vpn-group-policy temp_worker
vpn-tunnel-protocol webvpn
group-lock value temp_worker
service-type remote-access
webvpn
file-browsing disable
file-entry enable
url-entry disable
hidden-shares none
url-list value Corporate_Server
customization value temp_worker
tunnel-group temp_worker type remote-access
tunnel-group temp_worker general-attributes
default-group-policy temp_worker
tunnel-group temp_worker webvpn-attributes
customization temp_worker
group-alias temp_worker enable
group-url https://192.168.4.2/temp_worker enable
```

A junior network engineer configured the corporate Cisco ASA appliance to accommodate a new temporary worker. For security reasons, the IT department wants to restrict the internal network access of the new temporary worker to the corporate server, with an IP address of 10.0.4.10. After the junior network engineer finished the configuration, an IT security specialist tested the account of the temporary worker. The tester was able to access the URLs of additional secure servers from the WebVPN user account of the temporary worker.

What did the junior network engineer configure incorrectly?

- A. The ACL was configured incorrectly.
- B. The ACL was applied incorrectly or was not applied.
- C. Network browsing was not restricted on the temporary worker group policy.
- D. Network browsing was not restricted on the temporary worker user policy.

Answer: B

Explanation:

QUESTION NO: 13

Your corporate finance department purchased a new non-web-based TCP application tool to run on one of its servers. Certain finance employees need remote access to the software during nonbusiness hours. These employees do not have "admin" privileges to their PCs.

What is the correct way to configure the SSL VPN tunnel to allow this application to run?

- A.** Configure a smart tunnel for the application.
- B.** Configure a "finance tool" VNC bookmark on the employee clientless SSL VPN portal.
- C.** Configure the plug-in that best fits the application.
- D.** Configure the Cisco ASA appliance to download the Cisco AnyConnect SSL VPN Client to the finance employee each time an SSL VPN tunnel is established.

Answer: A

Explanation:

<http://www.cisco.com/en/US/docs/security/asa/asa80/configuration/guide/webvpn.html>

A smart tunnel is a connection between a TCP-based application and a private site, using a clientless (browserbased)SSL VPN session with the security appliance as the pathway, and the security appliance as a proxyserver. You can identify applications to which you want to grant smart tunnel access, and specify the local path to each application. For applications running on Microsoft Windows, you can also require a match of the SHA-1 hash of the checksum as a condition for granting smart tunnel access.

Lotus SameTime and Microsoft Outlook Express are examples of applications to which you might want to grant smart tunnel access.

Configuring smart tunnels requires one of the following procedures, depending on whether the application is a client or is a web-enabled application:

- Create one or more smart tunnel lists of the client applications, then assign the list to the group policies or local user policies for whom you want to provide smart tunnel access.
- Create one or more bookmark list entries that specify the URLs of the web-enabled applications eligible for smart tunnel access, then assign the list to the DAPs, group policies, or local user policies for whom you want to provide smart tunnel access.

You can also list web-enabled applications for which to automate the submission of login credentials in smart tunnel connections over clientless SSL VPN sessions.

Why Smart Tunnels?

Smart tunnel access lets a client TCP-based application use a browser-based VPN connection to connect to a service. It offers the following advantages to users, compared to plug-ins and the legacy technology, port forwarding:

- Smart tunnel offers better performance than plug-ins.
 - Unlike port forwarding, smart tunnel simplifies the user experience by not requiring the user connection of the local application to the local port.
 - Unlike port forwarding, smart tunnel does not require users to have administrator privileges.
- The advantage of a plug-in is that it does not require the client application to be installed on the remote computer.

Smart Tunnel Requirements, Restrictions, and Limitations

The following sections categorize the smart tunnel requirements and limitations.

General Requirements and Limitations

Smart tunnel has the following general requirements and limitations:

- The remote host originating the smart tunnel must be running a 32-bit version of Microsoft Windows Vista, Windows XP, or Windows 2000; or Mac OS 10.4 or 10.5.
- Smart tunnel auto sign-on supports only Microsoft Internet Explorer on Windows.
- The browser must be enabled with Java, Microsoft ActiveX, or both.
- Smart tunnel supports only proxies placed between computers running Microsoft Windows and the security appliance. Smart tunnel uses the Internet Explorer configuration (that is, the one intended for system-wide use in Windows). If the remote computer requires a proxy server to reach the security appliance, the URL of the terminating end of the connection must be in the list of URLs excluded from proxy services. If the proxy configuration specifies that traffic destined for the ASA goes through a proxy, all smart tunnel traffic goes through the proxy.

In an HTTP-based remote access scenario, sometimes a subnet does not provide user access to the VPN gateway. In this case, a proxy placed in front of the ASA to route traffic between the web and the end user's location provides web access. However, only VPN users can configure proxies placed in front of the ASA.

When doing so, they must make sure these proxies support the CONNECT method. For proxies that require authentication, smart tunnel supports only the basic digest authentication type.

- When smart tunnel starts, the security appliance by default passes all browser traffic through the VPN session if the browser process is the same. The security appliance also does this if a tunnel-all policy applies. If the user starts another instance of the browser process, it passes all traffic through the VPN session. If the browser process is the same and the security appliance does not provide access to a URL, the user cannot open it. As a workaround, assign a tunnel policy that is not tunnel-all.

- A stateful failover does not retain smart tunnel connections. Users must reconnect following a failover.

QUESTION NO: 14

Which statement about plug-ins is false?

- A. Plug-ins do not require any installation on the remote system.
- B. Plug-ins require administrator privileges on the remote system.
- C. Plug-ins support interactive terminal access.
- D. Plug-ins are not supported on the Windows Mobile platform.

Answer: B

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa80/asdm60/ssl_vpn_deployment_guide/deployhtml#wp1162435

Plug-ins

The security appliance supports Java plug-ins for clientless SSL VPN connections. Plug-ins are Java programs that operate in a browser. These plug-ins include SSH/Telnet, RDP, VNC, and Citrix.

Per the GNU General Public License (GPL), Cisco redistributes plug-ins without making any changes to them.

Per the GPL, Cisco cannot directly enhance these plug-ins.

To use plug-ins you must install Java Runtime Environment (JRE) 1.4.2.x or greater. You must also use a compatible browser specified

here: <http://www.cisco.com/en/US/docs/security/asa/compatibility/asa-vpncompatibility.html>

QUESTION NO: 15

A temporary worker must use clientless SSL VPN with an SSH plug-in, in order to access the console of an internal corporate server, the projects.xyz.com server. For security reasons, the network security auditor insists that the temporary user is restricted to the one internal corporate server, 10.0.4.18. You are the network engineer who is responsible for the network access of the temporary user.

What should you do to restrict SSH access to the one projects.xyz.com server?

- A. Configure access-list temp_user_acl extended permit TCP any host 10.0.4.18 eq 22.
- B. Configure access-list temp_user_acl standard permit host 10.0.4.18 eq 22.
- C. Configure access-list temp_acl webtype permit url ssh://10.0.4.18.

D. Configure a plug-in SSH bookmark for host 10.0.4.18, and disable network browsing on the clientless SSL VPN portal of the temporary worker.

Answer: C

Explanation:

Web ACLs

The Web ACLs table displays the filters configured on the security appliance applicable to Clientless SSL VPN traffic. The table shows the name of each access control list (ACL), and below and indented to the right of the ACL name, the access control entries (ACEs) assigned to the ACL. Each ACL permits or denies access to specific networks, subnets, hosts, and web servers. Each ACE specifies one rule that serves the function of the ACL. You can configure ACLs to apply to Clientless SSL VPN traffic. The following rules apply:

- If you do not configure any filters, all connections are permitted.
- The security appliance supports only an inbound ACL on an interface.
- At the end of each ACL, an implicit, unwritten rule denies all traffic that is not explicitly permitted. You can use the following wildcard characters to define more than one wildcard in the Webtype access list entry:

- Enter an asterisk "*" to match no characters or any number of characters.
- Enter a question mark "?" to match any one character exactly.
- Enter square brackets "[]" to create a range operator that matches any one character in a range. The following examples show how to use wildcards in Webtype access lists.
- The following example matches URLs such as `http://www.cisco.com/` and `http://www.caco.com/`:
`access-list test webtype permit url http://ww?.c*co*/`

QUESTION NO: 16

Authorization of a clientless SSL VPN defines the actions that a user may perform within a clientless SSL VPN session. Which statement is correct concerning the SSL VPN authorization process?

- A.** Remote clients can be authorized by applying a dynamic access policy, which is configured on an external AAA server.
- B.** Remote clients can be authorized externally by applying group parameters from an external database.
- C.** Remote client authorization is supported by RADIUS and TACACS+ protocols.
- D.** To configure external authorization, you must configure the Cisco ASA for cut-through proxy.

Answer: B

Explanation:

CISCO SSL VPN guide

The `aaa authentication` command is entered to specify an authentication list or server group under

aSSL VPN context configuration. If this command is not configured and AAA is configured globally on the router, global authentication will be applied to the context configuration.

The database that is configured for remote-user authentication on the SSL VPN gateway can be a local database, or the database can be accessed through any RADIUS or TACACS+ AAA server. We recommend that you use a separate AAA server, such as a Cisco Access Control Server (ACS). A separate AAA server provides a more robust security solution. It allows you to configure unique passwords for each remote user and accounting and logging for remote-user sessions.

QUESTION NO: 17

After adding a remote-access IPsec tunnel via the VPN wizard, an administrator needs to tune the IPsec policy parameters. Where is the correct place to tune the IPsec policy parameters in Cisco ASDM?

- A. IPsec user profile
- B. Crypto Map
- C. Group Policy
- D. IPsec Policy
- E. IKE Policy

Answer: B

Explanation:

QUESTION NO: 18

Refer to the exhibit.

%ASA-5-713259: Group = contractor, Username = vpnuser, IP = 172.16.1.20, Session is being torn down. Reason: Phase 2 Mismatch

While troubleshooting a remote-access application, a new NOC engineer received the logging message that is shown in the exhibit.

Which configuration is most likely to be mismatched?

- A. IKE configuration
- B. extended authentication configuration

- C. IPsec configuration
- D. digital certificate configuration

Answer: C

Explanation:

http://www.cisco.com/en/US/tech/tk583/tk372/technologies_tech_note09186a00800949c5.shtml
 d%ASA-5-713259: Group = groupname, Username = username, IP = peerIP,

Session is being torn down. Reason: reason


Explanation The termination reason for the ISAKMP session appears, which occurs when the session is torndown through session management.

- groupname—The tunnel group of the session being terminated
- username—The username of the session being terminated
- peerIP—The peer address of the session being terminated
- reason—The RADIUS termination reason of the session beingterminated. Reasons include thefollowing:

- Port Preempted (simultaneous logins)
- Idle Timeout
- Max Time Exceeded
- Administrator Reset

QUESTION NO: 19

Refer to the exhibit.



The ABC Corporation is changing remote-user authentication from pre-shared keys to certificate-based authentication. For most employee authentication, its group membership (the employees) governs corporate access. Certain management personnel need access to more confidential servers. Access is based on the group and name, such as finance and level_2. When it is time to pilot the new authentication policy, a finance manager is able to access the department-assigned servers but cannot access the restricted servers.

As the network engineer, where would you look for the problem?

- A. Check the validity of the identity and root certificate on the PC of the finance manager.
- B. Change the Management Certificate to Connection Profile Maps > Rule Priority to a number that is greater than 10.
- C. Check if the Management Certificate to Connection Profile Maps > Rules is configured correctly.
- D. Check if the Certificate to Connection Profile Maps > Policy is set correctly.

Answer: D

Explanation:

Cisco ASDM User Guide Version 6.1

To configure the evaluation of IPSec or SSL VPN connections against certificate criteria-based rules, use the IPSec Certificate to Connection Maps > Rules or Certificate to SSL VPN Connections Profile Maps panel.

This panel lets you create the certificate-based criteria for each IPSec and SSL VPN connection profile, as follows:

-
- Step 1** Use the table at the top (Certificate to Connection Profile Maps) to do one of the following:
- Create a list name, called a "map," specify the priority of the list, and assign the list to a connection profile.
ASDM highlights the list after you add it to the table.
 - Confirm that a list is assigned to the connection profile for which you want to add certificate-based rules.
ASDM highlights the list after you add it to the table and displays any associated list entries in the table at the bottom of the pane.
- Step 2** Use the table at the bottom (Mapping Criteria) to view, add, change or delete entries to the selected list. Each entry in the list consists of one certificate-based rule. All of the rules in the mapping criteria list need to match the contents of the certificate for the security appliance to choose the associated map index. To assign a connection if one criterion or another matches, create one list for each matching criterion.
-

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 20

Refer to the exhibit.

Configuration > Remote Access VPN > AAA/Local Users > Local Users

Create entries in the ASA local user database.

Command authorization must be enabled in order for the user account privileges to be enforced. To enable command authorization, go to [Authorization](#).

AAA authentication console commands must be enabled in order for certain access restrictions to be enforced. To enable AAA authentication command go to [Authentication](#).

Username	Privilege Level (Role)	Access Restrictions	VPN Group Policy	VPN Group Lock
employee1	15	Full	employee	-- Inherit Group Polic...
manager1	2	No ASDM/CLI	management	-- Inherit Group Polic...
contractor	15	Full	-- Inherit Group Policy --	-- Inherit Group Polic...
contractor1	2	No ASDM/CLI	new_hire	-- Inherit Group Polic...

Add Edit Delete

The user "contractor" inherits which VPN group policy?

- A. employee
- B. management
- C. DefaultWEBVPNGroup
- D. DfltGrpPolicy
- E. new_hire

Answer: D

Explanation:

QUESTION NO: 21

Refer to the exhibit.

```
access-list outside_cryptomap_1 line 1 extended deny tcp any host 10.0.4.4 eq https
access-list outside_cryptomap_1 line 1 extended permit tcp any host 10.0.4.0 255.255.255.0 eq https
crypto map outside_map 1 match address outside_cryptomap_1
```

In the CLI snippet that is shown, what is the function of the deny option in the access list?


- A. When set in conjunction with outbound connection-type bidirectional, its function is to prevent the specified traffic from being protected by the crypto map entry.
- B. When set in conjunction with connection-type originate-only, its function is to instruct the Cisco ASA to deny specific inbound traffic if it is not encrypted.
- C. When set in conjunction with outbound connection-type answer-only, its function is to instruct the Cisco ASA to deny specific outbound traffic if it is not encrypted.
- D. When set in conjunction with connection-type originate-only, its function is to cause all IP traffic that matches the specified conditions to be protected by the crypto map.

Answer: A

Explanation:

QUESTION NO: 22

Refer to the exhibit.



A new NOC engineer, while viewing a real-time log from an SSL VPN tunnel, has a question about a line in the log.

The IP address 172.26.26.30 is attached to which interface in the network?


- A. the Cisco ASA physical interface
- B. the physical interface of the end user
- C. the Cisco ASA SSL VPN tunnel interface
- D. the SSL VPN tunnel interface of the end user

Answer: B

Explanation:

QUESTION NO: 23

Refer to the exhibit.



When the user "contractor" Cisco AnyConnect tunnel is established, what type of Cisco ASA user restrictions are applied to the tunnel?

- A. full restrictions (no Cisco ASDM, no CLI, no console access)
- B. full restrictions (no read, no write, no execute permissions)
- C. full restrictions (CLI show commands and Cisco ASDM monitoring permissions only)
- D. full access with no restrictions

Answer: D

Explanation:

QUESTION NO: 24

Which statement regarding hashing is correct?

- A. MD5 produces a 64-bit message digest.
- B. SHA-1 produces a 160-bit message digest.
- C. MD5 takes more CPU cycles to compute than SHA-1.
- D. Changing 1 bit of the input to SHA-1 can change up to 5 bits in the output.

Answer: B

Explanation:

QUESTION NO: 25

When initiating a new SSL or TLS session, the client receives the server SSL certificate and validates it. After validating the server certificate, what does the client use the certificate for?

- A. The client and server use the server public key to encrypt the SSL session data.
- B. The server creates a separate session key and sends it to the client. The client decrypts the

session key by using the server public key.

C. The client and server switch to a DH key exchange to establish a session key.

D. The client generates a random session key, encrypts it with the server public key, and then sends it to the server.

Answer: D

Explanation:

QUESTION NO: 26

When attempting to tunnel FTP traffic through a stateful firewall that might be performing NAT or PAT, which type of VPN tunneling should you use to allow the VPN traffic through the stateful firewall?

A. clientless SSL VPN

B. IPsec over TCP

C. smart tunnel

D. SSL VPN plug-ins

Answer: B

Explanation:

IP Security (IPSec) over Transmission Control Protocol (TCP) enables a VPN Client to operate in an environment in which standard Encapsulating Security Protocol (ESP, Protocol 50) or Internet Key Exchange (IKE, User Datagram Protocol (UDP) 500) cannot function, or can function only with modification to existing firewall rules. IPSec over TCP encapsulates both the IKE and IPSec protocols within a TCP packet, and it enables secure tunneling through both Network Address Translation (NAT) and Port Address Translation (PAT) devices and firewalls.

QUESTION NO: 27

Refer to the exhibit.

"ASA-5-722006: Group (contractor) User (vpnuser) IP (172.16.1.20) Invalid address (0.0.0.0)" assigned to SVC connection.

While troubleshooting on a remote-access VPN application, a new NOC engineer received the message that is shown.

What is the most likely cause of the problem?

- A.** The IP address that is assigned to the PC of the VPN user is not within the range of addresses that are assigned to the SVC connection.
- B.** The IP address that is assigned to the PC of the VPN user is in use. The remote user needs to select a different host address within the range.
- C.** The IP address that is assigned to the PC of the VPN user is in the wrong subnet. The remote user needs to select a different host number within the correct subnet.
- D.** The IP address pool for contractors was not applied to their connection profile.

Answer: D

Explanation:

%ASA-5-722006: Group group User user-name IP IP_address Invalid address
IP_address assigned to SVC connection.

Explanation An invalid address was assigned to the user.

Recommended Action Verify and correct the address assignment, if possible.

QUESTION NO: 28

What is a valid reason for configuring a list of backup servers on the Cisco AnyConnect VPN Client profile?

- A.** to access a backup authentication server
- B.** to access a backup DHCP server
- C.** to access a backup VPN server
- D.** to access a backup CA server

Answer: C

Explanation:

QUESTION NO: 29

Which statement about CRL configuration is correct?

- A.** CRL checking is enabled by default.
- B.** The Cisco ASA relies on HTTPS access to procure the CRL list.
- C.** The Cisco ASA relies on LDAP access to procure the CRL list.
- D.** The Cisco Secure ACS can be configured as the CRL server.


Answer: C

Explanation:

ASA SSLVPN deployment guide:

The security appliance supports various authentication methods: RSA one-time passwords, Radius,

Kerberos, LDAP, NT Domain, TACACS, Local/Internal, digital certificates, and a combination of both authentication and certificates.



C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 30

You have been using pre-shared keys for IKE authentication on your VPN. Your network has grown rapidly, and now you need to create VPNs with numerous IPsec peers. How can you enable scaling to numerous IPsec peers?

- A. Migrate to external CA-based digital certificate authentication.
- B. Migrate to a load-balancing server.
- C. Migrate to a shared license server.
- D. Migrate from IPsec to SSL VPN client extended authentication.

Answer: A

Explanation:

QUESTION NO: 31

When preconfiguring a Cisco AnyConnect profile for the user group, which file is output by the Cisco AnyConnect profile editor?

- A. user.ini
- B. user.html
- C. user.pcf
- D. user.xml

Answer: D

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect30/administration/guide/ac02asaconfig.html

QUESTION NO: 32

Which Cisco ASA SSL VPN feature provides support for PCI compliance by allowing for the validation of two sets of username and password credentials on the SSL VPN login page?


- A. Single Sign-On
- B. Certificate to Profile Mapping
- C. Double Authentication
- D. RSA OTP

Answer: C

Explanation:

QUESTION NO: 33

Refer to the exhibit.



In the Edit Certificate Matching Rule Criterion window, you want to change the Mapped to Connection Profile. However, you cannot perform that action from this window.

Where should you navigate to and what should you do, in order to perform this change?

- A. Edit the entry in the Certificate Management window.
- B. Edit the entry in the Connection Profiles window.
- C. Edit the entry in the Certificate to Connection Profile Maps window.
- D. Edit the entry in IKE Policies window.
- E. Delete this entry in the Mapping Criteria window, and add a new entry in the same location.

Answer: C

Explanation:

QUESTION NO: 34

Which statement is correct regarding IKEv2 when implementing IPsec site-to-site VPNs?

- A. IKEv2 should be configured with a higher priority over IKEv1 policies within the same tunnel group.
- B. IKEv2 crypto maps can be configured to inherit IKEv1 parameters, if configured.
- C. IKE v1 and IKEv2 can coexist in the same tunnel group, with fallback to IKEv1 if the remote endpoint does not support IKEv2.

D. IKEv2 can be configured to support multiple peers.

Answer: C

Explanation:

QUESTION NO: 35

Which feature is supported when implementing an IPsec VPN configuration using IKEv2?

- A. IKEv2 authentication can be configured to negotiate authentication modes within the IKE policy when using Cisco ASDM.
- B. IKEv2 proposals are identical to IKEv1 policies.
- C. When implementing IKEv2 with a site-to-site VPN, authentication parameters should contain a fallback to PSKs, in case certificate-based authentication fails.
- D. IKEv2 peer authentication can be implemented with asymmetric authentication methods.

Answer: D

Explanation:

QUESTION NO: 36

Refer to the exhibit.

```
%ASA-5-713257: Phase 1 failure: Mismatched attribute types for class Group
Description: Rcv'd: Group 2 Cfg'd: Group 1
%ASA-7-713236: IP = 192.168.1.1, IKE_DECODE SENDING Message (msgid=0) with
payloads : HDR + NOTIFY (11) + NONE (0) total length : 132
%ASA-7-713906: IP = 192.168.1.1, All SA proposals found unacceptable
```

What is the likely cause of the failure?

- A. A msgid of 0 signifies a zero payload, indicating that the peer did not send any IKE proposals.
- B. The remote peer did not respond to the 11 notifications that were sent by the originating IPsec endpoint.
- C. There are mismatched IKE policies.
- D. There are mismatched tunnel groups.

Answer: C

Explanation:

%ASA-5-713257: Phase var1 failure: Mismatched attribute types for class var2: Rcv'd: var3 Cfg'd: var4

Explanation An adaptive security appliance has acted as the responder in a LAN-to-LAN connection. It indicates that the adaptive security appliance crypto configuration does not match the configuration of the initiator. The message specifies during which phase the mismatch occurred, and which attributes both the responder and the initiator had that were different.

- var1—The phase during which the mismatch occurred
- var2—The class to which the attributes that do not match belong
- var3—The attribute received from the initiator
- var4—The attribute configured

QUESTION NO: 37

When troubleshooting a site-to-site IPsec VPN deployment, you see a QM FSM message. What is the most likely cause of this message?

- A.** The Quick Mode timers have expired.
- B.** There are mismatched proxy identities.
- C.** Forward Secrecy Mode has failed.
- D.** IKE Phase 1 has failed authentication due to mismatched DH groups.

Answer: B**Explanation:**

http://www.cisco.com/en/US/tech/tk583/tk372/technologies_tech_note09186a00800949c5.shtml#qms

QM FSM Error


The IPsec L2L VPN tunnel does not come up on the PIX firewall or ASA, and the QM FSM error message appears.

One possible reason is the proxy identities, such as interesting traffic, access control list (ACL) or crypto ACL, do not match on both the ends. Check the configuration on both the devices, and make sure that the crypto ACLs match.

Another possible reason is mismatching of the transform set parameters. Make sure that at both ends, VPN gateways use the same transform set with the exact same parameters.

QUESTION NO: 38

Refer to the exhibit.



You are the network security administrator. You have received calls from site-to-site IPsec VPN users saying that they cannot connect into the network. In troubleshooting this problem, you discover that some sites can connect, but other sites cannot. It is not always the same sites experiencing problems. You suspect that the permitted number of simultaneous logins has been reached and needs to be increased.

In which configuration window or tab should you accomplish this task?

- A. in the IKE Policies window
- B. in the IKE Parameters window
- C. in the System Options window
- D. in the Device Management tab

Answer: C

Explanation:

Limit the maximum number of active IPsec VPN sessions

—Enables or disables limiting the maximum number of active IPsec VPN sessions. The range depends on the hardware platform and the software license.

– Maximum Active IPsec VPN Sessions—Specifies the maximum number of active IPsec VPN sessions allowed. This field is active only when you select the preceding check box to limit the maximum number of active IPsec VPN sessions.

QUESTION NO: 39

Refer to the exhibit.

```
tunnel-group BASIC-ANYCONNECT-PROFILE general-attributes
 authentication-server-group MY-RADIUS-SVRS
 secondary-authentication-server-group MY-LDAP-SVRS
!
tunnel-group BASIC-ANYCONNECT-PROFILE webvpn-attributes
 authentication aaa
```

Given the example that is shown, what can you determine?

- A. Users are required to perform RADIUS or LDAP authentication when connecting with the Cisco AnyConnect client.
- B. Users are required to perform AAA authentication when connecting via WebVPN.
- C. Users are required to perform double AAA authentication.
- D. The user access identity is prefilled at login, requiring users to enter only their password.

Answer: C

Explanation:

QUESTION NO: 40

You are the network security administrator. You receive a call from a user stating that he cannot log onto the network. In the process of troubleshooting, you determine that this user is accessing the network via certificate-based Cisco AnyConnect SSL VPN.

What is a troubleshooting step that you should perform to determine the cause of the access problem?

- A. Revoke and reissue the certificate, and have the user try again.
- B. Verify that a connection can be made without using certificates.
- C. Ask the user to use IPsec, and test the connection attempts.
- D. Check the WebACLs on the Cisco ASA.

Answer: B

Explanation:

QUESTION NO: 41

When deploying clientless SSL VPNs, what should you do to support external unmanaged VPN clients?

- A. Deploy a private PKI service.
- B. Issue self-signed identity certificates for the external clients that you wish to provide with access to your enterprise.
- C. Configure policies specifically for the clients that have a group userID and password.
- D. Implement a global PKI service.

Answer: D

Explanation:

QUESTION NO: 42

Which option limits a clientless SSL VPN user to specific resources upon successful login?

- A. modify the Cisco ASA Modular Policy Framework access control
- B. user-defined bookmarks
- C. RADIUS authorization
- D. disable portal features

Answer: B

Explanation:

Effective with Cisco IOS Release 12.4(15)T, users can bookmark URLs while connected through an SSLVPN tunnel. Users can access the bookmarked URLs by clicking the URLs. User-level bookmarking is turned by default. There is no way to turn it off. To set the storage location, administrators can use the user-profile location command. If the user-profile location

command is not configured, the location flash:/webvpn/{context name}/ is used.

QUESTION NO: 43

Some users are having problems connecting via clientless SSL VPN, while other users are experiencing no problems. What is one possible cause of this issue?

- A. The Cisco ASA identity certificates have not been generated.
- B. SSL version checking is enabled, and clients are connecting with denied versions.
- C. SSL VPN termination is not enabled.
- D. The Cisco ASA identity certificate is not bound to the SSL interface.

Answer: B

Explanation:

http://www.cisco.com/web/about/security/intelligence/05_08_SSL-VPN-Security.html

Host identity verification

There is a difference between trusting a user (after passing strong user authentication) and trusting that user's computer. While the former has traditionally been emphasized, only recently has the latter been given sufficient attention (see Trusted Platform Module - TPM). As discussed earlier, a Trojan-laden computer defeats strong user authentication. But a "company computer", which is typically supported and managed according to corporate security policies, typically deserves more trust than a "non-company computer". A secure SSL VPN infrastructure should allow you to verify a remote host's identity by checking on predefined end device parameters. Examples include registry entries, special files in a specified location, or digital certificates (as a form of device authentication). The host identity information can be used to make your access permission decisions.

QUESTION NO: 44

You have just configured new clientless SSL VPN access parameters.

However, when users connect, they are not getting the expected access that was configured.

What is one possible reason this is occurring?

- A. The correct Tunnel Group Lock is not properly set.
- B. The corresponding Cisco ASA interface is not enabled for SSL VPN access.
- C. The Connection Alias is not enabled.
- D. Portal features are disabled.

Answer: A

Explanation:

QUESTION NO: 45

When a VPN client that is using redundant peering and has obtained an IP address from the primary VPN gateway loses connection to that gateway, how is traffic rerouted?

- A. The secondary VPN gateway automatically routes the traffic back to the client using the same IP address.
- B. Redundant Internet routing protocols reroute the traffic to and from the client and the gateway.
- C. The secondary VPN gateway issues the client a new IP address and routes traffic accordingly.
- D. Traffic flow stops, and the client must reestablish connection. Once connection is established, the same IP address is issued to the client and similarly routed.

Answer: C

Explanation:

QUESTION NO: 46

When configuring dead peer detection for remote-access VPN, what does the confidence level parameter represent?

- A. It specifies the number of seconds the adaptive security appliance should allow a peer to idle before beginning keepalive monitoring.
- B. It specifies the number of seconds to wait between IKE keepalive retries.
- C. The higher the number, the more reliable the link is.
- D. It is determined dynamically based on reliability, uptime, and load.

Answer: A

Explanation:

```
Chicago(config)# crypto map outside_map 10 set connection-type originate-only
```

ISAKMP Keepalives

The ISAKMP keepalives feature is a way to determine whether the remote VPN peer is still reachable or there are any lingering SAs (SAs that do not get cleared properly). By default, Cisco ASA starts sending Dead Peer Detection (DPD) packets after it stops receiving encrypted traffic over the tunnel from the peer. If it does not hear from its peer for 10 seconds (confidence interval), it sends out a DPD R_U_THERE packet. It keeps sending the R_U_THERE packets every 2 seconds (the retry interval). If it does not receive R_U_THERE_ACK for four consecutive DPDs polling periods, the security appliance deletes the corresponding ISAKMP and IPSec SAs.

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 47

Which statement is true regarding Cisco ASA stateful failover?

- A. It is recommended to share the failover link with the inside interface for security purposes.
- B. The failover link is encrypted by default to protect eavesdropping.
- C. VPN users must reauthenticate, even though the connection remains established.
- D. Clientless features, such as smart tunnels and plug-ins, are not supported.

Answer: D

Explanation:

QUESTION NO: 48

Which statement is true about configuring the Cisco ASA for Active/Standby failover?

- A. All versions of Cisco ASA software need to have the same licensing on both devices.
- B. Both devices perform load sharing until a failure occurs.
- C. All VPN-related configurations and files are automatically replicated.
- D. VPN images, profiles, and plug-ins must be manually provisioned to both devices.

Answer: D

Explanation:

QUESTION NO: 49

When configuring the Cisco ASA for VPN clustering, which IP address or addresses does the end-user device connect to?

- A. It connects to individual device addresses of the cluster as provided in the connection profile.
- B. It connects to the virtual address.
- C. The virtual cluster manager sends the IP address of the least loaded device. The client then connects directly to that device.
- D. The connection IP address is dependent upon whether the initiator is using SSL or IPsec.

Answer: B

Explanation:

http://www.cisco.com/en/US/products/ps6120/products_configuration_example09186a00805fda25.shtml

QUESTION NO: 50

You are the network security administrator troubleshooting a clientless SSL VPN issue. Users can connect using SSL VPN, but they cannot access file folder bookmarks that they need.

Which problem could possibly cause this issue?


- A. a name mismatch from the certificate CN and the VPN URL
- B. misconfigured WebType ACLs
- C. disabled content rewriting
- D. disabled portal features

Answer: B

Explanation:

QUESTION NO: 51

Refer to the exhibit.



When an SSL VPN user, contractor1, enters https://192.168.4.2 (the outside address of the Cisco ASA appliance) into the browser, an SSL VPN Login screen appears.

In addition to the information that is contained in the Cisco ASDM configuration screens, what can an administrator determine about the state of the connection after the user clicks the Login button?

- A. The user login will succeed, and an IP address of 10.0.4.120 will be assigned.
- B. The user will be presented with a clientless VPN portal page.
- C. The user login will succeed, but the user will be connected to the "contractor" tunnel group.
- D. The login will fail.

Answer: D

Explanation:

QUESTION NO: 52

Refer to the exhibit.



As the administrator of a Cisco ASA security appliance for remote-access IPsec VPNs, you are assisting a user who has a digital certificate that is configured for the Cisco VPN Client.

Based on the exhibit, what do you do to find the MD5 thumbprint of the "level_2" certificate?

- A. Choose the certificate, then click Status > Certificates from the menu bar.
- B. Choose the certificate, then click the View button.
- C. Choose the certificate, then click Options > Properties from the menu bar.
- D. Choose the certificate, then click the Verify button.

Answer: B

Explanation:

QUESTION NO: 53

Refer to the exhibit.

Session Details					
Username	Group Policy	Protocol	Login Time	Bytes Tx	
IP Address	Connection Profile	Encryption	Duration	Bytes Rx	
contractor	new_hire	Clientless SSL-Tunnel DTL...	15:12:25 UTC Thu Jun 23 2011	4481	
10.0.1.50	contractor	AES128	0h:19m:59s	100576	

Details	ACL
---------	-----

VLAN Mapping Sessions: 1

ID	Type	Local Addr. / Subnet Mask / Protocol / Port	Encryption	Other	Bytes Tx	Bytes Rx
		Remote Addr. / Subnet Mask / Protocol / Port				
	Clientless		RC4	Tunnel ID: 5.1 Public IP: 192.168.2.10 Hashing: SHA1 Encapsulation: TLSv1.0 TCP Dst Port 443 Authentication Mode: Certificate and userPassw. Idle Time Out: 30 Minutes Idle TO Left: 13 Minutes Client Type: Web Browser Client Ver: Mozilla/4.0 (compatible; MSIE 8.0; Wi.	3407780	32170
	SSL-Tunnel		RC4	Tunnel ID: 5.2 Assigned IP 10.0.1.50 Public IP: 192.168.2.10 Hashing: SHA1 Encapsulation: TLSv1.0 TCP Src Port 4760 TCP Dst Port 443 Authentication Mode: Certificate and userPassw. Idle Time Out: 30 Minutes Idle TO Left: 13 Minutes Client Type: SSL VPN Client Client Ver: Cisco AnyConnect VPN Agent for Win. Packets Tx: 3	4481	176

Refresh Close Help

When you are testing SSL VPN in a non-production environment, certain variables in the Cisco ASDM session details can be viewed or changed under Configuration > AnyConnect Connection Profiles.

Which parameter can be viewed or changed in the AnyConnect Connection Profiles?

- A. Assigned IP address 10.0.1.50
- B. Client TypeE. SSL VPN Client
- C. Authentication ModeE. Certificate and User Password
- D. Client Ver: Cisco AnyConnect VPN Agent for Windows

Answer: C

Explanation:

QUESTION NO: 54

In a remote-access VPN solution, on which device or devices can dead peer detection be configured?

- A. remote device
- B. headend device
- C. both headend and remote devices

D. Dead peer detection can be configured only on site-to-site VPN.

Answer: C

Explanation: Dead Peer Detection Dead Peer Detection (DPD) ensures that the security appliance (gateway) or the client can quickly detect a condition where the peer is not responding, and the connection has failed.

Fields

- Gateway Side Detection—Uncheck the Disable check box to specify that DPD is performed by the security appliance (gateway). Enter the interval, from 30 to 3600 seconds, with which the security appliance performs

DPD.

- Client Side Detection—Uncheck the Disable check box to specify that DPD is performed by the client.

Enter the interval, from 30 to 3600 seconds, with which the client performs DPD.

QUESTION NO: 55

A Unified Communications Certificate is used on the Cisco ASA appliance to support which option?

- A.** certificate + double AAA authentication
- B.** certificate + AAA authentication
- C.** certificate maps
- D.** Cisco ASA VPN clustering load balancing

Answer: D

Explanation:

Server Certificate Types

Cisco uses these self-signed (own) certificate types in Cisco Unified Communications Manager servers:

HTTPS certificate (tomcat_cert)—This self-signed root certificate is generated during the Cisco Unified Communications Manager installation for the HTTPS server.

Cisco Unified Communications Manager node certificate—This self-signed root certificate automatically installs when you install Cisco Unified Communications Manager 5.1 for the Cisco Unified Communications Manager server. Cisco Unified Communications Manager certificates provide server identification, which includes the

Cisco Unified Communications Manager server name and the Global Unique Identifier (GUID).

CAPF certificate—The system copies this root certificate to all servers in the cluster after you

complete the Cisco CTL client configuration.

IPsec certificate (ipsec_cert)—This self-signed root certificate is generated during Cisco Unified Communications Manager installation for IPsec connections with MGCP and H.323 gateways.

SRST-enabled gateway certificate—When you configure a secure SRST reference in Cisco Unified

Communications Manager Administration, Cisco Unified Communications Manager retrieves the SRST-enabled gateway certificate from the gateway and stores it in the Cisco Unified Communications Manager database. After you reset the devices, the certificate is added to the phone configuration file. Because the certificate is stored in the database, this certificate is not integrated into the certificate management tool.

<https://supportforums.cisco.com/docs/DOC-5964>

For more information on VPN Load Balancing/Clustering High Availability services of the ASA appliances please consult the configuration guide at

<http://www.cisco.com/en/US/docs/security/asa/asa82/configuration/guide/vpnsysop.html#wp10488>

34. Please check cisco.com for new versions of the document.

For more information on configuring Certificates on the the ASA appliances please consult the configuration guide at

http://www.cisco.com/en/US/docs/security/asa/asa82/configuration/guide/cert_cfg.html

.Please check cisco.com for new versions of the document.

QUESTION NO: 56

In clientless SSL VPN, administrators can control user access to the internal network or resources of a company. What is this control based on?

- A. interface ACLs
- B. WebType ACLs
- C. per-user or per-group ACLs
- D. MPF-configured service policies


Answer: B

Explanation:

Creating WebType ACLs

Web Access control lists (ACLs) filter internet traffic for clientless users. The ACLs table displays the filters configured on the security appliance and the access control entries (ACEs) for each ACL. Each ACL permits or denies access to specific networks, subnets, hosts, and web servers; the ACE specifies one rule for the ACL. To create an ACL, follow these steps:

- Step 1** Navigate to Clientless SSL VPN Access > Advanced > Web ACLs.
- Step 2** Click Add and enter *Engineering* as the ACL name.




- Step 3** Click Add and select Add ACE .

C:\Documents and Settings\user-nw\Desktop\1.JPG

QUESTION NO: 57

Refer to the exhibit.



A new network engineer configured the ABC adaptive security appliance with two bookmarks for a new temporary worker. The temporary worker can connect to the administrator server via the temp_worker_admin bookmark but cannot connect to the project server via the temp_worker_projects bookmark (which is grayed out). It was determined that the URL and IP addressing information in the GUI screens is correct.

What is wrong with the configuration?

- A. URL Entry should be enabled.
- B. The File Server Entry Inherit parameter should be overwritten and set for enabled.
- C. The DNS server information is incorrect.
- D. File Server Browsing should be enabled.

Answer: C

Explanation:

QUESTION NO: 58

Refer to the exhibit.

Certificate to Connection Profile Maps

+ Add Edit Delete

Map Name	Rule Priority	Mapped to Connection Profile
management	15	management
employee	10	employee

Mapping Criteria

+ Add Edit Delete

Field	Component	Operator	Value
Subject	Organizational Unit (OU)	Equals	abc_corp

Certificate to Connection Profile Maps

+ Add Edit Delete

Map Name	Rule Priority	Mapped to Connection Profile
management	15	management
employee	10	employee

Mapping Criteria

+ Add Edit Delete

Field	Component	Operator	Value
Subject	Common Name (CN)	Equals	level_2
Subject	Organizational Unit (OU)	Equals	abc_corp

You have configured two SSL VPN Certificate to Connection Profile Maps for all employee and management users. The Connection Profiles for the management users are not being applied when the "management" users connect.

Based on the configuration that is shown, what is the most likely cause of this issue?

- A. The rule priority of the employee mapping is not low enough, and it needs to be lowered to 1.
- B. The priority of the employee mapping is too low, and it needs to be increased, but not higher than the rule priority of the management mapping.
- C. The priority of the management mapping is too high, and it needs to be lower than the rule priority of the employee mapping.
- D. The matching criteria for the management mapping is too specific, and the CN matching parameter should be removed.

Answer: C

Explanation:

ASDM user guide p[age 35 52

Use the Add/Edit Certificate Matching Rule dialog box to assign the name of a list (map) to a connectionprofile. Fields • Map—Choose one of the following: – Existing—Select the name of the map to include the rule. – New—Enter a new map name for a rule. • Rule Priority—Type a decimal to specify the sequence with which the security appliance evaluates the map when it receives a connection request. For the first rule defined, the default priority is 10. The security appliance

evaluates each connection against the map with the lowest priority number first. • Mapped to Connection Profile—Select the connection profile, formerly called a “tunnel group,” to map to this rule. If you do not assign a rule criterion to the map, as described in the next section, the security appliance ignores the map entry.



C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 59

Refer to the exhibit.

```
access-list temp_acl webtype permit tcp host 10.0.4.4 eq 3389 log default
webvpn
  memory-size percent 25
  enable outside
  svc enable
  tunnel-group-list enable
  rewrite order 10 disable resource-mask *://cisco.com/* name cisco-com-bypass
  smart-tunnel list Smart_tunnel_applications Microsoft-RDP-Client MSTSC.EXE platform
  windows
group-policy temp_worker internal
group-policy temp_worker attributes
  banner value Welcome Temp Workers!
vpn-tunnel-protocol svc webvpn
webvpn
  url-list value temp_worker
  filter value temp_acl
  customization value temp_worker
  smart-tunnel auto-start Smart_tunnel_applications
  file-entry disable
  file-browsing disable
  url-entry disable
group-policy DfltGrpPolicy attributes
vpn-tunnel-protocol IPSec svc webvpn
webvpn
  url-list value Corporate_Server
tunnel-group temp_worker type remote-access
tunnel-group temp_worker general-attributes
  default-group-policy temp_worker
tunnel-group temp_worker webvpn-attributes
  customization temp_worker
group-alias temp_worker enable
group-url https://192.168.4.2/temp_worker enable
```

The ABC Corporation has a Cisco ASA in its test bed. A new network administrator is instructed to add a smart tunnel application to the existing configuration. The configuration will enable a "temp_worker" who is using Microsoft native RDP to have RDP access to server 10.0.4.4 only.

Which statement is correct concerning the smart-tunnel configuration?


- A. The WebType access list is misconfigured.
- B. The smart tunnel list parameter is misconfigured.
- C. The smart tunnel group policy parameters are misconfigured.
- D. The smart tunnel configuration is configured correctly.

Answer: D

Explanation:

QUESTION NO: 60

Refer to the exhibit.



Today was the first day on a new project for an offsite temporary worker at the XYZ Corporation. The worker was told to launch the SSL VPN session and then use the smart tunnel application to start a remote desktop application on the project server, projects_server.xyz.com. The worker looked at the portal screen that was provided, but she did not know how to access the smart tunnel application.

As the help desk person, what should you instruct the temporary worker to do?

- A. Click the Web Applications button.
- B. Click the Applications Access button.
- C. Click the Browse Networks button.
- D. On the Home page, click the Address drop-down menu, choose RDP://, and fill in the destination host name, which is projects_server.abc.com.

Answer: B

Explanation:

QUESTION NO: 61

After adding a remote-access IPsec tunnel via the VPN wizard, an administrator needs to tune the IKE policy parameters. Where is the correct place to tune IKE policy parameters?

- A. Cisco IPsec VPN SW Client > Client Profile

- B. IPsec User Profile
- C. Group Policy
- D. IKE Policy
- E. Crypto Map

Answer: D

Explanation:

QUESTION NO: 62

When deploying remote-access IPsec VPN tunnels, what is the key benefit of digital certificates?


- A. resiliency
- B. simplification
- C. scalability
- D. centralization

Answer: C

Explanation:

QUESTION NO: 63

Refer to the exhibit.



After being with the company for more than six months, Sue is no longer considered a new hire employee. In converting her from a new hire to a full-time employee, her SSL VPN address will change from the "Client requested address 10.0.4.120" to a random address from the employee

address pool.

To "disable" the 10.0.4.120 IP address, the network administrator should navigate to which Cisco ASDM pane?

- A. Connection Profile
- B. Group Policies
- C. Local Users
- D. Address Pools

Answer: C

Explanation:

Users are assigned IP addresses based on the address pool associated with their group. Change group of Sueto to use employee address pool

Add/Edit Tunnel Group > General > Advanced

The Add or Edit Tunnel Group window, General, Advanced dialog box, lets you configure the following interface-specific attributes:

- Interface-Specific Authentication Server Groups—Lets you configure an interface and server group for authentication.
 - Interface—Lists available interfaces for selection.
 - Server Group—Lists authentication server groups available for this interface.
 - Use LOCAL if server group fails—Enables or disables fallback to the LOCAL database if the server group fails.
 - Add—Adds the association between the selected available interface and the authentication server group to the assigned list.
 - Remove—Moves the selected interface and authentication server group association from the assigned list to the available list.
 - Interface/Server Group/Use Fallback—Shows the selections you have added to the assigned list.
- Interface-Specific Client IP Address Pools—Lets you specify an interface and Client IP address pool. You can have up to 6 pools.
 - Interface—Lists the available interfaces to add.
 - Address Pool—Lists address pools available to associate with this interface.
 - Add—Adds the association between the selected available interface and the client IP address pool to the assigned list.
 - Remove—Moves the selected interface/address pool association from the assigned list to the available list.
 - Interface/Address Pool—Shows the selections you have added to the assigned list.

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 64

While configuring a new clientless SSL VPN group in Cisco ASDM, the administrator chooses to accept a number of the default parameter values. The administrator decides to view the actual value for the parameter, rather than just checking the inherit box.

Under which default group can the administrator verify the default value for the group parameter?

- A. DefaultRAGroup
- B. DefaultWEBVPNGroup
- C. DfltGrpPolicy
- D. DefaultSVCGroup

Answer: C

Explanation:

QUESTION NO: 65

SSL server-side authentication is used for a client to verify the identity of a server. This type of authentication is commonly used for servers that require secured transactions to protect user data or account information for online purchases. Which one of these steps is not a step in the authentication process?

- A. The client sends Hello to the server, listing all of its supported cipher suites.
- B. The server sends Hello to the client, listing all of its supported cipher suites.
- C. The server sends its certificate to the client.
- D. The client generates, encrypts, and sends a session key.
- E. The server sends Change Cipher Spec to indicate a shift to encrypted mode.

Answer: B

Explanation:

QUESTION NO: 66

If CRL checking is enabled on the Cisco ASA, where can the Cisco ASA find the CRL?

- A. The Cisco ASA polls the CA for an updated list at a predefined rate.
- B. The CA sends a CRL to the Cisco ASA directly at least once a week.
- C. The CRL distribution point is listed on the identity certificate.
- D. The CRL is sent out-of-band to the administrator at a negotiated rate, typically biweekly.
- E. The CRL distribution point can be configured in the Connection Profile or Group Policy.

Answer: C

Explanation:

QUESTION NO: 67

With SCEP enabled in a Cisco AnyConnect Connection Profile, what additional configuration step must you do when using Cisco ASA 8.4 software?

- A. Configure local authentication prior to the enrollment process.
- B. Configure the client to poll the CA for a response to the certificate request.
- C. Configure the location of the CA server.
- D. Configure the profile to inherit the SCEP forwarding URL.

Answer: C

Explanation:


http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect24/administration/guide/ac03features.html#wp1072891

CAURL	CertificateEnrollment	Identifies the SCEP CA server. Permitted values: Fully qualified domain name or IP Address of CA server. In the following example, the CAURL field identifies http://ca01.cisco.com as the name of the SCEP CA server. Attributes of CAURL: PromptForChallengePW: Used for manual get certificate requests. After the user clicks Get Certificate, they will be prompted for their username and one time password. Permitted values: true, false The PromptForChallengePW attribute in the example below is configured "true." Thumbprint: The CA's certificate thumbprint. Use SHA1 or MD5 hashes. The Thumbprint attribute in the example below is 8475B661202E3414D4BB223A464E6AAB8CA123AB. Note Obtain the CA URL and thumbprint, from your CA server administrator. The CA server administrator should retrieve the thumbprint directly from the server and not from a "fingerprint" or "thumbprint" attribute field in a certificate it issued.
-------	-----------------------	---

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 68

Refer to the exhibit.



After a remote user established a Cisco AnyConnect session from a wireless card through the Cisco ASA appliance of a partner to a remote server, the user opened the Cisco AnyConnect VPN Client Statistics Details screen.

What are the two sources of the IP addresses that are marked A and B? (Choose two.)

- A. IP address that is assigned to the wireless Ethernet adapter of the remote user
- B. IP address that is assigned to the remote user from the Cisco ASA address pool
- C. IP address of the Cisco ASA physical interface of the partner
- D. IP address of the Cisco ASA virtual HTTP server of the partner
- E. IP address of the default gateway router of the remote user
- F. IP address of the default gateway router of the partner

Answer: B,C

Explanation:

QUESTION NO: 69

In Cisco ASA Software Release 8.4.1, which three plug-ins are Cisco ASA-supported plug-ins?

(Choose three.)

- A. SSH
- B. TN3270
- C. SCP
- D. RDP
- E. ICA
- F. ARAP

Answer: A,D,E

Explanation:

Clientless Applications

Application Type	Panel	Filename
Standard	Application Access	app-access-hlp.inc
Standard	Browse Networks	file-access-hlp.inc
Standard	AnyConnect Client	net-access-hlp.inc
Standard	Web Access	web-access-hlp.inc
Plug-in	MetaFrame Access	ica-hlp.inc
Plug-in	Terminal Servers	rdp-hlp.inc
Plug-in	Telnet/SSH Servers	ssh,telnet-hlp.inc
Plug-in	VNC Connections	vnc-hlp.inc

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 70

To enable the Cisco ASA Host Scan with remediation capabilities, an administrator must have which two Cisco ASA licenses enabled on its security appliance? (Choose two.)

- A. Cisco AnyConnect Premium license
- B. Cisco AnyConnect Essentials license
- C. Cisco AnyConnect Mobile license
- D. Host Scan license
- E. Advanced Endpoint Assessment license
- F. Cisco Security Agent license

Answer: A,E

Explanation:

Platform Licenses	
AnyConnect Essentials	• Network Access Manager • Telemetry • Highly secure remote-access connectivity • Single license per device model • Full Tunneling access to enterprise applications
AnyConnect Premium	• Includes clientless SSL VPN, Cisco Secure Desktop capabilities (including Host Scan), and support for Cisco AnyConnect Secure Mobility. Provides Essentials capabilities, including Full Tunneling access to enterprise applications • License is based on number of simultaneous users, and is available as a single device or shared license • Cisco AnyConnect Secure Mobility also requires a Cisco IronPort Web Security Appliance license
Optional Feature Licenses	
AnyConnect Mobile	• Enables Mobile OS platform compatibility • One license required per ASA platform, in addition to Essentials or Premium license
Advanced Endpoint Assessment	• Enables advanced endpoint assessment capabilities (such as auto-remediation) • Required per device, in addition to Premium licenses (not available with AnyConnect Essentials)
Cisco Secure Mobility	• Enforce security policy in every transaction, independent of where the user is located • For use with Cisco IronPort Web Security Appliance license and optional AnyConnect Premium license, or standalone with AnyConnect Premium license

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 71

An engineer, while working at a home office, wants to launch the Cisco AnyConnect Client to the corporate offices while simultaneously printing network designs on the home network.

Without allowing access to the Internet, what are the two best ways for the administrator to configure this application? (Choose two.)

- A.** Select the Tunnel All Networks policy.
- B.** Select the Tunnel Network List Below policy.
- C.** Select the Exclude Network List Below policy.

- D. Configure an exempted network list.
- E. Configure a standard access list and apply it to the network list.
- F. Configure an extended access list and apply it to the network list.

Answer: C,E

Explanation:

http://www.cisco.com/en/US/products/ps6120/products_configuration_example09186a0080702992.shtml

QUESTION NO: 72

ABC Corporation has hired a temporary worker to help out with a new project. The network administrator gives you the task of restricting the internal clientless SSL VPN network access of the temporary worker to one server with the IP address of 172.26.26.50 via HTTP.

Which two actions should you take to complete the assignment? (Choose two.)

- A. Configure access-list temp_acl webtype permit url http://172.26.26.50.
- B. Configure access-list temp_acl_stand_ACL standard permit host 172.26.26.50.
- C. Configure access-list temp_acl_extended extended permit http any host 172.26.26.50.
- D. Apply the access list to the temporary worker Group Policy.
- E. Apply the access list to the temporary worker Connection Profile.
- F. Apply the access list to the outside interface in the inbound direction.

Answer: A,D

Explanation:

Web ACLs

The Web ACLs table displays the filters configured on the security appliance applicable to Clientless SSL VPN traffic. The table shows the name of each access control list (ACL), and below and indented to the right of the ACL name, the access control entries (ACEs) assigned to the ACL. Each ACL permits or denies access to specific networks, subnets, hosts, and web servers. Each ACE specifies one rule that serves the function of the ACL. You can configure ACLs to apply to Clientless SSL VPN traffic. The following rules apply:

- If you do not configure any filters, all connections are permitted.
- The security appliance supports only an inbound ACL on an interface.
- At the end of each ACL, an implicit, unwritten rule denies all traffic that is not explicitly permitted. You can use the following wildcard characters to define more than one wildcard in the Webtype access list entry:
 - Enter an asterisk "*" to match no characters or any number of characters.
 - Enter a question mark "?" to match any one character exactly.
 - Enter square brackets "[]" to create a range operator that matches any one character in a range. The

following examples show how to use wildcards in Webtype access lists. • The following example matches URLs such as `http://www.cisco.com/` and `http://www.caco.com/`:
access-list test webtype permit url `http://www?.c*co*/`

QUESTION NO: 73

In which three ways can a Cisco ASA security appliance obtain a certificate revocation list? (Choose three.)

- A. FTP
- B. SCEP
- C. TFTP
- D. HTTP
- E. LDAP
- F. SCP

Answer: B,D,E

Explanation:

CRLs

CRLs provide the ASA with one way of determining whether a certificate that is within its valid time range has been revoked by the issuing CA. CRL configuration is part of configuration of a trustpoint.

You can configure the ASA to make CRL checks mandatory when authenticating a certificate by using the `revocation-check crl` command. You can also make the CRL check optional by using the `revocation-check crl none` command, which allows the certificate authentication to succeed when the CA is unavailable to provide updated CRL data.

The ASA can retrieve CRLs from CAs using HTTP, SCEP, or LDAP. CRLs retrieved for each trustpoint are cached for a configurable amount of time for each trustpoint.

When the ASA has cached a CRL for longer than the amount of time it is configured to cache CRLs, the ASA considers the CRL too old to be reliable, or "stale." The ASA tries to retrieve a newer version of the CRL the next time that a certificate authentication requires a check of the stale CRL.

The ASA caches CRLs for an amount of time determined by the following two factors:

- The number of minutes specified with the `cache-time` command. The default value is 60 minutes.
- The `NextUpdate` field in the CRLs retrieved, which may be absent from CRLs. You control whether the ASA requires and uses the `NextUpdate` field with the `enforce nextupdate` command.

The ASA uses these two factors in the following ways:

- If the NextUpdate field is not required, the ASA marks CRLs as stale after the length of time defined by the cache-time command.
- If the NextUpdate field is required, the ASA marks CRLs as stale at the sooner of the two times specified by the cache-time command and the NextUpdate field. For example, if the cache-time command is set to 100 minutes and the NextUpdate field specifies that the next update is 70 minutes away, the ASA marks CRLs as stale in 70 minutes.

QUESTION NO: 74

An IT manager and a Security manager are discussing the deployment options for clientless SSL VPN. They are trying to decide which groups are best suited for this new deployment option. Which two groups are the best candidates for the clientless SSL VPN rollout? (Choose two.)

- A. an IT administrator who needs to manage servers from a corporate laptop
- B. employees who need occasional access to check their email accounts
- C. a vendor who needs access to confidential corporate presentations via Secure FTP
- D. customers who need interactive access to the corporate invoice server

Answer: B,C

Explanation:

QUESTION NO: 75

Your corporation has contractors that need remote access to server desktops, in order to diagnose issues and load software during nonbusiness hours. Which three clientless SSL VPN configurations allow these contractors to access the desktops of remote servers? (Choose three.)

- A. XWindows bookmark by using the XWindows plug-in
- B. RDP bookmark by using the RDP plug-in
- C. SCP bookmark by using SCP plug-in
- D. VNC bookmark by using the VNC plug-in
- E. SSH bookmark by using the SSH plug-in
- F. Citrix plug-in by using the Citrix plug-in

Answer: B,D,F

Explanation:

Clientless Applications

Application Type	Panel	Filename
Standard	Application Access	app-access-hlp.inc
Standard	Browse Networks	file-access-hlp.inc
Standard	AnyConnect Client	net-access-hlp.inc
Standard	Web Access	web-access-hlp.inc
Plug-in	MetaFrame Access	ica-hlp.inc
Plug-in	Terminal Servers	rdp-hlp.inc
Plug-in	Telnet/SSH Servers	ssh,telnet-hlp.inc
Plug-in	VNC Connections	vnc-hlp.inc

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 76

Which three Host Scan checks on a remote endpoint can you configure Cisco Secure Desktop to perform? (Choose three.)

- A. registry checks
- B. user rights checks
- C. group policy objects checks
- D. file checks
- E. virus software checks
- F. process checks

Answer: A,D,F

Explanation:

<http://www.cisco.com/en/US/docs/security/csd/csd341/configuration/guide/CSDhscan.html>

You can specify a set of registry entries, filenames, and process names, which form a part of Basic Host Scan.

Host Scan, which includes Basic Host Scan and Endpoint Assessment, or Advanced Endpoint Assessment; occurs after the prelogin assessment but before the assignment of a DAP. Following the Basic Host Scan, the security appliance uses the login credentials, the host scan results, prelogin policy, and other criteria you configure to assign a DAP.

See the sections that name the types of Basic Host Scan entries you would like to configure:

- Adding a File Check
- Adding a Registry Key Check
- Adding a Process Check

QUESTION NO: 77

Which three statements about clientless SSL VPN are true? (Choose three.)

- A. Users are not tied to a particular PC or workstation.
- B. Users have full application access to internal corporate resources.
- C. Minimal IT support is required.
- D. Cisco AnyConnect SSL VPN software is automatically downloaded to the remote user at the start of the clientless session.
- E. For security reasons, browser cookies are disabled for clientless SSL VPN sessions.
- F. Clientless SSL VPN requires an SSL-enabled web browser.

Answer: A,C,F

Explanation:

QUESTION NO: 78

A remote user who establishes a clientless SSL VPN session is presented with a web page. The administrator has the option to customize the "look and feel" of the page. What are three components of the VPN Customization Editor? (Choose three.)

- A. Application page
- B. Logon page
- C. Networking page
- D. Logout page
- E. Home page
- F. Portal page

Answer: B,D,F

Explanation: GUI Enhancements

In Cisco IOS Release 12.4(15)T, ergonomic improvements were made to the GUI user interface of the Cisco IOS SSL VPN gateway. The improved customization of the user interface provides for greater flexibility and the ability to tailor portal pages for individualized looks. Enhancements were made to the following web screens:

- Login screen
- Portal page

QUESTION NO: 79

When establishing a Cisco AnyConnect SSL VPN tunnel, a system administrator wants to restrict remote home office users to either print to their local printer or send the remaining traffic down the Cisco AnyConnect SSL VPN tunnel (with restricted Internet access).

Choose both a tunnel policy option and an ACL type to accomplish this design goal. (Choose two.)

- A. tunnel all networks
- B. tunnel network list below
- C. exclude network list from the tunnel
- D. standard ACL
- E. web ACL
- F. extended ACL

Answer: C,D

Explanation:

http://www.cisco.com/en/US/products/ps6120/products_configuration_example09186a0080702992.shtml

QUESTION NO: 80

The LAN-to-LAN tunnel is not established, but an administrator can ping the remote Cisco ASA.

Which three IPsec LAN-to-LAN configuration parameters should the administrator verify at both ends of the tunnel? (Choose three.)

- A. pre-shared key
- B. extended authentication password
- C. extended authentication username
- D. crypto ACL source IP address
- E. crypto ACL destination IP address
- F. tunnel connection-typeE. originate or answer

Answer: A,D,E

Explanation:

QUESTION NO: 81

Upon receiving a digital certificate, what are three steps that a Cisco ASA performs to authenticate the digital certificate? (Choose three.)

- A. The identity certificate validity period is verified against the system clock of the Cisco ASA.
- B. The identity certificate thumbprint is validated using the private key of the stored CA.
- C. The identity certificate signature is validated by using the stored root certificate.
- D. The signature is validated by using the stored identity certificate.
- E. If enabled, the Cisco ASA locates the CRL and validates the identity certificate.

Answer: A,C,E

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa80/configuration/guide/cert_cfg.html#wp1052825

Certificate Revocation Lists provide the security appliance with one means of determining whether a certificate that is within its valid time range has been revoked by its issuing CA. CRL configuration is a part of the configuration of a trustpoint.

You can configure the security appliance to make CRL checks mandatory when authenticating a certificate (revocation-check crl command). You can also make the CRL check optional by adding the none argument (revocation-check crl none command), which allows the certificate authentication to succeed when the CA is unavailable to provide updated CRL data.

The security appliance can retrieve CRLs from CAs using HTTP, SCEP, or LDAP. CRLs retrieved for each trustpoint are cached for a length of time configurable for each trustpoint.

When the security appliance has cached a CRL for more than the length of time it is configured to cache CRLs, the security appliance considers the CRL too old to be reliable, or "stale". The security appliance attempts to retrieve a newer version of the CRL the next time a certificate authentication requires checking the stale CRL.

The security appliance caches CRLs for a length of time determined by the following two factors:

- The number of minutes specified with the cache-time command. The default value is 60 minutes.
- The NextUpdate field in the CRLs retrieved, which may be absent from CRLs. You control whether the security appliance requires and uses the NextUpdate field with the enforce-next-update command.

The security appliance uses these two factors as follows:

- If the NextUpdate field is not required, the security appliance marks CRLs as stale after the length of time defined by the cache-time command.

•If the NextUpdate field is required, the security appliance marks CRLs as stale at the sooner of the two times specified by the cache-time command and the NextUpdate field. For example, if the cache-time command is set to 100 minutes and the NextUpdate field specifies that the next update is 70 minutes away, the security appliance marks CRLs as stale in 70 minutes.

QUESTION NO: 82

You are configuring bookmarks for the clientless SSL VPN portal without the use of plug-ins.

Which three bookmark types are supported? (Choose three.)

- A. RDP
- B. HTTP
- C. FTP
- D. CIFS
- E. SSH
- F. Telnet

Answer: B,C,D

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa80/asdm60/ssl_vpn_deployment_guide/deploy.html#wp1227212

QUESTION NO: 83

What are three methods for VPN address assignment? (Choose three.)

- A. RADIUS authentication server
- B. Kerberos server
- C. internal address pool
- D. RSA SecureID authentication server
- E. LDAP server

Answer: A,C,E

Explanation:

<http://www.cisco.com/en/US/docs/security/asa/asa82/configuration/guide/vpnadd.html>

Configuring an IP Address Assignment Method

The ASA can use one or more of the following methods for assigning IP addresses to remote access clients. If you configure more than one address assignment method, the ASA searches each of the options until it finds an IP address. By default, all methods are enabled. To view the current configuration, enter the `show running-config all vpn-addr-assign` command.

- **aaa**—Retrieves addresses from an external authentication server on a per-user basis. If you are using an authentication server that has IP addresses configured, we recommend using this method.
- **dhcp**—Obtains IP addresses from a DHCP server. If you want to use DHCP, you must configure a DHCP server. You must also define the range of IP addresses that the DHCP server can use.
- **local**—Use an internal address pool. Internally configured address pools are the easiest method of address pool assignment to configure. If you choose local, you must also use the `ip-local-pool` command to define the range of IP addresses to use.

To specify a method for assigning IP addresses to remote access clients, enter the `vpn-addr-assign` command in global configuration mode. The syntax is `vpn-addr-assign {aaa | dhcp | local}`.

QUESTION NO: 84

Datagram Transport Layer Security (DTLS) was introduced to solve performance issues. Choose three characteristics of DTLS. (Choose three.)

- A.** It uses TLS to negotiate and establish DTLS connections.
- B.** It uses DTLS to transmit datagrams.
- C.** It is disabled by default.
- D.** It uses TLS for data packet retransmission.
- E.** It replaces underlying transport layer with UDP 443.
- F.** It uses TLS to provide low-latency video application tunneling.

Answer: A,B,E

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect23/administration/23_admin2.html#wp1029596

Enabling Datagram Transport Layer Security (DTLS) with AnyConnect (SSL)

Datagram Transport Layer Security avoids latency and bandwidth problems associated with some SSL-only connections, including AnyConnect connections, and improves the performance of real-time applications that are sensitive to packet delays. DTLS is a standards-based SSL protocol that provides a low-latency data path using UDP. For detailed information about DTLS, see RFC 4347 (<http://www.ietf.org/rfc/rfc4347.txt>).

Datagram Transport Layer Security (DTLS) allows the AnyConnect client establishing an SSL VPN connection to use two simultaneous tunnels—an SSL tunnel and a DTLS tunnel. Using DTLS avoids latency and bandwidth problems associated with some SSL connections and improves the performance of real-time applications that are sensitive to packet delays.

If you do not enable DTLS, AnyConnect/SSL VPN connections connect with an SSL VPN tunnel only.

You cannot enable DTLS globally with ASDM. The following section describes how to enable DTLS for any specific interface.

To enable DTLS for a specific interface, select Configuration > Remote Access VPN > Network (Client) Access

> Advanced > SSL VPN Connection profiles. The SSL VPN Connection Profiles dialog box opens (Figure 2-3). Figure 2-3 Enable DTLS Check Box

Configuration > Remote Access VPN > Network (Client) Access > SSL VPN Connection Profiles

The security appliance automatically deploys the Cisco AnyConnect VPN Client or legacy SSL VPN Client to remote users upon connection. The initial client deployment requires end-user administrative rights. The Cisco AnyConnect VPN Client supports the HTTPS/TCP (SSL) and Datagram Transport Layer Security (DTLS) tunneling options.

(More client-related parameters, such as client images and client profiles, can be found at [Client Settings](#).)

Access Interfaces

☒ Enable Cisco AnyConnect VPN Client or legacy SSL VPN Client access on the interfaces selected in the table below

Interface	Allow Access	Require Client Certificate	Enable DTLS
outside	☒	☐	☒
DMZ	☒	☐	☒
dmz1	☐	☐	☐
inside	☒	☐	☒

Access Port: DTLS Port:

Click here to [Assign Certificate to Interface](#).

Connection Profiles

Connection profile (tunnel group) table below contains records that determine connection policies. A record identifies a default group policy for the connection and contains protocol-specific connection parameters.

Name	Aliases	SSL VPN Client Protocol	Group Policy
test2		Enabled	DfltGrpPolicy
mkgroup	writers, writers2	Enabled	DfltGrpPolicy
group		Enabled	DfltGrpPolicy
DefaultWEBVPNGroup		Enabled	DfltGrpPolicy
multi		Enabled	DfltGrpPolicy
mygroup		Enabled	DfltGrpPolicy
mk-ra-group		Enabled	DfltGrpPolicy
eureka		Enabled	DfltGrpPolicy
DefaultRAGroup		Enabled	DfltGrpPolicy

☒ Allow user to select connection, identified by alias in the table above, at login page

C:\Documents and Settings\user-nw\Desktop\1.JPG

Enabling Datagram Transport Layer Security (DTLS) allows the AnyConnect VPN Client establishing an SSL VPN connection to use two simultaneous tunnels—an SSL tunnel and a DTLS tunnel. Using DTLS avoids latency and bandwidth problems associated with some SSL connections and improves the performance of real-time applications that are sensitive to packet delays. If you do not enable DTLS, AnyConnect client users establishing SSL VPN connections connect with an SSL VPN tunnel only. Fields • Interface—Displays a list of interfaces

on the security appliance. • DTLS Enabled—Check to enable DTLS connections with the AnyConnect client on the interfaces. • UDP Port (default 443)—(Optional) Specify a separate UDP port for DTLS connections.

QUESTION NO: 85

Which three options are characteristics of WebType ACLs? (Choose three.)

- A. They are assigned per-connection profile.
- B. They are assigned per-user or per-group policy.
- C. They can be defined in the Cisco AnyConnect Profile Editor.
- D. They support URL pattern matching.
- E. They support implicit deny all at the end of the ACL.
- F. They support standard and extended WebType ACLs.

Answer: B,D,E

Explanation:

You can configure ACLs (Access Control Lists) to apply to user sessions. These are filters that permit or deny user access to specific networks, subnets, hosts, and web servers. • If you do not define any filters, all connections are permitted. • The security appliance supports only an inbound ACL on an interface. • At the end of each ACL, there is an implicit, unwritten rule that denies all traffic that is not permitted. If traffic is not explicitly permitted by an access control entry (ACE), the security appliance denies it. ACEs are referred to as rules in this topic. This pane lets you add and edit ACLs to be used for Clientless SSL VPN sessions, and the ACL entries each ACL contains. It also displays summary information about ACLs and ACEs, and lets you enable or disable them, and change their priority order.


QUESTION NO: 86

For clientless SSL VPN users, bookmarks can be assigned to their portal. What are three methods for assigning bookmarks? (Choose three.)

- A. connection profiles
- B. group policies
- C. XML profiles
- D. LDAP or RADIUS attributes
- E. the portal customization tool

F. user policies**Answer: B,D,F****Explanation:**

Create one or more bookmark list entries that specify the URLs of the web-enabled applications eligible for smart tunnel access, then assign the list to the DAPs, group policies, or local user policies for whom you want to provide smart tunnel access. e.g.



C:\Documents and Settings\user-nwz\Desktop\1.JPG

Dynamic access policies (DAP)

VPN gateways operate in dynamic environments. Multiple variables can affect each VPN connection, for example, intranet configurations that frequently change, the various roles each user may inhabit within an organization, and logins from remote access sites with different configurations and levels of security. The task of authorizing users is much more complicated in a VPN environment than it is in a network with a static configuration.

Dynamic Access Policies (DAP) on the security appliance let you configure authorization that addresses these many variables. You create a dynamic access policy by setting a collection of access control attributes that you associate with a specific user tunnel or session. These attributes address issues of multiple group membership and endpoint security. That is, the security appliance

grants access to a particular user for a particular session based on the policies you define. It generates a DAP at the time the user connects by selecting and/or aggregating attributes from one or more DAP records. It selects these DAP records based on the endpoint security information of the remote device and the AAA authorization information for the authenticated user. It then applies the DAP record to the user tunnel or session.

QUESTION NO: 87

Your IT department needs to run a custom-built TCP application within the clientless SSL VPN tunnel. The network administrator suggests running the smart tunnel application. Which three statements concerning smart tunnel applications are true? (Choose three.)

- A. They support active FTP and other RTSP-based applications.
- B. They do not require administrator privileges on the remote system.
- C. They require the enabling of port forwarding.
- D. They are supported on Windows and MAC OS X platforms.
- E. They support native client applications over SSL VPN.
- F. They require the modification of the Host file on the end-user PC.

Answer: B,D,E

Explanation:

Smart Tunnel—Connects a Winsock 2, TCP-based application installed on the end station to a server on the intranet, using a clientless (browser-based) SSL VPN session with the security appliance as the pathway, and the security appliance as a proxy server.

– **Smart Tunnel List**—Select the list name from the drop-down menu if you want to provide smart tunnel access.

Assigning a smart tunnel list to a group policy or username enables smart tunnel access for all users whose sessions are associated with the group policy or username, but restricts smart tunnel access to the application specified in the list. To view, add, modify, or delete a smart tunnel list, click the adjacent Manage button. – **Auto Start (Smart Tunnel List)**—Check to start smart tunnel access automatically upon user login. Uncheck to enable smart tunnel access upon user login, but require the user to start it manually, using the Application Access > Start Smart Tunnels button on the Clientless SSL VPN Portal Page.

– **Auto Sign-on Server List**—Select the list name from the drop-down menu if you want to reissue the user credentials when the user establishes a smart tunnel connection to a server. Each smart tunnel auto sign-on list entry identifies a server with which to automate the submission of user credentials. To view, add, modify, or delete a smart tunnel auto sign-on list, click the adjacent Manage button.

– **Domain Name (Optional)**—Specify the Windows domain to add it to the username during auto sign-on, if the universal naming convention (domain\username) is required for authentication. For

example, enter CISCO to specify CISCO\jsmith when authenticating for the username jsmith. You must also check the "Use Windows domain name with user name" option when configuring associated entries in the auto sign-on server list.

QUESTION NO: 88

When deploying clientless SSL VPN advanced application access, the administrator needs to collect information about the end-user system. Which three input parameters of an end-user system are important for the administrator to identify? (Choose three.)

- A. types of applications and application protocols that are supported
- B. types of encryption that are supported on the end-user system
- C. the local privilege level of the remote user
- D. types of wireless security that are applied to the end-user tunnel interface
- E. types of operating systems that are supported on the end-user system
- F. type of antivirus software that is supported on the end-user system

Answer: A,C,E

Explanation:

When enabling port forwarding, the SSL VPN gateway will modify the hosts file on the PC of the remote user. Some software configurations and software security applications will detect this modification and prompt the remote user to select "Yes" to permit. To permit the modification, the remote user must have local administrative privileges.

To securely access resources on a private network behind an SSL VPN gateway, the remote user of an SSL VPN service must have the following:

- "Thin Client" support used for TCP port-forwarding applications requires administrative privileges on the computer of the remote user.
- "Tunnel mode" for Cisco SSL VPN requires administrative privileges for initial installation of the full tunnel client.
- The remote user must have local administrative privileges to use thin client or full tunnel client features.

Operating system support

- Microsoft Windows 2000, Windows XP, or Windows Vista
 - Macintosh OS X 10.4.6
 - Linux (Redhat RHEL 3.0 +, FEDORA 5, or FEDORA 6)
- SSL VPN-supported browser—The following browsers have been verified for SSL VPN. Other browsers might not fully support SSL VPN features.

QUESTION NO: 89

Cisco Secure Desktop seeks to minimize the risks that are posed by the use of remote devices in establishing a Cisco clientless SSL VPN or Cisco AnyConnect VPN Client session. Which two statements concerning the Cisco Secure Desktop Host Scan feature are correct? (Choose two.)

- A. It is performed before a user establishes a connection to the Cisco ASA.
- B. It is performed after a user establishes a connection to the Cisco ASA but before logging in.
- C. It is performed after a user logs in but before a group profile is applied.
- D. It is supported on endpoints that run a Windows operating system only.
- E. It is supported on endpoints that run Windows and MAC operating systems only.
- F. It is supported on endpoints that run Windows, MAC, and Linux operating systems.

Answer: B,F

Explanation:

DAP and Anti-Virus, Anti-Spyware, and Personal Firewall Programs

The security appliance uses a DAP policy when the user attributes matches the configured AAA and endpoint attributes. The Prelogin Assessment and Host Scan modules of Cisco Secure Desktop return information to the security appliance about the configured endpoint attributes, and the DAP subsystem uses that information to select a DAP record that matches the values of those attributes. Most, but not all, anti-virus, anti-spyware, and personal firewall programs support active scan, which means that the programs are memory-resident, and therefore always running. Host Scan checks to see if an endpoint has a program installed, and if it is memory resident as follows:

- If the installed program does not support active scan, Host Scan reports the presence of the software. The DAP system selects DAP records that specify the program.
- If the installed program does support active scan, and active scan is enabled for the program, Host Scan reports the presence of the software. Again the security appliance selects DAP records that specify the program.
- If the installed program does support active scan and active scan is disabled for the program, Host Scan ignores the presence of the software. The security appliance does not select DAP records that specify the program. Further, the output of the debug trace command, which includes a lot of information about DAP, does not indicate the program presence, even though it is installed.

The following sequence outlines a typical remote access connection establishment.

1. A remote client attempts a VPN connection.
2. The security appliance performs posture assessment, using configured NAC and Cisco Secure Desktop Host Scan values.

Operating system support

- Microsoft Windows 2000, Windows XP, or Windows Vista
- Macintosh OS X 10.4.6
- Linux (Redhat RHEL 3.0 +, FEDORA 5, or FEDORA 6)

3. The security appliance authenticates the user via AAA. The AAA server also returns

authorization attributes for the user.

4. The security appliance applies AAA authorization attributes to the session, and establishes the VPN tunnel.
5. The security appliance selects DAP records based on the user AAA authorization information and the session posture assessment information.
6. The security appliance aggregates DAP attributes from the selected DAP records, and they become the DAP policy.
7. The security appliance applies the DAP policy to the session.

QUESTION NO: 90

Which four statements about the Advanced Endpoint Assessment are correct? (Choose four.)

- A. It examines the remote computer for personal firewall applications.
- B. It examines the remote computer for antivirus applications.
- C. It examines the remote computer for antispyware applications.
- D. It examines the remote computer for malware applications.
- E. It does not perform any remediation, but it provides input that can be evaluated by DAP records.
- F. It performs active remediation by applying rules, activating modules, and providing updates where applicable.

Answer: A,B,C,F

Explanation:

Host Scan	As a condition for the completion of a Cisco AnyConnect or clientless SSL VPN connection, the remote computer scans for a greatly expanded collection of antivirus and antispyware applications, firewalls, operating systems, and associated updates. It also scans for any registry entries, filenames, and process names that you specify. It sends the scan results to the security appliance. The security appliance uses both the user login credentials and the computer scan results to assign a Dynamic Access Policy (DAP). With an Advanced Endpoint Assessment License, you can enhance Host Scan by configuring an attempt to update noncompliant computers to meet version requirements. Cisco can provide timely updates to the list of applications and versions that Host Scan supports in a package that is separate from Cisco Secure Desktop.
-----------	--

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 91

The software-based Cisco IPsec VPN Client solution uses bidirectional authentication, in which

the client authenticates the Cisco ASA, and the Cisco ASA authenticates the user. Which three methods are software-based Cisco IPsec VPN Client to Cisco ASA authentication methods? (Choose three.)

- A. Unified Client Certificate authentication
- B. Secure Unit authentication
- C. Hybrid authentication
- D. Certificate authentication
- E. Group authentication

Answer: C,D,E

Explanation:

ASDM user guide Page 35-69

Authentication Mode—Specifies the authentication mode: none, xauth, or hybrid.

hybrid—Specifies the use of Hybrid mode, which lets you use digital certificates for security appliance authentication and a different, legacy method—such as RADIUS, TACACS+ or SecurID—for remote VPN user authentication. This mode breaks phase 1 of the Internet Key Exchange (IKE) into the following steps, together called hybrid authentication:

xauth—Specifies the use of IKE Extended Authentication mode, which provides the capability of authenticating a user within IKE using TACACS+ or RADIUS.

QUESTION NO: 92

Which two options are correct regarding IKE and IPv6 VPN support on the Cisco ASA using version 8.4? (Choose two.)

- A. The Cisco ASA supports full IKEv2 IPv6 for site-to-site VPNs only.
- B. The Cisco ASA supports full IKEv2 IPv6 for remote-access VPNs.
- C. The Cisco ASA supports IKEv1 and IKEv2 configuration on the same crypto map.
- D. The Cisco ASA supports negotiation of authentication type using IKEv2 with IPv6.
- E. The Cisco ASA supports all types of VPN configurations when using IPv6

Answer: A,C

Explanation:

http://www.cisco.com/en/US/prod/collateral/vpndevc/ps6032/ps6094/ps6120/product_bulletin_c25-593781.html

- IPv6 IPsec Site-to-Site VPN: Customers can now create encrypted IPsec VPN connections over IPv6 networks

http://www.cisco.com/en/US/docs/security/asa/asa84/configuration/guide/vpn_site2site.html#wp1061313

For IKEv2, you can configure multiple encryption and authentication types, and multiple integrity algorithms for a single policy. The ASA orders the settings from the most secure to the least secure and negotiates with the peer using that order. This allows you to potentially send a single proposal to convey all the allowed transforms instead of the need to send each allowed combination as with IKEv1.

QUESTION NO: 93

In Cisco ASDM v6.4, what are four ways to implement single sign-on (SSO)? (Choose four.)

- A. Use SSO for smart tunnels.
- B. Use Kerberos SSO.
- C. Use the HTTP Form protocol.
- D. Use a dedicated SSO server.
- E. Use SSO for application plug-ins.
- F. Use auto sign-on for servers that do not require authentication credentials.

Answer: A,C,D,E

Explanation:

The security appliance can use the HTTP Form protocol for single sign-on (SSO) authentication of WebVPN users only. Single sign-on support lets WebVPN users enter a username and password only once to access multiple protected services and Web servers. The WebVPN server running on the security appliance acts as a proxy for the user to the authenticating server. When a user logs in, the WebVPN server sends an SSO authentication request, including username and password, to the authenticating server using HTTPS. If the server approves the authentication request, it returns an SSO authentication cookie to the WebVPN server. The security appliance keeps this cookie on behalf of the user and uses it to authenticate the user to secure websites within the domain protected by the SSO server. In addition to the HTTP Form protocol, WebVPN administrators can choose to configure SSO with the HTTP Basic and NTLM authentication protocols (the `auto-signon` command), or with Computer Associates eTrust SiteMinder SSO server (formerly Netegrity SiteMinder) as well. For an in-depth discussion of configuring SSO with either HTTP Forms, auto-signon or SiteMinder, The Auto Signon window or tab lets you configure or edit auto signon for users of Clientless SSL VPN. Auto signon is a simplified single signon method that you can use if you do not already have an SSO method deployed on your internal network. With auto signon configured for particular internal servers, the security appliance passes the login credentials that the user of Clientless SSL VPN entered to log in to the security appliance (username and

password) to those particular internal servers. You configure the security appliance to respond to a specific authentication method for a particular range of servers. The authentication methods you can configure the security appliance to respond to consists of authentication using Basic (HTTP), NTLM, FTP and CIFS, or all of these methods. Auto signon is a straight-forward method for configuring SSO for particular internal servers. This section describes the procedure for setting up SSO with auto signon. If you already have SSO deployed using Computer Associates' SiteMinder SSO server, or if you have Security Assertion Markup Language (SAML) Browser Post Profile SSO,

QUESTION NO: 94

An on-screen keyboard is a programmable SSL VPN option. Which three options are keyboard-configurable parameters that the administrator can enable or disable? (Choose three.)

- A. Show only if Secure Desktop Vault is disabled.
- B. Do not show onscreen keyboard.
- C. Show only for the login page.
- D. Show for all user input fields.
- E. Show for all portal pages that require authentication.
- F. Show for all plug-in pages.

Answer: B,C,E

Explanation:

Onscreen keyboard

The security appliance includes an onscreen keyboard option for the login page and subsequent authentication requests for internal resources. This provides additional protection against software-based keystroke loggers by requiring a user to use a mouse to click characters in an onscreen keyboard for authentication, rather than entering the characters on a physical keyboard.

QUESTION NO: 95

Which three statements concerning keystroke logger detection are correct? (Choose three.)

- A. It requires administrative privileges in order to run.
- B. It runs on Windows and MAC OS X systems.
- C. It detects loggers that run as a process or kernel module.
- D. It detects both hardware- and software-based keystroke loggers.

E. It allows the administrator to define "safe" keystroke logger applications.

Answer: A,C,E

Explanation:

<http://www.cisco.com/en/US/docs/security/csd/csd321/configuration/guide/CSDJfaq.html>

and

http://www.cisco.com/en/US/docs/security/csd/csd_32/configuration/guide/CSDJtuto.html

QUESTION NO: 96

Cisco AnyConnect profiles can be used to set which three options? (Choose three.)

- A. Define a list of VPN gateways that are presented to users upon login.
- B. Define a quarantine VLAN for remote devices that fail a host scan.
- C. Define a guest VLAN to all "noncompany" Cisco IOS WebVPN users.
- D. Define a list of backup servers if primary gateways are unavailable.
- E. Activate the SSL VPN tunnel as part of the Windows login sequence.
- F. Configure the Cisco Secure Desktop vault.

Answer: A,D,E

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect20/administrative/guide/adminapa.pdf

QUESTION NO: 97

Which two types of digital certificate enrollment processes are available for the Cisco ASA security appliance? (Choose two.)

- A. LDAP
- B. FTP
- C. TFTP
- D. HTTP
- E. SCEP
- F. Manual

Answer: E,F

Explanation:

http://www.cisco.com/en/US/products/ps6120/products_configuration_example09186a0080b25dc1.shtml

http://www.cisco.com/en/US/products/ps6120/products_configuration_example09186a0080b3cff.shtml

QUESTION NO: 98

Which four parameters must be defined in an ISAKMP policy when you are creating an IPsec site-to-site VPN using the Cisco ASDM? (Choose four.)

- A. encryption algorithm
- B. hash algorithm
- C. authentication method
- D. IP address of remote IPsec peer
- E. D-H group
- F. perfect forward secrecy

Answer: A,B,C,E

Explanation:

ASDM User guide Page 34-5

Should this not be IKE policy?

Fields

Priority #—Type a number to set a priority for the IKE policy. The range is 1 to 65,543, with 1 the highest priority.

Encryption—Select an encryption method. This is a symmetric encryption method that protects data transmitted between two IPsec peers. The choices follow:

des	56-bit DES-CBC. Less secure but faster than the alternatives. The default.
3des	168-bit Triple DES.
aes	128-bit AES.
aes-192	192-bit AES.
aes-256	256-bit AES.

Hash—Select the hash algorithm that ensures data integrity. It ensures that a packet comes from whom you think it comes from, and that it has not been modified in transit.

sha	SHA-1	The default is SHA-1. MD5 has a smaller digest and is considered to be slightly faster than SHA-1. A successful (but extremely difficult) attack against MD5 has occurred; however, the HMAC variant IKE uses prevents this attack.
md5	MD5	

Authentication—Select the authentication method the security appliance uses to establish the identity of each IPsec peer. Pre-shared keys do not scale well with a growing network but are easier to set up in a small network. The choices follow:

pre-share	Pre-shared keys.
-----------	------------------

C:\Documents and Settings\user-nwz\Desktop\1.JPG

rsa-sig	A digital certificate with keys generated by the RSA signatures algorithm.
crack	IKE Challenge/Response for Authenticated Cryptographic Keys protocol for mobile IPsec-enabled clients which use authentication techniques other than certificates.

D-H Group—Select the Diffie-Hellman group identifier, which the two IPsec peers use to derive a shared secret without transmitting it to each other.

- | | | |
|---|--|--|
| 1 | Group 1 (768-bit) | The default, Group 2 (1024-bit Diffie-Hellman) requires less CPU time to execute but is less secure than Group 2 or 5. |
| 2 | Group 2 (1024-bit) | |
| 5 | Group 5 (1536-bit) | |
| 7 | Group 7 (Elliptical curve field size is 163 bits.) | Group 7 is for use with the Movian VPN client, but with any peer that supports Group 7 (ECC). |

Lifetime (secs)—Either select Unlimited or type an integer for the SA lifetime. The default is 86,400 seconds or 24 hours. With longer lifetimes, the security appliance sets up future IPsec security associations more quickly. Encryption strength is great enough to ensure security without using very fast rekey times, on the order of every few minutes. We recommend that you accept the default.

Time Measure—Select a time measure. The security appliance accepts the following values:

- 120 - 86,400 seconds
- 2 - 1440 minutes
- 1 - 24 hours
- 1 day

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 99

Which two statements about the Cisco ASA cluster load-balancing feature are correct? (Choose two.)

- A. The Cisco ASA load-balances both site-to-site and remote-access VPN tunnels.
- B. The Cisco ASA load-balances remote-access VPN tunnels only.
- C. The Cisco ASA load-balances IPsec VPN tunnels only.
- D. The Cisco ASA load-balances IPsec VPN and Cisco AnyConnect SSL VPN tunnels only.
- E. The Cisco ASA load-balances IPsec VPN, clientless, and Cisco AnyConnect SSL VPN tunnels.

Answer: B,E

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa71/asdm51/selected_procedures/asdm_lb.html#wp1005709

Eligible Clients

Load balancing is effective only on remote sessions initiated with the following clients:

- Cisco VPN Client (Release 3.0 and later)
- Cisco VPN 3002 Hardware Client (Release 3.5 or later)
- Cisco ASA model 5505 when configured as a hardware client
- Cisco PIX 501/506E when acting as an Easy VPN client.

Load balancing works with both IPSec clients and WebVPN sessions. All other clients, including LAN-to-LAN connections, can connect to a security appliance on which load balancing is enabled, but they cannot participate in load balancing.

http://www.cisco.com/en/US/docs/security/asa/asa84/configuration/guide/vpn_params.html#wp1048834

Load Balancing

Load balancing is a mechanism for equitably distributing remote-access VPN traffic among the devices in a virtual cluster. It is based on simple distribution of traffic without taking into account throughput or other factors.

A load-balancing cluster consists of two or more devices, one is the virtual master, and the other devices are the backup. These devices do not need to be of the exact same type, or have identical software versions or configurations.

QUESTION NO: 100

A Cisco AnyConnect user profile can be pushed to the PC of a remote user from a Cisco ASA.

Which three user profile parameters are configurable? (Choose three.)

- A. Backup Server list
- B. DTLS Override
- C. Auto Reconnect
- D. Simultaneous Tunnels
- E. Connection Profile Lock
- F. Auto Update

Answer: A,C,F

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect20/administrative/guide/adminapa.pdf

QUESTION NO: 101 DRAG DROP

On the right, a permanent (P) or temporary (T) license is added to a Cisco ASA 5520. The merged license results in new capabilities for the Cisco ASA 5520. Drag the new resultant license on the left to the merging licenses on the right.

Base (P) + 50 SSL users (P)	Base (P) and 25 SSL users (P). Add 50 SSL users (P).
Base (P) + 50 SSL users (T)	Base (P) and 50 SSL users (T). Add 25 SSL (P).
Base (P) + 25 SSL users (P)	Base (P) and 25 SSL users (P). Add Botnet (T).
Base + 25 SSL users + Botnet	Base (P) and 25 SSL users (P) and Botnet (T). Add 50 SSL (T).

Answer:

On the right, a permanent (P) or temporary (T) license is added to a Cisco ASA 5520. The merged license results in new capabilities for the Cisco ASA 5520. Drag the new resultant license on the left to the merging licenses on the right.

Base (P) + 50 SSL users (P)	Base (P) + 50 SSL users (P)
Base (P) + 50 SSL users (T)	Base (P) + 25 SSL users (P)
Base (P) + 25 SSL users (P)	Base + 25 SSL users + Botnet
Base + 25 SSL users + Botnet	Base (P) + 50 SSL users (T)

Explanation:

Base (P) + 50 SSL users (P)

Base (P) + 25 SSL users (P)

Base + 25 SSL Users + Botnet

Base (P) + 50 SSL Users (T)

QUESTION NO: 102 DRAG DROP

What is the selection hierarchy to which attributes are applied to a clientless SSL VPN user? Drag an attribute policy on the left to the correct priority level within the attribute hierarchy on the right.

Group Policy attributes attached to the user profile	highest priority
User Policy attributes	
DAP attributes	
Default Group Policy attributes	
Group Policy attributes attached to the connection profile	lowest priority

Answer:

What is the selection hierarchy to which attributes are applied to a clientless SSL VPN user? Drag an attribute policy on the left to the correct priority level within the attribute hierarchy on the right.

Group Policy attributes attached to the user profile	DAP attributes
User Policy attributes	User Policy attributes
DAP attributes	Group Policy attributes attached to the user profile
Default Group Policy attributes	Group Policy attributes attached to the connection profile
Group Policy attributes attached to the connection profile	Default Group Policy attributes

Explanation: DAP attributes

User Policy Attributes

Group Policy Attributes attached to the user profile

Group Policy Attributes attached to the connection profile

Default Group Policy Attributes

QUESTION NO: 103 DRAG DROP

Two temporary workers are given clientless SSL VPN access to the corporate network. To restrict their access to the network, match the Cisco ASDM attribute on the left to the restrictive action on the right.

Web ACL	Restrict prelogin policy.
Extended ACL	Restrict postlogin policy.
Group Policy	Restrict ability to browse.
Connection Profile	Restrict access to a specific site.
Disable URL entry	
Web Portal Network Access Navigation Pane	

Answer:

Two temporary workers are given clientless SSL VPN access to the corporate network. To restrict their access to the network, match the Cisco ASDM attribute on the left to the restrictive action on the right.

Web ACL	Connection Profile
Extended ACL	Group Policy
Group Policy	Disable URL entry
Connection Profile	Web ACL
Disable URL entry	
Web Portal Network Access Navigation Pane	

Explanation: Connection Profile

Group Policy

Disable URL entry

Web ACL

QUESTION NO: 104 DRAG DROP

Match the Diffie-Hellman group on the left with the correct application on the right. (Not all items will be used.)

D-H group 1	default for remote-access VPN—Aggressive mode
D-H group 2	recommended for remote-access VPN with PDAs
D-H group 3	recommended for remote-access VPN using AES-192
D-H group 5	default for site-to-site VPN—certificate-based
D-H group 7	

Answer:

Match the Diffie-Hellman group on the left with the correct application on the right. (Not all items will be used.)

D-H group 1	D-H group 2
D-H group 2	D-H group 7
D-H group 3	D-H group 5
D-H group 5	D-H group 3
D-H group 7	

Explanation: D-H group 2

D-H group 7

D-H group 5

D-H group 3

QUESTION NO: 105 DRAG DROP

Match the action on the left with the correct SSL VPN Portal Page Navigation button on the right.

To access files in your network to which you have been granted access	Web Application button
To access the Cisco AnyConnect client	Browse Networks button
To access smart tunnels	Application Access button
To access plug-in applications	Network Access button
To access only administrator defined corporate resources	VNC Connections button

Answer:

Match the action on the left with the correct SSL VPN Portal Page Navigation button on the right.

To access files in your network to which you have been granted access	To access plug-in applications
To access the Cisco AnyConnect client	To access files in your network to which you have been granted access
To access smart tunnels	To access smart tunnels
To access plug-in applications	To access the Cisco AnyConnect client
To access only administrator defined corporate resources	To access only administrator defined corporate resources

Explanation:

To access plug-in applications

To access files in your network to which you have been granted access

To access smart tunnels

To access the Cisco AnyConnect client

To access only administrator defined corporate resources

QUESTION NO: 106 DRAG DROP

Match the protocol or port number on the left with the correct protocol or application on the right. (Not all items used.)

IP Protocol 50	NAT-Traversal
IP Protocol 51	IKE
UDP Port 500	ESP
UDP Port 4500	IPsec over TCP
TCP Port 10000	
TCP Port 443	

Answer:

Match the protocol or port number on the left with the correct protocol or application on the right. (Not all items used.)

IP Protocol 50

IP Protocol 51

UDP Port 500

UDP Port 4500

TCP Port 10000

TCP Port 443

UDP Port 4500

UDP Port 500

IP Protocol 50

TCP Port 10000

Explanation: UDP Port 4500

UDP Port 500

IP Protocol 50

TCP Port 10000

QUESTION NO: 107 DRAG DROP

Match the characteristic on the left with the correct transport layer protocol on the right.

used to tunnel traffic over TCP 443

replaced underlying transport layer with UDP 443

enabled by default

requires retransmission of lost packets

used to transmit datagrams

Used to negotiate control messages

TLS

DTLS

Answer:

Match the characteristic on the left with the correct transport layer protocol on the right.

used to tunnel traffic over TCP 443	TLS
replaced underlying transport layer with UDP 443	used to tunnel traffic over TCP 443
enabled by default	requires retransmission of lost packets
requires retransmission of lost packets	Used to negotiate control messages
used to transmit datagrams	DTLS
Used to negotiate control messages	replaced underlying transport layer with UDP 443
	enabled by default
	used to transmit datagrams

Explanation: TLS

Used to tunnel traffic over TCP 443

Requires retransmission of lost packets

Used to negotiate control messages

DTLS

replaced underlying transport layer with UDP 443

enabled by default

used to transmit datagrams

QUESTION NO: 108 DRAG DROP

Match the characteristic on the left with the correct IKE Mode on the right.

IPsec Session Keys	IKE Main Mode
Supports dynamically addressed peers using PSK	
D-H Group 2-Default	
IPsec SA	IKE Aggressive Mode
D-H Group 1-Default	
Protects Peer Identity	IKE Quick Mode

Answer:

Match the characteristic on the left with the correct IKE Mode on the right.

IPsec Session Keys	IKE Main Mode
Supports dynamically addressed peers using PSK	Protects Peer Identity
D-H Group 2-Default	D-H Group 1-Default
IPsec SA	IKE Aggressive Mode
D-H Group 1-Default	Supports dynamically addressed peers using PSK
Protects Peer Identity	D-H Group 2-Default
	IKE Quick Mode
	IPsec Session Keys
	IPsec SA

Explanation:

Protects Peer Identity

D-H group 1-Default

Supports dynamically addressed peers using PSK


D-H Group 2-Default



IPSec Session Keys

IPSec SA

QUESTION NO: 109

Refer to following Exhibit and answer the following question below:






The user, contractor1, will receive an IP address when the VPN connection is established. Which statement regarding the IP address is true?

- A. Is sourced from the contractor pool
- B. Is sourced from the employee pool
- C. Is sourced from the engineering pool
- D. Is sourced from the management pool
- E. Is a dedicated address (10.0.4.1 20)

Answer: A

Explanation:




Through configuration

first see username in device management >> see its group policy then go to remote access VPN


>> connection profiles >> client address pools >> contractor >> select t see the address pool


Through Monitoring VPN statistics > session >> see username and its assigned ip address >> then find it out in configuration tab above procedure



QUESTION NO: 110

Refer to following Exhibit and answer the following question below:






Which group policy restricts the VPN user access to VLAN 100?

- A. Employee
- B. Contractor
- C. Management
- D. Engineering

Answer: B

Explanation:


configuration > network client access > any connect connection profiles > connection profiles > edit



C:\Documents and Settings\user-nwz\Desktop\1.JPG

Foreach profile > general > more options > restricted VLAN



Monitoring > VPN > VPN statistics Sessions, vlan mapping sessions



C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 111

Refer to following Exhibit and answer the following question below:




Which connection profile supports SSL VPN Client access only.

- A. Employee
- B. Contractor
- C. Management
- D. Engineering
- E. New_hire

Answer: B



Explanation: (Answer can change so follow the procedure below)


Configuration> network client access > any connect connection profiles > connection profiles > edit
for each profile > general > more options > tunneling protocol > see the check marks



QUESTION NO: 112

Refer to following Exhibit and answer the following question below:






After providing the correct VPN login credentials, user, contractor1, is enabled to use which VPN access type?

- A. Cisco Any Connect VPN
- B. Clientless VPN
- C. Cisco Any Connect VPN and clientless VPN
- D. Cisco Any Connect VPN, clientless VPN, and IPsec VPN

Answer: C


Explanation: Configuration> network client access > any connect connection profiles > connection profiles > edit for each profile > general > more options > tunneling protocol > see the check marks

Monitoring > VPN > VPN statistics > sessions filter by >>> choose contractor1



C:\Documents and Settings\user-nwz\Desktop\1.JPG



Monitoring > VPN > VPN statistics > sessions filter by >>> choose contractor1



C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 113

Refer to following Exhibit and answer the following question below:



Upon logging in, user employee1, has two privileges: (Choose two)

- A. Cisco ASDM, SSH, Telnet, and console access
- B. CLI login prompt for SSH, Telnet, and console only

- C. No Cisco ASDM, SSH, or console access
- D. Level 15
- E. Level 2
- F. Level 3


Answer: D,E

Explanation:

Command authorization

If you turn on command authorization using the local database, then the security appliance refers to the userprivilege level to determine what commands are available. Otherwise, the privilege level is not generally used.



By default, all commands are either privilege level 0 or level 15. ASDM allows you to enable three predefined privilege levels, with commands assigned to level 15 (Admin), level 5 (Read Only), and level 3 (Monitor Only). If you use the predefined levels, then assign users to one of these three privilege levels. This should show assigned levels for us; on my demo version I could get the advanced tab to appear on aaaauthorization to setup other commands but this shows how I setup contractor1



C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 114

Refer to following Exhibit and answer the following question below:



The user, contractor1, receives an IP address when the VPN connection is established. Which statement regarding the IP address is true?

- A. it is sourced from the contractor pool.
- B. it is sourced from the employee pool.
- C. it is sourced from the engineering pool.
- D. it is sourced from the management pool.
- E. it is dedicated address (10.0.4.120)

Answer: C

Explanation:

First see username in device management >> see its group policy then go to remote access VPN >> connectionprofiles >> client address pools >> contractor >> select to see the address pool Through MonitoringVPN statistics > session >> see username and its assigned ip address >> then find it out inconfiguration tab above procedureold DD download contained Exam question 30 (As Q29) that had answer of contractor not engineering like forthis question 35.


QUESTION NO: 115 CORRECT TEXT

Scenario

You are the firewall administrator for a small company. The company currently supports SSLVPN for employees only. Your job is to add support for a new group of AnyConnect SSLVPN users, contractors, on the Cisco ASA, using ASDM. For this exercise, the SSLVPN Wizard has been deactivated. You will be asked to add a new connection profile, a new group policy, and a new user account. The detailed information that you will need to complete the configurations is as follows:

- New connection profile
 - Name: contractor
 - AAA server group: LOCAL
 - Connection Alias: contractor
 - Group URL: <https://192.168.4.2/contractor>
- New IP address pool
 - Name: contractor
 - IP address range: 10.0.4.50/24 - 10.0.4.70/24
- New internal group policy
 - Name: contractor
 - Associate the new group policy to the contractor connection profile
 - Only these two tunneling protocols are permitted: client and clientless SSL VPN
 - Add a new banner: "Welcome Contractors"
- Local User
 - Name: contractor1
 - Password: cisco
 - "contractor1" access restrictions: no ASDM, SSH, Telnet, or console access
 - Lock contractor1 user to the contractor connection profile

Scenario | **TOPOLOGY**



Answer: Here is the solution step by step below:

Explanation:

My revised answer:

Navigate to:

Configuration > Remote Access VPN > Network (Client) Access > Address Assignment > Address Pools

C:\Documents and Settings\user-nwz\Desktop\1.JPG

Address Pools:

The screenshot shows the 'Add IP Pool' dialog box in Cisco ASDM. The dialog box has a title bar with a close button. The main area contains four labeled text boxes: 'Name' with the value 'contractor', 'Starting IP Address' with '10.0.4.50', 'Ending IP Address' with '10.0.5.70', and 'Subnet Mask' with '255.255.255.0'. At the bottom, there are three buttons: 'OK', 'Cancel', and 'Help'.


C:\Documents and Settings\user-nwz\Desktop\1.JPG

Navigate to:

Configuration > Remote Access VPN > Network (Client) Access > AnyConnect Connection Profiles

C:\Documents and Settings\user-nwz\Desktop\1.JPG

Connection Profiles ADD



C:\Documents and Settings\user-nwz\Desktop\1.JPG

Advanced SSLVPN:



C:\Documents and Settings\user-nwz\Desktop\1.JPG

Basic:

Add SSL VPN Connection Profile

Basic

Name: contractor

Aliases: contractor

Authentication

Method: ☒ AAA ☐ Certificate ☐ Both

AAA Server Group: LOCAL Manage...

☐ Use LOCAL if Server Group fails

Client Address Assignment

DHCP Servers:

Client Address Pools: contractor Select...

Default Group Policy

Group Policy: DfltGrpPolicy Manage...

(Following field is an attribute of the group policy selected above.)

☒ Enable SSL VPN Client protocol

Find: Next Previous

OK Cancel Help

C:\Documents and Settings\user-nw\Desktop\1.JPG

Navigate to:

[Configuration > Remote Access VPN > Network \(Client\) Access > Group Policies](#)

C:\Documents and Settings\user-nw\Desktop\1.JPG

Add Internal Group Policy

General

Name: contractor

Banner: ☐ Inherit Welcome Contractors

Address Pools: ☒ Inherit Select...

More Options

Tunneling Protocols: ☐ Inherit ☒ Clientless SSL VPN ☒ SSL VPN Client ☐ IPsec ☐ L2TP/IPsec

Filter: ☒ Inherit Manage...

NAC Policy: ☒ Inherit Manage...

Access Hours: ☒ Inherit Manage...

Simultaneous Logins: ☒ Inherit

Restrict access to VLAN: ☒ Inherit

Connection Profile (Tunnel Group) Lock: ☐ Inherit contractor

Maximum Connect Time: ☒ Inherit ☐ Unlimited minutes

Idle Timeout: ☒ Inherit ☐ Unlimited minutes

Find: Next Previous

OK Cancel Help


C:\Documents and Settings\user-nw\Desktop\1.JPG

Navigate back to:

[Configuration > Remote Access VPN > Network \(Client\) Access > AnyConnect Connection Profiles](#)

C:\Documents and Settings\user-nwz\Desktop\1.JPG

And update Default Group Policy



C:\Documents and Settings\user-nwz\Desktop\1.JPG

Navigate to:

Configuration > Remote Access VPN > AAA/Local Users > Local Users

C:\Documents and Settings\user-nwz\Desktop\1.JPG

Add User Account

Identity

- VPN Policy
 - Clientless SSL VPN
 - SSL VPN Client

Username: contractor1

Password: *****

Confirm Password: *****

☐ User authenticated using MSCHAP

Access Restriction

Select one of the options below to restrict ASDM, SSH, Telnet and Console access.
Note: All users have network access, regardless of these settings.

☐ Full access(ASDM, SSH, Telnet and Console)
Privilege level is used with command authorization.
Privilege Level: 2

☐ CLI login prompt for SSH, Telnet and console (no ASDM access)
This setting is effective only if AAA authenticate console command is configured.

☒ No ASDM, SSH, Telnet or Console access
This setting is effective only if AAA authenticate console command is configured.

Find: ☐ Next ☐ Previous

OK Cancel Help

C:\Documents and Settings\user-nw\Desktop\1.JPG

Then

Add User Account

Identity

- VPN Policy
 - Clientless SSL VPN
 - Customization
 - Single Signon
 - Session Settings
 - SSL VPN Client

Check an Inherit checkbox to let the corresponding setting take its value from the group policy.

Group Policy: ☐ Inherit contractor

Tunneling Protocols: ☒ Inherit ☐ Clientless SSL VPN ☐ SSL VPN Client ☐ IPsec ☐ L2TP/IPsec

Filter: ☒ Inherit Manage

Tunnel Group Lock: ☐ Inherit contractor

Store Password on Client System: ☒ Inherit ☐ Yes ☐ No

Connection Settings

Access Hours: ☒ Inherit Manage

Simultaneous Logins: ☒ Inherit

Maximum Connect Time: ☒ Inherit ☐ Unlimited Minutes

Idle Timeout: ☒ Inherit ☐ Unlimited Minutes

Dedicated IP Address (Optional)


IP Address: Subnet Mask:

Find: ☐ Next ☐ Previous

OK Cancel Help

C:\Documents and Settings\user-nw\Desktop\1.JPG

And we have:



C:\Documents and Settings\user-nwz\Desktop\1.JPG

OLD Answer: Here is the solution step by step below:

ip local pool contractor 10.1.4.50-10.1.4.70 mask 255.255.255.0

group-policy contractor internal

group-policy contractor attributes

vpn-tunnel-protocol ssl-clientless ssl-client

banner value Welcome Contractors

exit

tunnel-group contractor type remote-access

tunnel-group contractor general-attributes

default-group-policy contractors

address-pool contractor

tunnel-group contractors webvpn-attributes

group-alias contractor enable

group-url https://192.168.4.2/Contractor enable

username contractor1 password cisco privilege 2

username contractor1 attributes

service-type remote-access

vpn-group-policy contractors

exit

QUESTION NO: 116 DRAG DROP

Drag and drop each advanced application deployment option on the left to its correct detection on the right.

Application plug-ins

provides users with native application client access to enterprise resources

Smart tunnels

Provides users with thin application client access to enterprise resources

Port forwarding

Provides users with native application client access to enterprise resources on Linux workstations or older Cisco ASA software versions

Answer:

Drag and drop each advanced application deployment option on the left to its correct detection on the right.

Application plug-ins

Smart tunnels

Smart tunnels

Port forwarding

Port forwarding

Application plug-ins

Explanation:

Smart tunnels

Port forwarding

Application plug-ins

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 117

Refer to the exhibit.

```
http://server/homepage/CSCO_WEBVPN_USERNAME.html
ssh://sshserver/?cisco_sso=1
```

Which two statements are correct regarding these two Cisco ASA clientless SSL VPN bookmarks? (Choose two.)

- A. CSCO_WEBVPN_USERNAME is a user attribute.
- B. CSCO_WEBVPN_USERNAME is a Cisco predefined variable that is used for macro substitution.
- C. The CSCO_WEBVPN_USERNAME variable is enabled by using the Post SSO plug-in.
- D. CSCO_SSO is a Cisco predefined variable that is used for macro substitution.
- E. The CSCO_SSO=1 parameter enables SSO for the SSH plug-in.
- F. The CSCO_SSO variable is enabled by using the Post SSO plug-in.

Answer: B,E

Explanation:

http://www.cisco.com/en/US/docs/security/asa/asa80/asdm60/ssl_vpn_deployment_guide/deploy.html

Introduction to URL Variable Substitution:

Your configuration will most likely require personalized resources that contain the username and password, for example, in URL lists or in group URLs. URL variable substitution lets the remote user enter username and password credentials once, when initiating the session, then login automatically to internal resources such as Citrix, OWA, Sharepoint, and the internal portal.

Clientless SSL VPN supports the following macro substitutions:

CSCO_WEBVPN_USERNAME—User login name

CSCO_WEBVPN_PASSWORD—Obtained from user login password

CSCO_WEBVPN_INTERNAL_PASSWORD—Obtained from the Internal password field. You can use this field as Domain for Single Signon operations.

CSCO_WEBVPN_CONNECTION_PROFILE—User login group drop-down (tunnel group alias)

CSCO_WEBVPN_MACRO1—Set via Radius or LDAP vendor specific attribute

CSCO_WEBVPN_MACRO2—Set via Radius or LDAP vendor specific attribute

Each time the security appliance recognizes one of these strings in an end-user request, it replaces the string with the user-specific value before passing the request to a remote server.

For example, a URL list that contains the link:

http://someserver/homepage/CSCO_WEBVPN_USERNAME.

Html is translated by the security appliance to the following links for SSL VPN USER1 and USER2:

<http://someserver/homepage/USER1.html>

<http://someserver/homepage/USER2.html>

QUESTION NO: 118

Which three statements are Cisco AnyConnect VPN Client deployment options? (Choose three.)

- A.** Configure the Cisco AnyConnect profile to automatically launch client or clientless SSL VPN upon discovering a trusted network.
- B.** Automatically download the Cisco AnyConnect VPN Client upon Cisco IOS WebVPN login.
- C.** Prompt user upon Cisco IOS WebVPN login to select client or clientless SSL VPN within X seconds.
- D.** Configure the Cisco AnyConnect profile to automatically disconnect the client or clientless SSL VPN tunnel upon discovering an untrusted network.
- E.** User manually launches client from SSL VPN clientless portal.


Answer: B,C,E

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/anyconnect/anyconnect24/administration/guide/ac01intro.html

QUESTION NO: 119

Refer to the exhibit.



A network administrator is duplicating a VPN client profile to send out to all members of the finance group. Three parameters might have been configured incorrectly. For each three letters, choose the correct answer. (Choose three.)

- A.** A-Remote Client IP Address

- B. A-ASA Outside Interface IP Address
- C. B-Pre-Shared Keys Authentication Type
- D. B-Digital Certificate Authentication Type
- E. C-Save Password enabled
- F. C-Save Password disabled

Answer: B,C,E

Explanation:

http://www.cisco.com/en/US/docs/security/vpn_client/cisco_vpn_client/vpn_client500_501/administration/5vcAch5.html#wpmkr1201344

Host=	Remote server address The hostname or IP address of the Cisco remote access server (a VPN central-site device) to which remote users connect.	Internet hostname, or IP address in dotted decimal notation. Maximum 255 alphanumeric characters.	Connection Entry > New/Modify
AuthType=	Authentication type For a description of authentication and authentication types, see the VPN Client user guides for the platform you are using.	The authentication type of this user: 1 = Pre-shared keys (default) 3 = Digital Certificate using an RSA signature. 5 = Mutual authentication (see note below)	Connection Entry > New/Modify > Authentication
SaveUserPassword	Determines whether or not the user password or its encrypted version are valid in the profile. This value is pushed down from the VPN central-site device.	0 = (default) do not allow user to save password information locally. 1 = allow user to save password locally.	Does not appear in GUI.

C:\Documents and Settings\user-nwz\Desktop\1.JPG

QUESTION NO: 120

The administrator configured a Cisco ASA 5505 as a Cisco Easy VPN hardware client and also defined a list of Cisco Easy VPN backup servers in the Cisco ASA 5505. After an outage of the primary VPN server, you notice that your Cisco Easy VPN hardware client has now reconnected via a backup server that was not defined within the original Cisco Easy VPN backup servers list. Where did your Cisco Easy VPN hardware client get this backup server?

- A. The backup servers that you listed were no longer available, so the Cisco Easy VPN hardware client queried the load balance server for a "new" backup server address.
- B. The backup servers that you listed were no longer available, so a Group Policy that was

configured on the primary VPN server pushed "new" backup server addresses to your client.

C. The backup servers that you listed were no longer available, so the Cisco Easy VPN hardware client queried the primary VPN server via RADIUS protocol for a "new" backup server address.

D. The backup servers that you listed were no longer available, so the Cisco Easy VPN hardware client queried and received from a predefined LDAP server a "new" backup server address.

Answer: B

Explanation:

<http://www.cisco.com/en/US/docs/security/asa/asa84/command/reference/b.html#wp1366328>

Usage Guidelines

To remove the backup-servers attribute from the running configuration, use the no form of this command without arguments. This enables inheritance of a value for backup-servers from another group policy. IPsec backup servers let a VPN client connect to the central site when the primary ASA is unavailable. When you configure backup servers, the ASA pushes the server list to the client as the IPSec tunnel is established.

Configure backup servers either on the client or on the primary ASA. If you configure backup servers on the ASA, it pushes the backup server policy to the clients in the group, replacing the backup server list on the client if one is configured.

QUESTION NO: 121

A network architect designed a redundant site-to-site IPsec VPN. In this site-to-site IPsec VPN solution are two standalone Cisco ASA appliances that are deployed at the headquarters office site. A site-to-site VPN tunnel is established between the remote office and online peer (192.168.4.1).

To enable the remote office devices to be advertised correctly at headquarters, select the three

Cisco ASA parameters and the ends in which they should be applied. R=remote end; H=headquarters end. (Choose three)

- A. R-Configure Originate-Only
- B. H-Configure Originate-Only
- C. R-Configure Answer-Only
- D. H-Configure Answer-Only
- E. R-Enable RRI
- F. H-Enable RRI

Answer: A,D,F

Explanation:

<http://secret-epedemiology-statistic.org.ua/1587052091/ch15lev1sec4.html>

Connection Type

The Cisco ASA in the site-to-site tunnel can respond and initiate a VPN connection. This bidirectional default behavior can be changed to answer-only or originate-only mode. For example, if you want to limit the security Cisco ASA to just initiate IKE tunnels, you can set the connection type to originate-only. This way, if the remote VPN peer tries to initiate the connection, the local Cisco ASA will not honor the request. Similarly, if you want the security Cisco ASA to accept IKE tunnels only from the peer, then you can set the connection type to answer-only. The command syntax to set the connection type is

`Cryptomap map-name seq-num set connection-type {answer-only | bidirectional |`