Ultimo REST connector Jobs



Ultimo software version: Ultimo 2021 and rolling release

Document version: Version 1.0
Date: 2020-06-03






TABLE OF CONTENTS

1	Functional details	
2	Technical details	5



1 Functional details

This REST connector allows third parties to create a job in Ultimo. This functionality is similar to reporting a job in Ultimo. Ultimo acts as a server in this connector. The flow is simple and depicted below:



The following parameters are used in the request.

Description	The description of the job. This parameter is required.
ReportText	This is the additional information for a job. The value of
	this string will be set in the text field in section "Report".
	This parameter is required.
ReportDate	This is the date on which the job has been reported.
	Allowed formats:
	- yyyy-MM-dd hh:mm:ss (i.e. 2018-08-21 15:21:59)
	- UTC: yyyy-MM-ddThh:mm:ssZ (i.e. 2018-08-
	20T15:17:592).
	201.5
	This property is optional. The default value is the
	CurrentDateTime.
ProcessFunctionId	The Id of the entity ProcessFunction. This property is
1 TOCC331 di Tectorila	optional. It is possible to use ProcessFunction from
	every context (eg Fleetnumbers).
EquipmentId	The Id of the entity Equipment. This property is
Equipitiericia	
	optional. It is possible to use Equipment from every
Conservation	context (eg Objects).
SpaceId	The Id of the entity Space. This property is optional.
SiteId	The Id of the entity Site. This property is optional.
WorkOrderTypeId	The Id of the entity WorkOrderType (this is usually the
	job type of a job). This property is optional
Context	The context for the job. Allowed values: context
	values/numbers (eg 1) or context names (eg
	JobContext.TD). This property is optional. The default
	value is JobContext.TD.



When these parameters are properly filled in, Ultimo will give a HTTP 200 response with the following properties:

Jobid

The internal Id of the created job in Ultimo.

There are a few clarifications for using this connector:

- The created job will always have the status Open (JobStatus.Created), as a consequence this created job will be mostly found on the Prepare jobs screens in Ultimo.
- Active Service Level Agreements (SLA) can get triggered with this connector. However, the ReportDate can be freely editted in the request, in contrast to the Ultimo application where this field is protected. As a consequence, this means a report date can be set in the past. When an active SLA is triggered for say an equipment, it is possible the business logic will place the scheduled start date and the scheduled target date in the past as well. The connector will not give warnings about dates in the past or about expired Service Level Agreements (for a job). When the parameter ReportDate has no value or is not used as parameter, the default will be the CurrentDateTime.
- The Site will be filled on the job following a certain order. When the parameter SiteId has a valid value, the Site belonging to this Id will be filled on the job.
 If SiteId has no value, the Site of Equipment will be filled on the job. If the Equipment does not have a Site (or if there is no Equipment), the Site of ProcessFunction will be filled on the job. When a ProcessFunction does not have a Site either (or there is no ProcessFunction), and consequently no Site is filled on the job, the created record might not be visible because of active record authorisation.
- When Equipment has a Department and/or a CostCenter and the application settings 'Method: Determining the department" and "Method: Determining the cost centre" are set right, these fields will be also be filled on the job.
- If an equipment or a space has an additional building hierarchy (eg BuildingFloor, BuildingPart, Building), these fields will also be filled on the created job.



2 Technical details

Basic URL (POST):

https://customer.ultimo.com/api/V1/Action/REST ReportJob

Header data:

ApiKey	Request an API key at (application manager or consultant)
ApplicationElementId	Fixed value "1ba90cc1-b7f2-452d-8825- 101ad7e7a682"

Body (example):

```
{
   "Description": "Malfunction in bread line N.PRO.01",
   "ReportText": "The formatting machine is creating ugly shapes",
   "ProcessFunctionId": "N.PRO.01",
   "EquipmentId": "39772",
   "ReportDate": "2020-05-27 10:00:00",
   "SpaceId": "P-42",
   "SiteId": "02",
   "Context": "JobContext.TD",
   "WorkOrderTypeId": "007"
}
```

Normal response:

Status: 200 OK

```
{
    "properties": {
        "JobId": "0005446"
      }
}
```

Response when the action is not allowed:

Status: 400 Bad Request

```
{
    "message": "Job cannot be created.\r\nCause: Equipment '397722' cannot be found.",
    "type": 3,
    "code": "3399"
}
```

Response when the API-key is invalid:

Status: 401 Unauthorized

```
{
    "message": "Missing API key",
    "code": "MissingApiKey"
}
```



© 2019 Ultimo Software Solutions Ltd

This document is protected by copyright law. No part of this publication may be reproduced, stored in an automated database and/or published in any form or by any means, either electronically, mechanically, by means of photocopying, recording or otherwise, without the prior written approval of Ultimo Software Solutions Ltd.

Despite the fact that this document has been compiled with the utmost care and attention, Ultimo Software Solutions Ltd does not accept any liability for damage caused by errors and/or discrepancies in this document.

Ultimo and the Ultimo logo are registered wordmarks and logos of Ultimo Software Solutions Group bv. Other product and company names referred to in this manual are wordmarks, trademarks and tradenames of the relevant owners.