

CBOE Application Programming Interface

Version 9.0.2

CBOE API Volume 7: CBOEdirect Certification and Testing Procedures

Outlines test and certification procedures for client applications using the CMi interface to access the CBOE Network.

CBOE PROPRIETARY INFORMATION

15 July 2011

Document #[API-07]

Disclaimer

Copyright © 1999-2011 by the Chicago Board Options Exchange (CBOE), as an unpublished work. The information contained in this document constitutes confidential and/or trade secret information belonging to CBOE. This document is made available to CBOE members, member firms and other appropriate parties to enable them to develop software applications using the CBOE Market Interface (CMi), and its use is subject to the terms and conditions of a Software License Agreement that governs its use. This document is provided "AS IS" with all faults and without warranty of any kind, either express or implied.

Table of Contents

| DISCLAIMER | II |
|--|----|
| TABLE OF CONTENTS | 3 |
| Table of Figures | |
| TABLE OF TABLES | |
| CHANGE NOTICES | 6 |
| ABOUT THIS DOCUMENT | 8 |
| Purpose | |
| Intended Audience | |
| RELATED DOCUMENTS | |
| SUPPORT AND QUESTIONS REGARDING THIS DOCUMENT | |
| INTRODUCTION | |
| IMPLEMENTING AN APPLICATION USING THE CMI | |
| DEVELOPMENT | |
| TEST ENVIRONMENT. | |
| TESTING AND CERTIFICATION | |
| Phase 1. Stand Alone Testing using the CBOE Application Server Simulator | |
| Phase 2. Connectivity Testing with CBOE | |
| Phase 3. Application Test | |
| Phase 4. Assurance Test | |
| Phase 5. Production Test | |
| CERTIFICATION PROCESS | |
| | |
| CERTIFICATION TESTING PHASES | |
| Entry Criteria | |
| Inputs | |
| Process | |
| Outputs | |
| Exit Criteria | |
| PHASE 2 CONNECTIVITY TEST | |
| Entry Criteria | |
| Inputs | |
| Process | |
| Outputs | |
| Exit Criteria | |
| PHASE 3 APPLICATION TEST | |
| Entry Criteria | |
| Inputs | |
| Process | |
| Outputs | |
| Exit Criteria | |
| Phase 4 Assurance Test | |
| Entry Criteria | |
| Inputs | |
| Process | |
| Outputs | |
| Exit Criteria | |
| PHASE 5 PRODUCTION TEST | |
| Entry Criteria | |
| | |

| Inputs | |
|---|--------------------|
| Process | |
| Outputs | |
| Exit Criteria | 20 |
| GLOSSARY | 21 |
| TEST PLANS / REQUIREMENTS OVERVIEW | 22 |
| PHASE 1 CAS SIMULATOR REQUIREMENTS BY ROLE | |
| PHASE 2 TEST PLANS | 22 |
| Connectivity Test Plan | 22 |
| CAS User Session Test Plan | |
| APPLICATION TEST PLANS | 22 |
| 3a, Security Definition Test Plan | 22 |
| 3b, Market Data Test Plan | |
| 3c, Quote Test Plan – Hybrid-ONE-CFE | 22 |
| 3d, W_MAIN Order Test Plan | 22 |
| 3e, W_MAIN-ONE-CFE Order Test Plan | 22 |
| 3f, Clearing Firm, Duplicate Message Test Plan | 22 |
| 3g, Strategy Quote Test Plan (ONE) | 23 |
| 3h, W_MAIN Strategy Order Test Plan | 23 |
| 3i, W_MAIN-ONE-CFE Strategy Order Test Plan | |
| 3j, (Hybrid Sections of Quote Test Plan - not a separate document) | 23 |
| 3k, (CBOE Futures Exchange (CFE) Supplemental Tests - Contained within docume | ent 3e: Order Test |
| Plan) | 23 |
| 3L, (CBOE Futures Exchange (CFE) Supplemental Tests - Contained within docume Plan) | |
| 3m, Stock Trading On CBOEdirect (STOC) Order Test Plan | |
| 3n, Stock Trading On CBOEdirect (STOC) Quote Test Plan | |
| 30, Stock Trading On CBOEdirect (STOC) DPM Administrative Test Plan | 23 |
| PHASE 3 INTERFACE AND METHOD REQUIREMENTS | 23 |
| PHASE 3 V2 INTERFACE AND METHOD REQUIREMENTS FOR V2.5 ONLY | |
| PRODUCTION ENVIRONMENT TEST PLANS | |
| Phase 4 Test Plan | |
| Additional Information | |
| Callback interfaces | |
| Subscription methods | |
| Exception Handling | |
| • | |
| PHASE 1 CAS SIMULATOR REQUIREMENTS BY ROLE TABLE KEY | |
| CMI::MARKETQUERY INTERFACE | |
| CMIV2::MARKETQUERY INTERFACE | |
| CMI:ORDERENTRY INTERFACE | |
| CMI::ORDERQUERY INTERFACE | |
| CMIV2::OrderQuery Interface | |
| CMI::PRODUCTDEFINITION INTERFACE | |
| CMI::PRODUCTQUERY INTERFACE | |
| CMI::TRADINGSESSION INTERFACE | |
| CMI::QUOTE INTERFACE | |
| CMIV2::QUOTE INTERFACE | |
| CMIV2::USERHISTORY INTERFACE | |
| PHASE 3 INTERFACE AND METHOD REQUIREMENTS | |
| USER ACCESS INTERFACE | |
| CMIUSERSESSIONADMIN INTERFACE | |
| USER SESSION MANAGER INTERFACE | 32 |

| Market Query Interface | 34 |
|---|----|
| CMICURRENTMARKETCONSUMER INTERFACE | |
| CMINBBOCONSUMER INTERFACE | 35 |
| CMIEXPECTEDOPENINGPRICECONSUMER INTERFACE. | 36 |
| CMIRECAPCONSUMER INTERFACE | 36 |
| CMITICKERCONSUMER INTERFACE | 36 |
| CMIORDERBOOKCONSUMER INTERFACE | 36 |
| CMIORDERBOOKUPDATECONSUMER INTERFACE | 37 |
| CMIPRODUCTSTATUSCONSUMER INTERFACE | 37 |
| CMISTRATEGYSTATUSCONSUMER INTERFACE | 37 |
| QUOTE INTERFACE | 37 |
| CMIQUOTESTATUSCONSUMER INTERFACE | 39 |
| CMIRFQConsumer Interface | 39 |
| Order Query Interface | |
| Order Entry Interface | |
| CMIORDERSTATUSCONSUMER INTERFACE | 43 |
| PRODUCT QUERY INTERFACE | 44 |
| PRODUCT DEFINITION INTERFACE | |
| USER PREFERENCE QUERY INTERFACE | 45 |
| ADMINISTRATOR INTERFACE | |
| TRADING SESSION INTERFACE | |
| CMITradingSessionStatusConsumer Interface | |
| CMICLASSSTATUSCONSUMER INTERFACE | 47 |
| USER HISTORY INTERFACE | |
| USER TRADING PARAMETERS INTERFACE | 47 |
| VERSION INTERFACE | |
| | 40 |
| PHASE 3 V2 INTERFACE AND METHOD REQUIREMENTS FOR V2.5 AND HIGHER | |
| CMIV2::MarketQuery Interface | 49 |
| CMIV2::OrderQuery Interface CMIV2::Quote Interface | 31 |
| CMIV2::QUOTE INTERFACE | 52 |
| | |
| CMIV2::UserSessionManagerV2 Interface | 33 |
| PHASE 3 V2 INTERFACE AND METHOD REQUIREMENTS FOR V2.6 AND HIGHER | 55 |
| CMIINTERMARKET::INTERMARKETMANUALHANDLING INTERFACE | |
| CMIINTERMARKET::INTERMARKETQUERY INTERFACE | 56 |
| CMIINTERMARKET::INTERMARKET USER ACCESS INTERFACE | |
| CMIINTERMARKET::INTERMARKETUSERSESSIONMANAGER INTERFACE | 56 |
| CMIINTERMARKET::NBBOAGENT INTERFACE | 57 |
| CMIINTERMARKET::NBBOAGENTSESSIONMANAGER INTERFACE | 57 |
| CMIINTERMARKETCALLBACK::CMIINTERMARKETORDERSTATUSCONSUMER INTERFACE | 57 |
| CMIINTERMARKETCALLBACK::CMINBBOAGENTSESSIONADMIN INTERFACE | 58 |
| Table of Figures | |
| Figure 1 CBOEdirect Certification Process Flowchart | 13 |
| Table of Tables | 21 |
| Table 1 Glossary | 21 |

Change Notices

The following change notices are provided to assist users of the CMi in determining the impact of changes to their applications.

| Date | Version | Description of Change |
|--------------|---------|--|
| 15 Jul 2011 | V9.0.2 | No changes |
| 29 Apr 2011 | V9.0.1 | No changes |
| 14 Jan 2011 | V9.0 | No changes |
| 08 Jan 2010 | V7.0 | No changes |
| 12 Aug 2009 | V6.1 | No changes |
| 22 May 2009 | V6.0 | No changes |
| 25 Nov 2008 | V5.3 | No changes |
| 03 Oct 2008 | V5.2 | No changes |
| 18 Jul 2008 | V5.1 | No changes |
| 29 Feb 2008 | V5.0 | No changes |
| 18 Jan 2008 | V4.2.4 | No changes |
| 02 Nov 2007 | V4.2.3 | No changes |
| 01 June 2007 | V4.2.2 | No changes |
| 23 Feb 2007 | V4.2.1 | No changes |
| 15 Dec 2006 | V4.2 | No changes |
| 20 Sept 2006 | V4.1 | No changes |
| 25 May 2006 | V4.0 | Referenced the new MDX document, API-08 |
| 06 Jan 2006 | V3.2b | No changes |
| 12 Aug 2005 | V3.2 | No updates |
| 29 Jul 2005 | V3.2 | Modified section: Phase 5 Production test |
| | | Added a new section for the "Cert" environment |
| 08 Apr 2005 | V3.1a | No changes |
| 30 Nov 2004 | V3.1 | Updates for internalization and auctions. |
| 18 June 2004 | V3.0 | Updates for phase 1 quote requirements |
| 28 Apr 2004 | V2.52 | No changes. |
| 06 Feb 2004 | V2.63 | Added support for CBOE Futures |

| Date | Version | Description of Change |
|-------------------|---------|---|
| | | Exchange and Stock trading on CBOEdirect. |
| 10 Oct 2003 | V2.62 | No changes. |
| 29 Aug 2003 | V2.61 | Broker dealer support for quote lock messages and market linkage changes. |
| 31 July 2003 | V2.6 | Support for market linkage and stock |
| 08 July 2003 | V2.51 | Documentation Update |
| 14 Mar 2003 | V2.5 | Support for Hybrid |
| 24 Jan 2003 | V2.1 | Production release update to support Linkage P orders. |
| 20 May 2002 | V2.0.1 | No change. |
| 22 April 2002 | V2.0 | Production Release |
| 27 February 2002 | V2.0b | CMi Version 2.0b Software Development Kit Beta 2 |
| 23 January 2002 | V2.0a | CMi Version 2.0a Software Development Kit Beta 1 |
| 14 December 2001 | V2.0 | Updated documentation only for Version 2.0 |
| 18 May 2001 | V1.0b | Added Market Data role information. |
| 19 March 2001 | V1.0a | Production Update |
| 15 September 2000 | V0.9 | Initial Draft |

About This Document

Purpose

This document outlines and describes each phase of testing to obtain certification to access the CBOE Network using the CBOE Market Interface (CMi).

Intended Audience

Anyone who is involved in the deployment of an application using the CMi to access CBOEdirect®.

Related Documents

| Document Number | Document Description |
|------------------------|---|
| Roadmap.doc | CBOE API and CAS Document Road Map |
| API-01 | CBOE API Volume 1: Overview and Concepts |
| API-02 | CBOE API Volume 2: CMi Programmer's Guide to Interfaces and Operations |
| API-03 | CBOE API Volume 3: CMi Programmer's Guide to Messages and Data Types |
| API-04 | CBOE API Volume 4: CMi Dictionary of Attributes and Operations |
| API-05 | CBOE API Volume 5: Using CMi with Specific Object Request Brokers |
| API-06 | CBOE API Volume 6: Connecting to the CBOE Network |
| API-08 | CBOE API Volume 8: CMi Programmer's Guide to the Market Data Express (MDX) Data Feed |
| CAS-01 | CBOE Application Server Volume 1: Overview and Concepts |
| CAS-02 | CBOE Application Server Volume 2: CBOE Application Server Simulator for Stand Alone Testing |
| NET-01 | CBOE Network Connection Information |

Support and Questions Regarding This Document

Specific questions regarding setting up a test connection to CBOEdirect via CMi can be directed to cmiconnect@cboe.com. General questions regarding CBOEdirect APIs can be directed to 312.786.7300 or api@cboe.com.

Please email hybrid@cboe.com for support for production Hybrid application testing and general Hybrid business rules questions.

Introduction

The Chicago Board Options Exchange ("Exchange" or "CBOE") is adding new interfaces to provide access to Exchange services, including CBOEdirectTM. These interfaces are designed to support both electronic and open outcry trading at the CBOE.

The API discussed in this document is the CBOE Market Interface (CMi). This document describes in detail what must be done to pass each phase of testing to become a certified CMi user. Within each phase are entry criteria, inputs, processes, outputs, and exit criteria to move from one phase to the next.

This is a living document and will be updated periodically. The most current version of this document can be obtained at the CBOE API web site at http://systems.cboe.com/webapi/.

Implementing an application using the CMi

Development

Organizations wishing to interface to CBOE exchange services begin by signing the License Agreement and then downloading the CBOE CMi Software Development Kit ("SDK") from the CBOE web site. The SDK contains documentation, software, and example code to start development.

Test Environment

CBOE has a new environment available for firms to use for CMi development and testing. The new environment is called the "Certification" or "Cert" environment. This environment will be the exact same CMi version as production, which will make it easy for your firm to test production issues if they arise. In addition, if your firm is coding to CBOE's APIs to go live in production, your firm may wish to use this new Cert environment to ensure API version compatibility when going live. This environment has all sessions (W_MAIN, CFE_MAIN, ONE_MAIN, UNDERLYING, etc.), similar to the current test environment.

Testing and Certification

The testing and certification of your application is done in phases. Each testing phase must be performed in sequential order. Each phase is described below. Some software vendors supply an API to their end-user for certain functionality to be performed. The end-user would have to test the software vendor's API using this functionality in the CBOEdirect test environment before proceeding to the production environment (phase 4) despite the fact that the software vendor has already passed the functionality tests in the test environment.

Phase 1. Stand Alone Testing using the CBOE Application Server Simulator

Once an application has been developed it should be tested using the stand alone CBOE Application Server (CAS) Simulator that is provided with the CMi SDK. The CAS Simulator is a software program that emulates the CBOE Application Server. The Simulator is provided with a predefined set of responses that can be used to test applications written to the CBOE APIs. All firms that plan to dial in to the CBOEdirect CMi test environment of must first submit an error free CMi Simulator audit log showing message calls to all required methods before access to the test environment will be granted.

Phase 2. Connectivity Testing with CBOE

Verify that your application can talk to a version of the CAS running at CBOE.

2 CMi Phase 2 Test Plan

Phase 3. Application Test

Verify that your application behaves properly with a CAS running at the CBOE via a dial-up connection. All test plans must be repeated exception free.

- 3a Security Definition Test Plan
- 3b Market Data Test Plan
- 3c Quote Test Plan Hybrid-ONE-CFE
- 3d W_MAIN Order Test Plan
- 3e W_MAIN-ONE-CFE Order Test Plan
- 3f Clearing Firm, Duplicate Message Test Plan
- 3g Strategy Quote Test Plan ONE-CFE
- 3h W_MAIN Strategy Order Test Plan
- 3i W_MAIN-ONE-CFE Strategy Order Test Plan
- 3j Hybrid Quote Testing (Contained within 3c Quote Test Plan)
- 3k CBOE Futures Exchange (CFE) Supplemental Tests (Contained within document 3e: Order Test Plan)
- 3L CBOE Futures Exchange (CFE) Supplemental Tests (Contained within document 3c: Quote Test Plan)
- 3m Stock Trading On CBOEdirect (STOC) Order Test Plan
- 3n Stock Trading On CBOEdirect (STOC) Quote Test Plan
- 30 Stock Trading On CBOEdirect (STOC) DPM Administrative Test Plan
- 3x Functionality Acceptance Test

Phase 4. Assurance Test

Hybrid Options

Log on using your production CAS to the CBOEdirect production environment after trading hours. No application testing and no test plans are required.

OneChicago and CBOE Futures Exchange (CFE)

Test your application with the CAS installed at your site connecting to the CBOEdirect production environment outside of trading hours.

4 Phase 4 Test Plan

Stock Trading on CBOEdirect (STOC)

Ask your Systems Client Services (SCS, formerly API Client Relations and Systems Liaison) representative.

Phase 5. Production Test

Hybrid Options

Test your application in production from the CBOE Trading Floor during trading hours using your production hardware, software, and networking. CBOE Trading Operations department will run this test. No test plans are required. The following fake test classes will be used. These are not real stocks and are used for testing purposes only.

HYR (underlying market data is mapped to DJX production underlying market data - *HYR must only be used between 3:02 and 3:30 p.m.*)

HBB (underlying market data is mapped to EBAY production underlying market data)

HTS (underlying market data is mapped to IBM production underlying market data) **HBR** (underlying market data is mapped to MRK production underlying market data)

CBOE Futures Exchange (CFE)

Test your application in the production environment with the CBOE Production Help Desk prior to going live. No test plans are needed.

CH BT

OneChicago

Test your application in the production environment with the CBOE Production Help Desk prior to going live. No test plans are needed.

AK HOB


Stock Trading on CBOEdirect (STOC)

Ask your Systems Client Services representative.

Certification Process

Figure 1 provides an overview of the phases involved in certifying an application with CBOE.

Figure 1 CBOEdirect Certification Process Flowchart



Certification Testing Phases

Each testing phase is outlined below. If you have any questions regarding the certification process or connecting your application to CBOEdirect, call your Systems Client Services representative, call API support at 312.786-7300, or e-mail api@cboe.com. Please email hybrid@cboe.com for questions regarding phase 5 testing and general Hybrid business questions.

Phase 1 Stand-Alone Testing

During stand alone testing you will use the CAS Simulator that is provided with the CMi Software Development Kit (CMi/SDK). Once you are satisfied that your firm's application implements the required CAS Simulator interfaces and methods you will submit the *cas.audit* output log from the CAS Simulator to api@cboe.com. The CBOE will verify the test results before moving on to Phase 2 of testing.

Entry Criteria

• Enter into the appropriate software license agreement with CBOE.

Inputs

- CMi Documentation
- API web site (to access Software License Agreement and Software Development Kit).

Process

- Obtain the CMi/SDK from the CBOE API web site.
- Modify or develop an application that uses the CMi interface.
- Test your application using the CAS Simulator provided with the CMi/SDK.
- Submit the *cas.audit* output log from the CAS Simulator that verifies the interaction of your application with the CAS Simulator.
- Submit the Test Connection Request Form that can be downloaded on the API web site at: http://systems.cboe.com/webapi/.

Outputs

- Application that works with CMi.
- CAS Simulator *cas.audit* output log file that contains results of the interaction with your application. All phase 1 CAS Simulator Required Methods must appear in the log and be exception free (as defined in the *Phase 1 CAS Simulator Requirements by Role* Test Plan which is available for download at the CBOE API web site at: http://systems.cboe.com/webapi/).
- A completed CBOE CMi Test Connection Request Form received by CBOE.

Exit Criteria

- CBOE approval of cas.audit file.
- CBOE reply to CMi Test Connection Request.

Phase 2 Connectivity Test

During this phase your application will connect to a CAS in the test environment at the CBOE. This is done using an analog or ISDN dial-up TCP/IP connection. In lieu of using dial-up, firms may use the CBOE Managed WAN to connect to the CBOEdirect test environment. This test will verify the user's ability to establish a connection to the CAS and basic user session functionality.

Entry Criteria

• CBOE has provided you with a test connection for your firm and CAS configuration information, signifying that your application is ready for testing with the CBOE application testing environment.

Inputs

• Dial up network hardware (router, modem, firewall etc.) configured as described and in documents NET-01 and API-06.

Process

- Schedule the connectivity test with CBOE personnel by contacting api@cboe.com.
- Configure your test network to dial up and connect to the CBOE CMi test environment.
- Establish dial up connection to CBOE.
- Perform the following CMi Phase 2 Test Plans (available for download at the CBOE API web site at http://systems.cboe.com/webapi/):
 - ❖ Connectivity Test Plan: This plan tests network connectivity to the CBOE test environment by pinging the CBOE router, pinging CBOE CAS, and verifying the availability of the CAS HTTP Server.
 - CAS User Session Test Plan: This test plan verifies ability to access the UserAccess interface, login to the CAS, obtain the UserSessionManager interface, and verify acceptable implementation of the CMIUserSessionAdmin callback interface.

Outputs

• Log file from CAS running in CBOE Connectivity test environment.

Exit Criteria

• CBOE verifies results of connectivity tests and approves advancing to Phase 3.

Phase 3 Application Test

During this phase of testing your firm's application will test against a CAS in the test environment at the CBOE using an analog or ISDN dial-up TCP/IP connection. This test is intended to verify that your application operates successfully with a CAS. All of your application and debug logs generated during the testing should be saved for future reference.

Entry Criteria

Successful completion of Phase 2 testing.

Inputs

• Your firm's application establishes a user session with a CAS in the test environment at the CBOE via a dial-up connection.

Process

- The application test environment should be accessed with CBOE Systems Client Services supervision. The application test environment will normally be available 24 hours a day, seven days a week. The CBOE supports the test environment Monday through Friday during local regular business hours. Please contact the API group to find out when the test environment will be shut down for maintenance.
- Execute the appropriate *Phase 3 Application Test Plans* that are available for download at the CBOE API web site at http://systems.cboe.com/webapi/. CBOE will turn on logging and then all test plans must be repeated exception free for phase 3x.

| Test Plan | Broker- Dealer (Broker) | Market- Maker and DPM | Class Display | (Clearing) Firm | Firm Display |
|--|-------------------------------|-----------------------------|------------------|--------------------|-----------------|
| 3a, Security Definition Test Plan | Required | Required | Required | Required | Required |
| 3b, Market Data Test Plan | Suggested | DPM: Required MM: Suggested | Required | Optional | Optional |
| 3c, Quote Test Plan (W_MAIN / ONE) | N/A | Required | N/A | N/A | N/A |
| 3d, W_MAIN Order Test Plan | Required | Suggested | N/A | Required | N/A |
| 3e, W_MAIN / ONE Order Test Plans | Required | Suggested | N/A | Required | N/A |
| 3f, Clearing Firm, Duplicate Message | Required | Required | N/A | Required | Required |
| 3g, Strategy Quote Test Plan (ONE) | Optional | Optional | N/A | Optional | N/A |
| 3h, W_MAIN Strategy Order Test Plan | Optional | Optional | N/A | Optional | N/A |
| 3i, W_MAIN / ONE Strategy Order Test Plan | Optional | Optional | N/A | Optional | N/A |

| Test Plan | Broker- Dealer (Broker) | Market- Maker and DPM | Class Display | (Clearing) Firm | Firm Display |
|---|-------------------------------|---|------------------|--------------------|-----------------|
| 3j, Hybrid Quote Testing (Contained within 3c Quote Test Plan) | N/A | Required for Hybrid | N/A | N/A | N/A |
| 3k, CBOE Futures Exchange (CFE) Supplemental Tests (Contained within document 3e: Order Test Plan) | Required for CFE | Optional | N/A | N/A | N/A |
| 3L, CBOE Futures Exchange (CFE) Supplemental Tests (Contained within document 3c: Quote Test Plan) | N/A | Required for CFE | N/A | N/A | N/A |
| 3m, Stock Trading On CBOEdirect (STOC) Order Test Plan | Required for STOC | Optional for MM, Required for DPMs | N/A | Optional | N/A |
| 3n, Stock Trading On CBOEdirect (STOC) Quote Test Plan | N/A | Required for STOC | N/A | N/A | N/A |
| 30, Stock Trading On CBOEdirect (STOC) DPM Administrative Test Plan | N/A | DPM only | N/A | N/A | N/A |

Outputs

• Test results for each test plan and log review for the 3x portion of the test.

Exit Criteria

- CBOE verifies successful completion of all required methods in each test plan and produces audit log results of test plans.
- Firm calls all phase 3 required methods exception free during a logged 3x functionality acceptance test.
- CBOE approves advancing to the Phase 4 CBOE Acceptance Test.

Phase 4 Assurance Test

During this phase, you will use the production TCP/IP connection as described in document NET-01. CBOE will install and configure a CAS on your firm's premises. Your application will be tested against production CBOEdirect . If the user plans to use the CBOE Trader Workstation, then this phase must be performed.

Entry Criteria

- Successful completion of Phase 3 testing.
- Obtained production connection to CBOEdirect.

Inputs

• *NET-01 Connecting to the CBOE Network* – Production Connection Request

Process

- Acquire a production connection to the CBOE as defined in *NET-01* and *API-06*.
- CBOE will install a CAS on your premises. Related fees can be obtained at the API web site.
- Schedule a production testing session at least one day in advance.
- For Independent Software Vendors (ISV), this phase must be performed at every client site as it checks production connectivity.

Hybrid Options Process

 Log on using your production CAS to the CBOEdirect production environment after trading hours. No application testing and no test plans are required.

OneChicago Futures Process

• Test your application with the CAS installed at your site connecting to the CBOEdirect production environment outside of trading hours. Perform this test using the Phase 4 Test Plan.

Stock Trading on CBOEdirect (STOC)

• Ask your Systems Client Services representative

Outputs

• CBOE test logs for each test plan.

Exit Criteria

- Successful completion of all test plans.
- CBOE approves advancing to the Phase 5 Production Test.

Phase 5 Production Test

The final step in testing is in the production environment. If the user plans to use the CBOE Trader Workstation, then this phase must be performed.

Entry Criteria

You have successfully completed Phase 4 testing.

Inputs

• CMi application configured for production.

Process

- Configure your production environment for connections to CBOEdirect production environment.
- For Independent Software Vendors (ISV), this phase must be performed at each client site.

Hybrid Options

 Test your application in production from the CBOE Trading Floor during trading hours using your production hardware, software, and networking. CBOE Trading Operations department will run this test. No test plans are required. The following fake test classes will be used. These are not real stocks and are used for testing purposes only.

HYR (underlying market data is mapped to DJX production underlying market data - *HYR must only be used between 3:02 and 3:30 p.m.*)

HBB (underlying market data is mapped to EBAY production underlying market data)

HTS (underlying market data is mapped to IBM production underlying market data)

HBR (underlying market data is mapped to MRK production underlying market data)

CBOE Futures Exchange (CFE)

• Test your application in the production environment with the CBOE Production Help Desk prior to going live. No test plans are needed.

CH BT

OneChicago

 Test your application in the production environment with the CBOE Production Help Desk prior to going live. No test plans are needed.

AK HOB

Stock Trading on CBOEdirect (STOC)

• Ask your Systems Client Services representative

Outputs

• CBOE verifies results of testing as described above.

Exit Criteria

• Participation in the live CBOEdirect marketplace.

Glossary

The following contains a list of terms that you should be familiar with when using this document.

| Table 1 Glossary | |
|-------------------------------|--|
| Application Test Plan | Application test cases that certify that a firm is |
| | generating proper requests (for orders, cancel, |
| | cancel/replace) and is properly receiving responses |
| | (execution reports, rejects, cancel reports). |
| Application Test Environment | The CBOEdirect application test environment |
| | consists of a dial up IP network and a CAS that |
| | communicates with a test version of the |
| | CBOEdirect electronic trading system. |
| | The application test environment is used to validate |
| | your application using a CAS connected to the |
| | CBOEdirect electronic trading system. |
| CBOE Trader Workstation | (Also called CBOE GUI) This is a CBOE supplied |
| | graphical user interface that can be used for |
| | entering orders, individual quotes, viewing market |
| | data, etc. |
| Connection Test Environment | The CBOEdirect Connection Test Environment |
| | consists of a dial up IP network and a CAS |
| | Simulator running at the CBOE premises. |
| Connectivity Test Plan | Test cases that are used to verify connectivity |
| | between your application and the CAS that is |
| | running in the Connection Test Environment. |
| Production Connection Request | Form provided on the CBOE API web site |
| | http://systems.cboe.com/webapi to request a |
| | connection to the CBOE Network. |
| W_MAIN | Regular Trading Hours. The W_MAIN trading |
| | session takes place from 8:30 a.m. – 3:15 p.m. CT. |
| Test Connection Request | Form provided on the CBOE API web site |
| | http://systems.cboe.com/webapi that is used to |
| | request a connection to the CBOEdirect test |
| | environment. |
| Test Plan | A set of test cases that must be passed as part of the |
| | certification process. CBOEdirect Test Plans are |
| | available for download at the CBOE API web site |
| | at http://systems.cboe.com/webapi/ . |

Test Plans / Requirements Overview

Test Plans are available for download at the CBOE API web site at http://systems.cboe.com/webapi/.

Phase 1 CAS Simulator Requirements by Role

This section included in this document provides charts that list which methods from which interfaces must be tested and logged in the CAS.audit log file when submitting the file to the CBOE. This test plan applies to Phase 1 only. Currently, this section is not available for download as a separate document.

Phase 2 Test Plans

These test plans are available for download at the CBOE API web site.

Connectivity Test Plan

This test plan verifies proper firm application connectivity to the CBOE.

CAS User Session Test Plan

This test plan verifies that your firm's application properly connects to and establishes a user session with the CAS.

Application Test Plans

These test plans apply to phase 3 of CMi testing.

3a, Security Definition Test Plan

This test plan involves acquiring and dealing with products. It is required for all roles.

3b, Market Data Test Plan

This test plan is required for the Class Display role and suggested for all other roles. It is also required for options DPMs.

3c, Quote Test Plan – Hybrid-ONE-CFE

This test plan is required for Market-Makers and DPMs. It is not allowed for all other roles.

3d. W MAIN Order Test Plan

Contact your Systems Client Services representative to discuss this test plan.

3e. W MAIN-ONE-CFE Order Test Plan

This test plan is for users who intend to submit orders to CBOE, OneChicago, and CFE. It is required for the Broker (Broker-Dealer) and Firm role and suggested for Market-Makers and DPMs. It is not allowed for the Class Display and Firm Display roles.

3f, Clearing Firm, Duplicate Message Test Plan

This test plan is for the (Clearing) Firm, Firm Display, Market-Maker, Broker-Dealer, and DPM roles. It is used to test duplicate messages that are generated when a Firm or Firm Display role logs on to CBOE.

3g, Strategy Quote Test Plan (ONE)

This test plan is optional for Market-Makers and DPMs. It is not allowed for all other roles. It is used for entering complex (multi-leg) quotes in the ONE_MAIN session only.

3h, W_MAIN Strategy Order Test Plan

Contact your Systems Client Services representative to discuss this test plan.

3i, W_MAIN-ONE-CFE Strategy Order Test Plan

This test plan is for users who intend to submit strategy (complex, multi-leg) orders to CBOE and OneChicago. It is optional for the Broker (Broker-Dealer), Market-Maker, DPM, and Firm roles. It is not allowed for the Class Display and Firm Display roles.

3j, (Hybrid Sections of Quote Test Plan - not a separate document)

These sections are for users who intend to submit quotes to Hybrid. It is required for Hybrid Market-Makers and DPMs, but not allowed for all other roles.

3k, (CBOE Futures Exchange (CFE) Supplemental Tests - Contained within document 3e: Order Test Plan)

This test plan is for users who intend to submit orders to CFE. It is optional for the Broker (Broker-Dealer), Market-Maker, DPM, and Firm roles. It is not allowed for the Class Display and Firm Display roles.

3L, (CBOE Futures Exchange (CFE) Supplemental Tests - Contained within document 3c: Quote Test Plan)

These sections are for users who intend to submit quotes to CFE. It is required for CFE Market-Makers and DPMs, but not allowed for all other roles.

3m, Stock Trading On CBOEdirect (STOC) Order Test Plan

This test plan is for users who intend to submit orders to STOC. It is optional for the Broker (Broker-Dealer), Market-Maker, DPM, and Firm roles. It is not allowed for the Class Display and Firm Display roles.

3n, Stock Trading On CBOEdirect (STOC) Quote Test Plan

This test plan is for users who intend to submit quotes to STOC. It is required for STOC Market-Makers and DPMs, but not allowed for all other roles.

30, Stock Trading On CBOEdirect (STOC) DPM Administrative Test Plan

This test plan is required for STOC DPMs and not allowed for all other roles.

Phase 3 Interface and Method Requirements

This section included in this document describes requirements for all interfaces and methods for all roles. This section applies to Phases 3, 4, and 5 of CMi testing. Currently, this section appears in this document and is not available for download as a separate document. This section describes the interfaces and methods that were originally published in V2.0 but are still supported in V2.5.

Phase 3 V2 Interface and Method Requirements for V2.5 only

This section included in this document describes requirements for all interfaces and methods for all roles. This section applies to Phases 3, 4, and 5 of CMi testing. Currently, this section appears in this document and is not available for download as a separate document. This section describes the interfaces and methods that were introduced in V2.5.

Production Environment Test Plans

These test plans apply to Phases 4 of for OneChicago and CBOE Futures Exchange testing.

Phase 4 Test Plan

The Phase 4 Test Plan is a last minute checkout of application functionality before proceeding to phase 5 of CBOEdirect testing. This test plan is currently used for OneChicago and CBOE Futures Exchange only.

Additional Information

Callback interfaces

The implementation of most of the offered business service interfaces involves the use of callback interfaces. To implement and test the methods of the interface requires the developer to exercise the callback interfaces. For example, if the Order Entry interface is implemented, then all methods in the Order Status Callback interface must be tested. If your application calls a message in one of the new V2 interfaces, you will receive a callback from one of the V2 callback interfaces.

Subscription methods

It is recommended that you unsubscribe for any previously subscribed data streams if at any point during your session the data is no longer desired. If your application will not unsubscribe for any data stream until the close of the user session, you do not have to call the unsubscribe methods. The cleanup will take place at logout. Therefore, unsubscribe methods are listed as optional for testing.

Exception Handling

We perform limited tests of your exception handling code at this time. It is the trading system developer's responsibility to verify that all implemented method's expected exceptions are correctly processed. The expected exceptions are listed in the signatures of each method.

Phase 1 CAS Simulator Requirements By Role

Table Key

Shading indicates that a method is not allowed for new development.

The following roles are represented in the tables below:

Market-Maker = MM

DPM = DPM

Broker Dealer = Brok

Firm = Firm

Firm Display = Firm Disp

Class Display = Cls D

The following levels of requirements are used in the tables below:

R = Required

E = Encouraged

O = Optional

N = Not allowed

- = Not applicable

cmi::MarketQuery Interface

Not allowed for new development. The cmiV2::MarketQuery interface must be used instead.

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|-----------------|--|----|-----|------|------|--------------|-------|
| | getBookDepth | О | О | О | О | О | О |
| | (In W_MAIN, a user may only send this | | | | | | |
| | message once per 10 minutes per user for all | | | | | | |
| | options in the W_MAIN session) | | | | | | |
| | getMarketDataHistoryByTime | О | О | О | О | О | О |
| | subscribeBookDepth | N | N | N | N | N | N |
| | subscribeBookDepthUpdate | N | N | N | N | N | N |
| | subscribeCurrentMarketForClass | N | N | N | N | N | N |
| | subscribeCurrentMarketForProduct | N | N | N | N | N | N |
| | subscribeExpectedOpeningPrice | N | N | N | N | N | N |
| | subscribeNBBOForClass | N | N | N | N | N | N |
| | subscribeNBBOForProduct | N | N | N | N | N | N |
| | subscribeRecapForClass | N | N | N | N | N | N |
| | subscribeRecapForProduct | N | N | N | N | N | N |
| | subscribeTicker | N | N | N | N | N | N |
| | unsubscribeBookDepth | N | N | N | N | N | N |
| | unsubscribeBookDepthUpdate | N | N | N | N | N | N |
| | unsubscribeCurrentMarketForClass | N | N | N | N | N | N |
| | unsubscribeCurrentMarketForProduct | N | N | N | N | N | N |
| | unsubscribeExpectedOpeningPrice | N | N | N | N | N | N |
| | unsubscribeNBBOForClass | N | N | N | N | N | N |
| | unsubscribeNBBOForProduct | N | N | N | N | N | N |
| | unsubscribeRecapForClass | N | N | N | N | N | N |

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|--------------------|----------------------------|----|-----|------|------|--------------|-------|
| | unsubscribeRecapForProduct | N | N | N | N | N | N |
| | unsubscribeTicker | N | N | N | N | N | N |

cmiV2::MarketQuery Interface All messages optional for all roles.

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|--------------------|--|----|-----|------|------|--------------|-------|
| | getBookDepthDetails | О | О | О | О | О | 0 |
| | subscribeBookDepthForClassV2 | О | О | О | О | О | О |
| | (Not allowed for classes in W_MAIN. Not | | | | | | |
| | allowed for new development.) | | | | | | |
| | subscribeBookDepthForProductV2 | O | О | O | O | О | О |
| | (Not allowed for classes in W_MAIN. Not | | | | | | |
| | allowed for new development.) | | | | | | |
| | subscribeBookDepthUpdateForClassV2 | О | О | О | О | О | О |
| | (Not allowed for classes in W_MAIN. Not | | | | | | |
| | allowed for new development.) | | | | | | |
| | subscribeBookDepthUpdateForProductV2 | O | О | O | О | O | О |
| | (Not allowed for classes in W_MAIN. Not | | | | | | |
| | allowed for new development.) | | | | | | |
| | subscribeCurrentMarketForClassV2 | 0 | О | 0 | О | О | О |
| | subscribeCurrentMarketForProductV2 | O | О | O | O | О | О |
| | subscribeExpectedOpeningPriceForClassV2 | O | О | O | O | O | О |
| | subscribeExpectedOpeningPriceForProductV2 | O | О | O | O | О | О |
| | subscribeNBBOForClassV2 | О | О | О | О | О | O |
| | subscribeNBBOForProductV2 | О | О | О | О | О | О |
| | subscribeRecapForClassV2 | О | О | О | О | О | Ο |
| | subscribeRecapForProductV2 | O | О | O | О | O | О |
| | subscribeTickerForClassV2 | 0 | О | 0 | О | О | О |
| | subscribeTickerForProductV2 | Ο | О | Ο | О | О | О |
| | unsubscribeBookDepthForClassV2 | О | О | О | О | О | O |
| | unsubscribeBookDepthForProductV2 | О | О | О | О | О | O |
| | unsubscribeBookDepthUpdateForClassV2 | О | О | О | О | 0 | O |
| | unsubscribeBookDepthUpdateForProductV2 | О | О | О | О | О | O |
| | unsubscribeCurrentMarketForClassV2 | О | О | О | 0 | О | 0 |
| | unsubscribeCurrentMarketForProductV2 | О | О | О | 0 | О | 0 |
| | unsubscribeExpectedOpeningPriceForClassV2 | O | О | O | О | О | О |
| | unsubscribeExpectedOpeningPriceForProductV | O | О | O | О | О | О |
| | 2 | | | | | | |
| | unsubscribeNBBOForClassV2 | O | O | O | O | O | О |
| | unsubscribeNBBOForProductV2 | O | О | O | О | О | 0 |
| | unsubscribeRecapForClassV2 | О | О | О | О | О | О |
| | unsubscribeRecapForProductV2 | О | О | О | О | О | 0 |
| | unsubscribeTickerForClassV2 | O | O | Ο | О | О | 0 |

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|--------------------|-------------------------------|----|-----|------|------|--------------|-------|
| | unsubscribeTickerForProductV2 | O | О | О | О | О | О |

cmi::OrderEntry Interface

| Status | Operation | MM | DPM | Brok | Firm | Firm | Cls D |
|----------|---|----|-----|------|------|------|-------|
| (P or F) | | | | | | Disp | |
| | acceptOrder -or- | R | R | R | R | N | N |
| | acceptOrderByProductName | | | | | | |
| | acceptOrderCancelRequest | R | R | R | R | N | N |
| | acceptOrderUpdateRequest | Е | Е | Е | Е | N | N |
| | acceptOrderCancelReplaceRequest | R | R | R | R | N | N |
| | acceptCrossingOrder | - | - | - | - | - | - |
| | Currently not supported in CBOEdirect | | | | | | |
| | AcceptRequestForQuote | Е | Е | R | R | N | N |
| | acceptStrategyOrder | О | О | О | О | N | N |
| | acceptStrategyOrderUpdateRequest | О | О | О | О | N | N |
| | acceptStrategyOrderCancelReplaceRequest | О | О | О | О | N | N |

cmi::OrderQuery Interface

Subscription messages are not allowed for new development. The cmiV2::OrderQuery interface must be used for order subscriptions.

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|--------------------|-------------------------------------|----|-----|------|------|--------------|-------|
| (1 01 1) | getPendingAdjustmentOrdersByProduct | 0 | O | O | О | O | N |
| | getPendingAdjustmentOrdersByClass | | О | О | О | О | N |
| | queryOrderHistory | О | О | 0 | О | О | N |
| | getOrdersForProduct | Е | Е | Е | Е | N | N |
| | getOrdersForSession | Е | Е | Е | Е | N | N |
| | getOrderById | О | О | О | О | О | N |
| | getOrdersForType | О | О | 0 | О | 0 | N |
| | getOrdersForClass | О | О | 0 | О | 0 | N |
| | subscribeOrders -or- | N | N | N | N | N | N |
| | subscribeOrdersWithoutPublish | | | | | | |
| | subscribeOrdersByFirmWithoutPublish | N | N | N | N | N | N |
| | subscribeOrdersByFirm | N | N | N | N | N | N |
| | unsubscribeOrderStatusForProduct | N | N | N | N | N | N |
| | unsubscribeOrderStatusForSession | N | N | N | N | N | N |
| | unsubscribeOrderStatusForFirm | N | N | N | N | N | N |
| | unsubscribeAllOrderStatusForType | N | N | N | N | N | N |
| | unsubscribeOrderStatusByClass | N | N | N | N | N | N |

cmiV2::OrderQuery Interface

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|--------------------|---|----|-----|------|------|--------------|-------|
| | subscribeOrderStatusV2 -or- subscribeOrderStatusForClassV2 | | R | R | R | N | N |
| | subscribeOrderStatusForFirmV2 -or- subscribeOrderStatusForFirmForClassV2 | N | N | N | R | N | N |
| | unsubscribeOrderStatusV2 | О | О | О | N | N | N |
| | unsubscribeOrderStatusForClassV2 | О | О | О | N | N | N |
| | unsubscribeOrderStatusForFirmV2 | N | N | N | О | N | N |
| | unsubscribeOrderStatusForFirmForClassV2 | N | N | N | О | N | N |

cmi::ProductDefinition Interface

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|--------------------|----------------------------------|----|-----|------|------|--------------|-------|
| | acceptStrategy | О | О | О | О | О | О |
| | buildStrategyRequestByName | О | О | О | О | О | О |
| | buildStrategyRequestByProductKey | О | О | О | О | О | О |

cmi::ProductQuery Interface

| | Operation | MM | DPM | Brok | Firm | Firm | Cls D |
|----------|------------------------------|----|-----|------|------|------|-------|
| (P or F) | . D. 1 . W | | | | - | Disp | |
| | getProductTypes | О | О | О | О | О | О |
| | getProductClasses | О | O | O | O | O | О |
| | getProductsByClass | О | О | О | О | О | О |
| | getProducts | О | О | О | О | О | О |
| | getProductByName | О | О | О | О | О | О |
| | getProductNameStruct | О | О | О | О | О | О |
| | getProductClassByKey | О | О | О | О | О | О |
| | getProductByKey | О | О | О | О | О | О |
| | getClassByKey | О | О | О | О | О | О |
| | getClassBySymbol | О | О | О | О | О | О |
| | isValidProductName | О | О | О | О | О | О |
| | getAllPendingAdjustments | О | О | О | О | О | О |
| | getPendingAdjustments | О | О | О | О | О | О |
| | getPendingAdjustmentProducts | О | О | О | О | О | О |
| | getStrategyByKey | 0 | 0 | 0 | 0 | 0 | 0 |
| | getStrategiesByClass | О | О | О | О | О | О |
| | getStrategiesByComponent | 0 | 0 | 0 | 0 | 0 | 0 |

cmi::TradingSession Interface

| | Operation | MM | DPM | Brok | Firm | Firm | Cls D |
|----------|--|----|-----|------|------|------|-------|
| (P or F) | | | | | | Disp | |
| | getCurrentTradingSessions | R | R | R | R | R | R |
| | getProductTypesForSession | R | R | R | R | R | R |
| | getClassesForSession | R | R | R | R | R | R |
| | getProductsForSession | R | R | R | R | R | R |
| | getStrategiesByClassForSession | О | О | О | О | О | О |
| | getProductBySessionForKey | О | О | О | О | О | О |
| | getStrategyBySessionForKey | О | О | О | О | О | О |
| | getClassBySessionForKey | О | О | О | О | О | О |
| | getProductBySessionForName | О | О | О | О | О | О |
| | getClassBySessionForSymbol | О | О | О | О | О | О |
| | getStrategiesByComponent | О | О | О | О | О | О |
| | unsubscribeClassesByTypeForSession | О | О | О | О | О | О |
| | unsubscribeProductsByClassForSession | О | О | O | О | O | О |
| | unsubscribeStrategiesByClassForSession | О | О | O | О | O | О |
| | unsubscribeTradingSessionStatus | О | О | О | О | О | О |

cmi::Quote Interface

All messages except for getQuote, cancelQuote, cancelAllQuotes, and cancelQuotesByClass are not allowed for new development. The cmiV2::Quote interface must be used instead.

| | Operation | MM | DPM | Brok | Firm | Firm | Cls D |
|----------|------------------------------------|----|-----|------|------|------|-------|
| (P or F) | | | | | | Disp | |
| | acceptQuote | N | N | N | N | N | N |
| | acceptQuotesForClass | N | N | N | N | N | N |
| | getQuote | О | О | N | N | N | N |
| | cancelQuote | R | R | N | N | N | N |
| | cancelAllQuotes | О | О | N | N | N | N |
| | cancelQuotesByClass | R | R | N | N | N | N |
| | subscribeQuoteStatus | N | N | N | N | N | N |
| | subscribeRFQ | N | N | N | N | N | N |
| | subscribeQuoteStatusForFirm | N | N | N | N | N | N |
| | unsubscribeQuoteStatus | N | N | N | N | N | N |
| | unsubscribeRFQ | N | N | N | N | N | N |
| | unsubscribeQuoteStatusForFirm | N | N | N | N | N | N |
| | subscribeQuoteStatusWithoutPublish | N | N | N | N | N | N |

cmiV2::Quote Interface

| Status | Operation | MM | DPM | Brok | Firm | Firm | Cls D |
|----------|--|----|-----|------|------|------|-------|
| (P or F) | | | | | | Disp | |
| | acceptQuotesForClassV2 | R | R | N | N | N | N |
| | subscribeQuoteLockedNotification -or- | | R | О | N | N | N |
| | subscribeQuoteLockedNotificationForClass | | | | | | |
| | subscribeQuoteStatusV2 -or- | R | R | N | N | N | N |
| | subscribeQuoteStatusForClassV2 | | | | | | |
| | subscribeQuoteStatusForFirmV2 -or- | N | N | N | R | R | N |
| | subscribeQuoteStatusForFirmForClassV2 | | | | | | |
| | subscribeRFQV2 (required for futures, not | R | R | N | N | N | N |
| | required for options or STOC) | | | | | | |
| | unsubscribeQuoteLockedNotification | О | О | O | N | N | N |
| | unsubscribeQuoteLockedNotificationForClass | О | О | О | N | N | N |
| | unsubscribeQuoteStatusForClassV2 | Ο | О | N | N | N | N |
| | unsubscribeQuoteStatusForFirmForClassV2 | N | N | N | О | О | N |
| | unsubscribeQuoteStatusForFirmV2 | N | N | N | О | О | N |
| | unsubscribeQuoteStatusV2 | О | О | N | N | N | N |
| | unsubscribeRFQV2 | 0 | 0 | N | N | N | N |

cmiV2::UserHistory Interface

| Status (P or F) | Operation | MM | DPM | Brok | Firm | Firm Disp | Cls D |
|--------------------|--------------------------------|----|-----|------|------|--------------|-------|
| | getTraderClassActivityByTime | О | 0 | 0 | 0 | 0 | N |
| | getTraderProductActivityByTime | О | О | О | О | О | N |

Phase 3 Interface and Method Requirements

The following interfaces originally appeared in V2.0 but are still usable in V2.5. Some exceptions apply. Read the descriptions of each method below. Shading indicates that a method is not allowed for new development.

User Access Interface

| Status (P/F) | Method | Description |
|--------------|--------|-------------------------|
| | logon | Required for all roles. |

CMIUserSessionAdmin Interface

| Status (P/F) | Method | Description |
|--------------|----------------------------|-------------------------|
| | acceptHeartBeat | Required for all roles. |
| | acceptLogout | Required for all roles. |
| | acceptTextMessage | Required for all roles. |
| | acceptAuthenticationNotice | Required for all roles. |
| | acceptCallbackRemoval | Required for all roles. |

User Session Manager Interface

| Status (P/F) | Method | Description |
|--------------|--------------|-------------------------|
| | logout | Required for all roles. |
| | authenticate | Required for all roles. |

| Status (P/F) | Method | Description |
|--------------|--------------------------|--|
| | getAdministrator | Required for the Market Maker, DPM, Broker and Firm roles. Optional for the Firm Display role. Not allowed for the Class Display role |
| | getValidUser | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Optional for Class Display and Firm Display roles. |
| | changePassword | Required for all roles. |
| | getVersion | Required for all roles. |
| | getSystemDateTime | Optional for all roles. |
| | getTradingSession | Required for all roles. |
| | getMarketQuery | Optional for all roles but required for the Class Display role. |
| | getOrderQuery | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Not allowed for the Class Display and Firm Display roles. |
| | getProductDefinition | Implemented but not used in second Version of CBOEdirect. |
| | getProductQuery | Optional for all roles. |
| | getQuote | Required for Market-Makers and DPMs. Optional for the Broker-Dealer role. Not allowed for Class Display role. Optional for the Firm and Firm Display roles. |
| | getOrderEntry | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Not allowed for the Class Display and Firm Display roles. |
| | getUserTradingParameters | Not allowed for the Class Display or Firm Display role. Optional for all other roles. |
| | getUserHistory | Not allowed for the Class Display or Firm Display role. Optional for all other roles. |

| Status (P/F) | Method | Description |
|--------------|------------------------|--|
| | getUserPreferenceQuery | Not allowed for all roles. For CBOE internal use only. |

Market Query Interface

This interface is not allowed for new development. The MarketQueryV2 interface should be used instead.

| Status (P/F) | Method | Description |
|--------------|------------------------------------|--|
| | getBookDepth | In W_MAIN, a user may only send this message once per 10 minutes per user for all options in the W_MAIN session. Not allowed for the Class Display role. Optional for all other roles. |
| | getMarketDataHistoryByTime | Not allowed for the Class Display role. Optional for all other roles. |
| | subscribeTicker | Not allowed for new development. Optional for all roles. |
| | subscribeRecapForClass | Not allowed for new development. Optional for all roles. |
| | subscribeRecapForProduct | Not allowed for new development. Optional for all roles. |
| | subscribeCurrentMarketForClass | Not allowed for new development. Optional for all roles. |
| | subscribeCurrentMarketForProduct | Not allowed for new development. Optional for all roles. |
| | subscribeNBBOForClass | Not allowed for new development. Optional for all roles. |
| | subscribeNBBOForProduct | Not allowed for new development. Optional for all roles. |
| | subscribeExpectedOpeningPrice | Not allowed for new development. Optional for all roles. |
| | subscribeBookDepth | Not allowed for new development. Not allowed for the Class Display role. Optional for all other roles. |
| | subscribeBookDepthUpdate | Not allowed for new development. Not allowed for the Class Display role. Optional for all other roles. |
| | unsubscribeCurrentMarketForProduct | Not allowed for new development. Optional for all roles. |

| Status (P/F) | Method | Description |
|--------------|----------------------------------|--|
| | unsubscribeCurrentMarketForClass | Not allowed for new development. Optional for all roles. |
| | unsubscribeNBBOForProduct | Not allowed for new development. Optional for all roles. |
| | unsubscribeNBBOForClass | Not allowed for new development. Optional for all roles. |
| | unsubscribeRecapForProduct | Not allowed for new development. Optional for all roles. |
| | unsubscribeRecapForClass | Not allowed for new development. Optional for all roles. |
| | unsubscribeTicker | Not allowed for new development. Optional for all roles. |
| | unsubscribeExpectedOpeningPrice | Not allowed for new development. Optional for all roles. |
| | unsubscribeBookDepth | Not allowed for new development. Not allowed for the Class Display role. Optional for all other roles. |
| | unsubscribeBookDepthUpdate | Not allowed for new development. Not allowed for the Class Display role. Optional for all other roles. |

CMICurrentMarketConsumer Interface

| Status (P/F) | Method | Description |
|--------------|---------------------|---|
| | acceptCurrentMarket | Required if either subscribeCurrentMarketForClass or subscribeCurrentMarketForProduct is invoked. |

CMINBBOConsumer Interface

| Status (P/F) | Method | Description |
|--------------|------------|---|
| | acceptNBBO | Required if either the subscribeNBBOForClass or subscribeNBBOForProduct methods is invoked. |

CMIExpectedOpeningPriceConsumer Interface

| Status (P/F) | Method | Description |
|--------------|----------------------------|--|
| | acceptExpectedOpeningPrice | Required if the subscribeExpectedOpeningPrice method is invoked. |

CMIRecapConsumer Interface

| Status (P/F) | Method | Description |
|--------------|-------------|---|
| | acceptRecap | Required if subscribeRecapForClass or subscribeRecapForProduct method is invoked. |

CMITickerConsumer Interface

| Status (P/F) | Method | Description |
|--------------|--------------|--|
| | acceptTicker | Required if the subscribeTicker method is invoked. |

CMIOrderBookConsumer Interface

| Status (P/F) | Method | Description |
|--------------|-----------------|---|
| | acceptBookDepth | Required if the subscribeBookDepth method is invoked. |

CMIOrderBookUpdateConsumer Interface

| Status (P/F) | Method | Description |
|--------------|-----------------------|---|
| | acceptBookDepthUpdate | Required if the subscribeBookDepthUpdate method is invoked. |

CMIProductStatusConsumer Interface

| Status (P/F) | Method | Description |
|--------------|--------------------|-------------------------|
| | acceptProductState | Required for all roles. |
| | updatedProduct | Required for all roles. |

CMIStrategyStatusConsumer Interface

| Status (P/F | Method | Description |
|-------------|-----------------------|-------------------------|
| | updateProductStrategy | Optional for all roles. |

Quote Interface

Some messages are not allowed for new development. The QuoteV2 interface should be used instead

| Status (P/F) | Method | Description |
|--------------|-------------|---|
| | acceptQuote | Not allowed for new development. Required for Market-Makers and DPMs if the acceptQuotesForClass method is not used. Optional for Market-Makers and DPMs if the acceptQuotesForClass method is used. Not allowed for the Broker, Firm, Firm Display, and Class Display roles. |

| Status (P/F) | Method | Description |
|--------------|------------------------------------|---|
| | acceptQuotesForClass | Not allowed for new development. Required for Market-Makers and DPMs using an autoquoting application that would submit multiple quotes at one time. When autoquoting takes place each method call must contain multiple quotes. If only manual quoting is anticipated, then this method is optional. If not used, then the acceptQuote method is required for Market-Makers and DPMs. Not allowed for the Broker, Firm, Firm Display, and Class Display roles. |
| | getQuote | Encouraged for Market Makers and DPMs but not allowed for the Broker, Firm, Firm Display, and Class Display roles |
| | cancelQuote | Required for Market-Makers and DPMs but not allowed for the Broker, Firm, Firm Display, and Class Display roles. |
| | cancelAllQuotes | Strongly encouraged for Market-Makers and DPMs but not allowed for the Broker, Firm, Firm Display, and Class Display roles. |
| | cancelQuotesByClass | Required for Market-Makers and DPMs but not allowed for the Broker, Firm, Firm Display, and Class Display roles. |
| | subscribeRFQ | Not allowed for new development. Required for Market-Makers and DPMs but not allowed for Broker, Firm, Firm Display, and Class Display roles. Required for futures, optional for options. |
| | subscribeQuoteStatus | Not allowed for new development. Required for Market-Makers and DPMs but not allowed for Broker, Firm, Firm Display, and Class Display roles. |
| | subscribeQuoteStatusWithoutPublish | Not allowed for new development. Optional for Market-Makers and DPMs but not allowed for Broker, Firm, Firm Display, and Class Display roles. |
| | unsubscribeRFQ | Not allowed for new development. Optional for Market-Makers and DPMs but not allowed for Broker, Firm, Firm Display, and Class Display roles. |

| Status (P/F) | Method | Description |
|--------------|---|---|
| | unsubscribeQuoteStatus | Not allowed for new development. Optional for Market-Makers and DPMs but not allowed for Broker, Firm, Firm Display, and Class Display roles. |
| | subscribeQuoteStatusForFirm | Not allowed for new development. Only the Firm and Firm Display roles may use this method. |
| | subscribeQuoteStatusForFirmWithoutPublish | Not allowed for new development. Only the Firm and Firm Display roles may use this method. |
| | unsubscribeQuoteStatusForFirm | Not allowed for new development. Only the Firm and Firm Display roles may use this method. |

CMIQuoteStatusConsumer Interface

| Status (P/F) | Method | Description |
|--------------|-------------------------|---|
| | acceptQuoteStatus | Required for Market-Makers and DPMs. Optional for Firm and Firm Display roles. Not allowed for the Broker or Class Display roles. |
| | acceptQuoteFilledReport | Required for Market-Makers and DPMs. Optional for Firm and Firm Display roles. Not allowed for the Broker or Class Display roles. |
| | acceptQuoteBustReport | Required for Market-Makers and DPMs. Optional for Firm and Firm Display roles. Not allowed for the Broker or Class Display roles. |

CMIRFQConsumer Interface

| Status (P/F) | Method | Description |
|--------------|-----------|--|
| | acceptRFQ | Required for Market-Makers and DPMs but not allowed for Broker, Firm, Firm Display, and Class Display roles. Required for futures, optional for options. |

Order Query Interface

Subscription messages are not allowed for new development. The cmiV2::OrderQuery interface must be used for order subscriptions.

| Status (P/F) | Method | Description |
|--------------|-------------------------------------|--|
| | getOrdersForProduct | Encouraged for Broker and Firm roles. Encouraged for Market-Makers and DPMs who intend to submit orders. Not allowed for the Firm Display or Class Display role. |
| | getOrdersForSession | Encouraged for Broker and Firm roles. Encouraged for Market-Makers and DPMs who intend to submit orders. Not allowed for the Firm Display or Class Display role. |
| | getOrderById | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | getOrdersForType | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | getOrdersForClass | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | getPendingAdjustmentOrdersByProduct | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | getPendingAdjustmentOrdersByClass | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | queryOrderHistory | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |

| Status (P/F) | Method | Description |
|--------------|-------------------------------------|---|
| | subscribeOrders | Not allowed for new development. Required for Broker and Firm roles if the subscribeOrdersWithoutPublish method is not used. Required for Market-Makers and DPMs who intend to submit orders if the subscribeOrdersWithoutPublish method is not used. Not allowed for the Firm Display or Class Display role. |
| | subscribeOrdersWithoutPublish | Not allowed for new development. Required for Broker and Firm roles if the subscribeOrders method is not used. Required for Market-Makers and DPMs who intend to submit orders if the subscribeOrders method is not used. Not allowed for the Firm Display or Class Display role. |
| | unsubscribeOrderStatusForProduct | Not allowed for new development. Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | unsubscribeOrderStatusForSession | Not allowed for new development. Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | unsubscribeAllOrderStatusForType | Not allowed for new development. Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | unsubscribeOrderStatusByClass | Not allowed for new development. Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display role. |
| | subscribeOrdersByFirm | Not allowed for new development. Only the Firm and Firm Display roles may utilize this method. |
| | subscribeOrdersByFirmWithoutPublish | Not allowed for new development. Only the Firm and Firm Display roles may utilize this method. |
| | unsubscribeOrderStatusForFirm | Not allowed for new development. Only the Firm and Firm Display roles may utilize this method. |

Order Entry Interface

| Status (P/F) | Method | Description |
|--------------|----------------------------------|---|
| | acceptOrder | Required for Broker and Firm roles if acceptOrderByProductName is not used. Required for Market Maker and DPM roles who intend to submit orders if acceptOrderByProductName is not used. Not allowed for the Class Display or Firm Display role |
| | acceptOrderByProductName | Required for Broker and Firm roles if acceptOrder is not used. Required for Market Maker and DPM roles who intend to submit orders if acceptOrder is not used. Not allowed for the Firm Display or Class Display role. |
| | acceptOrderCancelRequest | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Not allowed for the Firm Display or Class Display roles. |
| | acceptOrderUpdateRequest | Strongly encouraged for Broker and Firm roles. Strongly encouraged for Market-Makers and DPMs who intend to submit orders. Not allowed for the Firm Display or Class Display roles. |
| | acceptOrderCancelReplaceRequest | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Not allowed for the Firm Display or Class Display role. |
| | acceptRequestForQuote | Required for Broker and Firm roles. Not allowed for the Firm Display or Class Display role. Encouraged for Market-Makers and DPMs. |
| | acceptCrossingOrder | This method is not supported in the current version of the CMi and is for future use in a subsequent version. |
| | acceptStrategyOrder | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display roles. |
| | acceptStrategyOrderUpdateRequest | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display roles. |

| Status (P/F) | Method | Description |
|--------------|---|--|
| | acceptStrategyOrderCancelReplaceRequest | Optional for Broker, Firm, Market-Maker, and DPM roles. Not allowed for Firm Display or Class Display roles. |

CMIOrderStatusConsumer Interface

| Status (P/F) | Method | Description |
|--------------|--------------------------------|--|
| | acceptNewOrder | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Optional for the Firm Display role. Not allowed for the Class Display role. |
| | acceptOrderStatus | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Optional for the Firm Display role. Not allowed for the Class Display role. |
| | acceptOrderBustReport | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Optional for the Firm Display role. Not allowed for the Class Display role. |
| | acceptOrderFilledReport | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Optional for the Firm Display role. Not allowed for the Class Display role. |
| | acceptOrderCanceledReport | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Optional for the Firm Display role. Not allowed for the Class Display role. |
| | acceptOrderBustReinstateReport | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Optional for the Firm Display role. Not allowed for the Class Display role. |

Product Query Interface

| Status (P/F) | Method | Description |
|--------------|------------------------------|-------------------------|
| | getProductTypes | Optional for all roles. |
| | getProductClasses | Optional for all roles. |
| | getProductsByClass | Optional for all roles. |
| | isValidProductName | Optional for all roles. |
| | getProductByName | Optional for all roles. |
| | getProductNameStruct | Optional for all roles. |
| | getAllPendingAdjustments | Optional for all roles. |
| | getPendingAdjustments | Optional for all roles. |
| | getPendingAdjustmentProducts | Optional for all roles. |
| | getStrategyByKey | Optional for all roles. |
| | getClassByKey | Optional for all roles. |
| | getProductByKey | Optional for all roles. |
| | getClassBySymbol | Optional for all roles. |
| | getStrategiesByComponent | Optional for all roles. |
| | getStrategiesByClass | Optional for all roles. |

Product Definition Interface

| Status (P/F) | Method | Description |
|--------------|----------------------------------|-------------------------|
| | acceptStrategy | Optional for all roles. |
| | buildStrategyRequestByName | Optional for all roles. |
| | buildStrategyRequestByProductKey | Optional for all roles. |

User Preference Query Interface Not allowed for all roles. For CBOE internal use only.

| Status (P/F) | Method | Description |
|--------------|-------------------------------|--|
| | getAllSystemPreferences | Not allowed for all roles. For CBOE internal use only. |
| | getAllUserPreferences | Not allowed for all roles. For CBOE internal use only. |
| | getSystemPreferencesByPrefix | Not allowed for all roles. For CBOE internal use only. |
| | getUserPreferencesByPrefix | Not allowed for all roles. For CBOE internal use only. |
| | removeUserPreference | Not allowed for all roles. For CBOE internal use only. |
| | removeUserPreferencesByPrefix | Not allowed for all roles. For CBOE internal use only. |
| | setUserPreferences | Not allowed for all roles. For CBOE internal use only. |

Administrator Interface

| Status (P/F) | Method | Description |
|--------------|--------|-------------|

| Status (P/F) | Method | Description |
|--------------|-------------|--|
| | sendMessage | Required for the Market-Maker, DPM, Broker and Firm roles. Optional for the Firm Display role. Not allowed for the Market Data role. |

Trading Session Interface

| Status (P/F) | Method | Description |
|--------------|--|---|
| | getCurrentTradingSessions | Required for all roles. |
| | getProductTypesForSession | Encouraged for all roles. |
| | getClassesForSession | Encouraged for all roles. |
| | getProductsForSession | Required for Market-Makers and DPMs and encouraged for all other roles. |
| | getStrategiesByClassForSession | Optional for all roles. |
| | getProductBySessionForKey | Optional for all roles. |
| | getStrategyBySessionForKey | Optional for all roles. |
| | getStrategiesByComponent | Optional for all roles. |
| | getProductBySessionForName | Optional for all roles. |
| | getClassBySessionForSymbol | Optional for all roles. |
| | unsubscribeTradingSessionStatus | Optional for all roles. |
| | unsubscribeClassesByTypeForSession | Optional for all roles. |
| | unsubscribeProductsByClassForSession | Optional for all roles. |
| | unsubscribeStrategiesByClassForSession | Optional for all roles. |
| | getClassBySessionForKey | Optional for all roles. |

CMITradingSessionStatusConsumer Interface

| Status (P/F) Method Description | , |
|-------------------------------------|---|

| Status (P/F) | Method | Description |
|--------------|---------------------------|-------------------------|
| | acceptTradingSessionState | Required for all roles. |

CMIClassStatusConsumer Interface

| Status (P/F) | Method | Description |
|--------------|--------------------|-------------------------|
| | updateProductClass | Required for all roles. |
| | acceptClassState | Required for all roles. |

User History Interface

| Status (P/F) | Method | Description |
|--------------|--------------------------------|---|
| | getTraderClassActivityByTime | Not allowed for the Firm Display and Class Display role. Optional for all |
| | | other roles. |
| | getTraderProductActivityByTime | Not allowed for the Firm Display and Class Display role. Optional for all |
| | | other roles. |

User Trading Parameters Interface

| Status (P/F) | Method | Description |
|--------------|--------------------------------------|---|
| | getAllQuoteRiskProfiles | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |
| | getQuoteRiskManagementProfileByClass | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |
| | setQuoteRiskManagementEnabledStatus | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |

| Status (P/F) | Method | Description |
|--------------|-------------------------------------|---|
| | getQuoteRiskManagementEnabledStatus | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |
| | getDefaultQuoteRiskProfile | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |
| | setQuoteRiskProfile | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |
| | removeQuoteRiskProfile | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |
| | removeAllQuoteRiskProfiles | Optional for Market-Makers and DPMs but not allowed for the Broker, |
| | | Firm, Firm Display, and Class Display role. |

Version Interface

| Status (P/F) | Method | Description |
|--------------|------------------|---------------------------|
| | getVersionNumber | Encouraged for all roles. |

Phase 3 V2 Interface and Method Requirements for V2.5 and higher

CMIV2::MarketQuery Interface

All of Market Query V2 (subscribing to market data) is optional for all users, but if any market query is used at all, it must be from the V2 interface, instead of the non-V2 interface. The only exception is that subscribeExpectedOpeningPriceForClassV2 or subscribeExpectedOpeningPriceForProductV2 is required for options DPMs.

| Status (P/F) | Method | Description |
|--------------|--------------------------------------|---|
| | getBookDepthDetails | Optional for all roles. |
| | subscribeBookDepthForClassV2 | Optional for all roles, but required if the firm wishes to subscribe to Book Depth, unless subscribeBookDepthForProductV2 is used. Not allowed for a class in W_MAIN. |
| | subscribeBookDepthForProductV2 | Optional for all roles, but required if the firm wishes to subscribe to Book Depth, unless subscribeBookDepthForClassV2is used. Not allowed for a class in W_MAIN. |
| | subscribeBookDepthUpdateForClassV2 | Optional for all roles, but required if the firm wishes to subscribe to Book Depth Updates, unless subscribeBookDepthUpdateForProductV2 is used. Not allowed for a class in W_MAIN. |
| | subscribeBookDepthUpdateForProductV2 | Optional for all roles, but required if the firm wishes to subscribe to Book Depth Updates, unless subscribeBookDepthUpdateForClassV2 is used. Not allowed for a class in W_MAIN. |
| | subscribeCurrentMarketForClassV2 | Optional for all roles, but required if the firm wishes to subscribe to Current Market unless subscribeCurrentMarketForProductV2 is used. |
| | subscribeCurrentMarketForProductV2 | Optional for all roles, but required if the firm wishes to subscribe to Current Market unless subscribeCurrentMarketForClassV2is used. |

| Method | Description |
|---|---|
| subscribeExpectedOpeningPriceForClassV2 | Required for Options DPMs. Optional for all other roles, but required if the firm wishes to subscribe to EOP unless subscribeExpectedOpeningPriceForProductV2 is used. |
| subscribeExpectedOpeningPriceForProductV2 | Required for Options DPMs. Optional for all other roles, but required if the firm wishes to subscribe to EOP unless subscribeExpectedOpeningPriceForProductV2 is used. |
| subscribeNBBOForClassV2 | NBBO is not implemented at this time. |
| subscribeNBBOForProductV2 | NBBO is not implemented at this time. |
| subscribeRecapForClassV2 | Optional for all roles, but required if the firm wishes to subscribe to Recap unless subscribeRecapForProductV2 is used. |
| subscribeRecapForProductV2 | Optional for all roles, but required if the firm wishes to subscribe to Recap unless subscribeRecapForClassV2 is used. |
| subscribeTickerForClassV2 | Optional for all roles, but required if the firm wishes to subscribe to Ticker unless subscribeTickerForProductV2 is used. |
| subscribeTickerForProductV2 | Optional for all roles, but required if the firm wishes to subscribe to Ticker unless subscribeTickerForClassV2 is used. |
| unsubscribeBookDepthForClassV2 | Optional for all roles. |
| unsubscribeBookDepthForProductV2 | Optional for all roles. |
| unsubscribeBookDepthUpdateForClassV2 | Optional for all roles. |
| unsubscribeBookDepthUpdateForProductV2 | Optional for all roles. |
| unsubscribeCurrentMarketForClassV2 | Optional for all roles. |
| unsubscribeCurrentMarketForProductV2 | Optional for all roles. |
| unsubscribeExpectedOpeningPriceForClassV2 | Optional for all roles. |
| unsubscribeExpectedOpeningPriceForProductV2 | Optional for all roles. |
| | subscribeExpectedOpeningPriceForClassV2 subscribeNBBOForClassV2 subscribeNBBOForProductV2 subscribeRecapForClassV2 subscribeRecapForProductV2 subscribeTickerForClassV2 subscribeTickerForClassV2 unsubscribeBookDepthForClassV2 unsubscribeBookDepthForProductV2 unsubscribeBookDepthUpdateForClassV2 unsubscribeBookDepthUpdateForProductV2 unsubscribeCurrentMarketForProductV2 unsubscribeCurrentMarketForProductV2 unsubscribeExpectedOpeningPriceForClassV2 |

| Status (P/F) | Method | Description |
|--------------|-------------------------------|-------------------------|
| | unsubscribeNBBOForClassV2 | Optional for all roles. |
| | unsubscribeNBBOForProductV2 | Optional for all roles. |
| | unsubscribeRecapForClassV2 | Optional for all roles. |
| | unsubscribeRecapForProductV2 | Optional for all roles. |
| | unsubscribeTickerForClassV2 | Optional for all roles. |
| | unsubscribeTickerForProductV2 | Optional for all roles. |

CMIV2::OrderQuery Interface

If any Order Query subscriptions are used at all, it must be from the V2 interface, instead of the non-V2 interface. These messages are required for order routing. They are not required for market-makers who enter quotes only.

| Status (P/F) | Method | Description |
|--------------|---------------------------------------|---|
| | subscribeOrderStatusV2 | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Not allowed for the Class Display and Firm Display roles. Optional if the subscribeOrderStatusForClassV2 method is used. |
| | subscribeOrderStatusForClassV2 | Required for Broker and Firm roles. Required for Market-Makers and DPMs who intend to submit orders. Not allowed for the Class Display and Firm Display roles. Optional if the subscribeOrderStatusV2 method is used. |
| | subscribeOrderStatusForFirmForClassV2 | Required for Broker and Firm roles. Not allowed for Market-Maker, DPM, Class Display, and Firm Display roles. Optional if the subscribeOrderStatusForFirmV2 method is used. |
| | subscribeOrderStatusForFirmV2 | Required for Broker and Firm roles. Not allowed for Market-Maker, DPM, Class Display, and Firm Display roles. Optional if the subscribeOrderStatusForFirmForClassV2 method is used. |

| Status (P/F) | Method | Description |
|--------------|---|-------------------------|
| | unsubscribeOrderStatusForClassV2 | Optional for all roles. |
| | un subscribe Order Status For Firm For Class V2 | Optional for all roles. |
| | unsubscribeOrderStatusForFirmV2 | Optional for all roles. |
| | unsubscribeOrderStatusV2 | Optional for all roles. |

CMIV2::Quote Interface

If any Quote messaging is used at all, it must be from the V2 interface, instead of the non-V2 interface. These messages are required for market-making. This interface is allowed for the Broker-Dealer role to subscribe to Quote Locked messages.

| Status (P/F) | Method | Description |
|--------------|--|--|
| | acceptQuotesForClassV2 | Required for Market-Makers and DPMs who plan to send two-sided quotes to CBOE. Not allowed for all other roles. |
| | subscribeQuoteLockedNotification | Required for Market-Makers and DPMs in Hybrid. Optional for Broker-Dealer role if "I" orders are used. Not allowed for all other roles or for futures. Optional if subscribeQuoteLockedNotificationForClass is used. |
| | subscribeQuoteLockedNotificationForClass | Required for Market-Makers and DPMs in Hybrid. Optional for Broker-Dealer role if "I" orders are used. Not allowed for all other roles or for futures. Optional if subscribeQuoteLockedNotification is used. |
| | subscribeQuoteStatusV2 | Required for Market-Makers and DPMs. Not allowed for all other roles. Optional if subscribeQuoteStatusForFirmForClassV2 is used. |
| | subscribeQuoteStatusForClassV2 | Required for Market-Makers and DPMs. Not allowed for all other roles. Optional if subscribeQuoteStatusForFirmForClassV2 is used. |
| | subscribeQuoteStatusForFirmV2 | Optional for Firm and Firm Display roles. |
| | subscribeQuoteStatusForFirmForClassV2 | Optional for Firm and Firm Display roles. |

| Status (P/F) | Method | Description |
|--------------|---|--|
| | subscribeRFQV2 | Required for futures market-makers. Not supported for options (Hybrid W_MAIN). Not allowed for Broker-Dealer, Firm, Firm Display, and Class Display roles. |
| | unsubscribeQuoteLockedNotification | Optional for all roles. |
| | unsubscribe Quote Locked Notification For Class | Optional for all roles. |
| | unsubscribeQuoteStatusForClassV2 | Optional for all roles. |
| | unsubscribeQuoteStatusForFirmForClassV2 | Optional for all roles. |
| | unsubscribeQuoteStatusForFirmV2 | Optional for all roles. |
| | unsubscribeQuoteStatusV2 | Optional for all roles. |
| | unsubscribeRFQV2 | Optional for all roles. |

CMIV2::UserAccessV2 Interface

| Status (P/F) | Method | Description |
|--------------|-------------------------|---|
| | logon | Required for Hybrid and all V2.5 users. |
| | getUserSessionManagerV2 | Required for Hybrid and all V2.5 users. |

CMIV2::UserSessionManagerV2 Interface

| Status (P/F) | Method | Description |
|--------------|------------------|--|
| | getMarketQueryV2 | Optional for Hybrid and all V2.5 users, but must be used if Market Query is used at all. |
| | getOrderQueryV2 | Optional for all V2.5 users, but must be used if Order Query is used at all. |

| Status (P/F) | Method | Description |
|--------------|------------|--|
| | getQuoteV2 | Required for Market-Makers and DPMs. Optional for all other users, but must be used if Quote messaging is used at all. |

Phase 3 V2 Interface and Method Requirements for V2.6 and higher

cmilntermarket::IntermarketManualHandling Interface

| Status (P/F) | Method | Description |
|--------------|------------------------------------|--|
| | acceptAdminMessage | This message is used for Intermarket Linkage users only. |
| | acceptCancelResponse | This message is used for Intermarket Linkage users only. |
| | acceptCustomerOrderSatisfy | This message is used for Intermarket Linkage users only. |
| | acceptFillReject | This message is used for Intermarket Linkage users only. |
| | acceptHeldOrderByClassReroute | This message is used for Intermarket Linkage users only. |
| | acceptHeldOrderFill | This message is used for Intermarket Linkage users only. |
| | acceptHeldOrderReroute | This message is used for Intermarket Linkage users only. |
| | acceptOpeningPriceForProduct | This message is used for Intermarket Linkage users only. |
| | acceptPreOpeningIndication | This message is used for Intermarket Linkage users only. |
| | acceptPreOpeningResponse | This message is used for Intermarket Linkage users only. |
| | acceptSatisfactionOrderFill | This message is used for Intermarket Linkage users only. |
| | acceptSatisfactionOrderInCrowdFill | This message is used for Intermarket Linkage users only. |
| | acceptSatisfactionOrderReject | This message is used for Intermarket Linkage users only. |
| | getAssociatedOrders | This message is used for Intermarket Linkage users only. |
| | getHeldOrderById | This message is used for Intermarket Linkage users only. |
| | getOrdersByOrderTypeAndClass | This message is used for Intermarket Linkage users only. |
| | getOrdersByOrderTypeAndProduct | This message is used for Intermarket Linkage users only. |

| Status (P/F) | Method | Description |
|--------------|-------------------------------|--|
| | lockProduct | This message is used for Intermarket Linkage users only. |
| | rerouteBookedOrderToHeldOrder | This message is used for Intermarket Linkage users only. |
| | unlockProduct | This message is used for Intermarket Linkage users only. |

cmiIntermarket::IntermarketQuery Interface

This interface should be used for Intermarket Linkage.

| Status (P/F) | Method | Description |
|--------------|-----------------------------------|--|
| | getAdminMessage | This message is used for Intermarket Linkage users only. |
| | getDetailedOrderBook | This message is used for Intermarket Linkage users only. |
| | getIntermarketByClassForSession | This message is used for Intermarket Linkage users only. |
| | getIntermarketByProductForSession | This message is used for Intermarket Linkage users only. |
| | showMarketableOrderBookAtPrice | This message is used for Intermarket Linkage users only. |
| | getOrderBookStatus | This message is used for Intermarket Linkage users only. |

cmiIntermarket::IntermarketUserAccess Interface

This interface should be used for Intermarket Linkage.

| Status (P/F) | Method | Description |
|--------------|----------------------------------|--|
| | getIntermarketUserSessionManager | This message is used for Intermarket Linkage users only. |
| | logon | This message is used for Intermarket Linkage users only. |

cmiIntermarket::IntermarketUserSessionManager Interface

| Status (P/F) | Method | Description |
|--------------|---------------------|--|
| | getIntermarketQuery | This message is used for Intermarket Linkage users only. |
| | getNBBOAgent | This message is used for Intermarket Linkage users only. |

cmiIntermarket::NBBOAgent Interface

This interface should be used for Intermarket Linkage.

| Status (P/F) | Method | Description |
|--------------|-----------------|--|
| | registerAgent | This message is used for Intermarket Linkage users only. |
| | unregisterAgent | This message is used for Intermarket Linkage users only. |

cmiIntermarket::NBBOAgentSessionManager Interface

This interface should be used for Intermarket Linkage.

| Status (P/F) | Method | Description |
|--------------|------------------------------|--|
| | getIntermarketManualHandling | This message is used for Intermarket Linkage users only. |

cmiIntermarketCallback::CMIIntermarketOrderStatusConsumer Interface

| Status (P/F) | Method | Description |
|--------------|-------------------------------|--|
| | acceptCancelHeldOrderRequest | This message is used for Intermarket Linkage users only. |
| | acceptFillRejectReport | This message is used for Intermarket Linkage users only. |
| | acceptHeldOrderCanceledReport | This message is used for Intermarket Linkage users only. |

| Status (P/F) | Method | Description |
|--------------|-----------------------------|--|
| | acceptHeldOrderFilledReport | This message is used for Intermarket Linkage users only. |
| | acceptHeldOrderStatus | This message is used for Intermarket Linkage users only. |
| | acceptNewHeldOrder | This message is used for Intermarket Linkage users only. |

cmiIntermarketCallback::CMINBBOAgentSessionAdmin Interface

| Status (P/F) | Method | Description |
|--------------|--|--|
| | acceptForcedOut | This message is used for Intermarket Linkage users only. |
| | acceptIntermarketAdminMessage | This message is used for Intermarket Linkage users only. |
| | acceptReminder | This message is used for Intermarket Linkage users only. |
| | acceptSatisfactionAlert | This message is used for Intermarket Linkage users only. |
| | acceptBroadcastIntermarketAdminMessage | This message is used for Intermarket Linkage users only. |