

Cisco BroadWorks Application Server Provisioning

Interface Specification

Release 23.0

Document Version 2



Notification

The BroadSoft BroadWorks has been renamed to Cisco BroadWorks. Beginning in September 2018, you will begin to see the Cisco name and company logo, along with the new product name on the software, documentation, and packaging. During this transition process, you may see both BroadSoft and Cisco brands and former product names. These products meet the same high standards and quality that both BroadSoft and Cisco are known for in the industry.

Copyright Notice

Copyright[©] 2019 Cisco Systems, Inc. All rights reserved.

Trademarks

Any product names mentioned in this document may be trademarks or registered trademarks of Cisco or their respective companies and are hereby acknowledged.



Document Revision History

Release	Version	Reason for Change	Date	Author
14.0	1	Updated document for rebranding.	March 6, 2006	Patricia Renaud
14.0	1	Deleted custom features.	May 17, 2006	Patricia Renaud
14.0	1	Updated section 5.2 to correct command line interface (CLI) level OCI/Reporting.	June 20, 2006	Robb Surridge
14.0	1	Added Release 13 to 14 changes and updated transactions and authorizations.	August 16, 2006	Bob Russell
14.0	1	Edited document.	September 2, 2006	Patricia Renaud
14.sp2	2	Added information for OCI-P over Simple Object Access Protocol (SOAP).	May 3, 2007	Doug Crank
14.sp2	2	Edited and published document.	May 18, 2007	Patricia Renaud
14.sp2	3	Added note about invalid session IDs and dropped connections to section 3.2 Technical Summary for EV 48809.	May 31, 2007	Robb Surridge
14.sp2	3	Edited changes and published document.	June 21, 2007	Andrea Fitzwilliam
14.sp2	4	Updated Operations Support System (OSS) interface information in section 1.17 Changes for Release 14.0 for EV 53540.	October 2, 2007	Roberta Boyle
14.sp2	4	Made small change to section 1.17 Changes for Release 14.0 for failed EV 53540.	October 18, 2007	Roberta Boyle
14.sp2	4	Added note to Domains in section 5.1 Base Configuration for EV 54703.	October 23, 2007	Roberta Boyle
14.sp2	4	Edited changes and published document.	November 12, 2007	Andrea Fitzwilliam
14.sp4	5	Updated transactions and authorizations for Release 14.sp4.	February 13, 2008	Bob Russell
14.sp4	5	Edited changes and published document.	February 15, 2008	Andrea Fitzwilliam
15.0	1	Updated document to 15.0.	June 17, 2008	Bob Russell
15.0	1	Edited changes from Release 14.0 and published document.	July 14, 2008	Andrea Fitzwilliam
15.0	2	Added section 9.2 SOAP Sessions with more information regarding cookies and sessions. Added section 12.7 What is the JSESSION ID and who creates it?	July 23, 2008	Steve Davis
15.0	2	Edited changes and published document.	August 26, 2008	Andrea Fitzwilliam
16.0	1	Updated document for Release 16.0.	June 9, 2009	Bob Russell
16.0	1	Updated section 7 XML Schema for EV 95752.	July 9, 2009	Roberta Boyle

cisco.

Release	Version	Reason for Change	Date	Author
16.0	1	Edited changes and published document.	July 15, 2009	Andrea Fitzwilliam
16.0	2	Updated the following sections for EV 100472: 12.4 Is there an OCI-P Demo Client? 12.5 Is there an OCI-P SOAP Demo Client?	November 25, 2009	Patricia Renaud
17.0	1	Updated document for Release 17.0.	March 10, 2010	Tony Pilote
17.0	1	Edited and published document.	March 24, 2010	Margot Hovey-Ritter
17.0	2	Added a section describing requests and responses for EV 110810.	August 25, 2010	Steve Davis
17.0	2	Updated section 3.1 Functional Summary for EV 117130.	August 31, 2010	Goska Auerbach
17.0	2	Updated section 11.1 MD5 Encrypted Password Calculation for EV 118637.	September 23, 2010	Goska Auerbach
17.0	2	Edited changes and published document.	November 2, 2010	Andrea Fitzwilliam
17.0	3	Updated document for EV 120558.	December 15, 2010	Goska Auerbach
17.0	3	Updated links to Xchange.	January 27, 2010	Goska Auerbach
17.0	3	Updated section 10 Backward Compatibility.	February 21, 2011	Engineering
17.0	3	Removed unnecessary BroadWorks Common Communication Transport (BCCT) references for EV 128395. Updated the demo client information.	February 24, 2011	Engineering
17.0	3	Made minor editorial changes.	February 25, 2011	Goska Auerbach
17.0	3	Edited changes and published document.	April 12, 2011	Jessica Boyle
17.0	4	Updated section 10 Backward Compatibility for EV 141758.	May 16, 2011	Engineering
17.0	4	Edited changes and published document.	July 13, 2011	Jessica Boyle
17.0	5	Updated section 3.1 Functional Summary for EV 145537.	July 14, 2011	Engineering
17.0	5	Edited changes and published document.	July 26, 2011	Jessica Boyle
18.0	1	Updated document for Release 18.0.	August 31, 2011	Engineering
18.0	1	Edited changes and published document.	October 4, 2011	Andrea Fitzwilliam
18.0	2	Updated sections 10.8 OCI Commands Removed in Release 18.0 and 10.9 OCI Commands Removed in Release 17.0.	October 27, 2011	Engineering
18.0	2	Edited changes and published document.	October 31, 2011	Andrea Fitzwilliam
19.0	1	Updated document for Release 19.0 and EV 162887 and EV 154303.	October 15, 2012	Engineering

cisco.

Delegas	Version	December Change	Data	Author
Release	version	Reason for Change	Date	Author
19.0	1	Edited changes and published document.	November 6, 2012	Patricia Renaud
20.0	1	Updated section 3.2 Technical Summary for EV 130317.	January 15, 2013	Renaud Beaudry- Magnan
20.0	1	Updated section 10 Backward Compatibility for EV 184329.	February 14, 2013	Goska Auerbach
20.0	1	Updated document for Release 20.0.	November 1, 2013	Engineering
20.0	1	Edited changes and published document.	November 11, 2013	Joan Renaud
21.0	1	Updated document for Release 21.0.	November 13, 2014	Engineering
21.0	1	Updated the BroadSoft legal notice and edited changes.	November 23, 2014	Joan Renaud
21.0	1	Rebranded and published document.	November 27, 2014	Joan Renaud
22.0	1	Updated document for Release 22.0.	September 30, 2016	Engineering
22.0	1	Edited changes and published document.	December 11, 2016	Joan Renaud
23.0	1	Updated section 4.1.1 Authorization Level for PR-56846.	January 29, 2018	Goska Auerbach
23.0	1	Updated document for Release 23.0.	September 21, 2018	Engineering
23.0	1	Rebranded document for Cisco. Added <i>Acronyms and Abbreviations</i> . Edited changes and published document.	September 28, 2018	Joan Renaud
23.0	2	Completed rebranding for Cisco and republished document.	March 17, 2019	Patricia Renaud



Table of Contents

1 Summary of Changes	10
1.1 Changes for Release 23.0, Document Version 2	10
1.2 Changes for Release 23.0, Document Version 1	
1.3 Changes for Release 22.0, Document Version 1	10
1.4 Changes for Release 21.0, Document Version 1	10
1.5 Changes for Release 20.0, Document Version 1	10
1.6 Changes for Release 19.0, Document Version 1	11
1.7 Changes for Release 18.0, Document Version 2	11
1.8 Changes for Release 18.0, Document Version 1	11
1.9 Changes for Release 17.0, Document Version 5	11
1.10 Changes for Release 17.0, Document Version 4	11
1.11 Changes for Release 17.0, Document Version 3	11
1.12 Changes for Release 17.0, Document Version 2	12
1.13 Changes for Release 17.0, Document Version 1	12
1.14 Changes for Release 16.0, Document Version 2	12
1.15 Changes for Release 16.0, Document Version 1	12
1.16 Changes for Release 15.0, Document Version 1	12
1.17 Changes for Release 14.0	12
1.18 Changes for Release 13.0	12
2 Overview	14
3 Overview of Open Client Interface-Provisioning	15
3.1 Functional Summary	15
3.2 Technical Summary	15
4 Details of Open Client Interface-Provisioning	16
4.1 Authorization Levels and Access Control	16
4.1.1 Authorization Level	16
4.1.2 Error Message Example	16
4.1.3 Password Expiration Behavior in OCI-P	17
4.2 Requests and Responses	17
4.3 Aggregate OCI Commands	
4.4 Upload Files within Transactions	
4.4.1 Binary Upload Method	
4.4.2 Indirect Upload Method	18
4.5 Validation	18
5 Cisco BroadWorks Hierarchy	19
5.1 Base Configuration	19
5.2 Department Configuration	20
5.3 Service Configuration	21
6 OCI Reporting	22

CISCO.

6.1 Acc	cess Control List	23	
6.2 Rep	Reporting Over TCP/IP		
6.3 Filte	ering OCI Messages	23	
6.4 Om	nissions	24	
7 XML	Schema	.25	
7.1 XM	L Schema Layout	25	
7.1.1	Base XML Schema	25	
7.1.2	Application Server XML Schema	25	
7.1.3	OCI Reporting XML Schema	26	
7.2 Sch	nema Zip Files	26	
8 Mess	age Examples	.27	
8.1 Gro	pup Add	27	
8.1.1	Request	27	
8.1.2	Success Response	27	
8.1.3	Error Response	27	
8.2 Ret	rieve Groups in Service Provider	28	
8.2.1	Request	28	
8.2.2	Response	28	
9 Open	Client Interface-Provisioning Using SOAP	.29	
9.1 Bro	adWorks OCI-P SOAP Interface	29	
9.2 SO	AP Sessions	31	
9.3 Tra	ce Example	31	
9.4 Sec	cure SOAP	33	
9.5 Tro	ubleshooting SOAP	34	
9.5.1	Common Problems	34	
10 Back	ward Compatibility	.36	
10.1 Dep	orecated Commands	36	
10.2 OC	I Command Naming	37	
10.3 OC	l Commands Removed in Release 23.0	37	
10.4 OC	I Commands Removed in Release 22.0	37	
10.5 OC	I Commands Removed in Release 21.0	37	
	l Commands Removed in Release 20.0		
	Commands Removed in Release 19.0		
	Commands Removed in Release 18.0		
	Commands Removed in Release 17.0		
	Commands Removed in Release 16.0		
	I Reporting Implications		
_	n Process		
12 Appe	ndix A: Frequently Asked Questions	.44	
12.1 Wh	at do acronyms mean?	44	
12.2 Wh	at are the recommendations?	44	

cisco.

12.3 How is the OCS Configured?	45
12.3.1 OCS Configuration Steps	45
12.3.2 Application Server Configuration Steps	46
12.4 Is there an OCI-P Demo Client?	46
12.5 Is there an OCI-P SOAP Demo Client?	46
12.6 What is the session ID and who creates it?	46
12.7 What is the JSESSION ID and who creates it?	46
12.8 Can I send more than one OCI message in a single SOAP message?	47
12.9 What character encodings can I use for special characters?	47
12.10 I do not see any SOAP headers used by the test client. Are they used?	47
12.11 How can I use TCPMON to see messages sent and received?	47
13 Appendix B: Authorization Levels	48
14 Appendix C: Client Licenses Mapping	148
Acronyms and Abbreviations	149



Table of Figures

Figure 1	Basic Relationships	19
Figure 2	OCI Reporting	22

1 Summary of Changes

This section describes the changes to this document for each release and document version.

1.1 Changes for Release 23.0, Document Version 2

This version of the document includes the following change:

Completed rebranding for Cisco and republished document.

1.2 Changes for Release 23.0, Document Version 1

This version of the document includes the following changes:

- Added section 4.1.3 Password Expiration Behavior in OCI-P.
- Updated section 5.1 Base Configuration to include resellers.
- Added section 10.3 OCI Commands Removed in Release 23.0.
- Updated Appendix B: Authorization Levels.
- Updated section 4.1.1 Authorization Level for PR-56846.

1.3 Changes for Release 22.0, Document Version 1

This version of the document includes the following changes:

- Added section 10.4 OCI Commands Removed in Release 22.0.
- Updated Appendix B: Authorization Levels.

1.4 Changes for Release 21.0, Document Version 1

This version of the document includes the following changes:

- Added section 10.5 OCI Commands Removed in Release 21.0.
- Updated Appendix B: Authorization Levels.
- Updated Appendix C: Client Licenses Mapping.

1.5 Changes for Release 20.0, Document Version 1

This version of the document includes the following changes:

- Updated section 3.2 Technical Summary for EV 130317.
- Updated section 10 Backward Compatibility for EV 184329.
- Added section 10.6 OCI Commands Removed in Release 20.0.
- Updated Appendix B: Authorization Levels.
- Updated Appendix C: Client Licenses Mapping.

1.6 Changes for Release 19.0, Document Version 1

This version of the document includes the following changes:

- Added section 7.2 Schema Zip Files.
- Updated section 9.3 Trace Example for EV 162887.
- Added section 10.2 OCI Command Naming.
- Added section 10.7 OCI Commands Removed in Release 19.0.
- Updated section 12.3 How is the OCS Configured? for EV 154303.
- Updated Appendix B: Authorization Levels.

1.7 Changes for Release 18.0, Document Version 2

This version of the document includes the following changes:

 Updated sections 10.8 OCI Commands Removed in Release 18.0 and 10.9 OCI Commands Removed in Release 17.0.

1.8 Changes for Release 18.0, Document Version 1

This version of the document includes the following changes:

- Updated section 6.4 Omissions to add Call Center Enhanced Reporting-related file upload into OCI-R omissions.
- Updated section 10 Backward Compatibility to describe the deprecated OCI commands in Release 18.0.
- Updated Appendix B: Authorization Levels.
- Updated Appendix C: Client Licenses Mapping to remove the services associated with Client License 14 and 15.

1.9 Changes for Release 17.0, Document Version 5

■ Updated section 3.1 Functional Summary for EV 145537.

1.10 Changes for Release 17.0, Document Version 4

Updated section 10 Backward Compatibility for EV 141758.

1.11 Changes for Release 17.0, Document Version 3

- Added Appendix C: Client Licenses Mapping for EV 120558.
- Updated links to Xchange.
- Updated section 10 Backward Compatibility.
- Removed all references to BCCT for EV 128395.
- Updated the demo client information in sections 12.4 Is there an OCI-P Demo Client? and 12.5 Is there an OCI-P SOAP Demo Client?.

1.12 Changes for Release 17.0, Document Version 2

- Added section 4.2 Requests and Responses for EV 110810.
- Updated section 3.1 Functional Summary for EV 117130.
- Updated section 11.1 MD5 Encrypted Password Calculation for EV 118637.

1.13 Changes for Release 17.0, Document Version 1

Creation of the document from Release 16.0 Version 2 with the following change:

Added a note about deprecation.

1.14 Changes for Release 16.0, Document Version 2

- Updated the following sections for EV 100472:
 - 12.4 Is there an OCI-P Demo Client?
 - 12.5 Is there an OCI-P SOAP Demo Client?

1.15 Changes for Release 16.0, Document Version 1

- Updated section 7 XML Schema for EV 95752.
- Updated document for Release 16.0.

1.16 Changes for Release 15.0, Document Version 1

The following changes were made to this document for Release 15.0:

- Sections 9.2 SOAP Sessions and 12.7 What is the JSESSION ID and who creates it? were added.
- The document was updated for Release 15.0.

1.17 Changes for Release 14.0

The ability to filter messages for each external system for Open Client Interface (OCI) reporting was added.

The Operations Support System (OSS) interface is supported in Release 14.0 and Release 14.sp1, without any enhancements for functionality that has been added to Cisco BroadWorks since Release 13.0. Any functionality added in any maintenance patches (MPs) subsequent to Release 13.0 and in Release 14.0, itself, is not supported by the OSS interface.

It is not possible to provision to a Cisco BroadWorks Application Server (AS) via the OSS interface in Release 14.sp2 and higher as the code is removed.

1.18 Changes for Release 13.0

The existing Operations Support System (OSS) interface is now obsolete and has been replaced with a new provisioning interface called the Open Client Interface-Provisioning (OCI-P), which is introduced in Release 13.0. The OSS interface, which is now obsolete, is supported through Release 14.sp1. For more information on the obsolete interface, see *Cisco BroadWorks Application Server Provisioning Interface Specification Obsolete*, Release 13.0.

The following list summarizes the major differences between the OSS interface and OCI:



- The OCI-P uses an eXtensible Markup Language (XML) schema instead of a Document Type Definition (DTD), providing easier and more complete integration with the provisioning interface.
- The OCI-P uses more discrete transactions that can easily be understood. For example, modifyUserService, which handled all user services and required developers to select the correct DTD elements, is replaced by a transaction for each service, such as UserDoNotDisturbModifyRequest.
- The OCI-P is a common interface provided with the web and CLI interfaces instead of a separate interface. By default, this allows all functionality for the web and CLI interfaces to be exposed in an external interface.
- The OCI-P supports backward compatibility for two releases.

The OCI-P has a reporting mechanism associated with it (OCI Reporting).



2 Overview

The Provisioning Server provides an external provisioning interface, which is a TCP-IP/XML-based interface that is used to allow third-party clients and legacy systems to interwork with the Application Server. The server also provides a reporting interface that can be subscribed to for changes that take place in the system.

This document describes the external provisioning interface, both at a functional level and a more detailed interface specification level.



3 Overview of Open Client Interface-Provisioning

3.1 Functional Summary

The Open Client Interface (OCI) consists of provisioning and provisioning reporting parts.

Prior to Release 13.0, the provisioning part was the OSS Interface. The OSS Interface is replaced with an interface simply known as the OCI or OCI-P (provisioning part of OCI).

In general, the Open Client Interface-Provisioning (OCI-P) is a provisioning interface that allows third-party applications to perform on all business functions by Cisco BroadWorks. This allows communication to legacy systems or the creation of value-added clients.

The OCI is assessed from the Open Client Server (OCS), which resides on the Xtended Services Platform.

The OCI also has a reporting mechanism that sends all messages received in the same format to an external system. It can be used to receive changes made in the system so that legacy systems can be updated or external business logic can be executed. Note that in a few cases the message is modified to remove passwords and large binary files.

3.2 Technical Summary

The OCI is an XML-based application programming interface (API). The interface uses an XML schema to define the structure, content, and semantics of an XML document.

The OCI is available on the Provisioning Server and OCS using Transmission Control Protocol/Internet Protocol (TCP/IP) connections. Note that the OCS uses a standard TCP/IP connection with no special headers and is also the recommended entry point to the Provisioning Server.

The OCI Reporting Interface can be accessed by opening a TCP/IP connection to port 8025 (default value) on the Provisioning Server. Note that it must first be configured in the CLI interface at the Interfaces/OCI/Reporting level, before it is used.

Note that currently each session is binded to a TCP connection and should a client attempt to execute a command using an invalid session ID, the connection will immediately be dropped. This is done for security reasons, since an invalid session ID may indicate a compromised connection. To prevent any drop in connectivity between the client application and the OCS, the session ID must be validated beforehand.

A second option to avoid a connection being dropped is to use the *containerOption* found under the OCS application named *sendErrorOnInvalidSessionID*. This option allows the system to send an error message to the user executing a command with an invalid session ID instead of dropping the connection. By activating this feature, if a client application acts has a connection concentrator, by sending all the users through common TCP connections, exposes itself to possible theft of session IDs from other mischievous users. In this scenario, it is crucial and also the responsibility of the client application to validate the session ID to prevent any user from stealing the session ID of another user.

4 Details of Open Client Interface-Provisioning

4.1 Authorization Levels and Access Control

Each OCI command has an authorization level and access permission that is used to prevent third-party software from accessing or modifying data that is outside the scope of the login ID. These permissions are taken from the authenticated login ID for the connection established with Cisco BroadWorks.

4.1.1 Authorization Level

Each command has an authorization level. If the login ID is not at least at the level of authorization, the transaction is denied. The following list shows the authorization levels in order of access. from the most access to the least:

- System
- Provisioning
- Service provider
- Group
- User

For more information on the different authorization levels (roles), see the section on roles and responsibilities in the Cisco BroadWorks Application Server System Provider Web Interface Administration Guide.

For a list of OCI commands and their respective authorization levels, see *Appendix B: Authorization Levels*.

Once the authorization level check is performed, each command is also checked for access control. Access control verifies that the login ID attempting to execute the command is allowed access to that data. This means service providers can only see the attributes of their service provider, their groups, and their users. The same principle applies for groups and users; they can only see data that "belongs" to them.

For example, only a service provider administrator from service provider A is allowed to retrieve groups from service provider A. A service provider administrator from service provider B would be denied access.

4.1.2 Error Message Example

The following example is an error message received from an unauthorized request or from a user who does not have access to the data.

```
<command xsi:type="c:ErrorResponse" echo="" type="Error">
  <summary>[Error 4003] Unauthorized request:
   UserDoNotDisturbGetRequestImpl</summary>
   <summaryEnglish>[Error 4003] Unauthorized request:
   UserDoNotDisturbGetRequestImpl</summaryEnglish>
  </command>
```

4.1.3 Password Expiration Behavior in OCI-P

By default, when a login ID has an expired password, OCI-P requests will still execute for the login ID. It is expected that the client uses the *passwordExpiresDays* field (when the value is less than or equal to 0) in the login response to enforce when the user should reset their password. If the desired behavior is for OCI-P requests not to execute, there is a system parameter, *enforcePasswordChangeOnExpiry*, that can be set to "true" which will only allow the LoginRequestXX and the PasswordModifyRequest OCI-P commands to be executed when the password has expired for the login ID. This means the client must be providing a mechanism for the user to reset their password.

4.2 Requests and Responses

The Open Client Interface-Provisioning follows a request/response pattern:

- When adding, deleting, or modifying data, the response indicates success or an error response.
- When retrieving information, the response contains either the requested data or an error response.

NOTE: The response to a delete command should not be used to determine whether data existed prior to sending the request. In most cases, when attempting to delete non-existing data, the response indicates success.

4.3 Aggregate OCI Commands

Each OCI transaction is an atomic business function that can be performed with no other transactions. In some cases, third-party applications can be set to perform multiple OCI transactions at a single time. For example, when displaying information about a user's profile and retrieving service data, it is possible to create an OCI request with multiple transactions in the body. Note that each transaction is still treated individually and is committed to the datastore individually. It is recommended to limit the number of actions to no more than 15 transactions (to use server resources efficiently).

4.4 Upload Files within Transactions

Various transactions require files to be uploaded to Cisco BroadWorks that are to be used by the system. This includes audio, video, and configuration files. OCI transactions support the ability to do this.

There are two methods that can be used to perform file uploads. The first method, binary upload, allows a binary stream to be placed within the OCI transaction itself. The second method, indirect upload, allows a system to place the file on the Application Server, through a different mechanism (for example, File Transfer Protocol [FTP]) and direct the OCI transaction to move the file to the correct location on the Application Server.

The following data types are used to upload files:

- File Resource Allows uploading of files only.
- Labeled File Resource Extends the file resource to also include a description of where the original file name is stored so that it can be displayed to users at a later time
- Extended File Resource Allows uploading of files and has the ability to specify a Uniform Resource Locator (URL) to use for a file instead of storing the file on Cisco BroadWorks.



4.4.1 Binary Upload Method

For the binary upload method, the file is converted to base64BINARY and is included in the OCI command. For more information on base64BINARY, go to http://www.w3.org/TR/2004/PER-xmlschema-2-20040318/#base64Binary.

4.4.2 Indirect Upload Method

For the indirect upload method, the external system is required to put the file in a specific location on the Application Server. This location is defined in the *appserver.properties* file with the name customerSoundFileDir and by default is in the /war/broadworks/userfiles/customFiles/ directory. Once uploaded, by placing the file name in the OCI command, the transaction moves the file to the appropriate location.

4.5 Validation

The OCI is fully validated at the backend. Only basic validation is performed in the XML schema itself, since Cisco BroadWorks is required to provide error messages in multiple languages, which is beyond the capability of the XML schema. All validation performed by the XML schema must be validated by the system sending the transactions, to avoid receiving cryptic XML parsing errors.

5 Cisco BroadWorks Hierarchy

5.1 Base Configuration

The Cisco BroadWorks Application Server has four main levels of control:

- System provider
- Service provider/enterprise
- Group
- User

All other elements are associated with these levels. *Figure 1 Basic Relationships* illustrates the basic relationships so that commands can be more easily used. It is recommended that before using this interface, a developer must have a good working knowledge of the Application Server.




Figure 1 Basic Relationships

The system provider is the operator of the system. There is one logical system provider object on the Application Server. However, there can be multiple administrative accounts for the system provider.

The reseller is an optional level of the hierarchy. It allows true "resellers" to be modeled such that both the enterprise and small group models are supported. Some of the system level commands are allowed by a reseller (see *Appendix B: Authorization Levels*). When executed by a reseller administrator, it is implicit that the scope of the command is limited to the reseller.



If a system provider is supporting the concept of "resellers", the system provider can create one or more service providers. A service provider can be assigned a finite set of phone numbers (DNs) and service instances by the system provider. The service provider can then create groups and users and distribute or resell DNs and services. If the concept of reselling is not implemented, the operator of the Application Server can act as both the system provider and service provider. In this case, only a single service provider exists in the system. In addition, note that an enterprise is the same as a service provider. All commands used for service providers apply to enterprises. There are a few specific enterprise commands that are listed separately since they apply only to enterprises and not to service providers.

A group represents the concept of a company (business model) or a family (residential model). A group has a finite amount of resources (services, DNs, and access devices) assigned to it. A group is assigned one or more administrators; these administrators can create, delete, and modify the members and resources assigned to the group.

An end user is a member of a group and can modify his or her service data.

Actions can be taken on each logical object via the Open Client Interface-Provisioning (OCI-P). For example, the OCI can query a group for a list of the DNs assigned to the group, or it can query a service provider for a list of DNs assigned to the service provider.

The following are the main elements, not including the four described above, used by the Application Server:

- Administrator Administrators are allowed to make changes to the above base elements. Administrators can be created as system administrators, service provider/enterprise administrators, and group administrators.
- Domain Domains are resources in the Cisco BroadWorks system. They are allocated by the system provider to the service provider, who can give them to groups who can use them to create users. The *domainName* value must be unique regardless of case.
- Phone Number Phone numbers, directory numbers (DNs), or telephone numbers (TNs) are resources in the Cisco BroadWorks system. They are allocated by the system provider to the service provider, who can give them to groups who can use them for users and services.
- Access Device Access devices are used by users to make and receive calls, which can be Integrated Access Devices (IADs), Internet Protocol (IP) phones, soft clients, or others. They can be created at the service provider/enterprise level and shared by users across groups, or they can be created at the group level and only used by users in that group.

5.2 Department Configuration

For departments, a list is created for each group (enterprise) and is associated to users. It provides a way to group users inside a group (enterprise). Department commands are included in group and user commands.

The ability of a department administrator to perform actions is not controlled by the interface, but by the front end. A department administrator has all the capabilities of a group administrator in this interface. This allows different interfaces to expose more or less control for these types of administrators.



5.3 Service Configuration

Services are the building blocks used to provide service within Cisco BroadWorks. Services, in most cases, must be given to the groups and users to provide the functionality required. The following steps are required for this to occur:

- Authorizing the services to the service provider Services must be authorized to the service provider or enterprise before being used by lower levels. This allows a system provider to restrict what services a service provider/enterprise sells or uses.
- Authorizing the services to the group Only services that are authorized to the service provider can be authorized to the group. Services must be authorized to the group before being used by the group or users.
- Assigning services to the group (group services only) Group services must be assigned to the group to enable the capability of those services. A service must be authorized to the group before being assigned.
- Assigning services to the user (user services only) User services must be assigned
 to the user to enable the capability of those services. A service must be authorized to
 the group before being assigned.
 - In addition, the group has two additional capabilities involving the assignment of services:
- New User services The New User services command allows a list of user services to be defined as the list of services that should be automatically assigned when a new user is created.
- Existing user services The Existing User services command allows a list of user services to be assigned or unassigned to all users within the group. This command is only for small groups of users (less than 50). If many services must be assigned or unassigned to or from users, use the Service Pack Migration feature.

6 OCI Reporting

If configured, the Application Server relays all successful OCI modification requests to external systems, as shown in *Figure 2 OCI Reporting*. Each OCI modification request is relayed as an OCIReportingReportNotification over TCP/IP. The OCIReportingReportNotification contains the following:

- User ID and authorization level of the account enacting the OCI modification request
- XML string of the OCI modification request

In some cases, the XML string included in the OCIReportingReportNotification differs from that received over the OCI; some data can be omitted. In such an event, the OCIReportingReportNotification also contains indicators related to the omission. For more information, see section *6.4 Omissions*.

The Application Server sends a separate OCIReportingReportNotification for each successful OCI modification request. This is the case even when the OCI modification requests from the provisioning client have been aggregated.

Within a redundant Application Server pair, each Application Server sends OCIReportingReportNotifications independently of each other. External systems must connect to both nodes in a redundant Application Server pair to receive all modifications made to the pair. The rest of this section focuses on the behavior within an Application Server node.




Figure 2 OCI Reporting



6.1 Access Control List

Only system administrators can configure reporting. The system administrator can do this using one of the following two methods:

- The system administrator can add the addresses (can be an IP address or a fully qualified host name) of all external systems to the access control list via the AS CLI/System/NetworkAccessLists/OCIReporting level.
- The system administrator can configure access control lists by submitting OCI requests.

External systems whose addresses are in the access control list are permitted to connect to the Application Server. One connection is permitted per IP address. The Application Server sends OCIReportingReportNotifications to all connections.

6.2 Reporting Over TCP/IP

The system administrator can configure the following via the AS_CLI/Interface/OCI/Reporting level:

- The server port to which external systems connect. The default value is 8025.
- Whether to enable pinging to verify the continued availability of each connection.
 Pinging is enabled by default.
- The interval at which ping messages are sent. The default value is 30 minutes.
- Whether passwords sent in reports of OCI modification requests are modified to "XXXXX" for security. If true, the OCIReportingReportNotification contains the "isAltered" element. The default value is "true".

Modification of any of these attributes requires a restart of the Application Server.

When pinging is enabled, the Application Server periodically sends OCIReportingServerStatusNotifications to all connections. No response is expected. The external system must handle this message (receipt of the ping message at the configured interval indicates to the external system that the connection is up). The Application Server sends the OCIReportingServerStatusNotification to detect and clean up broken connections.

6.3 Filtering OCI Messages

The system administrator can restrict messages sent to each external system by setting restrictMessages to "true" for that external system. The system administrator can configure which messages the external system received by adding the full message names one by one in the <code>AS_CLI/System/NetworkAccessLists/OCIReporting/MessageTypes</code> level. If the external system is interested in a group of messages that begin with the same name (for instance all commands that begin with Group), the <code>messageStartsWith</code> parameter can be set to "Group", when adding a message type for the external system.

6.4 Omissions

Under most circumstances, the OCI modification request XML string in the OCIReportingReportNotification is identical to that received over the OCI. Differences center on elements of type "FileResource" as defined in the OCI schema. The FileResource is a choice of sourceFileName (specifying a previously uploaded file), or fileContent (binary content of the uploaded file). To mitigate the impact to capacity:

- The elements of type FileResource are omitted from the OCI modification request if those elements are used to upload media files (audio files and video files) or conferencing documents.
- The omission element (of type OCIReportingOmission) is included in the OCIReportingReportNotification to indicate that the uploaded file contents were omitted.
- This omission can invalidate the OCI modification request, for example, it fails validation against the OCI schema because the omitted element is mandatory. In such cases, the requestInvalidated element is included in the OCIReportingReportNotification to indicate this.

The FileResource element remains in the OCI modification request if the FileResource element is used to specify a previously uploaded file.

Given the above, external systems do not have access to the uploaded media file or conferencing document over the OCI Reporting Interface. However, they are informed that an upload occurred; they are also informed of the selection of a previously uploaded media file or conferencing document.

If an external system is archiving OCIReportingReportNotifications and re-submitting their contents over the OCI to re-provision an Application Server, it is possible for the resubmitted OCI requests that specify a previously uploaded file to fail, since the file contents of uploaded media files and conferencing documents were not included in OCIReportingReportNotifications.

For this release, the FileResource element is omitted from reports of the following OCI-based upload functions:

- Conferencing document upload
- Voice Portal branding file upload
- Personalized Name file upload
- Auto Attendant greeting file upload
- Music On Hold file upload
- Intercept Announcement file upload
- Voice Messaging greetings file upload
- Call Center Enhanced Reporting branding file upload
- Call Center Enhanced Reporting template/style template file upload

Reports for the following OCI-based file upload functions are not affected:

- Enhanced device configuration/Subnetwork Access Protocol (SNAP)
- Phone list import
- Call Processing Language (CPL) file upload

7 XML Schema

NOTE: The "XXX" in the zip file references refers to the release number on which you are deployed.

7.1 XML Schema Layout

The XML schema is available in the XXX_OCISchemaBASE.zip, XXX_OCISchemaAS.zipfile, and XXX_OCISchemaReporting.zip files. This section describes the structure of the XML schema.

7.1.1 Base XML Schema

The base XML schema is included in the XXX_OCISchemaBASE.zip file. It contains only two files. It contains the base definitions for messages, success and error messages, tables, and other low-level attributes. No functional transactions are defined in these files.

7.1.2 Application Server XML Schema

The Application Server (AS) XML schema is included in the *XXX_OCISchemaAS.zip* file. It contains all functional transactions for the system. The following files are available:

- OCISchemaAS.xsd This file is the base file for the Application Server XML schema files. This file references all included files.
- OCISchemaDataTypes.xsd This file contains the data types used in the XML schema that are used at multiple levels in the hierarchy, such as the definitions of an IP address or phone number.
- OCISchemaLogin.xsd This file contains the transactions related to logging a user in to the system.
- OCISchemaSystem.xsd This file contains the transactions that apply for the entire system, such as adding Media Servers or Network Servers, maintaining the language settings, and modifying system administrators.
- OCISchemaServiceProvider.xsd This file contains the transactions that apply for the service provider, such as adding service providers, modifying service provider administrators, and authorizing services to service providers. Note that in the OCI, an enterprise and a service provider are the same. When adding a service provider, specify if it is an enterprise or a service provider.
- OCISchemaEnterprise.xsd This file contains the transactions that only apply to enterprises and not to service providers. Most enterprise transactions are found in the OCISchemaServiceProvider.xsd file.
- OCISchemaGroup.xsd This file contains the transactions that apply to groups, such as adding groups, modifying group administrators, and authorizing services to groups.
- OCISchemaUser.xsd This file contains the transactions that apply to users, such as adding users and assigning services to users.
- OCISchemaSearchCriteria.xsd This file contains search criteria data types used in the XML schema files.
- OCISchemaSortCriteria.xsd This file contains sort criteria data types used in the XML schema files.



 OCISchemaService*.xsd – Each service that can be licensed has a file that contains all transactions that apply for that service. For example, the OCISchemaServiceDoNotDisturb.xsd file contains all Do Not Disturb transactions.

7.1.3 OCI Reporting XML Schema

The OCI Reporting XML schema contains all functional transactions for the system. The following files are available:

- OCISchemaReporting.xsd This file is the base file for the Application Server XML Schema files. This file references all included files.
- OCISchemaReportingBASE.xsd This file contains the base elements for OCI reporting.
- OCISchemaReportingDataTypes.xsd This file contains the data types used in the XML Schema.
- OCISchemaReportingReportNotification.xsd This file contains the notification XML Schema.
- OCISchemaReportingServerStatusNotifiction.xsd This file contains the server status XML Schema.

7.2 Schema Zip Files

Cisco provides the AS OCI-P schema as part of a zip file that contains all schemas and MIBs per release on Xchange at xchange.broadsoft.com. Additionally there is an HTML version of the AS OCI-P schema available for download on Xchange.

For service patches that are built on top of a major release (for example, 19sp1), a new version of the schema zip file is uploaded to Xchange when each patch is made available.

8 Message Examples

This section provides examples of messages.

8.1 Group Add

8.1.1 Request

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<BroadsoftDocument protocol="OCI" xmlns="C"</pre>
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <sessionIdxmlns="">BB1A413DF12D404128F8956459FBD4D9/sessionId>
  <command xsi:type="GroupAddRequest" xmlns="">
    <serviceProviderId>sp1</serviceProviderId>
    <groupId>group2</groupId>
    <defaultDomain>broadworks</defaultDomain>
    <userLimit>25</userLimit>
    <groupName>Group 2</groupName>
    <callingLineIdName>Group 2 Line ID</callingLineIdName>
    <timeZone>America/New York</timeZone>
    <contact>
      <contactName>Joe Smith</contactName>
      <contactNumber>301-555-1212</contactNumber>
      <contactEmail>joe.smith@broadworks.net</contactEmail>
    </contact>
  </command>
</BroadsoftDocument>
```

8.1.2 Success Response

8.1.3 Error Response

8.2 Retrieve Groups in Service Provider

8.2.1 Request

8.2.2 Response

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<BroadsoftDocument protocol="OCI" xmlns="C"</pre>
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
<sessionId xmlns="">BB1A413DF12D404128F8956459FBD4D9</sessionId>
  <command debugInfo="3:130" echo=""</pre>
xsi:type="GroupGetListInServiceProviderResponse" xmlns="">
    <groupTable>
      <colHeading>Group Id</colHeading>
      <colHeading>Group Name</colHeading>
      <colHeading>User Limit</colHeading>
        <col>group1</col>
        <co1/>
        <col>25</col>
      </row>
      <row>
        <col>group2</col>
        <col>Group 2</col>
        <col>25</col>
      </row>
    </groupTable>
  </command>
</BroadsoftDocument>
```

9 Open Client Interface-Provisioning Using SOAP

9.1 BroadWorks OCI-P SOAP Interface

The Open Client Interface-Provisioning (OCI-P) is also available via SOAP to the Web Server. The Cisco BroadWorks login sequence and the OCI-P message payloads are exactly the same as they are when not using SOAP.

Tomcat uses the Axis engine to wrap and unwrap the OCI message payload in the SOAP envelope, calling on the Provisioning Service servlet with the contents.

The Provisioning Service servlet, acting as an OCS client, matches HTTP requests and responses to a connection to the OCS, and passes OCI data back and forth on that connection. This servlet uses a configuration xml file called <code>public_html/webservice/WEB-INF/serviceconfig.xml</code>, which should look similar to the one shown in the following example. Note that if you need to make changes to this configuration, you must edit this file manually.

The OCS passes messages on to the Provisioning Server. For information on configuring the OCS, see *Appendix A: Frequently Asked Questions*.

The Web Service Definition Language (WSDL) is automatically generated by Axis and is shown in the following example. It shows how to construct messages and what to expect in return. Essentially each call contains one or more OCI request message as a single string argument, and returns the OCI response message(s) as a single string value.

You can retrieve the WSDL with the following URL, substituting an appropriate value for "yourWSServer":

http://yourWSServer/webservice/services/ProvisioningService?wsdl

Two method names in the WSDL, *processMessage* and *processOCIMessage*, are shown. Note that *processOCIMessage* is the preferred name to use. Currently the Cisco SOAP interface uses the document/literal encoding as specified in the WSDL.

```
<element name="processMessageResponse">
        <complexType>
          <sequence>
           <element name="processMessageReturn" type="xsd:string"/>
          </sequence>
        </complexType>
      </element>
      <element name="processOCIMessage">
        <complexType>
          <sequence>
            <element name="request" type="xsd:string"/>
          </sequence>
        </complexType>
      </element>
      <element name="processOCIMessageResponse">
        <complexType>
          <sequence>
            <element name="processOCIMessageReturn" type="xsd:string"/>
          </sequence>
        </complexType>
      </element>
    </schema>
  </wsdl:types>
 <wsdl:message name="processMessageResponse">
    <wsdl:part element="impl:processMessageResponse" name="parameters"/>
  </wsdl:message>
  <wsdl:message name="processMessageRequest">
    <wsdl:part element="impl:processMessage" name="parameters"/>
  </wsdl:message>
  <wsdl:message name="processOCIMessageRequest">
    <wsdl:part element="impl:processOCIMessage" name="parameters"/>
  </wsdl:message>
  <wsdl:message name="processOCIMessageResponse">
    <wsdl:part element="impl:processOCIMessageResponse"</pre>
name="parameters"/>
 </wsdl:message>
  <wsdl:portType name="BWProvisioningService">
    <wsdl:operation name="processMessage">
      <wsdl:input message="impl:processMessageRequest"</pre>
name="processMessageRequest"/>
     <wsdl:output message="impl:processMessageResponse"</pre>
name="processMessageResponse"/>
   </wsdl:operation>
    <wsdl:operation name="processOCIMessage">
      <wsdl:input message="impl:processOCIMessageRequest"</pre>
name="processOCIMessageRequest"/>
      <wsdl:output message="impl:processOCIMessageResponse"</pre>
name="processOCIMessageResponse"/>
    </wsdl:operation>
 </wsdl:portType>
 <wsdl:binding name="ProvisioningServiceSoapBinding"</pre>
type="impl:BWProvisioningService">
    <wsdlsoap:binding style="document"</pre>
transport="http://schemas.xmlsoap.org/soap/http"/>
    <wsdl:operation name="processMessage">
      <wsdlsoap:operation soapAction=""/>
      <wsdl:input name="processMessageRequest">
        <wsdlsoap:body use="literal"/>
      </wsdl:input>
```

```
<wsdl:output name="processMessageResponse">
        <wsdlsoap:body use="literal"/>
      </wsdl:output>
    </wsdl:operation>
    <wsdl:operation name="processOCIMessage">
      <wsdlsoap:operation soapAction=""/>
      <wsdl:input name="processOCIMessageRequest">
        <wsdlsoap:body use="literal"/>
      </wsdl:input>
      <wsdl:output name="processOCIMessageResponse">
        <wsdlsoap:body use="literal"/>
      </wsdl:output>
    </wsdl:operation>
  </wsdl:binding>
 <wsdl:service name="BWProvisioningServiceService">
   <wsdl:port binding="impl:ProvisioningServiceSoapBinding"</pre>
name="ProvisioningService">
      <wsdlsoap:address</pre>
location="http://localhost/webservice/services/ProvisioningService"/>
    </wsdl:port>
 </wsdl:service>
</wsdl:definitions>
```

9.2 SOAP Sessions

All OCI-P messages contain a session ID used to uniquely identify a session. In addition, when using OCI-P over SOAP, there is another kind of session identifier called the JSESSIONID. The JSESSIONID is a cookie.

OCI-P session IDs are created by the client application. JSESSIONIDs are created by the Cisco BroadWorks Web Server.

The first request sent to Cisco BroadWorks contains the AuthenticationRequest. The JSESSIONID cookie should not be specified in the AuthenticationRequest. Cisco BroadWorks responds with an AuthenticationResponse. The HTTP response from Cisco BroadWorks contains the JSESSIONID cookie. This cookie must be remembered and returned to Cisco BroadWorks in all subsequent requests for this session.

Each OCI-P session ID is associated with a unique JSESSIONID. Do not attempt to send commands for multiple OCI-P sessions over a single JSESSION. Similarly, do not attempt to spread the commands for a single OCI-P session across multiple JSESSIONS.

9.3 Trace Example

The following example shows a trace containing a SOAP request and response, including HTTP headers and the body. Each Cisco OCI message embedded in the SOAP envelope is shown in bold. Additional formatting changes have been made for indentation, in which case, the Content-Length header value is probably no longer correct.

The following example shows the UserGetRequest (readable version) that has been sent.



</BroadsoftDocument>

The following is the full output of the request.

```
POST /webservice/services/ProvisioningService HTTP/1.0
Content-Type: text/xml; charset=utf-8
Accept: application/soap+xml, application/dime, multipart/related, text/*
User-Agent: Axis/1.3
Host: 127.0.0.1:80
Cache-Control: no-cache
Pragma: no-cache
SOAPAction: ""
Content-Length: 931
Cookie: JSESSIONID=B348060A6B30CD5BCE9F05B7A68C18F7
<?xml version="1.0" encoding="UTF-8"?>
<soapenv:Envelope</pre>
xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/"
 xmlns:xsd="http://www.w3.org/2001/XMLSchema"
 xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
 <soapenv:Body>
    cprocess0CIMessage
soapenv:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/">
     <arg0 xsi:type="soapenc:string"</pre>
xmlns:soapenc="http://schemas.xmlsoap.org/soap/encoding/">
<?xml version=&quot;1.0&quot; encoding=&quot;ISO-8859-1&quot;?&gt;
<BroadsoftDocument protocol=&quot;OCI&quot; xmlns=&quot;C&quot;
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"&qt;
 <sessionId
xmlns=""&qt;192.168.40.90,4890830,1178037541796</sessionId&q
 <command xsi:type=&quot;UserGetRequest18&quot;
xmlns=" " >
   <userId&gt;sp1g1user1&lt;/userId&gt;
  </command&qt;
</BroadsoftDocument&gt;
     </arg0>
    </soapenv:Body>
</soapenv:Envelope>
```

The Provisioning Server responds as follows.

```
HTTP/1.1 200 OK
Date: Tue, 01 May 2007 16:40:24 GMT
Server: Apache/2.0.55 (Win32) DAV/2 mod ss1/2.0.55 OpenSSL/0.9.8a
mod jk/1.2.15
Connection: close
Content-Type: text/xml; charset=utf-8
<?xml version="1.0" encoding="utf-8"?>
<soapenv:Envelope</pre>
xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/"
 xmlns:xsd="http://www.w3.org/2001/XMLSchema"
 xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <soapenv:Body>
    cprocessOCIMessageResponse xmlns="">
      <ns1:processOCIMessageReturn
xmlns:ns1="urn:com:broadsoft:webservice">
        <?xml version=&quot;1.0&quot; encoding=&quot;ISO-8859-
1"?>
```



```
<BroadsoftDocument protocol=&quot;OCI&quot; xmlns=&quot;C&quot;
xmlns:xsi="http://www.w3.org/2001/XMLSchema-
instance"><sessionId
xmlns=""&qt;10.2.199.11,3849351,1351619186392</sessionId&qt;
<command echo=&quot;&quot; xsi:type=&quot;UserGetResponse18&quot;
xmlns=""&qt;<serviceProviderId&qt;sp1&lt;/serviceProviderId&
qt; < qroupId&qt; sp1q1&lt; /qroupId&qt; &lt; lastName&qt; sp1q1user1&lt; /las
tName><firstName&gt;splgluser1&lt;/firstName&gt;&lt;callingLineIdLa
stName>splqluser1</callingLineIdLastName&gt;&lt;callingLineIdFirstN
ame>splgluserl</callingLineIdFirstName&gt;&lt;hiraganaLastName&gt;s
plgluser1</hiraganaLastName&gt;&lt;hiraganaFirstName&gt;splgluser1&lt;
/hiraganaFirstName&qt;<language&qt;English&lt;/language&qt;&lt;timeZon
e>America/New York</timeZone&gt;&lt;timeZoneDisplayName&gt;(GMT-
04:00) (US) Eastern
Time</timeZoneDisplayName&qt;&lt;defaultAlias&qt;splqluserl@broadworks
</defaultAlias&gt;&lt;countryCode&gt;1&lt;/countryCode&gt;&lt;/command
> < /BroadsoftDocument&gt
     </ns1:processOCIMessageReturn>
   </soapenv:Body>
</soapenv:Envelope>
```

The readable version of the actual OCI UserGetResponse18 response is as follows.

```
<?xml version="1.0"?>
        <BroadsoftDocument protocol="OCI" xmlns="C"</pre>
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
          <sessionId
xmlns="">192.168.40.90,4890830,1178037541796</sessionId>
          <command debugInfo="16:468" echo="" xmlns=""</pre>
xsi:type="UserGetResponse18">
            <serviceProviderId>sp1</serviceProviderId>
            <groupId>splg1</groupId><lastName>splg1user1</lastName>
            <firstName>splgluser1</firstName>
            <callingLineIdLastName>sp1gluser1</callingLineIdLastName>
            <callingLineIdFirstName>sp1gluser1</callingLineIdFirstName>
            <hiraganaLastName>splgluser1</hiraganaLastName>
            <hiraganaFirstName>splgluser1</hiraganaFirstName>
            <language>English</language>
            <timeZone>America/New York</timeZone>
            <timeZoneDisplayName>(GMT-04:00) (US) Eastern
Time</timeZoneDisplayName>
            <defaultAlias>splgluser1@broadworks</defaultAlias>
          </command>
        </BroadsoftDocument>
```

9.4 Secure SOAP

OCI-P/SOAP requests can be submitted over a secure HTTP connection by changing the server's URL scheme to HTTPS instead of HTTP. This means that the Cisco BroadWorks Web Server's certificate must be captured and then imported with Sun's keytool utility (provided with Java). A method to do this is as follows.

 Obtain a copy of the certificate in X.509 format using Microsoft's Internet Explorer Version 6, by accessing the HTTPS URL. A dialog requesting permission to accept the certificate appears. Click the *View Certificate* button, then the *Details* tab. Click *Copy to File*, then *Next* and select the Base-64 encoded X.509 (.CER) option. Click *Next* to save the file.



- 2) Import the .cer file using the keytool utility, which can be found in the bin directory for a Java installation. Using this tool, the .cer file is imported into a cacerts file, which is located in the lib/security directory of a Java installation. The simplest method is to copy the .cer file obtained using Internet Explorer to your Java home dir/lib/security directory.
 - \$../../bin/keytool.exe –import –storepass changeit –file mycert.cer –keystore cacerts alias mycert
- 3) The only changes required are the name of the certificate (in this case *mycert.cer*) and the alias (mycert). Do this in the same VM as you run your client.

For more information on Secure Sockets Layer (SSL), see the *Cisco BroadWorks SSL Support Options Guide*.

9.5 Troubleshooting SOAP

To troubleshoot a problem, a good starting point is to see if the OCI-P sample SOAP client can successfully log in and exchange messages. Many problems can be identified by following this checklist:

- Verify the URL used to log in.
- Verify that the correct username and password have been supplied.
- Verify that the web service is available. Can you access the Apache Axis page (http://localhost/webservice) and click view to see the list of deployed services?
- Verify that the web service is connected to the OCS. Is the test client able to successfully send and receive messages?
- Verify the login sequence (authentication and login) was successful before sending other messages.
- Verify that all requests (after the first request) contain the JSESSIONID cookie returned in the first response.
- If you are using HTTPS, verify that the correct certificate is installed locally. For more information, see section 9.4 Secure SOAP.

9.5.1 Common Problems

The following list describes some common problems:

Problem: org.xml.sax.SAXException: Bad envelope tag: html Fault String: org.xml.sax.SAXException:

-or-

Problem: The Axis engine could not find a target service to invoke!

- Check the URL. The following shows an example of an incorrect and correct URL:
- incorrect: http://localhost/webservices/<u>service</u>/Provisioning<u>Server</u>
- correct: http://localhost/webservice/<u>services</u>/Provisioning<u>Service</u>
- Problem: NO_OCS_CONNECTION The connection from the web service to OCS has been lost, or does not exist.
 - Verify that public_html/webservice/WEB-INF/serviceconfig.xml has been initialized correctly, (as described in section 9.1 BroadWorks OCI-P SOAP Interface), on the web server you are accessing.

- Use the CLI to verify that the OCS is configured correctly (as described in section 12.3.1 OCS Configuration), and is running.
- Verify that all requests (after the first request) contain the JSESSIONID cookie returned in the first response.
- Problem: ACCESS_DENIED Access was denied because the user is invalid; the service detected an InvalidUserException.
 - Verify that you are using the correct user ID.
- Problem: LOGIN_FAILED An error occurred while the service was logging in to the Provisioning Server. This is a catchall for non-specific errors.
 - Please try again.
- Problem: REQUEST_TIMEOUT The OCS, or the Provisioning Server through the OCS, did not respond in a timely manner; the service may have received a RequestTimeoutException.
 - Verify that the Provisioning Server is running.
 - Verify that the OCS is communicating with the Provisioning Server.
- Problem: INVALID_MESSAGE The SOAP message received from the client could not be parsed.
 - Correct the message format.
- Problem: INVALID_REQUEST Cannot process any request before user is logged in. Either the Authentication Request or Login Request was invalid.
 - Correct the login sequence before sending other messages.
 - Verify that each session uses a unique session ID/jsession ID pair.
- Problem: javax.net.ssl.SSLHandshakeException
 - This is probably a problem with the certificate. For information on installing a certificate, see section 9.4 Secure SOAP and the Cisco BroadWorks SSL Support Options Guide.

For more information, see Appendix A: Frequently Asked Questions.

10 Backward Compatibility

The Open Client Interface-Provisioning (OCI-P) is backward compatible for up to two releases. This allows you to run the deprecated OCI-P commands from Release n on Releases n+1 and n+2. Release n+3 no longer supports deprecated commands from Release n. This also allows customers and partners to upgrade their systems without requiring a code change in almost all situations. However, there are important items to note:

- Elements that are required in a new version of software have values populated by the older transaction in the way that makes the most sense. This does not always mean that the application functions as desired by all customers and partners.
- Commands are backward compatible. However, they are not identical. Changes considered not to impact backward compatibility can be performed without deprecating the command. Some examples of this (although not exhaustive) are:
 - Adding an optional element to a request
 - Making an element "nillable" in a request
 - Making an element an array in a request, where minOccurs > 1
 - Adding a OCITable column
 - Changing a required element to be optional in a request
- Error message changes are not considered to impact backward compatibility. Software should be designed to accept the error message and perform the appropriate action. New errors can be added, existing errors may have the text modified, and existing errors may be deleted.

There are also a few exceptions in which the schema would not be made backward compatible. They are:

- When a new release adds a new value to an enumerated type, the new value may appear unexpectedly in a non-deprecated response. The validation should be relaxed to allow additional values.
- When there is a more restrictive validation, the schema is not necessarily made backward compatible. In the rare case that data such as string size or integer range need to be restricted more than in previous releases, the interface is not backward compatible.

10.1 Deprecated Commands

After an upgrade to a backward-compatible release, systems that use OCI-P are required to update their commands to use the most recent version. To perform this work, a list of deprecated transactions needs to be reviewed. Each release of the OCI-P schema contains a deprecated file list. These are the commands that have been updated but are still supported in the release to which the schema corresponds. Therefore, to determine the list of commands that have been deprecated, these files should be obtained for each release since the system was developed.



For example, Company ABC developed a system using OCI-P in Release 13.0 and is upgrading to Release 15.0. Once the upgrade is complete, they want to update the system so that they can upgrade to Release 17.0 next year. The developer retrieves the schema for Release 15.0 and looks at the deprecated commands files (one for Release 13.0 and one for Release 14.0). The developer then compares this list to the list of commands they are using. If a command being used is on the list, the developer upgrades the command to the most recent one.

10.2 OCI Command Naming

When a new version of an OCI-P command deprecates the current version, the naming convention for the new command is such that it is appended with the release number from which the new command was introduced. For example, if the existing command is UserDeleteRequest and this command is deprecated in Release 18, the new version of the command will be named UserDeleteRequest18. In service patches, the naming convention is similar except the appended number will have sp1. In the previous example, the new command name will be UserDeleteRequest18sp1. If the same command needs to be deprecated by multiple service patches, the next versions of the command will contain V2, V3, and so on.

Release Type	New Command Name
Major Release (for example, 18)	UserDeleteRequest18
Service Patch (first deprecation)	UserDeleteRequest18sp1
Subsequent Service Patches	UserDeleteRequest18sp1V2

Note that in some circumstances when the development of the feature was not planned to be in a feature patch but ultimately ends up being patched, the OCI-P command will be named as was implemented in the major release.

10.3 OCI Commands Removed in Release 23.0

There are no OCI-P commands removed in Release 23.0.

Developers should update their applications to stop using deprecated commands and they should use the newer replacement commands instead. The deprecated commands are captured in the following OCI-P schema file:

OCISchemaDeprecated.xsd

10.4 OCI Commands Removed in Release 22.0

There are no OCI-P commands removed in Release 22.0.

Developers should update their applications to stop using deprecated commands and they should use the newer replacement commands instead. The deprecated commands are captured in the following OCI-P schema file:

OCISchemaDeprecated.xsd

NOTE: All previous release-specific files were merged into one file and each release has a commented section in the file.

10.5 OCI Commands Removed in Release 21.0

There are no OCI-P commands removed in Release 21.0.



Developers should update their applications to stop using deprecated commands and they should use the newer replacement commands instead. The deprecated commands are captured in the following OCI-P schema files:

- OCISchemaDeprecated14.xsd
- OCISchemaDeprecated15.xsd
- OCISchemaDeprecated16.xsd
- OCISchemaDeprecated17.xsd
- OCISchemaDeprecated18.xsd
- OCISchemaDeprecated19.xsd
- OCISchemaDeprecated20.xsd

10.6 OCI Commands Removed in Release 20.0

There are no OCI-P commands removed in Release 20.0.

Developers should update their applications to stop using deprecated commands and they should use the newer replacement commands instead. The deprecated commands are captured in the following OCI-P schema files:

- OCISchemaDeprecated14.xsd
- OCISchemaDeprecated15.xsd
- OCISchemaDeprecated16.xsd
- OCISchemaDeprecated17.xsd
- OCISchemaDeprecated18.xsd
- OCISchemaDeprecated19.xsd

10.7 OCI Commands Removed in Release 19.0

There are no OCI-P commands removed in Release 19.0.

Developers should update their applications to stop using deprecated commands and they should use the newer replacement commands instead. The deprecated commands are captured in the following OCI-P schema files:

- OCISchemaDeprecated14.xsd
- OCISchemaDeprecated15.xsd
- OCISchemaDeprecated16.xsd
- OCISchemaDeprecated17.xsd
- OCISchemaDeprecated18.xsd

10.8 OCI Commands Removed in Release 18.0

There are no OCI-P commands removed in Release 18.0.

Developers should update their applications to stop using deprecated commands and they should use the newer replacement commands instead. The deprecated commands are captured in the following OCI-P schema files:

- OCISchemaDeprecated14.xsd
- OCISchemaDeprecated15.xsd



- OCISchemaDeprecated16.xsd
- OCISchemaDeprecated17.xsd

10.9 OCI Commands Removed in Release 17.0

There are no OCI-P commands removed in Release 17.0.

10.10 OCI Commands Removed in Release 16.0

The following is a list of the deprecated OCI commands that were removed in Release 16.0:

- GroupAccessDeviceAddRequest
- GroupAccessDeviceGetAvailableDetailListRequest
- GroupAccessDeviceGetEnhancedConfigurationTypeRequest
- GroupAccessDeviceGetRequest
- GroupAccessDeviceGetRequest13mp2
- GroupAccessDeviceModifyRequest
- ServiceProviderAddRequest
- GroupAssignUserServiceListRequest
- GroupAutoAttendantAddInstanceRequest
- GroupAutoAttendantGetInstanceRequest
- GroupUnassignUserServiceListRequest
- GroupCallCenterAddInstanceRequest
- GroupCallCenterAddInstanceRequest13mp13
- GroupCallCenterGetInstanceRequest
- GroupCallCenterGetInstanceRequest13mp13
- GroupCallProcessingGetPolicyRequest
- GroupCallProcessingModifyPolicyRequest
- GroupDigitCollectionGetRequest
- GroupHuntGroupAddInstanceRequest
- GroupHuntGroupAddInstanceRequest13mp13
- GroupHuntGroupGetInstanceRequest
- GroupHuntGroupGetInstanceRequest13mp13
- GroupInstantConferencingAddInstanceRequest
- GroupInstantConferencingGetInstanceRequest
- GroupInstantGroupCallAddInstanceRequest
- GroupInstantGroupCallGetInstanceRequest
- GroupMusicOnHoldAddInstanceRequest
- GroupMusicOnHoldGetInstanceRequest
- GroupMusicOnHoldModifyInstanceRequest



- GroupServiceScriptsClearLogRequest
- GroupServiceScriptsGetLogRequest
- GroupServiceScriptsGetRequest
- GroupServiceScriptsModifyRequest
- GroupTrunkGroupAddInstanceRequest
- GroupTrunkGroupGetInstanceListRequest
- GroupTrunkGroupGetInstanceRequest
- GroupTrunkGroupModifyInstanceRequest
- GroupVoiceMessagingGroupGetVoicePortalRequest
- ServiceProviderAccessDeviceAddRequest
- LoginRequest
- ServiceProviderAccessDeviceGetRequest
- ServiceProviderAccessDeviceGetRequest13mp2
- SystemIntelligentNetworkServiceControlGetRequest
- ServiceProviderAccessDeviceModifyRequest
- ServiceProviderAdminAddRequest
- ServiceProviderAdminGetPolicyRequest
- ServiceProviderPasswordRulesGetRequest
- ServiceProviderAdminGetListRequest
- ServiceProviderAdminGetRequest
- ServiceProviderAdminModifyPolicyRequest
- ServiceProviderCallProcessingGetPolicyRequest
- ServiceProviderCallProcessingGetPolicyRequest13mp10
- ServiceProviderCallProcessingModifyPolicyRequest
- ServiceProviderDigitCollectionGetRequest
- ServiceProviderGetRequest
- ServiceProviderThreeWayCallGetRequest
- ServiceProviderThreeWayCallModifyRequest
- SystemAccessDeviceGetIPPhoneTypeDetailListRequest
- SystemAccessDeviceGetListRequest
- SystemAccessDeviceTypeGetInfoListRequest
- SystemAccessDeviceTypeGetInfoRequest
- SystemCallProcessingGetPolicyRequest
- SystemCallProcessingGetPolicyRequest13mp10
- SystemCallProcessingModifyPolicyRequest
- SystemCallingNameRetrievalGetRequest

cisco.

- SystemCAPAddACLEntryRequest
- SystemCAPGetACLListRequest
- SystemCAPModifyACLEntryRequest
- SystemDigitCollectionGetRequest
- SystemDomainModifyDefaultRequest
- SystemExternalEmergencyRoutingParametersGetRequest
- SystemExternalEmergencyRoutingParametersModifyRequest
- SystemInstantConferencingAddDeviceRequest
- SystemInstantConferencingGetDeviceListRequest
- SystemInstantConferencingGetDeviceRequest
- SystemInstantConferencingModifyDeviceRequest
- SystemLongCallAccountingGetRequest
- SystemLongCallAccountingModifyRequest
- SystemMediaServerAddRequest
- SystemNetworkServerAddRequest
- SystemNetworkServerDeleteRequest
- SystemNetworkServerGetListRequest
- SystemNetworkServerModifyRequest
- SystemOverloadControlsGetRequest
- SystemOverloadControlsModifyRequest
- SystemOCIReportingAddACLEntryRequest
- SystemPasswordRulesGetRequest
- SystemPolicyGetDefaultRequest
- SystemPolicyModifyDefaultRequest
- SystemRoutingAddRouteDeviceRequest
- SystemSIPAddACLEntryRequest
- SystemThreeWayCallGetRequest
- SystemThreeWayCallModifyRequest
- SystemVoiceMessagingGroupGetPasscodeRulesRequest
- SystemVoiceMessagingGroupGetRequest
- SystemVoiceMessagingGroupGetVoicePortalMenusRequest
- UserAddRequest
- UserCallForwardingNoAnswerGetRequest
- UserGetRequest
- UserCallProcessingGetPolicyRequest
- UserCallProcessingModifyPolicyRequest



- UserCommPilotExpressSRGetRequest
- UserHotelingGuestGetRequest
- UserHotelingHostGetRequest
- UserInstantConferencingGetStandAloneConferenceDocumentListRequest
- UserInstantConferencingModifyConferenceRequest
- UserModifyRequest
- UserSequentialRingGetRequest
- UserServiceScriptsClearLogRequest
- UserServiceScriptsGetRequest
- UserServiceScriptsModifyRequest
- UserServiceScriptsGetLogRequest
- UserSharedCallAppearanceAddEndpointRequest
- UserSharedCallAppearanceDeleteEndpointListRequest
- UserSharedCallAppearanceGetRequest
- UserThirdPartyVoiceMailSupportGetRequest
- UserThirdPartyVoiceMailSupportGetRequest13mp8
- UserTwoStageDialingGetRequest
- UserVoiceMessagingUserGetGreetingRequest
- UserVideoAddOnGetRequest
- UserVideoAddOnModifyRequest
- UserVoiceMessagingUserGetVoiceManagementRequest

10.11 OCI Reporting Implications

OCI Reporting reports on the OCI transaction that is called. When functionality is included in maintenance patches that have an OCI transaction impact, the associated web and CLI commands call the new OCI transactions. This causes Reporting to start reporting on the new commands. In the future, there will be a method to prevent new functionality from showing in these interfaces.



11 Log-in Process

All connections require an authenticated session to execute commands. This is performed by logging into the system with a valid login ID. The login ID can be for any administrator or user. The login process requires a valid login ID and the password in plain text. The following messages are used for the login process:

- Login Request Sent to the server to log in a user. This message contains a login ID and the plain text password. The message digest of the user's plain password is calculated using the Secure Hash Algorithm (SHA-256) along with "Salt", a cryptographically strong random number.
- Login Response Sent in response to the previous message. This message confirms that the user was logged in or gives an error message when the login was not successful (for example, the password was incorrect). If the login was unsuccessful, the process must be repeated.

12 Appendix A: Frequently Asked Questions

This section provides answers to frequently asked questions (FAQs).

12.1 What do acronyms mean?

The following list describes acronyms used in this document.

Acronym	Description
Open Client Interface (OCI)	This is the term used to refer to the open interfaces (provisioning and execution) of an Application Server. In certain cases, OCI can also refer to all interfaces, OCI-P, OCI-C, CAP, or OSS interface.
Open Client Server (OCS)	This is a process that resides on a Web Server Farm (WSF) or Element Management System (EMS), which proxies OCI messages from clients to their appropriate Application Server.
Operation Support System (OSS)	This is the obsolete provisioning interface of an Application Server, which was part of the OCI.
Client Application Protocol (CAP)	This is the execution interface of an Application Server. It is the call processing portion of the OCI and is also referred to as OCI-C.
Open Client Interface- Provisioning (OCI- P)	This is the new provisioning interface for an Application Server. It is the provisioning part of the OCI. It is sometimes referred to simply as the OCI.
BroadWorks Common Communication Transport (BCCT)	This is the TCP/IP framework for Cisco BroadWorks, which all servers use to manage TCP/IP communication.
Apache Extensible Interaction System (Axis)	A framework for constructing SOAP processors, running on a Web Server.
Simple Object Access Protocol (SOAP)	A method for a program running with one type of operating system to communicate with a program running in the same or another type of operating system by using the Web's Hypertext Transfer Protocol (HTTP) and its Extensible Markup Language (XML) as the mechanism for information exchange.
Web Services Description Language (WSDL)	An XML format for describing network services as a set of endpoints operating on messages containing either document-oriented or procedure-oriented information.

12.2 What are the recommendations?

It is recommended to do the following:

- Use the OCS as the interface to Cisco BroadWorks. Do not go directly to the Application Server. You should use the OCS on the Web Server Farm or EMS. The OCS on the Application Server should only be used in a lab environment. It is not supported for a performance or production environment.
- Configure the OCS before using it. For information on how to do this, see section 12.3 How is the OCS Configured?
- Connect to the OCS via a TCP/IP connection.
- Use the client provided to test the setup of your server. For client use, see section 12.3 How is the OCS Configured?



Do not log in via the OCS as a system administrator since this is not supported.

12.3 How is the OCS Configured?

The OCS must be configured to support OCI-P. The following steps describe how to configure the server for this use.

12.3.1 OCS Configuration Steps

1) Verify the nsSeedClusterAddress parameter is set.

```
XSP_CLI /System/CommunicationUtility/DefaultSettings> get
   NS:
   nsSeedClusterAddress=ns.com
   asOCIPort=2220
   asOCISecurePort=2320
   asOCICPort=2221
   asOCICSecurePort=2321
   provisionOnSecondary=false
   reconnectionTimerSecs=30
   responseTimeoutSecs=10
   globalTransactionLimit=25000
   userTransactionLimit=10000
   transactionLimitPeriodSecs=1
   useSecureBCCT=false
```

The Network Server (NS) seed cluster address is used to communicate with the Network Server to get the list of Application Servers being served.

2) Configure the system domain in the OCS General Settings.

```
XSP_CLI/Applications/OpenClientServer/GeneralSettings> get
  clientPort = 2208
  clientPortEnabled = true
  secureClientPort = 2209
  secureClientPortEnabled = true
  systemDomain = as.eng.broadsoft.com
```

The *systemDomain* is used to complete incomplete user IDs before performing user location or authentication for a given request. This needs to be configured.

3) Turn the OCI proxy on. The configuration should look similar to the following.

```
XSP_CLI/Applications/OpenClientServer/OCIProxy> get
enabled = true
enableLoginLevelScreening = false
enableResponseCaching = false
responseCacheDurationHours = 24
responseCacheRenewPeriodMins = 30
messageQueueCapacity = 50
messageQueueTimeoutSeconds = 1800
```

The applicable attribute and its meaning is as follows:

■ enabled – Enables the OSS/OCI-P proxy capability. This must be turned on.

12.3.2 Application Server Configuration Steps

1) BCCT, which is used by the OCS, is already configured by default. These settings can be viewed in the following levels.

```
AS_CLI/Interface/CommonCommunicationTransport> get
   XSUnlimitedConnections = true
   PSUnlimitedConnections = true
   XSListeningPort = 2221
   PSListeningPort = 2220

AS_CLI/Interface/CommonCommunicationTransport/OCI/Provisioning> get
   unlimitedConnections = true
   restrictInterfaces = false
```

2) Usually, the only item required for configuration on the Application Server is to allow the OCS in the access control list. To add to the access control list, you use the add command as follows.

12.4 Is there an OCI-P Demo Client?

Cisco provides a demonstration (demo) client that can be used to test messages and connectivity. The executable and source code are available in the *Rel 21.0 asociclient.zip* file, available from Cisco at xchange.broadsoft.com.

A *Read Me* file that describes how to use the client is provided. The following list provides some additional recommendations:

- Set the *connectionMode* to "OCS" since BCCT is not used.
- Do not change the loginMode. (Note the unsecure mode is not a third-party mode.)
- Make sure there is a line feed at the end of each XML command.

12.5 Is there an OCI-P SOAP Demo Client?

Cisco provides a demo client that can be used to test messages and connectivity. The SOAP client is called *Rel_16.0_asocisoapclient.zip* and it is available from Cisco at xchange.broadsoft.com.

A *Read Me* file that describes how to use the client is provided.

12.6 What is the session ID and who creates it?

The client creates the session ID. It must be unique to each session and each message in the session must carry the same session ID.

12.7 What is the JSESSION ID and who creates it?

The JSESSIONID is a cookie used to identify the session when using OCI over SOAP. The Cisco BroadWorks Web Server creates the JSESSIONID cookie. It must be unique to each session, and each message (after the first message) in the session must carry the same JSESSIONID cookie.



12.8 Can I send more than one OCI message in a single SOAP message?

Yes.

12.9 What character encodings can I use for special characters?

The following XML predefined entities can be included in an OCI transaction by encoding them as shown in the following list:

- 1) < the less-than sign, opening angle bracket <
- 2) > the greater-than sign, closing angle bracket >
- 3) & ampersand & amp;
- 4) 'apostrophe, straight single quote & apos;
- 5) " straight double quotation marks "

12.10 I do not see any SOAP headers used by the test client. Are they used?

The Cisco OCI-P SOAP interface does not use any SOAP headers.

12.11 How can I use TCPMON to see messages sent and received?

The "tcpmon" utility can be found in the org.apache.axis.utils package. To run it from the command line, enter:

% java org.apache.axis.utils.tcpmon [listenPort targetHost targetPort]

To use the program, you select a local port that topmon monitors for incoming connections, a target host where it forwards such connections, and the port number on the target machine to which it should be "tunneled". Without any arguments, you get a GUI and can enter these values. For more information, see the *Axis User's Guide*.



13 Appendix B: Authorization Levels

The following is a list of OCI transactions that shows the authorization level required to execute each transaction.

Townsellon	Andhardan Laral
Transaction	Authorization Level
AuthenticationRequest	NOT_AUTHORIZED
AuthenticationVerificationRequest22	NOT_AUTHORIZED
AuthenticationVerifyRequest	NOT_AUTHORIZED
AuthenticationVerifyRequest14sp8	NOT_AUTHORIZED
AuthenticationVerifyRequest21sp1	NOT_AUTHORIZED
AuthenticationVerifyRequest22	NOT_AUTHORIZED
AuthenticationVerifyRequest22V2	NOT_AUTHORIZED
AvailabilityTestRequest	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest17	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest18	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest20sp1	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest21	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest21sp1	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest22	NOT_AUTHORIZED
DeviceManagementFileAuthLocationGetRequest22V2	NOT_AUTHORIZED
DeviceManagementPutFileRequest	NOT_AUTHORIZED
EnterpriseBroadWorksMobileManagerActivationRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerAddHomeZoneRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerAddRequest	SYSTEM_LEVEL
Enterprise Broad Works Mobile Manager Delete Home Zone List Request	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerDeleteHomeZoneRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerDeleteRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerGetDomainListRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerGetHomeZoneListRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerGetHomeZoneRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerGetRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerModifyHomeZoneRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerModifyRequest	SYSTEM_LEVEL
EnterpriseBroadWorksMobileManagerSendCarrierFilesRequest	SYSTEM_LEVEL
lem:lem:lem:lem:lem:lem:lem:lem:lem:lem:	SERVICE_PROVIDER_LEVEL



EnterpriseBroadWorksMobilityMobileSubscriberDirectoryNumberGetAvailableListR equest EnterpriseBroadWorksMobilityMobileSubscriberDirectoryNumberGetAvailablePage GROUP_LEVEL SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV EnterpriseCallCenterAgentThresholdProfileAddAgentListRequest EnterpriseCallCenterAgentThresholdProfileDeteAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest Enterp	Transaction	Authorization Level
EnterpriseCallCenterAgentThresholdProfileGetAgeuest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileAddAgentListRequest EnterpriseCallCenterAgentThresholdProfileAddAgentListRequest EnterpriseCallCenterAgentThresholdProfileAddAgentListRequest EnterpriseCallCenterAgentThresholdProfileAddRequest EnterpriseCallCenterAgentThresholdProfileDeleteAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentDagedSortedListReq Uest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentDagedSortedListReq Uest EnterpriseCallCenterAgentThresholdProfileGetDagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallCenterCallCenterCallCenterCallCenterCallCenterCallCenterCallCenterCallCenterCallCente	$\label{lem:entropy} Enterprise Broad Works Mobility Mobile Subscriber Directory Number Get Assignment Paged Sorted List Request$	GROUP_LEVEL
EnterpriseCallCenterAgentThresholdPefaultProfileGetRequest EnterpriseCallCenterAgentThresholdProfileAddAgentListRequest EnterpriseCallCenterAgentThresholdProfileAddRequest EnterpriseCallCenterAgentThresholdProfileAddRequest EnterpriseCallCenterAgentThresholdProfileAddRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAn	$\label{lem:eq:linear_problem} Enterprise Broad Works Mobility Mobile Subscriber Directory Number Get Available List Request$	GROUP_LEVEL
EnterpriseCallCenterAgentThresholdProfileAddAgentListRequest EnterpriseCallCenterAgentThresholdProfileAddRequest EnterpriseCallCenterAgentThresholdProfileDeleteAgentListRequest EnterpriseCallCenterAgentThresholdProfileDeleteAgentListRequest EnterpriseCallCenterAgentThresholdProfileDeleteRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListRequest EnterpriseCallCenterAgentThresholdProfileGetBetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingSGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingSGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingSGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingSGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingSGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest Ent	$\label{lem:enterprise} Enterprise Broad Works Mobility Mobile Subscriber Directory Number Get Available Paged Sorted List Request$	GROUP_LEVEL
EnterpriseCallCenterAgentThresholdProfileAddRequest EnterpriseCallCenterAgentThresholdProfileDeleteAgentListRequest EnterpriseCallCenterAgentThresholdProfileDeleteRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest Service_Provider_Lev EnterpriseCallCenterCurrentAndPastAgentGetListRequest Service_Provider_Lev EnterpriseCallCenterCurrentAndPastAgentGetListRequest Service_Provider_Lev EnterpriseCallCenterCurrentAndPastAgentGetListRequest Service_Provider_Lev EnterpriseCallCenterCurrentAndPastAgentGetLi	EnterpriseCallCenterAgentThresholdDefaultProfileGetRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentThresholdProfileDeleteAgentListRequest EnterpriseCallCenterAgentThresholdProfileDeleteRequest EnterpriseCallCenterAgentThresholdProfileDeleteRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentThresholdProfileAddAgentListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentThresholdProfileDeleteRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeDeleteRequest EnterpriseCallCenterAgentUnavailableCodeDeleteRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNI	EnterpriseCallCenterAgentThresholdProfileAddRequest	SERVICE_PROVIDER_LEVEL
Enterprise Call Center Agent Threshold Profile Get Available Agent List Request Enterprise Call Center Agent Threshold Profile Get Available Agent Paged Sorted List Request Enterprise Call Center Agent Threshold Profile Get List Request Enterprise Call Center Agent Threshold Profile Get List Request Enterprise Call Center Agent Threshold Profile Get Paged Sorted Request Enterprise Call Center Agent Threshold Profile Get Paged Sorted Request Enterprise Call Center Agent Threshold Profile Get Paged Sorted Request Enterprise Call Center Agent Threshold Profile Modify Request Enterprise Call Center Agent Unavailable Code Add Request Enterprise Call Center Agent Unavailable Code Get List Request Enterprise Call Center Agent Unavailable Code Get Request Enterprise Call Center Agent Unavailable Code Get Request Enterprise Call Center Agent Unavailable Code Get Request Enterprise Call Center Agent Unavailable Code Settings Get Request Enterprise Call Center Agent Unavailable Code Settings Get Request Enterprise Call Center Agent Unavailable Code Settings Get Request Enterprise Call Center Agent Unavailable Code Settings Modify Request Enterprise Call Center Agent Unavailable Code Settings Modify Request Enterprise Call Center Call Disposition Code Add Request Enterprise Call Center Call Disposition Code Delete Request Enterprise Call Center Call Disposition Code Get List Request Enterprise Call Center Call Disposition Code Get Usage List Request Enterprise Call Center Call Disposition Code Get Usage List Request Enterprise Call Center Call Disposition Code Modify Active List Request Enterprise Call Center Call Disposition Code Modify Re	EnterpriseCallCenterAgentThresholdProfileDeleteAgentListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentPagedSortedListReq uest EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileModifyRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastOallCenterGetListRequest EnterpriseCallCenterCurrentAndPastOallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndP	EnterpriseCallCenterAgentThresholdProfileDeleteRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentThresholdProfileGetListRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileModifyRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeDeleteRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetListRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCallDispositionCodeModifyRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCallDispositionCodeModifyRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentThresholdProfileGetAvailableAgentListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileModifyRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest	$\label{lem:entropy} Enterprise Call Center Agent Threshold Profile Get Available Agent Paged Sorted List Request$	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentThresholdProfileGetRequest EnterpriseCallCenterAgentThresholdProfileModifyRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeDeleteRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentThresholdProfileGetListRequest	GROUP_LEVEL
EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeDeleteRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastAgentGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentThresholdProfileGetPagedSortedRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeAddRequest EnterpriseCallCenterAgentUnavailableCodeDeleteRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest17sp4 USER_LEVEL EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentThresholdProfileGetRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeDeleteRequest EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest17sp4 EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentThresholdProfileModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeGetListRequest EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest	EnterpriseCallCenterAgentUnavailableCodeAddRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeGetRequest EnterpriseCallCenterAgentUnavailableCodeModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterCurrentAndPastCallCenterCurrentAndPastCallCenterCurrentAndPastCallCenterCurrentAndPa	EnterpriseCallCenterAgentUnavailableCodeDeleteRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeModifyRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest17sp4 EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest17sp4 EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentUnavailableCodeGetListRequest	USER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest17sp4 EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest	EnterpriseCallCenterAgentUnavailableCodeGetRequest	USER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest17sp4 EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest USER_LEVEL EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest	EnterpriseCallCenterAgentUnavailableCodeModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest	USER_LEVEL
EnterpriseCallCenterCallDispositionCodeAddRequest EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentUnavailableCodeSettingsGetRequest17sp4	USER_LEVEL
EnterpriseCallCenterCallDispositionCodeDeleteRequest EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV	EnterpriseCallCenterAgentUnavailableCodeSettingsModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterCallDispositionCodeGetListRequest EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV	EnterpriseCallCenterCallDispositionCodeAddRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterCallDispositionCodeGetRequest EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV	EnterpriseCallCenterCallDispositionCodeDeleteRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterCallDispositionCodeGetUsageListRequest EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV	EnterpriseCallCenterCallDispositionCodeGetListRequest	USER_LEVEL
EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV	EnterpriseCallCenterCallDispositionCodeGetRequest	USER_LEVEL
EnterpriseCallCenterCallDispositionCodeModifyRequest EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV	EnterpriseCallCenterCallDispositionCodeGetUsageListRequest	USER_LEVEL
EnterpriseCallCenterCurrentAndPastAgentGetListRequest EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV SERVICE_PROVIDER_LEV	EnterpriseCallCenterCallDispositionCodeModifyActiveListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest SERVICE_PROVIDER_LEV EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterCallDispositionCodeModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterCurrentAndPastDNISGetListRequest SERVICE_PROVIDER_LEV	EnterpriseCallCenterCurrentAndPastAgentGetListRequest	SERVICE_PROVIDER_LEVEL
	EnterpriseCallCenterCurrentAndPastCallCenterGetListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingBrandingGetRequest GROUP LEVEL	EnterpriseCallCenterCurrentAndPastDNISGetListRequest	SERVICE_PROVIDER_LEVEL
	EnterpriseCallCenterEnhancedReportingBrandingGetRequest	GROUP_LEVEL



Transaction	Authorization Level
EnterpriseCallCenterEnhancedReportingBrandingModifyRequest	GROUP_LEVEL
Enterprise Call Center Enhanced Reporting Get Available Report Template List Request	USER_LEVEL
EnterpriseCallCenterEnhancedReportingGetRequest	USER_LEVEL
EnterpriseCallCenterEnhancedReportingGetRequest19	USER_LEVEL
EnterpriseCallCenterEnhancedReportingModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingModifyRequest19	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingReportTemplateAddRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingReportTemplateDeleteRequest	SERVICE_PROVIDER_LEVEL
Enterprise Call Center Enhanced Reporting Report Template Get List Request	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingReportTemplateGetRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingReportTemplateModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingScheduledReportAddRequest	USER_LEVEL
EnterpriseCallCenterEnhancedReportingScheduledReportDeleteRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingScheduledReportGetActiveListRequest	SERVICE_PROVIDER_LEVEL
$\label{lem:enterprise} Enterprise Call Center Enhanced Reporting Scheduled Report Get Completed List Request$	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingScheduledReportGetListRequest	USER_LEVEL
$\label{lem:enterprise} Enterprise Call Center Enhanced Reporting Scheduled Report Get Report Template Usage \\ eList Request$	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterEnhancedReportingScheduledReportGetRequest	SERVICE_PROVIDER_LEVEL
Enterprise Call Center Enhanced Reporting Scheduled Report Modify Request	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterGetRequest	USER_LEVEL
EnterpriseCallCenterGetRequest17sp4	USER_LEVEL
EnterpriseCallCenterGetRoutingPolicyRequest	USER_LEVEL
EnterpriseCallCenterModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCallCenterModifyRoutingPolicyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommonPhoneListAddListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommonPhoneListDeleteListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommonPhoneListGetListRequest	USER_LEVEL
EnterpriseCommonPhoneListModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommunicationBarringAuthorizationCodeAddListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommunicationBarringAuthorizationCodeDeleteListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommunicationBarringAuthorizationCodeGetListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommunicationBarringAuthorizationCodeGetRequest	SERVICE_PROVIDER_LEVEL
EnterpriseCommunicationBarringAuthorizationCodeModifyRequest	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
EnterpriseDepartmentDeleteRequest	SERVICE_PROVIDER_LEVEL
EnterpriseDepartmentGetAvailableParentListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseDepartmentGetListRequest	USER_LEVEL
EnterpriseDepartmentModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkAddRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkAddRequest21	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkAddUserListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkDeleteRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkDeleteUserListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkForceAssignUserListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkGetAvailableTrunkGroupListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkGetAvailableUserListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkGetListRequest	GROUP_LEVEL
EnterpriseEnterpriseTrunkGetRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkGetRequest21	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkGetUserListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseEnterpriseTrunkModifyRequest	SERVICE_PROVIDER_LEVEL
EnterprisePhoneDirectoryGetListRequest	USER_LEVEL
EnterprisePhoneDirectoryGetListRequest17	USER_LEVEL
EnterprisePhoneDirectoryGetListRequest17sp3	USER_LEVEL
EnterprisePhoneDirectoryGetListRequest18	USER_LEVEL
EnterprisePhoneDirectoryGetPagedListRequest	USER_LEVEL
EnterprisePhoneDirectoryGetPagedSortedListRequest	USER_LEVEL
EnterprisePreAlertingAnnouncementGetRequest	SERVICE_PROVIDER_LEVEL
EnterprisePreAlertingAnnouncementModifyRequest	SERVICE_PROVIDER_LEVEL
Enterprise Route List Enterprise Trunk Number Prefix Get Available List Request	GROUP_LEVEL
Enterprise Route List Enterprise Trunk Number Prefix Get Summary List Request	SERVICE_PROVIDER_LEVEL
EnterpriseRouteListEnterpriseTrunkNumberRangeGetAvailableListRequest	GROUP_LEVEL
Enterprise Route List Enterprise Trunk Number Range Get Summary List Request	SERVICE_PROVIDER_LEVEL
EnterpriseSecurityClassificationCustomizationGetAvailableListRequest	GROUP_LEVEL
EnterpriseSessionAdmissionControlGetAvailableDeviceListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupAddDeviceListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupAddRequest	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupAddRequest19sp1	SERVICE_PROVIDER_LEVEL
Enterprise Session Admission Control Group Delete Device List Request	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
EnterpriseSessionAdmissionControlGroupDeleteListRequest	SERVICE_PROVIDER_LEVEL
Enterprise Session Admission Control Group Get List Request	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupGetRequest	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupGetRequest19sp1	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupGetRequest21sp1	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupGetRequest21sp1V2	SERVICE_PROVIDER_LEVEL
EnterpriseSessionAdmissionControlGroupModifyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseUserCallForwardingSettingsGetListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseUserCallingPlanSettingsGetListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseUserCallWaitingSettingsGetListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseUserHotelingGuestSettingsGetListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVirtualOnNetEnterpriseExtensionsGetUserListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNAddPolicyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNDeletePolicyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNGetDefaultRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNGetPolicyListRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNGetPolicyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNGetRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNGetRequest14sp3	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNModifyPolicyRequest	SERVICE_PROVIDER_LEVEL
EnterpriseVoiceVPNModifyRequest	SERVICE_PROVIDER_LEVEL
ExternalAuthenticationAuthorizeTokenRequest	NOT_AUTHORIZED
ExternalAuthenticationAuthorizeTokenRequest22	NOT_AUTHORIZED
ExternalAuthenticationCreateLoginTokenRequest	USER_LEVEL
GroupAccessDeviceAddRequest14	GROUP_LEVEL
GroupAccessDeviceAvailablePortGetListRequest	GROUP_LEVEL
GroupAccessDeviceCustomTagAddRequest	GROUP_LEVEL
GroupAccessDeviceCustomTagDeleteListRequest	GROUP_LEVEL
GroupAccessDeviceCustomTagGetListRequest	GROUP_LEVEL
GroupAccessDeviceCustomTagModifyRequest	GROUP_LEVEL
GroupAccessDeviceDeleteRequest	GROUP_LEVEL
GroupAccessDeviceFileGetListRequest	GROUP_LEVEL
GroupAccessDeviceFileGetListRequest14sp8	GROUP_LEVEL
GroupAccessDeviceFileGetRequest	GROUP_LEVEL
GroupAccessDeviceFileGetRequest14sp8	GROUP_LEVEL



Transaction	Authorization Level
GroupAccessDeviceFileGetRequest16sp1	GROUP_LEVEL
GroupAccessDeviceFileGetRequest20	GROUP_LEVEL
GroupAccessDeviceFileModifyRequest	GROUP_LEVEL
GroupAccessDeviceFileModifyRequest14sp8	GROUP_LEVEL
GroupAccessDeviceGetAvailableDetailListRequest14	GROUP_LEVEL
GroupAccessDeviceGetAvailableDetailListRequest19	GROUP_LEVEL
GroupAccessDeviceGetEnhancedConfigurationTypeListRequest	GROUP_LEVEL
GroupAccessDeviceGetEnhancedConfigurationTypeRequest14	GROUP_LEVEL
GroupAccessDeviceGetListRequest	GROUP_LEVEL
GroupAccessDeviceGetPagedSortedListRequest	GROUP_LEVEL
GroupAccessDeviceGetRequest14	GROUP_LEVEL
GroupAccessDeviceGetRequest14sp3	GROUP_LEVEL
GroupAccessDeviceGetRequest14sp6	GROUP_LEVEL
GroupAccessDeviceGetRequest16	GROUP_LEVEL
GroupAccessDeviceGetRequest18sp1	GROUP_LEVEL
GroupAccessDeviceGetUserListRequest	GROUP_LEVEL
GroupAccessDeviceGetUserListRequest21sp1	GROUP_LEVEL
GroupAccessDeviceModifyRequest14	GROUP_LEVEL
GroupAccessDeviceModifyUserRequest	GROUP_LEVEL
GroupAccessDeviceResetRequest	GROUP_LEVEL
GroupAccessDeviceTagSetGetRequest	GROUP_LEVEL
GroupAccessDeviceTagSetModifyRequest	GROUP_LEVEL
GroupAccountAuthorizationCodesAddListRequest	GROUP_LEVEL
GroupAccountAuthorizationCodesDeleteListRequest	GROUP_LEVEL
Group Account Authorization Codes Get Available User List Request	GROUP_LEVEL
GroupAccountAuthorizationCodesGetListRequest	USER_LEVEL
GroupAccountAuthorizationCodesGetRequest	GROUP_LEVEL
GroupAccountAuthorizationCodesModifyRequest	GROUP_LEVEL
GroupAddRequest	SERVICE_PROVIDER_LEVEL
GroupAdminAddRequest	GROUP_LEVEL
GroupAdminDeleteRequest	GROUP_LEVEL
GroupAdminGetListRequest	GROUP_LEVEL
GroupAdminGetPagedSortedListRequest	GROUP_LEVEL
GroupAdminGetPolicyRequest	GROUP_LEVEL
GroupAdminGetPolicyRequest14sp1	GROUP_LEVEL



Transaction	Authorization Level
GroupAdminGetPolicyRequest16sp1	GROUP_LEVEL
GroupAdminGetPolicyRequest16sp2	GROUP_LEVEL
GroupAdminGetPolicyRequest17	GROUP_LEVEL
GroupAdminGetPolicyRequest17sp3	GROUP_LEVEL
GroupAdminGetPolicyRequest18	GROUP_LEVEL
GroupAdminGetPolicyRequest19sp1	GROUP_LEVEL
GroupAdminGetPolicyRequest20	GROUP_LEVEL
GroupAdminGetRequest	GROUP_LEVEL
GroupAdminGetRequest21sp1	GROUP_LEVEL
GroupAdminModifyPolicyRequest	GROUP_LEVEL
GroupAdminModifyRequest	GROUP_LEVEL
GroupAdviceOfChargeGetRequest	GROUP_LEVEL
GroupAdviceOfChargeModifyRequest	GROUP_LEVEL
GroupAnnouncementFileAddRequest	GROUP_LEVEL
GroupAnnouncementFileDeleteListRequest	GROUP_LEVEL
GroupAnnouncementFileGetListRequest	GROUP_LEVEL
GroupAnnouncementFileGetPagedSortedListRequest	GROUP_LEVEL
GroupAnnouncementFileGetRequest	GROUP_LEVEL
GroupAnnouncementFileModifyRequest	GROUP_LEVEL
GroupAnnouncementRepositoryGetSettingsRequest	GROUP_LEVEL
GroupApplicationServerSetGetRequest	SYSTEM_LEVEL
GroupApplicationServerSetModifyRequest	SYSTEM_LEVEL
GroupAutoAttendantAddInstanceRequest14	GROUP_LEVEL
GroupAutoAttendantAddInstanceRequest16	GROUP_LEVEL
GroupAutoAttendantAddInstanceRequest17sp1	GROUP_LEVEL
GroupAutoAttendantAddInstanceRequest19	GROUP_LEVEL
GroupAutoAttendantAddInstanceRequest20	GROUP_LEVEL
GroupAutoAttendantConsolidatedAddInstanceRequest	GROUP_LEVEL
GroupAutoAttendantConsolidatedDeleteInstanceRequest	GROUP_LEVEL
Group Auto Attendant Consolidated Modify Instance Request	GROUP_LEVEL
GroupAutoAttendantDeleteInstanceRequest	GROUP_LEVEL
GroupAutoAttendantGetInstanceListRequest	GROUP_LEVEL
GroupAutoAttendantGetInstancePagedSortedListRequest	GROUP_LEVEL
GroupAutoAttendantGetInstanceRequest14	GROUP_LEVEL
GroupAutoAttendantGetInstanceRequest16	GROUP_LEVEL



GroupAutoAttendantGetInstanceRequest175p1 GROUP_LEVEL GroupAutoAttendantGetInstanceRequest175p1 GROUP_LEVEL GroupAutoAttendantGetInstanceRequest19 GROUP_LEVEL GroupAutoAttendantGetInstanceRequest20 GROUP_LEVEL GroupAutoAttendantGetInstanceRequest20 GROUP_LEVEL GroupAutoAttendantModifyActiveInstanceListRequest GroupAutoAttendantModifyInstanceRequest18cquest GroupAutoAttendantModifyInstanceRequest16 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest16 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest17cp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest17cp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetIstRequest GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest50 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyIndextenstanceListRequest4 GROUP_LEVEL GroupBroadWorksAnywhereModifyIndextenstanceListRequest4 GROUP_LEVEL GroupBroadWorksAnywhereModifyIndextenstanceListRequest4 GROUP_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest5 SYSTEM_L	Transaction	Authorization Level
GroupAutoAttendantGetInstanceRequest199 GROUP_LEVEL GroupAutoAttendantGetInstanceRequest19sp1 GROUP_LEVEL GroupAutoAttendantGetInstanceRequest20 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceExecutionServerRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest16 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuOeleteListRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBro	GroupAutoAttendantGetInstanceRequest17	GROUP_LEVEL
GroupAutoAttendantGetInstanceRequest19sp1 GROUP_LEVEL GroupAutoAttendantGetInstanceRequest20 GROUP_LEVEL GroupAutoAttendantModifyActiveInstanceListRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest16 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest30 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest30 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest4 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest50 GROUP_LEVEL GroupAroadWorksAnywhereAddInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest4 SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest4 SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest5 SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest5 SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest5 SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest5	GroupAutoAttendantGetInstanceRequest17sp1	GROUP_LEVEL
GroupAutoAttendantGetInstanceRequest20 GROUP_LEVEL GroupAutoAttendantModifyActiveInstanceListRequest GroupAutoAttendantModifyInstanceExecutionServerRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest16 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuDeleteListRequest GROUP_LEVEL GroupAutoAttendantSubmenuGetListRequest GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerPeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerPeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupAutoAttendantGetInstanceRequest19	GROUP_LEVEL
GroupAutoAttendantModifyActiveInstanceExecutionServerRequest GroupAutoAttendantModifyInstanceExecutionServerRequest GroupAutoAttendantModifyInstanceRequest GroupAutoAttendantModifyInstanceRequest16 GroupAutoAttendantModifyInstanceRequest17sp1 GroupAutoAttendantModifyInstanceRequest20 GroupAutoAttendantModifyInstanceRequest20 GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuGett.istRequest GroupAutoAttendantSubmenuGett.istRequest GroupAutoAttendantSubmenuGettelgeuest20 GroupAutoAttendantSubmenuGettelgeuest20 GroupAutoAttendantSubmenuGettelgeuest20 GroupAutoAttendantSubmenuGettelgeuest20 GroupAutoAttendantSubmenuGettelgeuest20 GroupAutoAttendantSubmenuGettelgeuest20 GroupAutoAttendantSubmenuGettelgeuest20 GroupAutoAttendantSubmenuModifyRequest20 GroupAutoAttendantSubmenuModifyRequest20 GroupAutoAttendantSubmenuModifyRequest20 GroupLeveL GroupBroadWorksAnywhereAddInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereGetInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereGetInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereGetInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereGetInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereGetInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereModifyInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereModifyInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereModifyInstanceRequest3 Group_LeveL GroupBroadWorksAnywhereModifyInstanceRequest3 GroupBroadWorksAnywhereModifyInstanceRequest3 GroupBroadWorksMobileManagerAddHomeZoneRequest3 GroupBroadWorksMobileManagerDeleteHomeZoneRequest3 GroupBroadWorksMobileManagerDeleteHomeZoneRequest3 GroupBroadWorksMobileManagerDeleteHomeZoneRequest3 GroupBroadWorksMobileManagerDeleteRequest3 GroupBroadWorksMobileManagerDeleteRequest3 GroupBroadWorksMobileManagerDeleteRequest3 GroupBroadWorksMobileManagerDeleteRequest3 GroupBroadWorksMob	GroupAutoAttendantGetInstanceRequest19sp1	GROUP_LEVEL
GroupAutoAttendantModifyInstanceExecutionServerRequest GroupAutoAttendantModifyInstanceRequest GroupAutoAttendantModifyInstanceRequest16 GroupAutoAttendantModifyInstanceRequest17sp1 GroupAutoAttendantModifyInstanceRequest17sp1 GroupAutoAttendantModifyInstanceRequest20 GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuGett.istRequest GroupAutoAttendantSubmenuGett.istRequest GroupAutoAttendantSubmenuGettelistRequest GroupAutoAttendantSubmenuGettRequest20 GroupAutoAttendantSubmenuGettRequest20 GroupAutoAttendantSubmenuGettRequest20 GroupAutoAttendantSubmenuGettRequest20 GroupAutoAttendantSubmenuGettRequest20 GroupAutoAttendantSubmenuGettRequest20 GroupAutoAttendantSubmenuGettRequest3 GroupLevEL GroupArdoAttendantSubmenuGettRequest4 GroupLevEL GroupArdoAttendantSubmenuGettRequest4 GroupLevEL GroupArdoAttendantSubmenuModifyRequest20 GroupLevEL GroupBroadWorksAnywhereAddInstanceRequest GroupLevEL GroupBroadWorksAnywhereGetInstanceListRequest GroupLevEL GroupBroadWorksAnywhereGetInstanceRequest GroupLevEL GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19p1 GroupBroadWorksAnywhereGetInstanceRequest19p1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupLevEL GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerAddHomeZoneRequest SySTEM_LevEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LevEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LevEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LevEL	GroupAutoAttendantGetInstanceRequest20	GROUP_LEVEL
GroupAutoAttendantModifyinstanceRequest GROUP_LEVEL GroupAutoAttendantModifyinstanceRequest16 GroupAutoAttendantModifyinstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyinstanceRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuDeleteListRequest GROUP_LEVEL GroupAutoAttendantSubmenuDeleteListRequest GROUP_LEVEL GroupAutoAttendantSubmenuGett.sitRequest GROUP_LEVEL GroupAutoAttendantSubmenuGettRequest GROUP_LEVEL GroupAutoAttendantSubmenuGettRequest GROUP_LEVEL GroupAutoAttendantSubmenuGettSequest GROUP_LEVEL GroupAutoAttendantSubmenuGettSequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL	GroupAutoAttendantModifyActiveInstanceListRequest	GROUP_LEVEL
GroupAutoAttendantModifyInstanceRequest16 GroupAutoAttendantModifyInstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest4 GroupAutoAttendantSubmenuGetVasgeListRequest4 GroupAutoAttendantSubmenuModifyRequest4 GroupAutoAttendantSubmenuModifyRequest4 GroupAutoAttendantSubmenuModifyRequest4 GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest4 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceRequest4 GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest4 SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL	GroupAutoAttendantModifyInstanceExecutionServerRequest	GROUP_LEVEL
GroupAutoAttendantModifyInstanceRequest17sp1 GROUP_LEVEL GroupAutoAttendantModifyInstanceRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereDeleteInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL	GroupAutoAttendantModifyInstanceRequest	GROUP_LEVEL
GroupAutoAttendantModifyInstanceRequest20 GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GroupAutoAttendantSubmenuModifyRequest20 GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerAddRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LEVEL	GroupAutoAttendantModifyInstanceRequest16	GROUP_LEVEL
GroupAutoAttendantSubmenuAddRequest GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerAddRequest SySTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest	GroupAutoAttendantModifyInstanceRequest17sp1	GROUP_LEVEL
GroupAutoAttendantSubmenuAddRequest20 GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GroupAutoAttendantSubmenuModifyRequest20 GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereGetleInstanceRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerAddHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LEVEL	GroupAutoAttendantModifyInstanceRequest20	GROUP_LEVEL
GroupAutoAttendantSubmenuDeleteListRequest GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SySTEM_LEVEL GroupBroadWorksMobileManagerAddRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL	GroupAutoAttendantSubmenuAddRequest	GROUP_LEVEL
GroupAutoAttendantSubmenuGetListRequest GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetRequest20 GROUP_LEVEL GroupAutoAttendantSubmenuGetUsageListRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest GROUP_LEVEL GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereDeleteInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupAutoAttendantSubmenuAddRequest20	GROUP_LEVEL
GroupAutoAttendantSubmenuGetRequest GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SySTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LEVEL	GroupAutoAttendantSubmenuDeleteListRequest	GROUP_LEVEL
GroupAutoAttendantSubmenuGetRequest20 GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereDeleteInstanceListRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SySTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LEVEL	GroupAutoAttendantSubmenuGetListRequest	GROUP_LEVEL
GroupAutoAttendantSubmenuGetUsageListRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SySTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LEVEL	GroupAutoAttendantSubmenuGetRequest	GROUP_LEVEL
GroupAutoAttendantSubmenuModifyRequest GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereDeleteInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL	GroupAutoAttendantSubmenuGetRequest20	GROUP_LEVEL
GroupAutoAttendantSubmenuModifyRequest20 GROUP_LEVEL GroupBroadWorksAnywhereAddInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereDeleteInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL	GroupAutoAttendantSubmenuGetUsageListRequest	GROUP_LEVEL
GroupBroadWorksAnywhereAddInstanceRequest GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SySTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LEVEL	GroupAutoAttendantSubmenuModifyRequest	GROUP_LEVEL
GroupBroadWorksAnywhereDeleteInstanceRequest GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupAutoAttendantSubmenuModifyRequest20	GROUP_LEVEL
GroupBroadWorksAnywhereGetInstanceListRequest GroupBroadWorksAnywhereGetInstanceRequest GroupBroadWorksAnywhereGetInstanceRequest17 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereGetInstanceRequest19sp1 GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SySTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SySTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SySTEM_LEVEL	GroupBroadWorksAnywhereAddInstanceRequest	GROUP_LEVEL
GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupBroadWorksAnywhereDeleteInstanceRequest	GROUP_LEVEL
GroupBroadWorksAnywhereGetInstanceRequest17 GROUP_LEVEL GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GROUP_LEVEL GroupBroadWorksAnywhereModifyInstanceRequest GROUP_LEVEL GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	Group Broad Works Anywhere GetInstance List Request	GROUP_LEVEL
GroupBroadWorksAnywhereGetInstanceRequest19sp1 GROUP_LEVEL GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupBroadWorksAnywhereGetInstanceRequest	GROUP_LEVEL
GroupBroadWorksAnywhereModifyActiveInstanceListRequest GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest GroupBroadWorksMobileManagerAddHomeZoneRequest GroupBroadWorksMobileManagerAddRequest GroupBroadWorksMobileManagerAddRequest GroupBroadWorksMobileManagerDeleteHomeZoneListRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest GroupBroadWorksMobileManagerDeleteRequest GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest	GroupBroadWorksAnywhereGetInstanceRequest17	GROUP_LEVEL
GroupBroadWorksAnywhereModifyInstanceRequest GroupBroadWorksMobileManagerActivationRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerAddRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneListRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL SYSTEM_LEVEL SYSTEM_LEVEL SYSTEM_LEVEL	GroupBroadWorksAnywhereGetInstanceRequest19sp1	GROUP_LEVEL
GroupBroadWorksMobileManagerActivationRequest GroupBroadWorksMobileManagerAddHomeZoneRequest GroupBroadWorksMobileManagerAddRequest GroupBroadWorksMobileManagerDeleteHomeZoneListRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	Group Broad Works Anywhere Modify Active Instance List Request	GROUP_LEVEL
GroupBroadWorksMobileManagerAddHomeZoneRequest GroupBroadWorksMobileManagerAddRequest GroupBroadWorksMobileManagerDeleteHomeZoneListRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupBroadWorksAnywhereModifyInstanceRequest	GROUP_LEVEL
GroupBroadWorksMobileManagerAddRequest GroupBroadWorksMobileManagerDeleteHomeZoneListRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL SYSTEM_LEVEL SYSTEM_LEVEL	GroupBroadWorksMobileManagerActivationRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerDeleteHomeZoneListRequest GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL SYSTEM_LEVEL SYSTEM_LEVEL SYSTEM_LEVEL	GroupBroadWorksMobileManagerAddHomeZoneRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerDeleteHomeZoneRequest SYSTEM_LEVEL GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupBroadWorksMobileManagerAddRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerDeleteRequest SYSTEM_LEVEL	GroupBroadWorksMobileManagerDeleteHomeZoneListRequest	SYSTEM_LEVEL
·	GroupBroadWorksMobileManagerDeleteHomeZoneRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerGetDomainListRequest SYSTEM_LEVEL	GroupBroadWorksMobileManagerDeleteRequest	SYSTEM_LEVEL
	GroupBroadWorksMobileManagerGetDomainListRequest	SYSTEM_LEVEL



Transaction	Authorization Level
GroupBroadWorksMobileManagerGetHomeZoneListRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerGetHomeZoneRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerGetRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerModifyHomeZoneRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerModifyRequest	SYSTEM_LEVEL
GroupBroadWorksMobileManagerSendCarrierFilesRequest	SYSTEM_LEVEL
GroupBroadWorksMobilityGetRequest	SYSTEM_LEVEL
GroupBroadWorksMobilityGetRequest19sp1	GROUP_LEVEL
GroupBroadWorksMobilityGetRequest21sp1	GROUP_LEVEL
GroupBroadWorksMobilityGetRequest21sp1V2	GROUP_LEVEL
GroupBroadWorksMobilityGetRequest22	GROUP_LEVEL
GroupBroadWorksMobilityGetRequest22V2	GROUP_LEVEL
GroupBroadWorksMobilityGetRequest22V3	GROUP_LEVEL
Group Broad Works Mobility Mobile Subscriber Directory Number Assign List Request	SERVICE_PROVIDER_LEVEL
lem:comp:comp:comp:comp:comp:comp:comp:com	GROUP_LEVEL
$\label{lem:control} Group Broad Works Mobility Mobile Subscriber Directory Number Get Available List Request$	GROUP_LEVEL
Group Broad Works Mobility Mobile Subscriber Directory Number Unassign List Request	SERVICE_PROVIDER_LEVEL
GroupBroadWorksMobilityModifyRequest	RESELLER_LEVEL
GroupCallCapacityManagementAddInstanceRequest	GROUP_LEVEL
GroupCallCapacityManagementAddUserListRequest	GROUP_LEVEL
GroupCallCapacityManagementDeleteInstanceListRequest	GROUP_LEVEL
GroupCallCapacityManagementDeleteUserListRequest	GROUP_LEVEL
GroupCallCapacityManagementGetAvailableUserListRequest	GROUP_LEVEL
GroupCallCapacityManagementGetInstanceListRequest	GROUP_LEVEL
GroupCallCapacityManagementGetInstanceRequest	GROUP_LEVEL
GroupCallCapacityManagementModifyInstanceRequest	GROUP_LEVEL
GroupCallCenterAddAgentListRequest	USER_LEVEL
GroupCallCenterAddDNISRequest	USER_LEVEL
GroupCallCenterAddInstanceRequest14	GROUP_LEVEL
GroupCallCenterAddInstanceRequest14sp3	GROUP_LEVEL
GroupCallCenterAddInstanceRequest14sp9	GROUP_LEVEL
GroupCallCenterAddInstanceRequest16	GROUP_LEVEL
GroupCallCenterAddInstanceRequest17	GROUP_LEVEL
GroupCallCenterAddInstanceRequest17sp1	GROUP_LEVEL



Transaction	Authorization Level
GroupCallCenterAddInstanceRequest17sp3	GROUP_LEVEL
GroupCallCenterAddInstanceRequest19	GROUP_LEVEL
GroupCallCenterAddInstanceRequest22	GROUP_LEVEL
GroupCallCenterAddSupervisorListRequest	USER_LEVEL
GroupCallCenterAgentThresholdDefaultProfileGetRequest	GROUP_LEVEL
GroupCallCenterAgentThresholdProfileAddAgentListRequest	GROUP_LEVEL
GroupCallCenterAgentThresholdProfileAddRequest	GROUP_LEVEL
Group Call Center Agent Threshold Profile Delete Agent List Request	GROUP_LEVEL
GroupCallCenterAgentThresholdProfileDeleteRequest	GROUP_LEVEL
$\label{lem:convergence} Group Call Center Agent Threshold Profile Get Available Agent List Request$	GROUP_LEVEL
$\label{thm:convergence} Group Call Center Agent Threshold Profile Get Available Agent Paged Sorted List Request$	GROUP_LEVEL
GroupCallCenterAgentThresholdProfileGetListRequest	GROUP_LEVEL
GroupCallCenterAgentThresholdProfileGetPagedSortedRequest	GROUP_LEVEL
GroupCallCenterAgentThresholdProfileGetRequest	GROUP_LEVEL
GroupCallCenterAgentThresholdProfileModifyRequest	GROUP_LEVEL
GroupCallCenterAgentUnavailableCodeAddRequest	GROUP_LEVEL
GroupCallCenterAgentUnavailableCodeDeleteRequest	GROUP_LEVEL
GroupCallCenterAgentUnavailableCodeGetListRequest	USER_LEVEL
GroupCallCenterAgentUnavailableCodeGetRequest	USER_LEVEL
GroupCallCenterAgentUnavailableCodeModifyRequest	GROUP_LEVEL
GroupCallCenterAgentUnavailableCodeSettingsGetRequest	USER_LEVEL
GroupCallCenterAgentUnavailableCodeSettingsGetRequest17sp4	USER_LEVEL
GroupCallCenterAgentUnavailableCodeSettingsModifyRequest	GROUP_LEVEL
GroupCallCenterBouncedCallGetRequest	USER_LEVEL
GroupCallCenterBouncedCallGetRequest17	USER_LEVEL
GroupCallCenterBouncedCallModifyRequest	USER_LEVEL
GroupCallCenterCallDispositionCodeAddRequest	GROUP_LEVEL
GroupCallCenterCallDispositionCodeDeleteRequest	GROUP_LEVEL
GroupCallCenterCallDispositionCodeGetListRequest	USER_LEVEL
GroupCallCenterCallDispositionCodeGetRequest	USER_LEVEL
GroupCallCenterCallDispositionCodeGetUsageListRequest	USER_LEVEL
GroupCallCenterCallDispositionCodeModifyActiveListRequest	GROUP_LEVEL
GroupCallCenterCallDispositionCodeModifyRequest	GROUP_LEVEL
GroupCallCenterComfortMessageBypassGetRequest	USER_LEVEL
GroupCallCenterComfortMessageBypassGetRequest17	USER_LEVEL



Transaction	Authorization Level
GroupCallCenterComfortMessageBypassGetRequest20	USER_LEVEL
GroupCallCenterComfortMessageBypassModifyRequest	USER_LEVEL
GroupCallCenterComfortMessageBypassModifyRequest17	USER_LEVEL
GroupCallCenterComfortMessageBypassModifyRequest20	USER_LEVEL
GroupCallCenterCurrentAndPastAgentGetListRequest	GROUP_LEVEL
GroupCallCenterCurrentAndPastCallCenterGetListRequest	GROUP_LEVEL
GroupCallCenterCurrentAndPastDNISGetListRequest	GROUP_LEVEL
GroupCallCenterDeleteAgentListRequest	USER_LEVEL
GroupCallCenterDeleteDNISRequest	USER_LEVEL
GroupCallCenterDeleteInstanceRequest	GROUP_LEVEL
GroupCallCenterDeleteSupervisorListRequest	USER_LEVEL
GroupCallCenterDistinctiveRingingGetRequest	USER_LEVEL
GroupCallCenterDistinctiveRingingModifyRequest	USER_LEVEL
GroupCallCenterEnhancedGetRequest	USER_LEVEL
GroupCallCenterEnhancedModifyRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingBrandingGetRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingBrandingModifyRequest	GROUP_LEVEL
Group Call Center Enhanced Reporting Get Available Report Template List Request	USER_LEVEL
GroupCallCenterEnhancedReportingGetRequest	USER_LEVEL
GroupCallCenterEnhancedReportingGetRequest19	USER_LEVEL
GroupCallCenterEnhancedReportingModifyRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingModifyRequest19	GROUP_LEVEL
GroupCallCenterEnhancedReportingReportTemplateAddRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingReportTemplateDeleteRequest	GROUP_LEVEL
$\label{lem:convergence} Group Call Center Enhanced Reporting Report Template Get List Request$	GROUP_LEVEL
GroupCallCenterEnhancedReportingReportTemplateGetRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingReportTemplateModifyRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingScheduledReportAddRequest	USER_LEVEL
GroupCallCenterEnhancedReportingScheduledReportDeleteRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingScheduledReportGetActiveListRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingScheduledReportGetCompletedListRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingScheduledReportGetListRequest	USER_LEVEL
lem:groupCallCenterEnhancedReportingScheduledReportGetReportTemplateUsageListRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingScheduledReportGetRequest	GROUP_LEVEL
GroupCallCenterEnhancedReportingScheduledReportModifyRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupCallCenterForcedForwardingGetRequest	USER_LEVEL
GroupCallCenterForcedForwardingGetRequest17	USER_LEVEL
GroupCallCenterForcedForwardingGetRequest20	USER_LEVEL
GroupCallCenterForcedForwardingModifyRequest	USER_LEVEL
GroupCallCenterForcedForwardingModifyRequest17	USER_LEVEL
GroupCallCenterForcedForwardingModifyRequest20	USER_LEVEL
GroupCallCenterGetAgentListRequest	USER_LEVEL
GroupCallCenterGetAgentPagedSortedListRequest	USER_LEVEL
GroupCallCenterGetAnnouncementRequest	USER_LEVEL
GroupCallCenterGetAnnouncementRequest14sp6	USER_LEVEL
GroupCallCenterGetAnnouncementRequest16	USER_LEVEL
GroupCallCenterGetAnnouncementRequest17	USER_LEVEL
GroupCallCenterGetAnnouncementRequest17sp4	USER_LEVEL
GroupCallCenterGetAnnouncementRequest19	USER_LEVEL
GroupCallCenterGetAnnouncementRequest20	USER_LEVEL
GroupCallCenterGetAnnouncementRequest22	USER_LEVEL
GroupCallCenterGetAvailableAgentListRequest	USER_LEVEL
GroupCallCenterGetAvailableAgentPagedSortedListRequest	USER_LEVEL
GroupCallCenterGetAvailableSupervisorListRequest	USER_LEVEL
GroupCallCenterGetAvailableUserListRequest	USER_LEVEL
GroupCallCenterGetDistinctiveRingingRequest	USER_LEVEL
GroupCallCenterGetDNISAgentListRequest	USER_LEVEL
GroupCallCenterGetDNISAnnouncementRequest	USER_LEVEL
GroupCallCenterGetDNISAnnouncementRequest17sp4	USER_LEVEL
GroupCallCenterGetDNISAnnouncementRequest19	USER_LEVEL
GroupCallCenterGetDNISAnnouncementRequest20	USER_LEVEL
GroupCallCenterGetDNISAnnouncementRequest22	USER_LEVEL
GroupCallCenterGetDNISListRequest	USER_LEVEL
GroupCallCenterGetDNISRequest	USER_LEVEL
GroupCallCenterGetInstanceListRequest	USER_LEVEL
GroupCallCenterGetInstancePagedSortedListRequest	USER_LEVEL
GroupCallCenterGetInstanceQueueStatusRequest	USER_LEVEL
GroupCallCenterGetInstanceRequest14	USER_LEVEL
GroupCallCenterGetInstanceRequest14sp3	USER_LEVEL
GroupCallCenterGetInstanceRequest14sp9	USER_LEVEL



Transaction	Authorization Level
GroupCallCenterGetInstanceRequest16	USER_LEVEL
GroupCallCenterGetInstanceRequest17	USER_LEVEL
GroupCallCenterGetInstanceRequest17sp1	USER_LEVEL
GroupCallCenterGetInstanceRequest17sp3	USER_LEVEL
GroupCallCenterGetInstanceRequest19	USER_LEVEL
GroupCallCenterGetInstanceRequest19sp1	USER_LEVEL
GroupCallCenterGetInstanceRequest22	USER_LEVEL
GroupCallCenterGetInstanceStatisticsReportingRequest	USER_LEVEL
GroupCallCenterGetInstanceStatisticsReportingRequest16	USER_LEVEL
GroupCallCenterGetInstanceStatisticsReportingRequest17sp1	USER_LEVEL
GroupCallCenterGetInstanceStatisticsRequest13mp8	USER_LEVEL
GroupCallCenterGetInstanceStatisticsRequest14sp9	USER_LEVEL
GroupCallCenterGetRequest	USER_LEVEL
GroupCallCenterGetRequest17sp4	USER_LEVEL
GroupCallCenterGetRoutingPolicyRequest	USER_LEVEL
GroupCallCenterGetSupervisorListRequest	USER_LEVEL
GroupCallCenterGetSupervisorListRequest16	USER_LEVEL
GroupCallCenterGetUnlicensedAgentListRequest	USER_LEVEL
GroupCallCenterHolidayServiceGetRequest	USER_LEVEL
GroupCallCenterHolidayServiceGetRequest17	USER_LEVEL
GroupCallCenterHolidayServiceGetRequest17sp1	USER_LEVEL
GroupCallCenterHolidayServiceGetRequest20	USER_LEVEL
GroupCallCenterHolidayServiceModifyRequest	USER_LEVEL
GroupCallCenterHolidayServiceModifyRequest17	USER_LEVEL
GroupCallCenterHolidayServiceModifyRequest17sp1	USER_LEVEL
GroupCallCenterHolidayServiceModifyRequest20	USER_LEVEL
GroupCallCenterModifyActiveInstanceListRequest	USER_LEVEL
GroupCallCenterModifyAgentListRequest	USER_LEVEL
GroupCallCenterModifyAnnouncementRequest	USER_LEVEL
GroupCallCenterModifyAnnouncementRequest14sp6	USER_LEVEL
GroupCallCenterModifyAnnouncementRequest16	USER_LEVEL
GroupCallCenterModifyAnnouncementRequest17	USER_LEVEL
GroupCallCenterModifyAnnouncementRequest20	USER_LEVEL
GroupCallCenterModifyDistinctiveRingingRequest	USER_LEVEL
GroupCallCenterModifyDNISAnnouncementRequest	USER_LEVEL



GroupCallCenterModifyDNISAnnouncementRequest20 GroupCallCenterModifyDNISRequest GroupCallCenterModifyInstanceRequest GroupCallCenterModifyInstanceRequest GroupCallCenterModifyInstanceRequest16 GroupCallCenterModifyInstanceRequest16 GroupCallCenterModifyInstanceRequest17sp11 GroupCallCenterModifyInstanceRequest17sp1 GroupCallCenterModifyInstanceRequest199 GroupCallCenterModifyInstanceRequest199 GroupCallCenterModifyInstanceRequest22 GroupCallCenterModifyInstanceStatisticsReportingRequest GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterMightServiceGetRequest17 USER_LEVEL GroupCallCenterMightServiceGetRequest17 GroupCallCenterMightServiceGetRequest17 GroupCallCenterMightServiceGetRequest17 GroupCallCenterMightServiceGetRequest17 GroupCallCenterMightServiceGetRequest17 GroupCallCenterMightServiceModifyRequest17 GroupCallCenterMightServiceModifyRequest17 GroupCallCenterMightServiceModifyRequest17 GroupCallCenterMightServiceModifyRequest17 GroupCallCenterMightServiceModifyRequest17 GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowModifyRequest17 GroupCallCenterOverflowM	Transaction	Authorization Level
GroupCallCenterModifyDNISRequest GroupCallCenterModifyInstanceRequest16 GroupCallCenterModifyInstanceRequest16 GroupCallCenterModifyInstanceRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceRequest19 GroupCallCenterModifyInstanceRequest29 GroupCallCenterModifyInstanceStatisticsReportingRequest GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifySequest GroupCallCenterModifyRequest GroupCallCenterModifySequest GroupCallCenterModifySequest10 GroupCallCenterModifySequest10 GroupCallCenterModifySequest10 GroupCallCenterModifySupervisort.istRequest16 GroupCallCenterModifySupervisort.istRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflo	GroupCallCenterModifyDNISAnnouncementRequest20	USER_LEVEL
GroupCallCenterModifyInstanceRequest16 GroupCallCenterModifyInstanceRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceRequest19 GroupCallCenterModifyInstanceRequest22 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceWeightedCallDistributionRequest GroupCallCenterModifySequest GroupCallCenterModifySequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterModifySupervisorListRequest16 USER_LEVEL GroupCallCenterNightServiceGetRequest USER_LEVEL GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModify	GroupCallCenterModifyDNISParametersRequest	USER_LEVEL
GroupCallCenterModifyInstanceRequest16 GroupCallCenterModifyInstanceRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceRequest19 GroupCallCenterModifyInstanceRequest22 USER_LEVEL GroupCallCenterModifyInstanceRequest22 GroupCallCenterModifyInstanceStatisticsReportingRequest USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyRoutingPolicyRequest GROUP_LEVEL GroupCallCenterModifyRoutingPolicyRequest GROUP_LEVEL GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest16 USER_LEVEL GroupCallCenterModifySupervisorListRequest16 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL US	GroupCallCenterModifyDNISRequest	USER_LEVEL
GroupCallCenterModifyInstanceRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceRequest29 USER_LEVEL GroupCallCenterModifyInstanceRequest22 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest16 USER_LEVEL GroupCallCenterModifySupervisorListRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverdiowModifyRequest20 USER_LEVEL	GroupCallCenterModifyInstanceRequest	USER_LEVEL
GroupCallCenterModifyInstanceRequest19 GroupCallCenterModifyInstanceRequest22 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceWeightedCallDistributionRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterMightServiceGetRequest USER_LEVEL GroupCallCenterMightServiceGetRequest17 USER_LEVEL GroupCallCenterMightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterMightServiceGetRequest20 USER_LEVEL GroupCallCenterMightServiceModifyRequest USER_LEVEL GroupCallCenterMightServiceModifyRequest17 USER_LEVEL GroupCallCenterMightServiceModifyRequest17 USER_LEVEL GroupCallCenterMightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL	GroupCallCenterModifyInstanceRequest16	USER_LEVEL
GroupCallCenterModifyInstanceRequest22 GroupCallCenterModifyInstanceStatisticsReportingRequest GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceWeightedCallDistributionRequest GroupCallCenterModifyInstanceWeightedCallDistributionRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterNightServiceGetRequest GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNowflowGetRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverdecallDispositionCodeGetRequest USER_LEVEL GroupCallCenterOverGetCallDispositionCodeGetRequest USER_LEVEL	GroupCallCenterModifyInstanceRequest17sp1	USER_LEVEL
GroupCallCenterModifyInstanceStatisticsReportingRequest GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceWeightedCallDistributionRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterNightServiceGetRequest USER_LEVEL USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverdowGetRequest10 USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL	GroupCallCenterModifyInstanceRequest19	USER_LEVEL
GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9 USER_LEVEL GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 USER_LEVEL GroupCallCenterModifyInstanceWeightedCallDistributionRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifyRequest GROUP_LEVEL GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterModifySupervisorListRequest USER_LEVEL GroupCallCenterNightServiceGetRequest USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL	GroupCallCenterModifyInstanceRequest22	USER_LEVEL
GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1 GroupCallCenterModifyInstanceWeightedCallDistributionRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest16 GroupCallCenterModifySupervisorListRequest17 GroupCallCenterNightServiceGetRequest GroupCallCenterNightServiceGetRequest17 GroupCallCenterNightServiceGetRequest17 GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL	GroupCallCenterModifyInstanceStatisticsReportingRequest	USER_LEVEL
GroupCallCenterModifyInstanceWeightedCallDistributionRequest GroupCallCenterModifyRequest GroupCallCenterModifyRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest16 GroupCallCenterModifySupervisorListRequest16 GroupCallCenterNightServiceGetRequest GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL	GroupCallCenterModifyInstanceStatisticsReportingRequest14sp9	USER_LEVEL
GroupCallCenterModifyRequest GroupCallCenterModifyRoutingPolicyRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest16 GroupCallCenterNightServiceGetRequest GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL	GroupCallCenterModifyInstanceStatisticsReportingRequest17sp1	USER_LEVEL
GroupCallCenterModifyRoutingPolicyRequest GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest16 GroupCallCenterModifySupervisorListRequest16 GroupCallCenterNightServiceGetRequest GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL	Group Call Center Modify Instance Weighted Call Distribution Request	GROUP_LEVEL
GroupCallCenterModifySupervisorListRequest GroupCallCenterModifySupervisorListRequest16 USER_LEVEL GroupCallCenterMightServiceGetRequest USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL	GroupCallCenterModifyRequest	GROUP_LEVEL
GroupCallCenterModifySupervisorListRequest16 GroupCallCenterNightServiceGetRequest GroupCallCenterNightServiceGetRequest17 GroupCallCenterNightServiceGetRequest17 GroupCallCenterNightServiceGetRequest17sp1 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL	GroupCallCenterModifyRoutingPolicyRequest	GROUP_LEVEL
GroupCallCenterNightServiceGetRequest17 GroupCallCenterNightServiceGetRequest17 GroupCallCenterNightServiceGetRequest17sp1 GroupCallCenterNightServiceGetRequest20 GroupCallCenterNightServiceModifyRequest GroupCallCenterNightServiceModifyRequest GroupCallCenterNightServiceModifyRequest17 GroupCallCenterNightServiceModifyRequest17 GroupCallCenterNightServiceModifyRequest17sp1 GroupCallCenterNightServiceModifyRequest20 GroupCallCenterNightServiceModifyRequest20 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterQueueCallDispositionCodeAddRequest GroupCallCenterQueueCallDispositionCodeDeleteRequest GroupCallCenterQueueCallDispositionCodeGetListRequest GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL	GroupCallCenterModifySupervisorListRequest	USER_LEVEL
GroupCallCenterNightServiceGetRequest17 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceGetRequest20 USER_LEVEL GroupCallCenterNightServiceModifyRequest USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL	GroupCallCenterModifySupervisorListRequest16	USER_LEVEL
GroupCallCenterNightServiceGetRequest17sp1 GroupCallCenterNightServiceGetRequest20 GroupCallCenterNightServiceModifyRequest GroupCallCenterNightServiceModifyRequest17 GroupCallCenterNightServiceModifyRequest17 GroupCallCenterNightServiceModifyRequest17sp1 GroupCallCenterNightServiceModifyRequest20 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest17 GroupCallCenterOverflowModifyRequest17 GroupCallCenterOverflowModifyRequest20 GroupCallCenterOverflowModifyRequest20 GroupCallCenterQueueCallDispositionCodeAddRequest GroupCallCenterQueueCallDispositionCodeDeleteRequest GroupCallCenterQueueCallDispositionCodeGetListRequest GroupCallCenterQueueCallDispositionCodeGetRequest GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL	GroupCallCenterNightServiceGetRequest	USER_LEVEL
GroupCallCenterNightServiceGetRequest20 GroupCallCenterNightServiceModifyRequest GroupCallCenterNightServiceModifyRequest17 GroupCallCenterNightServiceModifyRequest17 GroupCallCenterNightServiceModifyRequest17sp1 GroupCallCenterNightServiceModifyRequest20 GroupCallCenterOverflowGetRequest GroupCallCenterOverflowGetRequest GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest17 GroupCallCenterOverflowModifyRequest17 GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL	GroupCallCenterNightServiceGetRequest17	USER_LEVEL
GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17 USER_LEVEL GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL USER_LEVEL	GroupCallCenterNightServiceGetRequest17sp1	USER_LEVEL
GroupCallCenterNightServiceModifyRequest17 GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL USER_LEVEL USER_LEVEL	GroupCallCenterNightServiceGetRequest20	USER_LEVEL
GroupCallCenterNightServiceModifyRequest17sp1 USER_LEVEL GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest USER_LEVEL GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL	GroupCallCenterNightServiceModifyRequest	USER_LEVEL
GroupCallCenterNightServiceModifyRequest20 USER_LEVEL GroupCallCenterOverflowGetRequest GroupCallCenterOverflowGetRequest17 USER_LEVEL GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL	GroupCallCenterNightServiceModifyRequest17	USER_LEVEL
GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowGetRequest17 GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL	GroupCallCenterNightServiceModifyRequest17sp1	USER_LEVEL
GroupCallCenterOverflowGetRequest20 USER_LEVEL GroupCallCenterOverflowModifyRequest USER_LEVEL	GroupCallCenterNightServiceModifyRequest20	USER_LEVEL
GroupCallCenterOverflowGetRequest20 GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL	GroupCallCenterOverflowGetRequest	USER_LEVEL
GroupCallCenterOverflowModifyRequest GroupCallCenterOverflowModifyRequest17 USER_LEVEL GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL	GroupCallCenterOverflowGetRequest17	USER_LEVEL
GroupCallCenterOverflowModifyRequest17 GroupCallCenterOverflowModifyRequest20 USER_LEVEL GroupCallCenterQueueCallDispositionCodeAddRequest USER_LEVEL GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL	GroupCallCenterOverflowGetRequest20	USER_LEVEL
GroupCallCenterOverflowModifyRequest20 GroupCallCenterQueueCallDispositionCodeAddRequest GroupCallCenterQueueCallDispositionCodeDeleteRequest GroupCallCenterQueueCallDispositionCodeGetListRequest GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL	GroupCallCenterOverflowModifyRequest	USER_LEVEL
GroupCallCenterQueueCallDispositionCodeAddRequest GroupCallCenterQueueCallDispositionCodeDeleteRequest USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL	GroupCallCenterOverflowModifyRequest17	USER_LEVEL
GroupCallCenterQueueCallDispositionCodeDeleteRequest GroupCallCenterQueueCallDispositionCodeGetListRequest USER_LEVEL USER_LEVEL USER_LEVEL USER_LEVEL	GroupCallCenterOverflowModifyRequest20	USER_LEVEL
GroupCallCenterQueueCallDispositionCodeGetListRequest GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL USER_LEVEL	GroupCallCenterQueueCallDispositionCodeAddRequest	USER_LEVEL
GroupCallCenterQueueCallDispositionCodeGetRequest USER_LEVEL	GroupCallCenterQueueCallDispositionCodeDeleteRequest	USER_LEVEL
· · · · · · · · · · · · · · · · · · ·	GroupCallCenterQueueCallDispositionCodeGetListRequest	USER_LEVEL
GroupCallCenterQueueCallDispositionCodeModifyRequest USER_LEVEL	GroupCallCenterQueueCallDispositionCodeGetRequest	USER_LEVEL
	GroupCallCenterQueueCallDispositionCodeModifyRequest	USER_LEVEL



Transaction	Authorization Level
GroupCallCenterQueueCallDispositionCodeSettingsGetRequest	USER_LEVEL
GroupCallCenterQueueCallDispositionCodeSettingsModifyRequest	USER_LEVEL
GroupCallCenterQueueStatusNotificationGetRequest	USER_LEVEL
GroupCallCenterQueueStatusNotificationModifyRequest	USER_LEVEL
GroupCallCenterQueueThresholdsGetRequest	USER_LEVEL
GroupCallCenterQueueThresholdsModifyRequest	USER_LEVEL
GroupCallCenterStrandedCallGetRequest	USER_LEVEL
GroupCallCenterStrandedCallGetRequest17	USER_LEVEL
GroupCallCenterStrandedCallGetRequest20	USER_LEVEL
GroupCallCenterStrandedCallModifyRequest	USER_LEVEL
GroupCallCenterStrandedCallModifyRequest17	USER_LEVEL
GroupCallCenterStrandedCallModifyRequest20	USER_LEVEL
GroupCallCenterStrandedCallUnavailableGetRequest	USER_LEVEL
GroupCallCenterStrandedCallUnavailableGetRequest20	USER_LEVEL
GroupCallCenterStrandedCallUnavailableModifyRequest	USER_LEVEL
GroupCallCenterStrandedCallUnavailableModifyRequest20	USER_LEVEL
GroupCallCenterSupervisorReportingGetRequest	USER_LEVEL
GroupCallCenterSupervisorReportingModifyRequest	USER_LEVEL
GroupCallingLineIdGetRequest	GROUP_LEVEL
GroupCallingLineIdModifyRequest	GROUP_LEVEL
GroupCallingPlanAddDigitPatternRequest	GROUP_LEVEL
GroupCallingPlanDeleteDigitPatternListRequest	GROUP_LEVEL
GroupCallingPlanGetDigitPatternListRequest	USER_LEVEL
GroupCallingPlanModifyDigitPatternRequest	GROUP_LEVEL
GroupCallParkAddInstanceRequest	GROUP_LEVEL
GroupCallParkAddInstanceRequest16sp2	GROUP_LEVEL
GroupCallParkDeleteInstanceRequest	GROUP_LEVEL
GroupCallParkGetAvailableAlternateRecallUserListRequest	GROUP_LEVEL
Group Call Park Get Available Alternate Recall User Paged Sorted List Request	GROUP_LEVEL
GroupCallParkGetAvailableUserListRequest	GROUP_LEVEL
GroupCallParkGetAvailableUserPagedSortedListRequest	GROUP_LEVEL
GroupCallParkGetInstanceListRequest	GROUP_LEVEL
GroupCallParkGetInstancePagedSortedListRequest	GROUP_LEVEL
GroupCallParkGetInstancePagedSortedRequest	GROUP_LEVEL
GroupCallParkGetInstanceRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupCallParkGetInstanceRequest16sp2	GROUP_LEVEL
GroupCallParkGetRequest	GROUP_LEVEL
GroupCallParkGetRequest16sp2	GROUP_LEVEL
GroupCallParkModifyInstanceRequest	GROUP_LEVEL
GroupCallParkModifyRequest	GROUP_LEVEL
GroupCallPickupAddInstanceRequest	GROUP_LEVEL
GroupCallPickupDeleteInstanceRequest	GROUP_LEVEL
GroupCallPickupGetAvailableUserListRequest	GROUP_LEVEL
GroupCallPickupGetAvailableUserPagedSortedListRequest	GROUP_LEVEL
GroupCallPickupGetInstanceListRequest	GROUP_LEVEL
GroupCallPickupGetInstancePagedSortedListRequest	GROUP_LEVEL
GroupCallPickupGetInstancePagedSortedRequest	GROUP_LEVEL
GroupCallPickupGetInstanceRequest	GROUP_LEVEL
GroupCallPickupModifyInstanceRequest	GROUP_LEVEL
GroupCallProcessingGetPolicyRequest14	USER_LEVEL
GroupCallProcessingGetPolicyRequest14sp1	USER_LEVEL
GroupCallProcessingGetPolicyRequest14sp4	USER_LEVEL
GroupCallProcessingGetPolicyRequest14sp7	USER_LEVEL
GroupCallProcessingGetPolicyRequest15	USER_LEVEL
GroupCallProcessingGetPolicyRequest15sp2	USER_LEVEL
GroupCallProcessingGetPolicyRequest16	USER_LEVEL
GroupCallProcessingGetPolicyRequest16sp2	USER_LEVEL
GroupCallProcessingGetPolicyRequest17	USER_LEVEL
GroupCallProcessingGetPolicyRequest17sp3	USER_LEVEL
GroupCallProcessingGetPolicyRequest17sp4	USER_LEVEL
GroupCallProcessingGetPolicyRequest18	USER_LEVEL
GroupCallProcessingGetPolicyRequest18sp1	USER_LEVEL
GroupCallProcessingGetPolicyRequest19sp1	USER_LEVEL
GroupCallProcessingGetPolicyRequest21sp1	USER_LEVEL
GroupCallProcessingGetPolicyRequest21sp2	USER_LEVEL
GroupCallProcessingGetPolicyRequest22	USER_LEVEL
GroupCallProcessingGetPolicyRequest22V2	USER_LEVEL
GroupCallProcessingModifyPolicyRequest14	GROUP_LEVEL
GroupCallProcessingModifyPolicyRequest14sp7	GROUP_LEVEL
GroupCallProcessingModifyPolicyRequest15	GROUP_LEVEL



Transaction	Authorization Level
GroupCallProcessingModifyPolicyRequest15sp2	GROUP_LEVEL
GroupCallRecordingGetRequest	GROUP_LEVEL
GroupCallRecordingModifyRequest	GROUP_LEVEL
GroupCollaborateBridgeAddInstanceRequest	GROUP_LEVEL
GroupCollaborateBridgeAddInstanceRequest20sp1	GROUP_LEVEL
GroupCollaborateBridgeConsolidatedAddInstanceRequest	GROUP_LEVEL
GroupCollaborateBridgeConsolidatedDeleteInstanceRequest	GROUP_LEVEL
GroupCollaborateBridgeConsolidatedModifyInstanceRequest	GROUP_LEVEL
GroupCollaborateBridgeDeleteInstanceRequest	GROUP_LEVEL
GroupCollaborateBridgeGetAvailableUserListRequest	GROUP_LEVEL
GroupCollaborateBridgeGetAvailableUserPagedSortedListRequest	GROUP_LEVEL
GroupCollaborateBridgeGetInstanceListRequest	GROUP_LEVEL
GroupCollaborateBridgeGetInstancePagedSortedListRequest	GROUP_LEVEL
GroupCollaborateBridgeGetInstanceRequest	GROUP_LEVEL
GroupCollaborateBridgeGetInstanceRequest20sp1	GROUP_LEVEL
GroupCollaborateBridgeModifyInstanceRequest	GROUP_LEVEL
GroupCollaborateBridgeModifyInstanceRequest20sp1	GROUP_LEVEL
GroupCommonPhoneListAddListRequest	GROUP_LEVEL
GroupCommonPhoneListDeleteListRequest	GROUP_LEVEL
GroupCommonPhoneListGetListRequest	USER_LEVEL
GroupCommonPhoneListModifyRequest	GROUP_LEVEL
GroupCommunicationBarringAuthorizationCodeAddListRequest	GROUP_LEVEL
GroupCommunicationBarringAuthorizationCodeAddListRequest21sp1	GROUP_LEVEL
GroupCommunicationBarringAuthorizationCodeDeleteListRequest	GROUP_LEVEL
GroupCommunicationBarringAuthorizationCodeGetListRequest	GROUP_LEVEL
GroupCommunicationBarringAuthorizationCodeGetListRequest21sp1	GROUP_LEVEL
GroupCommunicationBarringAuthorizationCodeGetRequest	GROUP_LEVEL
GroupCommunicationBarringAuthorizationCodeModifyRequest	GROUP_LEVEL
GroupCommunicationBarringGetRequest	SERVICE_PROVIDER_LEVEL
GroupCommunicationBarringModifyRequest	SERVICE_PROVIDER_LEVEL
GroupCommunicationBarringProfileGetAssignedListRequest	GROUP_LEVEL
GroupCommunicationBarringProfileModifyListRequest	SERVICE_PROVIDER_LEVEL
GroupCPEConfigRebuildConfigFileRequest	GROUP_LEVEL
GroupCPEConfigRebuildDeviceConfigFileRequest	GROUP_LEVEL
Croup of Leoning Robania Device Commignition Request	Ortool _LLTLL



Transaction	Authorization Level
GroupCPEConfigResetDeviceRequest	GROUP_LEVEL
GroupCPEConfigResetDeviceTypeRequest	GROUP_LEVEL
GroupCPEConfigSetConfigFileRequest	GROUP_LEVEL
GroupCustomContactDirectoryAddRequest	GROUP_LEVEL
GroupCustomContactDirectoryAddRequest17	GROUP_LEVEL
GroupCustomContactDirectoryDeleteRequest	GROUP_LEVEL
GroupCustomContactDirectoryGetAvailableUserListRequest	GROUP_LEVEL
GroupCustomContactDirectoryGetAvailableUserListRequest17	GROUP_LEVEL
GroupCustomContactDirectoryGetListRequest	USER_LEVEL
GroupCustomContactDirectoryGetRequest	USER_LEVEL
GroupCustomContactDirectoryGetRequest17	USER_LEVEL
GroupCustomContactDirectoryModifyRequest	GROUP_LEVEL
GroupCustomContactDirectoryModifyRequest17	GROUP_LEVEL
GroupCustomRingbackGroupGetRequest	GROUP_LEVEL
GroupCustomRingbackGroupGetRequest16	GROUP_LEVEL
GroupCustomRingbackGroupGetRequest20	GROUP_LEVEL
GroupCustomRingbackGroupModifyRequest	GROUP_LEVEL
GroupCustomRingbackGroupModifyRequest16	GROUP_LEVEL
GroupCustomRingbackGroupModifyRequest20	GROUP_LEVEL
GroupDeleteRequest	SERVICE_PROVIDER_LEVEL
GroupDepartmentAddRequest	GROUP_LEVEL
GroupDepartmentAdminAddRequest	GROUP_LEVEL
GroupDepartmentAdminDeleteRequest	GROUP_LEVEL
GroupDepartmentAdminGetListRequest	GROUP_LEVEL
GroupDepartmentAdminGetRequest	GROUP_LEVEL
GroupDepartmentAdminModifyRequest	GROUP_LEVEL
GroupDepartmentDeleteRequest	GROUP_LEVEL
GroupDepartmentGetAvailableParentListRequest	GROUP_LEVEL
GroupDepartmentGetListRequest	USER_LEVEL
GroupDepartmentGetListRequest18	USER_LEVEL
GroupDepartmentGetRequest	GROUP_LEVEL
GroupDepartmentModifyRequest	GROUP_LEVEL
GroupDeviceManagementEventGetListRequest	GROUP_LEVEL
GroupDeviceManagementEventGetListRequest22	GROUP_LEVEL
GroupDeviceManagementGetAccessDeviceCountForDeviceTypeGroupRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupDeviceManagementInProgressAndPendingEventCancelRequest	GROUP_LEVEL
GroupDeviceTypeCustomTagAddRequest	GROUP_LEVEL
GroupDeviceTypeCustomTagDeleteListRequest	GROUP_LEVEL
GroupDeviceTypeCustomTagGetListRequest	GROUP_LEVEL
GroupDeviceTypeCustomTagModifyRequest	GROUP_LEVEL
GroupDeviceTypeFileGetListRequest	GROUP_LEVEL
GroupDeviceTypeFileGetListRequest14sp8	GROUP_LEVEL
GroupDeviceTypeFileGetListRequest21	GROUP_LEVEL
GroupDeviceTypeFileGetRequest	GROUP_LEVEL
GroupDeviceTypeFileGetRequest14sp8	GROUP_LEVEL
GroupDeviceTypeFileGetRequest16sp1	GROUP_LEVEL
GroupDeviceTypeFileModifyRequest	GROUP_LEVEL
GroupDeviceTypeFileModifyRequest14sp8	GROUP_LEVEL
GroupDeviceTypeTagSetGetRequest	GROUP_LEVEL
GroupDeviceTypeTagSetModifyRequest	GROUP_LEVEL
GroupDialableCallerIDCriteriaAddRequest	GROUP_LEVEL
GroupDialableCallerIDCriteriaDeleteRequest	GROUP_LEVEL
GroupDialableCallerIDCriteriaGetRequest	GROUP_LEVEL
GroupDialableCallerIDCriteriaModifyRequest	GROUP_LEVEL
GroupDialableCallerIDGetRequest	GROUP_LEVEL
GroupDialableCallerIDModifyRequest	GROUP_LEVEL
GroupDialPlanPolicyAddAccessCodeRequest	GROUP_LEVEL
GroupDialPlanPolicyDeleteAccessCodeRequest	GROUP_LEVEL
GroupDialPlanPolicyGetAccessCodeListRequest	GROUP_LEVEL
GroupDialPlanPolicyGetAccessCodeRequest	GROUP_LEVEL
GroupDialPlanPolicyGetRequest	GROUP_LEVEL
GroupDialPlanPolicyGetRequest17	GROUP_LEVEL
GroupDialPlanPolicyModifyAccessCodeRequest	GROUP_LEVEL
GroupDialPlanPolicyModifyRequest	GROUP_LEVEL
GroupDigitCollectionGetRequest13mp4	GROUP_LEVEL
GroupDigitCollectionModifyRequest	GROUP_LEVEL
GroupDirectoryNumberHuntingGetAvailableUserListRequest	GROUP_LEVEL
GroupDirectoryNumberHuntingGetRequest	GROUP_LEVEL
GroupDirectoryNumberHuntingGetRequest17sp1	GROUP_LEVEL
GroupDirectoryNumberHuntingModifyRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupDnActivateListRequest	GROUP_LEVEL
GroupDnAssignListRequest	SERVICE_PROVIDER_LEVE
GroupDnDeactivateListRequest	GROUP_LEVEL
GroupDnGetActivationListRequest	GROUP_LEVEL
GroupDnGetAssignmentListRequest	GROUP_LEVEL
GroupDnGetAssignmentListRequest18	GROUP_LEVEL
GroupDnGetAssignmentPagedSortedListRequest	GROUP_LEVEL
GroupDnGetAvailableListRequest	GROUP_LEVEL
GroupDnGetAvailableRangesListRequest	GROUP_LEVEL
GroupDnGetDetailedAvailableListRequest	GROUP_LEVEL
GroupDnGetListRequest	GROUP_LEVEL
GroupDnGetSummaryListRequest	GROUP_LEVEL
GroupDnListAssignDepartmentRequest	GROUP_LEVEL
GroupDnUnassignListRequest	SERVICE_PROVIDER_LEVE
GroupDomainAssignListRequest	SERVICE_PROVIDER_LEVE
GroupDomainGetAssignedListRequest	GROUP_LEVEL
GroupDomainGetAssignedUserListRequest	GROUP_LEVEL
GroupDomainUnassignListRequest	SERVICE_PROVIDER_LEVE
GroupEmergencyCallNotificationGetRequest	GROUP_LEVEL
GroupEmergencyCallNotificationModifyRequest	GROUP_LEVEL
GroupEmergencyZonesAddHomeZoneListRequest	GROUP_LEVEL
GroupEmergencyZonesDeleteHomeZoneListRequest	GROUP_LEVEL
GroupEmergencyZonesGetHomeZoneListRequest	GROUP_LEVEL
GroupEmergencyZonesGetRequest	GROUP_LEVEL
GroupEmergencyZonesModifyHomeZoneListRequest	GROUP_LEVEL
GroupEmergencyZonesModifyRequest	GROUP_LEVEL
GroupEndpointGetListRequest	GROUP_LEVEL
GroupEnterpriseTrunkAddRequest	GROUP_LEVEL
GroupEnterpriseTrunkAddRequest21	GROUP_LEVEL
GroupEnterpriseTrunkAddUserListRequest	GROUP_LEVEL
GroupEnterpriseTrunkDeleteRequest	GROUP_LEVEL
GroupEnterpriseTrunkDeleteUserListRequest	GROUP_LEVEL
GroupEnterpriseTrunkForceAssignUserListRequest	GROUP_LEVEL
GroupEnterpriseTrunkGetAvailableTrunkGroupListRequest	GROUP_LEVEL
GroupEnterpriseTrunkGetAvailableUserListRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupEnterpriseTrunkGetListRequest	GROUP_LEVEL
GroupEnterpriseTrunkGetRequest	GROUP_LEVEL
GroupEnterpriseTrunkGetRequest21	GROUP_LEVEL
GroupEnterpriseTrunkGetUserListRequest	GROUP_LEVEL
GroupEnterpriseTrunkModifyRequest	GROUP_LEVEL
GroupExchangeIntegrationGetRequest	GROUP_LEVEL
GroupExchangeIntegrationModifyRequest	GROUP_LEVEL
GroupExistingUsersAssignUserServiceListRequest	GROUP_LEVEL
GroupExistingUsersUnassignUserServiceListRequest	GROUP_LEVEL
GroupExtensionLengthGetRequest	GROUP_LEVEL
GroupExtensionLengthGetRequest17	GROUP_LEVEL
GroupExtensionLengthModifyRequest	GROUP_LEVEL
GroupExtensionLengthModifyRequest17	GROUP_LEVEL
GroupFeatureAccessCodeGetListRequest	GROUP_LEVEL
GroupFeatureAccessCodeGetRequest	GROUP_LEVEL
GroupFeatureAccessCodeGetRequest20	GROUP_LEVEL
GroupFeatureAccessCodeGetRequest21	GROUP_LEVEL
GroupFeatureAccessCodeModifyListRequest	GROUP_LEVEL
GroupFeatureAccessCodeModifyRequest	GROUP_LEVEL
GroupFeatureAccessCodeModifyRequest20	GROUP_LEVEL
GroupFeatureAccessCodeModifyRequest21	GROUP_LEVEL
GroupFileRepositoryDeviceUserAddRequest	GROUP_LEVEL
GroupFileRepositoryDeviceUserDeleteRequest	GROUP_LEVEL
GroupFileRepositoryDeviceUserGetListRequest	GROUP_LEVEL
GroupFileRepositoryDeviceUserModifyRequest	GROUP_LEVEL
GroupFindMeFollowMeAddAlertingGroupRequest	GROUP_LEVEL
Group Find MeFollow MeAdd Alerting Group Selective Criteria Request	GROUP_LEVEL
GroupFindMeFollowMeAddInstanceRequest	GROUP_LEVEL
Group Find MeFollow MeAlerting Group Get Available User List Request	GROUP_LEVEL
GroupFindMeFollowMeDeleteAlertingGroupRequest	GROUP_LEVEL
$\label{prop:selectiveCriteriaRequest} Group Find MeFollow MeDelete Alerting Group Selective Criteria Request$	GROUP_LEVEL
GroupFindMeFollowMeDeleteInstanceRequest	GROUP_LEVEL
GroupFindMeFollowMeGetAlertingGroupListRequest	GROUP_LEVEL
GroupFindMeFollowMeGetAlertingGroupRequest	GROUP_LEVEL
GroupFindMeFollowMeGetAlertingGroupSelectiveCriteriaRequest	GROUP_LEVEL



Transaction	Authorization Level
Group Find MeFollow MeGet Alerting Group Selective Criteria Request 21	GROUP_LEVEL
GroupFindMeFollowMeGetInstanceListRequest	GROUP_LEVEL
GroupFindMeFollowMeGetInstanceRequest	GROUP_LEVEL
GroupFindMeFollowMeGetInstanceRequest19sp1	GROUP_LEVEL
GroupFindMeFollowMeModifyActiveInstanceListRequest	GROUP_LEVEL
GroupFindMeFollowMeModifyAlertingGroupListRequest	GROUP_LEVEL
GroupFindMeFollowMeModifyAlertingGroupRequest	GROUP_LEVEL
Group Find MeFollow MeModify Alerting Group Selective Criteria Request	GROUP_LEVEL
GroupFindMeFollowMeModifyInstanceRequest	GROUP_LEVEL
GroupFlexibleSeatingAccessDeviceGetListRequest	USER_LEVEL
GroupFlexibleSeatingHostAddInstanceRequest	GROUP_LEVEL
GroupFlexibleSeatingHostAddInstanceRequest22	GROUP_LEVEL
GroupFlexibleSeatingHostDeleteInstanceRequest	GROUP_LEVEL
GroupFlexibleSeatingHostGetInstanceListRequest	GROUP_LEVEL
GroupFlexibleSeatingHostGetInstanceRequest	GROUP_LEVEL
GroupFlexibleSeatingHostGetInstanceRequest22	GROUP_LEVEL
GroupFlexibleSeatingHostGuestAssociationGetRequest	GROUP_LEVEL
GroupFlexibleSeatingHostGuestAssociationModifyRequest	GROUP_LEVEL
GroupFlexibleSeatingHostModifyActiveInstanceListRequest	GROUP_LEVEL
GroupFlexibleSeatingHostModifyInstanceRequest	GROUP_LEVEL
GroupFlexibleSeatingHostModifyInstanceRequest22	GROUP_LEVEL
GroupFlexibleSeatingHostRoutingPoliciesGetRequest	GROUP_LEVEL
GroupFlexibleSeatingHostRoutingPoliciesModifyRequest	GROUP_LEVEL
GroupGetDefaultRequest	SERVICE_PROVIDER_LEVEL
GroupGetListInServiceProviderPagedSortedListRequest	GROUP_LEVEL
GroupGetListInServiceProviderRequest	USER_LEVEL
GroupGetListInSystemRequest	RESELLER_LEVEL
GroupGetRequest	USER_LEVEL
GroupGetRequest14sp7	USER_LEVEL
GroupGetRequest22	USER_LEVEL
GroupGetRequest22V2	USER_LEVEL
GroupGetUserServiceAssignedUserListRequest	GROUP_LEVEL
GroupGroupNightForwardingGetRequest	USER_LEVEL
GroupGroupNightForwardingModifyRequest	GROUP_LEVEL
GroupGroupPagingAddInstanceRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupGroupPagingAddOriginatorListRequest	GROUP_LEVEL
GroupGroupPagingAddTargetListRequest	GROUP_LEVEL
GroupGroupPagingDeleteInstanceRequest	GROUP_LEVEL
GroupGroupPagingDeleteOriginatorListRequest	GROUP_LEVEL
GroupGroupPagingDeleteTargetListRequest	GROUP_LEVEL
GroupGroupPagingGetAvailableOriginatorListRequest	GROUP_LEVEL
GroupGroupPagingGetAvailableTargetListRequest	GROUP_LEVEL
GroupGroupPagingGetInstanceListRequest	GROUP_LEVEL
GroupGroupPagingGetInstanceRequest	GROUP_LEVEL
GroupGroupPagingGetInstanceRequest17sp3	GROUP_LEVEL
GroupGroupPagingGetInstanceRequest19sp1	GROUP_LEVEL
GroupGroupPagingGetOriginatorListRequest	GROUP_LEVEL
GroupGroupPagingGetTargetListRequest	GROUP_LEVEL
GroupGroupPagingModifyActiveInstanceListRequest	GROUP_LEVEL
GroupGroupPagingModifyInstanceRequest	GROUP_LEVEL
GroupGroupPagingModifyOriginatorListRequest	GROUP_LEVEL
GroupGroupPagingModifyTargetListRequest	GROUP_LEVEL
GroupGroupPagingTargetsCapacityGetRequest	GROUP_LEVEL
GroupGroupPagingTargetsCapacityModifyRequest	SERVICE_PROVIDER_LEVEL
GroupHolidayScheduleAddRequest	GROUP_LEVEL
GroupHolidayScheduleDeleteRequest	GROUP_LEVEL
GroupHolidayScheduleGetListRequest	USER_LEVEL
GroupHolidayScheduleGetRequest	USER_LEVEL
GroupHolidayScheduleModifyRequest	GROUP_LEVEL
GroupHuntGroupAddInstanceRequest14	GROUP_LEVEL
GroupHuntGroupAddInstanceRequest17sp1V1	GROUP_LEVEL
GroupHuntGroupAddInstanceRequest17sp3	GROUP_LEVEL
GroupHuntGroupAddInstanceRequest17sp4	GROUP_LEVEL
GroupHuntGroupAddInstanceRequest19	GROUP_LEVEL
GroupHuntGroupAddInstanceRequest20	GROUP_LEVEL
GroupHuntGroupConsolidatedAddInstanceRequest	GROUP_LEVEL
GroupHuntGroupConsolidatedDeleteInstanceRequest	GROUP_LEVEL
GroupHuntGroupConsolidatedModifyInstanceRequest	GROUP_LEVEL
GroupHuntGroupDeleteInstanceRequest	GROUP_LEVEL
GroupHuntGroupGetAvailableUserListRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupHuntGroupGetAvailableUserPagedSortedListRequest	GROUP_LEVEL
GroupHuntGroupGetInstanceListRequest	GROUP_LEVEL
GroupHuntGroupGetInstancePagedSortedListRequest	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest14	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest17	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest17sp1V1	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest17sp3	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest17sp4	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest19	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest19sp1	GROUP_LEVEL
GroupHuntGroupGetInstanceRequest20	GROUP_LEVEL
GroupHuntGroupModifyActiveInstanceListRequest	GROUP_LEVEL
GroupHuntGroupModifyInstanceRequest	GROUP_LEVEL
GroupHuntGroupModifyInstanceWeightedCallDistributionRequest	GROUP_LEVEL
GroupIMRNAssignListRequest	GROUP_LEVEL
GroupIMRNGetListRequest	GROUP_LEVEL
GroupIMRNUnassignListRequest	GROUP_LEVEL
GroupIncomingCallingPlanGetListRequest	GROUP_LEVEL
GroupIncomingCallingPlanModifyListRequest	GROUP_LEVEL
GroupInstantGroupCallAddInstanceRequest14	GROUP_LEVEL
GroupInstantGroupCallDeleteInstanceRequest	GROUP_LEVEL
GroupInstantGroupCallGetInstanceListRequest	GROUP_LEVEL
GroupInstantGroupCallGetInstanceRequest14	GROUP_LEVEL
GroupInstantGroupCallGetInstanceRequest17	GROUP_LEVEL
GroupInstantGroupCallGetInstanceRequest19sp1	GROUP_LEVEL
GroupInstantGroupCallModifyActiveInstanceListRequest	GROUP_LEVEL
GroupInstantGroupCallModifyInstanceRequest	GROUP_LEVEL
GroupIntegratedIMPGetRequest	GROUP_LEVEL
GroupIntegratedIMPGetRequest21sp1	GROUP_LEVEL
GroupIntegratedIMPModifyRequest	GROUP_LEVEL
GroupInterceptGroupGetRequest	GROUP_LEVEL
GroupInterceptGroupGetRequest16	GROUP_LEVEL
GroupInterceptGroupGetRequest16sp1	GROUP_LEVEL
GroupInterceptGroupGetRequest21sp1	GROUP_LEVEL
GroupInterceptGroupModifyRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupInterceptGroupModifyRequest16	GROUP_LEVEL
GroupInterceptGroupModifyRequest21sp1	GROUP_LEVEL
GroupInventoryReportGetRequest	GROUP_LEVEL
GroupMeetMeConferencingAddInstanceRequest	GROUP_LEVEL
GroupMeetMeConferencingAddInstanceRequest18	GROUP_LEVEL
GroupMeetMeConferencingAddInstanceRequest19	GROUP_LEVEL
GroupMeetMeConferencingDeleteInstanceRequest	GROUP_LEVEL
GroupMeetMeConferencingGetAvailableUserListRequest	GROUP_LEVEL
GroupMeetMeConferencingGetInstanceListRequest	GROUP_LEVEL
GroupMeetMeConferencingGetInstanceRequest	USER_LEVEL
GroupMeetMeConferencingGetInstanceRequest17sp3	USER_LEVEL
GroupMeetMeConferencingGetInstanceRequest17sp4	USER_LEVEL
GroupMeetMeConferencingGetInstanceRequest18	USER_LEVEL
GroupMeetMeConferencingGetInstanceRequest19	USER_LEVEL
GroupMeetMeConferencingGetInstanceRequest19sp1	USER_LEVEL
GroupMeetMeConferencingGetRequest	GROUP_LEVEL
Group Meet MeConferencing Modify Active Instance List Request	GROUP_LEVEL
GroupMeetMeConferencingModifyInstanceRequest	GROUP_LEVEL
GroupMeetMeConferencingModifyRequest	SERVICE_PROVIDER_LEVEL
GroupModifyRequest	GROUP_LEVEL
GroupMusicOnHoldAddInstanceRequest14	GROUP_LEVEL
GroupMusicOnHoldAddInstanceRequest14sp4	GROUP_LEVEL
GroupMusicOnHoldAddInstanceRequest14sp6	GROUP_LEVEL
GroupMusicOnHoldAddInstanceRequest16	GROUP_LEVEL
GroupMusicOnHoldAddInstanceRequest20	GROUP_LEVEL
GroupMusicOnHoldAddInstanceRequest22	GROUP_LEVEL
GroupMusicOnHoldDeleteInstanceRequest	GROUP_LEVEL
GroupMusicOnHoldGetDepartmentListRequest	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest14	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest14sp4	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest14sp6	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest16	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest19	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest20	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest21	GROUP_LEVEL



Transaction	Authorization Level
GroupMusicOnHoldGetInstanceRequest22	GROUP_LEVEL
GroupMusicOnHoldGetInstanceRequest22V2	GROUP_LEVEL
GroupMusicOnHoldModifyInstanceRequest14	GROUP_LEVEL
GroupMusicOnHoldModifyInstanceRequest14sp6	GROUP_LEVEL
GroupMusicOnHoldModifyInstanceRequest16	GROUP_LEVEL
GroupMusicOnHoldModifyInstanceRequest20	GROUP_LEVEL
GroupMusicOnHoldModifyInstanceRequest22	GROUP_LEVEL
${\tt Group MWIDelivery To Mobile Endpoint Custom Template Add Request}$	GROUP_LEVEL
GroupMWIDeliveryToMobileEndpointCustomTemplateDeleteRequest	GROUP_LEVEL
Group MWIDe livery To Mobile Endpoint Custom Template Get Request	GROUP_LEVEL
Group MWIDe livery To Mobile Endpoint Custom Template Modify Request	GROUP_LEVEL
GroupMWIDeliveryToMobileEndpointGetRequest	GROUP_LEVEL
GroupMWIDeliveryToMobileEndpointModifyRequest	GROUP_LEVEL
GroupNetworkClassOfServiceAssignListRequest	SERVICE_PROVIDER_LEVEL
GroupNetworkClassOfServiceAssignListRequest21	SERVICE_PROVIDER_LEVEL
GroupNetworkClassOfServiceAssignToAllUsersRequest	GROUP_LEVEL
GroupNetworkClassOfServiceGetAssignedListRequest	GROUP_LEVEL
GroupNetworkClassOfServiceGetAssignedUserListRequest	GROUP_LEVEL
GroupNetworkClassOfServiceGetAssignedUserListRequest21	GROUP_LEVEL
GroupNetworkClassOfServiceModifyDefaultRequest	GROUP_LEVEL
GroupNetworkClassOfServiceUnassignListRequest	SERVICE_PROVIDER_LEVEL
GroupNetworkClassOfServiceUnassignListRequest21	SERVICE_PROVIDER_LEVEL
GroupNewUserTemplateAssignUserServiceListRequest	GROUP_LEVEL
GroupNewUserTemplateUnassignUserServiceListRequest	GROUP_LEVEL
GroupOfficeZoneAssignListRequest	SERVICE_PROVIDER_LEVEL
GroupOfficeZoneGetAssignedListRequest	GROUP_LEVEL
GroupOfficeZoneGetAssignedUserListRequest	GROUP_LEVEL
GroupOfficeZoneUnassignListRequest	SERVICE_PROVIDER_LEVEL
GroupOutgoingCallingPlanAuthorizationCodeGetListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanCallMeNowGetListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanCallMeNowModifyListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanDepartmentAuthorizationCodeAddListRequest	GROUP_LEVEL
Group Outgoing Calling Plan Department Authorization Code Delete List Request	GROUP_LEVEL
GroupOutgoingCallingPlanDepartmentAuthorizationCodeGetListRequest	USER_LEVEL
GroupOutgoingCallingPlanDigitPlanCallMeNowGetListRequest	GROUP_LEVEL



Transaction	Authorization Level
Group Outgoing Calling Plan Digit Plan Call Me Now Modify List Request	GROUP_LEVEL
GroupOutgoingCallingPlanDigitPlanOriginatingGetListRequest	GROUP_LEVEL
Group Outgoing Calling Plan Digit Plan Originating Modify List Request	GROUP_LEVEL
GroupOutgoingCallingPlanDigitPlanRedirectingGetListRequest	GROUP_LEVEL
Group Outgoing Calling Plan Digit Plan Redirecting Modify List Request	GROUP_LEVEL
GroupOutgoingCallingPlanOriginatingGetListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanOriginatingModifyListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanPinholeDigitPatternAddRequest	GROUP_LEVEL
Group Outgoing Calling Plan Pinhole Digit Pattern Delete List Request	GROUP_LEVEL
GroupOutgoingCallingPlanPinholeDigitPatternGetListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanPinholeDigitPatternModifyRequest	GROUP_LEVEL
GroupOutgoingCallingPlanPinholeDigitPlanCallMeNowGetListRequest	GROUP_LEVEL
Group Outgoing Calling Plan Pinhole Digit Plan Call Me Now Modify List Request	GROUP_LEVEL
GroupOutgoingCallingPlanPinholeDigitPlanOriginatingGetListRequest	GROUP_LEVEL
Group Outgoing Calling Plan Pinhole Digit Plan Originating Modify List Request	GROUP_LEVEL
GroupOutgoingCallingPlanPinholeDigitPlanRedirectingGetListRequest	GROUP_LEVEL
Group Outgoing Calling Plan Pinhole Digit Plan Redirecting Modify List Request	GROUP_LEVEL
GroupOutgoingCallingPlanRedirectedGetListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanRedirectedModifyListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanRedirectingGetListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanRedirectingModifyListRequest	GROUP_LEVEL
GroupOutgoingCallingPlanTransferNumbersGetListRequest	GROUP_LEVEL
Group Outgoing Calling Plan Transfer Numbers Modify List Request	GROUP_LEVEL
GroupPasswordRulesGetRequest	USER_LEVEL
GroupPasswordRulesGetRequest16	USER_LEVEL
GroupPasswordRulesGetRequest22	USER_LEVEL
GroupPasswordRulesModifyRequest	GROUP_LEVEL
GroupPhoneDirectoryGetListRequest	USER_LEVEL
GroupPhoneDirectoryGetListRequest17	USER_LEVEL
GroupPhoneDirectoryGetListRequest17sp3	USER_LEVEL
GroupPhoneDirectoryGetListRequest18	USER_LEVEL
GroupPhoneDirectoryGetPagedListRequest	USER_LEVEL
GroupPhoneDirectoryGetPagedSortedListRequest	USER_LEVEL
GroupPolicyGetRequest	GROUP_LEVEL
GroupPolicyGetRequest14sp1	GROUP_LEVEL



Transaction	Authorization Level
GroupPolicyGetRequest14sp4	GROUP_LEVEL
GroupPolicyGetRequest17	GROUP_LEVEL
GroupPolicyGetRequest20	GROUP_LEVEL
GroupPolicyGetRequest22	GROUP_LEVEL
GroupPolicyModifyRequest	GROUP_LEVEL
GroupPolicyModifyRequest22	GROUP_LEVEL
GroupPolycomPhoneServicesGetRequest	USER_LEVEL
GroupPolycomPhoneServicesModifyRequest	USER_LEVEL
GroupPortalPasscodeRulesGetRequest	GROUP_LEVEL
GroupPortalPasscodeRulesGetRequest19	GROUP_LEVEL
GroupPortalPasscodeRulesModifyRequest	GROUP_LEVEL
GroupPreAlertingAnnouncementGetRequest	GROUP_LEVEL
GroupPreAlertingAnnouncementGetRequest20	GROUP_LEVEL
GroupPreAlertingAnnouncementModifyRequest	GROUP_LEVEL
GroupPreAlertingAnnouncementModifyRequest20	GROUP_LEVEL
GroupPreferredCarrierGroupGetRequest	GROUP_LEVEL
GroupPreferredCarrierGroupModifyRequest	GROUP_LEVEL
GroupRouteListEnterpriseTrunkNumberPrefixAssignListRequest	SERVICE_PROVIDER_LEVEL
GroupRouteListEnterpriseTrunkNumberPrefixGetAvailableListRequest	GROUP_LEVEL
GroupRouteListEnterpriseTrunkNumberPrefixGetSummaryListRequest	GROUP_LEVEL
GroupRouteListEnterpriseTrunkNumberPrefixUnassignListRequest	SERVICE_PROVIDER_LEVEL
GroupRouteListEnterpriseTrunkNumberRangeAssignListRequest	SERVICE_PROVIDER_LEVEL
GroupRouteListEnterpriseTrunkNumberRangeGetAvailableListRequest	GROUP_LEVEL
GroupRouteListEnterpriseTrunkNumberRangeGetSummaryListRequest	GROUP_LEVEL
GroupRouteListEnterpriseTrunkNumberRangeUnassignListRequest	SERVICE_PROVIDER_LEVEL
GroupRoutePointAddDNISRequest	USER_LEVEL
GroupRoutePointAddInstanceRequest	GROUP_LEVEL
GroupRoutePointAddInstanceRequest22	GROUP_LEVEL
GroupRoutePointBouncedCallGetRequest	USER_LEVEL
GroupRoutePointBouncedCallModifyRequest	USER_LEVEL
GroupRoutePointDeleteDNISRequest	USER_LEVEL
GroupRoutePointDeleteInstanceRequest	GROUP_LEVEL
GroupRoutePointDistinctiveRingingGetRequest	USER_LEVEL
GroupRoutePointDistinctiveRingingModifyRequest	USER_LEVEL



Transaction	Authorization Level
GroupRoutePointExternalSystemGetAssignedListRequest	GROUP_LEVEL
GroupRoutePointExternalSystemGetAssignedRoutePointListRequest	GROUP_LEVEL
GroupRoutePointExternalSystemUnassignListRequest	SERVICE_PROVIDER_LEVEL
GroupRoutePointForcedForwardingGetRequest	USER_LEVEL
GroupRoutePointForcedForwardingGetRequest20	USER_LEVEL
GroupRoutePointForcedForwardingModifyRequest	USER_LEVEL
GroupRoutePointForcedForwardingModifyRequest20	USER_LEVEL
GroupRoutePointGetAnnouncementRequest	USER_LEVEL
GroupRoutePointGetAnnouncementRequest19	USER_LEVEL
GroupRoutePointGetAnnouncementRequest20	USER_LEVEL
GroupRoutePointGetAnnouncementRequest22	USER_LEVEL
GroupRoutePointGetDNISAgentListRequest	USER_LEVEL
GroupRoutePointGetDNISAnnouncementRequest	USER_LEVEL
GroupRoutePointGetDNISAnnouncementRequest19	USER_LEVEL
GroupRoutePointGetDNISAnnouncementRequest20	USER_LEVEL
GroupRoutePointGetDNISAnnouncementRequest22	USER_LEVEL
GroupRoutePointGetDNISListRequest	USER_LEVEL
GroupRoutePointGetDNISRequest	USER_LEVEL
GroupRoutePointGetFailoverPolicyRequest	USER_LEVEL
GroupRoutePointGetInstanceListRequest	USER_LEVEL
GroupRoutePointGetInstanceRequest	USER_LEVEL
GroupRoutePointGetInstanceRequest19sp1	USER_LEVEL
GroupRoutePointGetInstanceRequest22	USER_LEVEL
GroupRoutePointHolidayServiceGetRequest	USER_LEVEL
GroupRoutePointHolidayServiceGetRequest17sp1	USER_LEVEL
GroupRoutePointHolidayServiceGetRequest20	USER_LEVEL
GroupRoutePointHolidayServiceModifyRequest	USER_LEVEL
GroupRoutePointHolidayServiceModifyRequest17sp1	USER_LEVEL
GroupRoutePointHolidayServiceModifyRequest20	USER_LEVEL
GroupRoutePointManualFailoverRequest	USER_LEVEL
GroupRoutePointModifyActiveInstanceListRequest	USER_LEVEL
GroupRoutePointModifyAnnouncementRequest	USER_LEVEL
GroupRoutePointModifyAnnouncementRequest20	USER_LEVEL
GroupRoutePointModifyDNISAnnouncementRequest	USER_LEVEL
GroupRoutePointModifyDNISAnnouncementRequest20	USER_LEVEL



Transaction	Authorization Level
GroupRoutePointModifyDNISParametersRequest	USER_LEVEL
GroupRoutePointModifyDNISRequest	USER_LEVEL
GroupRoutePointModifyFailoverPolicyRequest	USER_LEVEL
GroupRoutePointModifyInstanceRequest	USER_LEVEL
GroupRoutePointModifyInstanceRequest22	USER_LEVEL
GroupRoutePointNightServiceGetRequest	USER_LEVEL
GroupRoutePointNightServiceGetRequest17sp1	USER_LEVEL
GroupRoutePointNightServiceGetRequest20	USER_LEVEL
GroupRoutePointNightServiceModifyRequest	USER_LEVEL
GroupRoutePointNightServiceModifyRequest17sp1	USER_LEVEL
GroupRoutePointNightServiceModifyRequest20	USER_LEVEL
GroupRoutePointOverflowGetRequest	USER_LEVEL
GroupRoutePointOverflowGetRequest20	USER_LEVEL
GroupRoutePointOverflowModifyRequest	USER_LEVEL
GroupRoutePointOverflowModifyRequest20	USER_LEVEL
GroupRoutePointQueueCallDispositionCodeAddRequest	USER_LEVEL
GroupRoutePointQueueCallDispositionCodeDeleteRequest	USER_LEVEL
GroupRoutePointQueueCallDispositionCodeGetListRequest	USER_LEVEL
GroupRoutePointQueueCallDispositionCodeGetRequest	USER_LEVEL
GroupRoutePointQueueCallDispositionCodeModifyRequest	USER_LEVEL
GroupRoutePointQueueCallDispositionCodeSettingsGetRequest	USER_LEVEL
GroupRoutePointQueueCallDispositionCodeSettingsModifyRequest	USER_LEVEL
GroupRoutingProfileGetRequest	RESELLER_LEVEL
GroupRoutingProfileModifyRequest	RESELLER_LEVEL
GroupScheduleAddEventRequest	GROUP_LEVEL
GroupScheduleAddRequest	GROUP_LEVEL
GroupScheduleDeleteEventListRequest	GROUP_LEVEL
GroupScheduleDeleteListRequest	GROUP_LEVEL
GroupScheduleGetEventDetailListRequest	USER_LEVEL
GroupScheduleGetEventListRequest	USER_LEVEL
GroupScheduleGetEventRequest	USER_LEVEL
GroupScheduleGetListRequest	GROUP_LEVEL
GroupScheduleGetListRequest17sp1	GROUP_LEVEL
GroupScheduleGetPagedSortedListRequest	GROUP_LEVEL
GroupScheduleModifyEventRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupScheduleModifyRequest	GROUP_LEVEL
GroupScheduleUsageRequest	GROUP_LEVEL
GroupSecurityClassificationCustomizationGetAvailableListRequest	GROUP_LEVEL
GroupSeriesCompletionAddInstanceRequest	GROUP_LEVEL
GroupSeriesCompletionDeleteInstanceRequest	GROUP_LEVEL
GroupSeriesCompletionGetAvailableUserListRequest	GROUP_LEVEL
GroupSeriesCompletionGetInstanceListRequest	GROUP_LEVEL
GroupSeriesCompletionGetInstanceRequest	GROUP_LEVEL
GroupSeriesCompletionModifyInstanceRequest	GROUP_LEVEL
GroupServiceAssignListRequest	GROUP_LEVEL
GroupServiceGetAuthorizationListRequest	GROUP_LEVEL
GroupServiceGetAuthorizationRequest	GROUP_LEVEL
GroupServiceGetAuthorizedListRequest	GROUP_LEVEL
GroupServiceInstancePrivacyGetRequest	USER_LEVEL
GroupServiceInstancePrivacyGetRequest17sp4	USER_LEVEL
GroupServiceInstancePrivacyModifyRequest	USER_LEVEL
GroupServiceIsAssignedRequest	USER_LEVEL
GroupServiceModifyAuthorizationListRequest	SERVICE_PROVIDER_LEVEL
GroupServicePhoneNumberLookupRequest	GROUP_LEVEL
GroupServiceUnassignListRequest	GROUP_LEVEL
GroupSessionAdmissionControlGetAvailableDeviceListRequest	GROUP_LEVEL
GroupSessionAdmissionControlGetRequest	GROUP_LEVEL
GroupSessionAdmissionControlGroupAddDeviceListRequest	GROUP_LEVEL
GroupSessionAdmissionControlGroupAddRequest	GROUP_LEVEL
GroupSessionAdmissionControlGroupAddRequest19sp1	GROUP_LEVEL
GroupSessionAdmissionControlGroupDeleteDeviceListRequest	GROUP_LEVEL
GroupSessionAdmissionControlGroupDeleteListRequest	GROUP_LEVEL
GroupSessionAdmissionControlGroupGetListRequest	GROUP_LEVEL
GroupSessionAdmissionControlGroupGetRequest	GROUP_LEVEL
GroupSessionAdmissionControlGroupGetRequest19sp1	GROUP_LEVEL
GroupSessionAdmissionControlGroupGetRequest21sp1	GROUP_LEVEL
GroupSessionAdmissionControlGroupGetRequest21sp1V2	GROUP_LEVEL
GroupSessionAdmissionControlGroupModifyRequest	GROUP_LEVEL
GroupSessionAdmissionControlModifyRequest	SERVICE_PROVIDER_LEVEL
GroupShInterfaceGetUserListRequest	SYSTEM LEVEL



Transaction	Authorization Level
GroupShInterfaceGetUserListRequest21sp1	SYSTEM_LEVEL
GroupSpeedDial100GetRequest	USER_LEVEL
GroupSpeedDial100GetRequest17sp1	USER_LEVEL
GroupSpeedDial100ModifyRequest	GROUP_LEVEL
GroupThirdPartyVoiceMailSupportGetRequest	GROUP_LEVEL
GroupThirdPartyVoiceMailSupportModifyRequest	GROUP_LEVEL
GroupTimeScheduleAddRequest	GROUP_LEVEL
GroupTimeScheduleDeleteRequest	GROUP_LEVEL
GroupTimeScheduleGetListRequest	USER_LEVEL
GroupTimeScheduleGetRequest	USER_LEVEL
GroupTimeScheduleModifyRequest	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest14	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest14sp1	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest14sp4	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest14sp9	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest14sp9A	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest15	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest15sp2	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest17	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest17sp3	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest17sp4	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest19	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest19sp1	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest20sp1	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest21	GROUP_LEVEL
GroupTrunkGroupAddInstanceRequest22	GROUP_LEVEL
GroupTrunkGroupDeleteInstanceRequest	GROUP_LEVEL
GroupTrunkGroupDeleteInstanceRequest14sp4	GROUP_LEVEL
GroupTrunkGroupGetAvailableDetailListRequest	GROUP_LEVEL
GroupTrunkGroupGetAvailableHostedUserListRequest	GROUP_LEVEL
GroupTrunkGroupGetInstanceListRequest14	GROUP_LEVEL
GroupTrunkGroupGetInstanceListRequest14sp4	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest14	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest14sp1	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest14sp4	GROUP_LEVEL



Transaction	Authorization Level
GroupTrunkGroupGetInstanceRequest14sp5	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest14sp9	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest14sp9A	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest15	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest15sp2	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest17	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest17sp3	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest17sp4	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest17sp4V2	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest19	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest19sp1	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest19sp1V2	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest19V2	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest20sp1	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest21	GROUP_LEVEL
GroupTrunkGroupGetInstanceRequest23	GROUP_LEVEL
GroupTrunkGroupGetInstanceUserListRequest	GROUP_LEVEL
GroupTrunkGroupGetInstanceUserListRequest14sp4	GROUP_LEVEL
GroupTrunkGroupGetRequest	GROUP_LEVEL
GroupTrunkGroupGetRequest14sp1	GROUP_LEVEL
GroupTrunkGroupGetRequest14sp9	GROUP_LEVEL
GroupTrunkGroupModifyInstanceRequest14	GROUP_LEVEL
GroupTrunkGroupModifyInstanceRequest14sp4	GROUP_LEVEL
GroupTrunkGroupModifyInstanceRequest14sp9A	GROUP_LEVEL
GroupTrunkGroupModifyInstanceRequest15	GROUP_LEVEL
GroupTrunkGroupModifyInstanceRequest19sp1	GROUP_LEVEL
GroupTrunkGroupModifyInstanceRequest20sp1	GROUP_LEVEL
GroupTrunkGroupModifyRequest	SERVICE_PROVIDER_LEVEL
GroupTrunkGroupModifyRequest14sp9	SERVICE_PROVIDER_LEVEL
Group Trunk Group Options Message Response Status Code Add List Request	GROUP_LEVEL
GroupTrunkGroupSecurityClassificationGetRequest	GROUP_LEVEL
GroupTrunkGroupSecurityClassificationModifyRequest	GROUP_LEVEL
GroupTrunkGroupUserCreationTaskAddRequest	GROUP_LEVEL
GroupTrunkGroupUserCreationTaskAddRequest14sp4	GROUP_LEVEL
GroupTrunkGroupUserCreationTaskDeleteRequest	GROUP_LEVEL



Transaction	Authorization Level
GroupTrunkGroupUserCreationTaskDeleteRequest14sp4	GROUP_LEVEL
GroupTrunkGroupUserCreationTaskGetListRequest	GROUP_LEVEL
GroupTrunkGroupUserCreationTaskGetListRequest14sp4	GROUP_LEVEL
GroupTrunkGroupUserCreationTaskGetRequest	GROUP_LEVEL
GroupTrunkGroupUserCreationTaskGetRequest14sp4	GROUP_LEVEL
GroupUserCallForwardingSettingsGetListRequest	GROUP_LEVEL
GroupUserCallingPlanSettingsGetListRequest	GROUP_LEVEL
GroupUserCallWaitingSettingsGetListRequest	GROUP_LEVEL
GroupUserHotelingGuestSettingsGetListRequest	GROUP_LEVEL
GroupVirtualOnNetEnterpriseExtensionsAddUserRequest	GROUP_LEVEL
GroupVirtualOnNetEnterpriseExtensionsDeleteUserRequest	GROUP_LEVEL
GroupVirtualOnNetEnterpriseExtensionsGetUserListRequest	GROUP_LEVEL
GroupVirtualOnNetEnterpriseExtensionsGetUserRequest	GROUP_LEVEL
GroupVirtualOnNetEnterpriseExtensionsModifyUserRequest	GROUP_LEVEL
GroupVoiceMessagingGroupConsolidatedModifyVoicePortalRequest	GROUP_LEVEL
GroupVoiceMessagingGroupGetPasscodeRulesRequest	GROUP_LEVEL
GroupVoiceMessagingGroupGetRequest	USER_LEVEL
GroupVoiceMessagingGroupGetVoicePortalBrandingRequest	GROUP_LEVEL
GroupVoiceMessagingGroupGetVoicePortalBrandingRequest16	GROUP_LEVEL
GroupVoiceMessagingGroupGetVoicePortalBrandingRequest20	GROUP_LEVEL
GroupVoiceMessagingGroupGetVoicePortalRequest14	USER_LEVEL
GroupVoiceMessagingGroupGetVoicePortalRequest15	USER_LEVEL
GroupVoiceMessagingGroupGetVoicePortalRequest17	USER_LEVEL
GroupVoiceMessagingGroupGetVoicePortalRequest17sp4	USER_LEVEL
GroupVoiceMessagingGroupGetVoicePortalRequest19sp1	USER_LEVEL
GroupVoiceMessagingGroupGetVoicePortalRequest21sp1	USER_LEVEL
GroupVoiceMessagingGroupModifyPasscodeRulesRequest	GROUP_LEVEL
GroupVoiceMessagingGroupModifyRequest	GROUP_LEVEL
GroupVoiceMessagingGroupModifyVoicePortalBrandingExecutionServerRequest	GROUP_LEVEL
GroupVoiceMessagingGroupModifyVoicePortalBrandingRequest	GROUP_LEVEL
GroupVoiceMessagingGroupModifyVoicePortalBrandingRequest16	GROUP_LEVEL
GroupVoiceMessagingGroupModifyVoicePortalBrandingRequest20	GROUP_LEVEL
GroupVoiceMessagingGroupModifyVoicePortalRequest	GROUP_LEVEL
GroupVoiceXmlAddInstanceRequest	GROUP_LEVEL
GroupVoiceXmlDeleteInstanceRequest	GROUP_LEVEL



GroupVoiceXmiGetInstanceListRequest GroupVoiceXmiGetInstanceRequest GroupVoiceXmiGetInstanceRequest 19sp1 GroupVoiceXmiGetInstanceRequest19sp1 GroupVoiceXmiGetInstanceRequest22 GroupVoiceXmiModifyActiveInstanceListRequest GroupVoiceXmiModifyActiveInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest LoginRequest14sp4 NOT_AUTHORIZED LoginRequest21sp1 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22 LoginRequest22 NOT_AUTHORIZED LoginRequest22 LoginRequest22 LoginRequest2 LoginRequest4 LoginRequest4 LoginRequest5 LogoufRequest LoginRequest6 LoginRequest8 LogoufRequest LoginRequest LoginRequest8 LogoufRequest LoginRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminSelnControlPoliciesGetRequest ResellerAdminSelnControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyRequest ResellerCallNotifyReq	Transaction	Authorization Level
GroupVoiceXmiGetInstanceRequest19sp1 GROUP_LEVEL GroupVoiceXmiGetInstanceRequest22 GROUP_LEVEL GroupVoiceXmiModifyActiveInstanceListRequest GROUP_LEVEL GroupVoiceXmiModifyInstanceRequest GROUP_LEVEL GroupVoiceXmiModifyInstanceRequest GROUP_LEVEL LoginRequest13mp10 NOT_AUTHORIZED LoginRequest14sp4 NOT_AUTHORIZED LoginRequest21sp1 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22V2 NOT_AUTHORIZED LoginRequest22V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V4 LoginRequest2V4 LOSER_LEVEL LOGI-WedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest GROUP_LEVEL PasswordModifyRequest USER_LEVEL PasswordModifyRequest USER_LEVEL PublicClusterGetFullyQualifiedDomainNameRequest NOT_AUTHORIZED ResellerAddRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallConterGetRequest ResellerCallConterGetRequest ResellerCallControlPoliciesModifyRequest ResellerCallControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPoliciesModifyRequest ResellerCallAdmiscinfyControlPolic	GroupVoiceXmlGetInstanceListRequest	GROUP_LEVEL
GroupVoiceXmiGetInstanceRequest22 GroupVoiceXmiModifyActiveInstanceListRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest LoginRequest13mp10 NOT_AUTHORIZED LoginRequest14sp4 NOT_AUTHORIZED LoginRequest21sp1 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LogoutRequest USER_LEVEL LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest GROUP_LEVEL PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest NOT_AUTHORIZED NOT_AUTHORIZED NOT_AUTHORIZED ResellerAddRequest ResellerAdminAddRequest ResellerAdminAddRequest ResellerAdminGetListRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallOutifyGetRequest ResellerCallOutify	GroupVoiceXmlGetInstanceRequest	GROUP_LEVEL
GroupVoiceXmiModifyActiveInstanceListRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest GroupVoiceXmiModifyInstanceRequest LoginRequest13mp10 NOT_AUTHORIZED LoginRequest21sp1 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22 LoginRequest22V2 NOT_AUTHORIZED LoginRequest22V3 NOT_AUTHORIZED LoginRequest2U3 LogoutRequest USER_LEVEL LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest GROUP_LEVEL PasswordGenerateRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PublicClusterGetFullyQualifiedDomainNameRequest NOT_AUTHORIZED ResellerAddRequest ResellerAddRequest ResellerAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest Res	GroupVoiceXmlGetInstanceRequest19sp1	GROUP_LEVEL
GroupVoiceXmiModifyInstanceRequest LoginRequest13mp10 NOT_AUTHORIZED LoginRequest14sp4 NOT_AUTHORIZED LoginRequest21sp1 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22V2 NOT_AUTHORIZED LoginRequest22V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V4 LoginRequest USER_LEVEL LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest GROUP_LEVEL PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest PublicClusterGetFullyQualifiedDomainNameRequest NOT_AUTHORIZED ResellerAddRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyRequest ResellerCallNotifyRequest ResellerCallOntortoftQetRequest ResellerCallNotifyRequest ResellerCallNotifyRequest ResellerCollaborateModifyRequest Res	GroupVoiceXmlGetInstanceRequest22	GROUP_LEVEL
LoginRequest13mp10 LoginRequest14sp4 NOT_AUTHORIZED LoginRequest21sp1 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22V2 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V3 LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest4 USER_LEVEL PasswordGenerateRequest GROUP_LEVEL PasswordGenerateRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest NOT_AUTHORIZED ResellerAddRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallConterGetRequest ResellerCallControlPoliciesModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallControlPoliciesModifyRequest ResellerCallControlFoliciesModifyRequest ResellerCallC	GroupVoiceXmlModifyActiveInstanceListRequest	GROUP_LEVEL
LoginRequest14sp4 LoginRequest21sp1 NOT_AUTHORIZED LoginRequest22 NOT_AUTHORIZED LoginRequest22V2 LoginRequest22V3 NOT_AUTHORIZED LoginRequest22V3 LoginRequest LoginRequest LoginRequest LoginRequest LoginRequest LoginRequest LoginRequest USER_LEVEL LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest PrimaryInfoGetRequest PrimaryInfoGetRequest PrimaryInfoGetRequest ProvisionNing_LEVEL PresellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerCallAdminsionControlPoliciesGetRequest ResellerCallAdminsionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallConterModifyRequest ResellerCallConterModifyRequest ResellerCallConterModifyRequest ResellerCallConterModifyRequest ResellerCallConterModifyRequest ResellerCallConterGetRequest ResellerCall	GroupVoiceXmlModifyInstanceRequest	GROUP_LEVEL
LoginRequest21sp1 LoginRequest22 LoginRequest22V2 LoginRequest22V3 NOT_AUTHORIZED NOT_AUTHORIZED LoginRequest22V3 NOT_AUTHORIZED LogoulRequest LogoulRequest USER_LEVEL LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest GROUP_LEVEL PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest PrimaryInfoGetRequest PrimaryInfoGetRequest ResellerAddRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminSocontrolPoliciesGetRequest ResellerAdminSocontrolPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyModifyRequest ResellerCallCenterModifyRequest ResellerCallCente	LoginRequest13mp10	NOT_AUTHORIZED
LoginRequest22 LoginRequest22V2 LoginRequest22V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LoginRequest2V3 NOT_AUTHORIZED LogoutRequest USER_LEVEL LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest GROUP_LEVEL PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest NOT_AUTHORIZED ResellerAddRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminSeinControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRe	LoginRequest14sp4	NOT_AUTHORIZED
LoginRequest22V2 LoginRequest22V3 NOT_AUTHORIZED LoginRequest22V3 NOT_AUTHORIZED LoginRequest22V3 NOT_AUTHORIZED USER_LEVEL LongLivedTokenRevokeRequest PasswordGenerateRequest PasswordGenerateRequest PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest PrimaryInfoGetRequest PublicClusterGetFullyQualifiedDomainNameRequest NOT_AUTHORIZED ResellerAddrinAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminSoinControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyMedifyRequest ResellerCallDotrateGetRequest ResellerCallNotifyModifyRequest ResellerCallDotrateGetRequest ResellerCallDotrateGetRequest ResellerCallDotrateGetRequest ResellerCallNotifyModifyRequest ResellerCallAdmisorateModifyRequest ResellerCallAdmisorateModifyRequest ResellerCallAdmisorateGetRequest ResellerC	LoginRequest21sp1	NOT_AUTHORIZED
LogoirRequest22V3 LogoirRequest LogoirRequest LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest PasswordGenerateRequest PasswordModifyRequest PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest PublicClusterGetFullyQualifiedDomainNameRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterGetRequest ResellerCallRequest ResellerCallRequest ResellerCallRequest ResellerCallCenterGetRequest ResellerCallRequest ResellerCallCenterGetRequest ResellerCallRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallRequest ResellerCallRequest ResellerCallRequest ResellerCallCenterGetRequest Res	LoginRequest22	NOT_AUTHORIZED
LogoutRequest LongLivedTokenRevokeRequest USER_LEVEL PasswordGenerateRequest PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PublicClusterGetFullyQualifiedDomainNameRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallRequest ResellerCallReque	LoginRequest22V2	NOT_AUTHORIZED
LongLivedTokenRevokeRequest PasswordGenerateRequest PasswordModifyRequest PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest PublicClusterGetFullyQualifiedDomainNameRequest ResellerAddRequest ResellerAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallRequest ResellerCallCenterGetRequest ResellerCallRequest ResellerCallReq	LoginRequest22V3	NOT_AUTHORIZED
PasswordGenerateRequest PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PublicClusterGetFullyQualifiedDomainNameRequest NoT_AUTHORIZED ResellerAddRequest PROVISIONING_LEVEL ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallReguest Reseller	LogoutRequest	USER_LEVEL
PasswordModifyRequest USER_LEVEL PrimaryInfoGetRequest USER_LEVEL PublicClusterGetFullyQualifiedDomainNameRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGotPequest ResellerAdminGetRequest ResellerAdminGotPequest ResellerAdminGotPequest ResellerAdminGotPequest ResellerAdminGotPequest ResellerAdminGotPequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallRequest	LongLivedTokenRevokeRequest	USER_LEVEL
PrimaryInfoGetRequest PublicClusterGetFullyQualifiedDomainNameRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallRequest Reseller	PasswordGenerateRequest	GROUP_LEVEL
PublicClusterGetFullyQualifiedDomainNameRequest ResellerAddRequest ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyDetRequest ResellerCallCetRequest ResellerCallCe	PasswordModifyRequest	USER_LEVEL
ResellerAddRequest ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallDedetRequest ResellerCallDedetRequest ResellerCallDedetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCelleteRequest ResellerC	PrimaryInfoGetRequest	USER_LEVEL
ResellerAdminAddRequest ResellerAdminDeleteRequest ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCelleteRequest Rese	PublicClusterGetFullyQualifiedDomainNameRequest	NOT_AUTHORIZED
ResellerAdminDeleteRequest ResellerAdminGetListRequest ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCelleteRequest ResellerCe	ResellerAddRequest	PROVISIONING_LEVEL
ResellerAdminGetListRequest ResellerAdminGetRequest ResellerAdminGetRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCelleteRequest Res	ResellerAdminAddRequest	RESELLER_LEVEL
ResellerAdminGetRequest ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCelleteRequest ResellerCelleteR	ResellerAdminDeleteRequest	RESELLER_LEVEL
ResellerAdminModifyRequest ResellerCallAdmissionControlPoliciesGetRequest SYSTEM_LEVEL ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCelletRequest ResellerCelletRequest ResellerCelletRequest ResellerCelletRequest ResellerCellRequest ResellerCellReq	ResellerAdminGetListRequest	RESELLER_LEVEL
ResellerCallAdmissionControlPoliciesGetRequest ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCelleteRequest ResellerCelleteRequest ResellerCelleteRequest ResellerCelleteRequest ResellerCelleteRequest ResellerCelleteRequest ResellerCelleteRequest ResellerCelleteRequest ResellerCelleteRequest	ResellerAdminGetRequest	RESELLER_LEVEL
ResellerCallAdmissionControlPoliciesModifyRequest ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest	ResellerAdminModifyRequest	RESELLER_LEVEL
ResellerCallCenterGetRequest ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest	ResellerCallAdmissionControlPoliciesGetRequest	SYSTEM_LEVEL
ResellerCallCenterModifyRequest ResellerCallNotifyGetRequest ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest	ResellerCallAdmissionControlPoliciesModifyRequest	SYSTEM_LEVEL
ResellerCallNotifyGetRequest ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest ResellerDeleteRequest	ResellerCallCenterGetRequest	RESELLER_LEVEL
ResellerCallNotifyModifyRequest ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerCollaborateModifyRequest ResellerDeleteRequest ResellerDeleteRequest ResellerEmergencyCallNotificationGetRequest ResellerEmergencyCallNotificationGetRequest	ResellerCallCenterModifyRequest	RESELLER_LEVEL
ResellerCollaborateGetRequest ResellerCollaborateModifyRequest ResellerDeleteRequest ResellerDeleteRequest ResellerEmergencyCallNotificationGetRequest ResellerEmergencyCallNotificationGetRequest	ResellerCallNotifyGetRequest	RESELLER_LEVEL
ResellerCollaborateModifyRequest ResellerDeleteRequest ResellerEmergencyCallNotificationGetRequest ResellerEmergencyCallNotificationGetRequest ResellerEmergencyCallNotificationGetRequest	ResellerCallNotifyModifyRequest	RESELLER_LEVEL
ResellerDeleteRequest PROVISIONING_LEVEL ResellerEmergencyCallNotificationGetRequest RESELLER_LEVEL	ResellerCollaborateGetRequest	RESELLER_LEVEL
ResellerEmergencyCallNotificationGetRequest RESELLER_LEVEL	ResellerCollaborateModifyRequest	RESELLER_LEVEL
	ResellerDeleteRequest	PROVISIONING_LEVEL
ResellerEmergencyCallNotificationModifyRequest RESELLER_LEVEL	ResellerEmergencyCallNotificationGetRequest	RESELLER_LEVEL
	ResellerEmergencyCallNotificationModifyRequest	RESELLER_LEVEL



Transaction	Authorization Level
ResellerEmergencyZonesGetRequest	RESELLER_LEVEL
ResellerEmergencyZonesModifyRequest	RESELLER_LEVEL
ResellerGetListRequest	PROVISIONING_LEVEL
ResellerGetRequest	RESELLER_LEVEL
ResellerIntegratedIMPGetRequest	SYSTEM_LEVEL
ResellerIntegratedIMPGetRequest22	SYSTEM_LEVEL
ResellerIntegratedIMPModifyRequest	SYSTEM_LEVEL
ResellerMailParametersGetRequest	RESELLER_LEVEL
ResellerMailParametersModifyRequest	RESELLER_LEVEL
ResellerMeetMeConferencingGetRequest	RESELLER_LEVEL
ResellerMeetMeConferencingModifyRequest	RESELLER_LEVEL
ResellerModifyRequest	RESELLER_LEVEL
ResellerNetworkClassOfServiceAssignListRequest	SYSTEM_LEVEL
ResellerNetworkClassOfServiceGetAssignedListRequest	RESELLER_LEVEL
ResellerNetworkClassOfServiceGetAssignedServiceProviderListRequest	RESELLER_LEVEL
ResellerNetworkClassOfServiceModifyDefaultRequest	RESELLER_LEVEL
ResellerNetworkClassOfServiceUnassignListRequest	SYSTEM_LEVEL
ResellerResourcePriorityGetRequest	SYSTEM_LEVEL
ResellerResourcePriorityModifyRequest	SYSTEM_LEVEL
ResellerServiceAuthorizationGetRequest	RESELLER_LEVEL
ResellerServiceAuthorizationModifyRequest	SYSTEM_LEVEL
ResellerVoiceMessagingGroupGetRequest	RESELLER_LEVEL
ResellerVoiceMessagingGroupModifyRequest	RESELLER_LEVEL
ServiceProviderAccessDeviceAddRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceCustomTagAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceCustomTagDeleteListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceCustomTagGetListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceCustomTagModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceFileGetListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceFileGetListRequest14sp8	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceFileGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceFileGetRequest14sp8	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceFileGetRequest16sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceFileGetRequest20	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
ServiceProviderAccessDeviceFileModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceFileModifyRequest14sp8	SERVICE_PROVIDER_LEVEL
Service Provider Access Device Get Enhanced Configuration Type List Request	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetEnhancedConfigurationTypeRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetRequest14sp3	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetRequest14sp6	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetRequest16	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetRequest18sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetUserListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceGetUserListRequest21sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceModifyRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceModifyUserRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceResetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceTagSetGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAccessDeviceTagSetModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAddRequest13mp2	RESELLER_LEVEL
ServiceProviderAdminAddRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetListRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPagedSortedListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest16sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest16sp2	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest17	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest17sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest17sp3	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest18	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetPolicyRequest20	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminGetRequest21sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderAdministratorPasswordRulesGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminModifyPolicyRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderAdminModifyRequest	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
ServiceProviderAdviceOfChargeGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderAdviceOfChargeModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderAnswerConfirmationGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderAnswerConfirmationGetRequest16	SERVICE_PROVIDER_LEVE
ServiceProviderAnswerConfirmationModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderAnswerConfirmationModifyRequest16	SERVICE_PROVIDER_LEVE
ServiceProviderApplicationServerSetGetRequest	SYSTEM_LEVEL
ServiceProviderApplicationServerSetModifyRequest	SYSTEM_LEVEL
ServiceProviderBroadWorksCommunicatorGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksCommunicatorModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityGetRequest	SYSTEM_LEVEL
ServiceProviderBroadWorksMobilityGetRequest19sp1	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityGetRequest21sp1	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityGetRequest21sp1V2	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityGetRequest22	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityGetRequest22V2	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityGetRequest22V3	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityMobileSubscriberDirectoryNumberAddListRequest	PROVISIONING_LEVEL
ServiceProviderBroadWorksMobilityMobileSubscriberDirectoryNumberAddListRequest21	RESELLER_LEVEL
ServiceProviderBroadWorksMobilityMobileSubscriberDirectoryNumberDeleteListRe quest	RESELLER_LEVEL
ServiceProviderBroadWorksMobilityMobileSubscriberDirectoryNumberGetAvailable ListRequest	GROUP_LEVEL
ServiceProviderBroadWorksMobilityMobileSubscriberDirectoryNumberGetSummary ListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderBroadWorksMobilityModifyRequest	RESELLER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest14	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest14sp1	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest14sp4	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest14sp7	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest15	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest15sp2	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest16	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest16sp2	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest17	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest17sp3	USER_LEVEL



Transaction	Authorization Level
ServiceProviderCallProcessingGetPolicyRequest17sp4	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest18sp1	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest19sp1	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest21sp1	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest21sp2	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest22	USER_LEVEL
ServiceProviderCallProcessingGetPolicyRequest22V2	USER_LEVEL
ServiceProviderCallProcessingModifyPolicyRequest14	SERVICE_PROVIDER_LEVEL
ServiceProviderCallProcessingModifyPolicyRequest15	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringCriteriaAssignListRequest	SYSTEM_LEVEL
Service Provider Communication Barring Criteria Get Assigned List Request	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringCriteriaUnassignListRequest	SYSTEM_LEVEL
Service Provider Communication Barring Digit Pattern Criteria Add Request	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringDigitPatternCriteriaDeleteRequest	SERVICE_PROVIDER_LEVEL
Service Provider Communication Barring Digit Pattern Criteria Get List Request	SERVICE_PROVIDER_LEVEL
Service Provider Communication Barring Digit Pattern Criteria Get Pattern List Request	SERVICE_PROVIDER_LEVEL
Service Provider Communication Barring Digit Pattern Criteria Get Request	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringDigitPatternCriteriaModifyRequest	SERVICE_PROVIDER_LEVEL
Service Provider Communication Barring Incoming Criteria Assign List Request	SYSTEM_LEVEL
Service Provider Communication Barring Incoming Criteria Get Assigned List Request	SERVICE_PROVIDER_LEVEL
Service Provider Communication Barring Incoming Criteria Unassign List Request	SYSTEM_LEVEL
ServiceProviderCommunicationBarringProfileAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileAddRequest17sp3	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileAddRequest19sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileGetAssignedGroupListRequest	SERVICE_PROVIDER_LEVEL
Service Provider Communication Barring Profile Get Criteria Usage List Request	SERVICE_PROVIDER_LEVEL
Service Provider Communication Barring Profile Get Digit Pattern Criteria Usage List Request	SERVICE_PROVIDER_LEVEL
$Service Provider Communication Barring Profile GetIncoming Criteria Usage List Reques\\t$	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileGetListRequest	GROUP_LEVEL
ServiceProviderCommunicationBarringProfileGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileGetRequest17sp3	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileGetRequest19sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileGetRequest19sp1V2	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
ServiceProviderCommunicationBarringProfileModifyDefaultRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCommunicationBarringProfileModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCPEConfigRebuildConfigFileRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCPEConfigRebuildDeviceConfigFileRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCPEConfigReorderDeviceLinePortsRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCPEConfigResetDeviceRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCPEConfigResetDeviceTypeRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderCPEConfigSetConfigFileRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeleteRequest	RESELLER_LEVEL
ServiceProviderDeviceManagementEventGetListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceManagementEventGetListRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceManagementGetAccessDeviceCountForDeviceTypeServiceProviderRequest	SERVICE_PROVIDER_LEVEL
Service Provider Device Management In Progress And Pending Event Cancel Request	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceProfileAuthenticationPasswordRulesGetRequest	GROUP_LEVEL
Service Provider Device Profile Authentication Password Rules Modify Request	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeCustomTagAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeCustomTagDeleteListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeCustomTagGetListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeCustomTagModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeFileGetListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeFileGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeFileModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeTagSetGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDeviceTypeTagSetModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialableCallerIDCriteriaAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialableCallerIDCriteriaDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialableCallerIDCriteriaGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialableCallerIDCriteriaModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialableCallerIDGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialableCallerIDModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialPlanPolicyAddAccessCodeRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialPlanPolicyDeleteAccessCodeRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialPlanPolicyGetAccessCodeListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialPlanPolicyGetAccessCodeRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderDialPlanPolicyGetRequest	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
ServiceProviderDialPlanPolicyGetRequest17	SERVICE_PROVIDER_LEVE
ServiceProviderDialPlanPolicyModifyAccessCodeRequest	SERVICE_PROVIDER_LEVE
ServiceProviderDialPlanPolicyModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderDigitCollectionGetRequest13mp4	SERVICE_PROVIDER_LEVE
ServiceProviderDigitCollectionModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderDnAddListRequest	RESELLER_LEVEL
ServiceProviderDnDeleteListRequest	RESELLER_LEVEL
ServiceProviderDnGetAvailableListRequest	GROUP_LEVEL
ServiceProviderDnGetSummaryListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderDomainAssignListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderDomainGetAssignedGroupListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderDomainGetAssignedListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderDomainUnassignListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderEmergencyCallNotificationGetRequest	GROUP_LEVEL
ServiceProviderEmergencyCallNotificationModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderEndpointGetListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderEnhancedCallLogsGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderEnhancedCallLogsGetRequest17sp4	SERVICE_PROVIDER_LEVE
ServiceProviderEnhancedCallLogsModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderExternalCustomRingbackGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderExternalCustomRingbackModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderFeatureAccessCodeGetListRequest	GROUP_LEVEL
ServiceProviderFeatureAccessCodeGetListRequest20	GROUP_LEVEL
ServiceProviderFeatureAccessCodeGetListRequest21	GROUP_LEVEL
ServiceProviderFeatureAccessCodeModifyListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderFeatureAccessCodeModifyListRequest20	SERVICE_PROVIDER_LEVE
ServiceProviderFeatureAccessCodeModifyListRequest21	SERVICE_PROVIDER_LEVE
ServiceProviderFileRepositoryDeviceUserAddRequest	SERVICE_PROVIDER_LEVE
ServiceProviderFileRepositoryDeviceUserDeleteRequest	SERVICE_PROVIDER_LEVE
ServiceProviderFileRepositoryDeviceUserGetListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderFileRepositoryDeviceUserModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderGetDefaultRequest	RESELLER_LEVEL
ServiceProviderGetListRequest	RESELLER_LEVEL
ServiceProviderGetPagedSortedListRequest	RESELLER_LEVEL
ServiceProviderGetRequest13mp2	USER_LEVEL



ServiceProviderGetRequest22 ServiceProviderGetRequest22V2 ServiceProviderGetRequest22V2 ServiceProviderGroupPagingTargetsCapacityGetRequest ServiceProviderGroupPagingTargetsCapacityModifyRequest ServiceProviderHPBXAlternateCarrierSelectionGetRequest ServiceProviderHPBXAlternateCarrierSelectionModifyRequest ServiceProviderIMRNAssignListRequest ServiceProviderIMRNAssignListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest22 ServiceProviderIntegratedIMPGetRequest22	USER_LEVEL USER_LEVEL
ServiceProviderGetRequest22V2 ServiceProviderGroupPagingTargetsCapacityGetRequest ServiceProviderGroupPagingTargetsCapacityModifyRequest ServiceProviderHPBXAlternateCarrierSelectionGetRequest ServiceProviderHPBXAlternateCarrierSelectionModifyRequest ServiceProviderIMRNAssignListRequest ServiceProviderIMRNGetListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	USER_LEVEL
ServiceProviderGroupPagingTargetsCapacityGetRequest ServiceProviderGroupPagingTargetsCapacityModifyRequest ServiceProviderHPBXAlternateCarrierSelectionGetRequest ServiceProviderHPBXAlternateCarrierSelectionModifyRequest ServiceProviderIMRNAssignListRequest ServiceProviderIMRNGetListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	
ServiceProviderGroupPagingTargetsCapacityModifyRequest ServiceProviderHPBXAlternateCarrierSelectionGetRequest ServiceProviderHPBXAlternateCarrierSelectionModifyRequest ServiceProviderIMRNAssignListRequest ServiceProviderIMRNGetListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	
ServiceProviderHPBXAlternateCarrierSelectionGetRequest ServiceProviderIMRNAssignListRequest ServiceProviderIMRNAssignListRequest ServiceProviderIMRNGetListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest17 ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderIMRNAssignListRequest ServiceProviderIMRNGetListRequest ServiceProviderIMRNGetListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	RESELLER_LEVEL
ServiceProviderIMRNAssignListRequest ServiceProviderIMRNGetListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest17 ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderIMRNGetListRequest ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest17 ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderIMRNUnassignListRequest ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest17 ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderInCallServiceActivationGetRequest ServiceProviderInCallServiceActivationGetRequest17 ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderInCallServiceActivationGetRequest17 ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderInCallServiceActivationModifyRequest ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	USER_LEVEL
ServiceProviderInCallServiceActivationModifyRequest17 ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	USER_LEVEL
ServiceProviderIntegratedIMPGetRequest ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderIntegratedIMPGetRequest21 ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SERVICE_PROVIDER_LEVEL
ServiceProviderIntegratedIMPGetRequest21sp1 ServiceProviderIntegratedIMPGetRequest22	SYSTEM_LEVEL
ServiceProviderIntegratedIMPGetRequest22	RESELLER_LEVEL
	RESELLER_LEVEL
ServiceProviderIntegratedIMPModifyRequest	RESELLER_LEVEL
	RESELLER_LEVEL
ServiceProviderLanguageAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderLanguageDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderLanguageGetAvailableListRequest	USER_LEVEL
ServiceProviderLanguageGetListRequest	USER_LEVEL
ServiceProviderLanguageModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMaliciousCallTraceGetRequest	PROVISIONING_LEVEL
ServiceProviderMaliciousCallTraceModifyRequest	PROVISIONING_LEVEL
ServiceProviderMeetMeConferencingGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMeetMeConferencingModifyRequest	RESELLER_LEVEL
ServiceProviderModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMWIDeliveryToMobileEndpointCustomTemplateAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMWIDeliveryToMobileEndpointCustomTemplateDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMWIDeliveryToMobileEndpointCustomTemplateGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMWIDeliveryToMobileEndpointCustomTemplateModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMWIDeliveryToMobileEndpointGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderMWIDeliveryToMobileEndpointModifyRequest	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
ServiceProviderNetworkClassOfServiceAssignListRequest	PROVISIONING_LEVEL
ServiceProviderNetworkClassOfServiceAssignListRequest21	RESELLER_LEVEL
ServiceProviderNetworkClassOfServiceAssignListToAllGroupsRequest	SERVICE_PROVIDER_LEVE
ServiceProviderNetworkClassOfServiceAssignToAllUsersRequest	SERVICE_PROVIDER_LEVE
ServiceProviderNetworkClassOfServiceGetAssignedGroupListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderNetworkClassOfServiceGetAssignedListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderNetworkClassOfServiceModifyDefaultRequest	SERVICE_PROVIDER_LEVE
ServiceProviderNetworkClassOfServiceUnassignListRequest	PROVISIONING_LEVEL
ServiceProviderNetworkClassOfServiceUnassignListRequest21	RESELLER_LEVEL
ServiceProviderNumberPortabilityQueryAddListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderNumberPortabilityQueryGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderNumberPortabilityQueryModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderOfficeZoneAssignListRequest	SYSTEM_LEVEL
ServiceProviderOfficeZoneGetAssignedGroupListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderOfficeZoneGetAssignedListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderOfficeZoneUnassignListRequest	SYSTEM_LEVEL
ServiceProviderPasswordRulesGetRequest13mp2	USER_LEVEL
ServiceProviderPasswordRulesGetRequest16	USER_LEVEL
ServiceProviderPasswordRulesGetRequest22	USER_LEVEL
ServiceProviderPasswordRulesModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPasswordRulesModifyRequest14sp3	SERVICE_PROVIDER_LEVE
ServiceProviderPortalPasscodeRulesGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPortalPasscodeRulesGetRequest19	SERVICE_PROVIDER_LEVE
ServiceProviderPortalPasscodeRulesModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPreferredCarrierAddRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPreferredCarrierDeleteRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPreferredCarrierGetAvailableCountryCodeListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPreferredCarrierGetCarrierListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPreferredCarrierGetListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPreferredCarrierGetRequest	SERVICE_PROVIDER_LEVE
ServiceProviderPreferredCarrierModifyRequest	SERVICE_PROVIDER_LEVE
ServiceProviderRouteListEnterpriseTrunkNumberPrefixActivateListRequest	SERVICE_PROVIDER_LEVE
ServiceProviderRouteListEnterpriseTrunkNumberPrefixAddListRequest	RESELLER_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberPrefixDeactivateListRequest	SERVICE_PROVIDER_LEVE
ocividei Tovidei Codicelsie Incipiise Tranki Valibeit Telix Deactivate Eisti Cequest	OLITATION DEIT_LEVE



Transaction	Authorization Level
ServiceProviderRouteListEnterpriseTrunkNumberPrefixGetAvailableListRequest	GROUP_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberPrefixGetSummaryListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberRangeActivateListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberRangeAddListRequest	RESELLER_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberRangeDeactivateListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberRangeDeleteListRequest	RESELLER_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberRangeGetAvailableListRequest	GROUP_LEVEL
ServiceProviderRouteListEnterpriseTrunkNumberRangeGetSummaryListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderRoutePointExternalSystemAssignListRequest	RESELLER_LEVEL
ServiceProviderRoutePointExternalSystemGetAssignedGroupListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderRoutePointExternalSystemGetAssignedListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderRoutePointExternalSystemUnassignListRequest	RESELLER_LEVEL
ServiceProviderRoutingProfileGetRequest	RESELLER_LEVEL
ServiceProviderRoutingProfileModifyRequest	RESELLER_LEVEL
ServiceProviderScheduleAddEventRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderScheduleAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderScheduleDeleteEventListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderScheduleDeleteListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderScheduleGetEventDetailListRequest	USER_LEVEL
ServiceProviderScheduleGetEventListRequest	USER_LEVEL
ServiceProviderScheduleGetEventRequest	USER_LEVEL
ServiceProviderScheduleGetListRequest	GROUP_LEVEL
ServiceProviderScheduleModifyEventRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderScheduleModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServiceGetAuthorizationListRequest	GROUP_LEVEL
ServiceProviderServiceGetAuthorizationRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServiceGetUserAssignableListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServiceModifyAuthorizationListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackAddServiceListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackGetDetailListRequest	GROUP_LEVEL
ServiceProviderServicePackGetListRequest	GROUP_LEVEL
ServiceProviderServicePackGetServiceUsageListRequest	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
ServiceProviderServicePackMigrationTaskAddRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskAddRequest21	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskCopyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskDeleteRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskGetAvailableGroupListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskGetListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskGetListRequest21	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskGetRequest14sp4	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskGetRequest21	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskModifyAssignmentListRequest	SERVICE_PROVIDER_LEVEL
Service Provider Service Pack Migration Task Modify Group List Request	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskModifyRemovalListRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskModifyUserSelectionRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackMigrationTaskTerminateRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePackModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderServicePhoneNumberLookupRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderSessionAdmissionControlGetRequest	GROUP_LEVEL
ServiceProviderSessionAdmissionControlModifyRequest	RESELLER_LEVEL
ServiceProviderSessionAdmissionControlWhiteListGetRequest	SERVICE_PROVIDER_LEVEL
Service Provider Session Admission Control White List Modify Request	SERVICE_PROVIDER_LEVEL
ServiceProviderSIPAuthenticationPasswordRulesGetRequest	GROUP_LEVEL
ServiceProviderSIPAuthenticationPasswordRulesModifyRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderTrunkGroupGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderTrunkGroupGetRequest14sp1	SERVICE_PROVIDER_LEVEL
ServiceProviderTrunkGroupModifyRequest	RESELLER_LEVEL
Service Provider Voice Messaging Group Get Pass code Rules Request	SERVICE_PROVIDER_LEVEL
ServiceProviderVoiceMessagingGroupGetRequest	SERVICE_PROVIDER_LEVEL
Service Provider Voice Messaging Group Get Voice Portal Branding Request	SERVICE_PROVIDER_LEVEL
ServiceProviderVoiceMessagingGroupGetVoicePortalBrandingRequest16	SERVICE_PROVIDER_LEVEL
ServiceProviderVoiceMessagingGroupGetVoicePortalRequest	GROUP_LEVEL
ServiceProviderVoiceMessagingGroupModifyPasscodeRulesRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderVoiceMessagingGroupModifyRequest	SERVICE_PROVIDER_LEVEL
Service Provider Voice Messaging Group Modify Voice Portal Branding Request	SERVICE_PROVIDER_LEVEL



Transaction	Authorization Level
ServiceProviderVoiceMessagingGroupModifyVoicePortalBrandingRequest16	SERVICE_PROVIDER_LEVEL
ServiceProviderVoiceMessagingGroupModifyVoicePortalRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderZoneCallingRestrictionsGetRequest	SERVICE_PROVIDER_LEVEL
ServiceProviderZoneCallingRestrictionsModifyRequest	SERVICE_PROVIDER_LEVEL
SessionStartRequest	NOT_AUTHORIZED
SystemAccessDeviceAddRequest	SYSTEM_LEVEL
SystemAccessDeviceCustomTagAddRequest	SYSTEM_LEVEL
SystemAccessDeviceCustomTagDeleteListRequest	SYSTEM_LEVEL
SystemAccessDeviceCustomTagGetListRequest	SYSTEM_LEVEL
SystemAccessDeviceCustomTagModifyRequest	SYSTEM_LEVEL
SystemAccessDeviceDeleteRequest	SYSTEM_LEVEL
SystemAccessDeviceFileGetListRequest	SYSTEM_LEVEL
SystemAccessDeviceFileGetListRequest14sp8	SYSTEM_LEVEL
SystemAccessDeviceFileGetRequest	SYSTEM_LEVEL
SystemAccessDeviceFileGetRequest14sp8	SYSTEM_LEVEL
SystemAccessDeviceFileGetRequest16sp1	SYSTEM_LEVEL
SystemAccessDeviceFileGetRequest20	SYSTEM_LEVEL
SystemAccessDeviceFileModifyRequest	SYSTEM_LEVEL
SystemAccessDeviceFileModifyRequest14sp8	SYSTEM_LEVEL
SystemAccessDeviceGetAllRequest	RESELLER_LEVEL
SystemAccessDeviceGetListRequest14	SYSTEM_LEVEL
SystemAccessDeviceGetRequest	SYSTEM_LEVEL
SystemAccessDeviceGetRequest14sp3	SYSTEM_LEVEL
SystemAccessDeviceGetRequest14sp6	SYSTEM_LEVEL
SystemAccessDeviceGetRequest16	SYSTEM_LEVEL
SystemAccessDeviceGetRequest18sp1	SYSTEM_LEVEL
SystemAccessDeviceGetUserListRequest	SYSTEM_LEVEL
SystemAccessDeviceGetUserListRequest21sp1	SYSTEM_LEVEL
SystemAccessDeviceModifyRequest	SYSTEM_LEVEL
SystemAccessDeviceModifyUserRequest	SYSTEM_LEVEL
SystemAccessDeviceMonitorAddDeviceTypeRequest	SYSTEM_LEVEL
SystemAccessDeviceMonitorDeleteDeviceTypeRequest	SYSTEM_LEVEL
SystemAccessDeviceMonitorGetDeviceTypeListRequest	SYSTEM_LEVEL
SystemAccessDeviceMonitorParametersGetRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemAccessDeviceResetRequest	SYSTEM_LEVEL
SystemAccessDeviceTagSetGetRequest	SYSTEM_LEVEL
SystemAccessDeviceTagSetModifyRequest	SYSTEM_LEVEL
SystemAccessDeviceTypeGetEnhancedConfigurableListRequest	GROUP_LEVEL
SystemAccessDeviceTypeGetListRequest	GROUP_LEVEL
SystemAccountingAddChargingFunctionElementServerRequest	SYSTEM_LEVEL
SystemAccountingAddRadiusServerRequest	SYSTEM_LEVEL
SystemAccountingDeleteChargingFunctionElementServerRequest	SYSTEM_LEVEL
SystemAccountingDeleteRadiusServerRequest	SYSTEM_LEVEL
SystemAccountingGetChargingFunctionElementServerListRequest	SYSTEM_LEVEL
SystemAccountingGetRadiusServerListRequest	SYSTEM_LEVEL
System Accounting Inhibited Attribute Value Pair Code Add Request	SYSTEM_LEVEL
SystemAccountingInhibitedAttributeValuePairCodeDeleteRequest	SYSTEM_LEVEL
System Accounting Inhibited Attribute Value Pair Code Get List Request	SYSTEM_LEVEL
SystemAccountingModifyChargingFunctionElementServerRequest	SYSTEM_LEVEL
SystemAccountingModifyRadiusServerRequest	SYSTEM_LEVEL
SystemAccountingReorderChargingFunctionElementServerRequest	SYSTEM_LEVEL
SystemAdminAddRequest	PROVISIONING_LEVEL
SystemAdminDeleteRequest	PROVISIONING_LEVEL
SystemAdminGetListRequest	PROVISIONING_LEVEL
SystemAdminGetRequest	PROVISIONING_LEVEL
SystemAdminModifyRequest	PROVISIONING_LEVEL
SystemAdviceOfChargeCostInformationSourceAddRequest	SYSTEM_LEVEL
SystemAdviceOfChargeCostInformationSourceDeleteRequest	SYSTEM_LEVEL
SystemAdviceOfChargeCostInformationSourceGetListRequest	SYSTEM_LEVEL
SystemAdviceOfChargeCostInformationSourceModifyRequest	SYSTEM_LEVEL
SystemAdviceOfChargeGetRequest	SYSTEM_LEVEL
SystemAdviceOfChargeGetRequest19sp1	SYSTEM_LEVEL
SystemAdviceOfChargeModifyRequest	SYSTEM_LEVEL
SystemAdviceOfChargeModifyRequest19sp1	SYSTEM_LEVEL
SystemAliasAddRequest	SYSTEM_LEVEL
SystemAliasDeleteRequest	SYSTEM_LEVEL
SystemAliasGetListRequest	SYSTEM_LEVEL
SystemAlternateUserIdGetListRequest	RESELLER LEVEL
Cystem, inclinate section to quest	.,



Transaction	Authorization Level
SystemAnonymousCallRejectionModifyRequest	SYSTEM_LEVEL
SystemApplicationControllerAddRequest	SYSTEM_LEVEL
SystemApplicationControllerDeleteRequest	SYSTEM_LEVEL
SystemApplicationControllerGetListRequest	SYSTEM_LEVEL
SystemASRParametersGetRequest	SYSTEM_LEVEL
SystemASRParametersGetRequest14sp5	SYSTEM_LEVEL
SystemASRParametersGetRequest14sp7	SYSTEM_LEVEL
SystemASRParametersGetRequest23	SYSTEM_LEVEL
SystemASRParametersModifyRequest	SYSTEM_LEVEL
SystemASRParametersModifyRequest14sp7	SYSTEM_LEVEL
SystemAuthenticationLockoutExportDataGetRequest	SYSTEM_LEVEL
SystemAuthenticationLockoutSettingsGetRequest	SYSTEM_LEVEL
SystemAuthenticationLockoutSettingsModifyRequest	SYSTEM_LEVEL
SystemAutomaticCallbackAddReleaseCauseListRequest	SYSTEM_LEVEL
SystemAutomaticCallbackDeleteReleaseCauseListRequest	SYSTEM_LEVEL
SystemAutomaticCallbackGetReleaseCauseListRequest	SYSTEM_LEVEL
SystemAutomaticCallbackGetRequest	SYSTEM_LEVEL
SystemAutomaticCallbackGetRequest15	SYSTEM_LEVEL
SystemAutomaticCallbackGetRequest15sp2	SYSTEM_LEVEL
SystemAutomaticCallbackGetRequest17	SYSTEM_LEVEL
SystemAutomaticCallbackModifyRequest	SYSTEM_LEVEL
SystemAutomaticCallbackModifyRequest15	SYSTEM_LEVEL
SystemAutomaticCollectCallGetRequest	SYSTEM_LEVEL
SystemAutomaticCollectCallModifyRequest	SYSTEM_LEVEL
SystemAutomaticCollectCallPrefixDigitsAddListRequest	SYSTEM_LEVEL
SystemAutomaticCollectCallPrefixDigitsDeleteListRequest	SYSTEM_LEVEL
SystemAutomaticCollectCallPrefixDigitsGetListRequest	SYSTEM_LEVEL
SystemBCCTAddOCIInterfaceAddressRequest	SYSTEM_LEVEL
SystemBCCTDeleteOCIInterfaceAddressRequest	SYSTEM_LEVEL
SystemBCCTGetOCIInterfaceAddressListRequest	SYSTEM_LEVEL
SystemBroadCloudGetRequest	SYSTEM_LEVEL
SystemBroadCloudModifyRequest	SYSTEM_LEVEL
SystemBroadWorksAnywhereGetRequest	SYSTEM_LEVEL
SystemBroadWorksAnywhereModifyRequest	SYSTEM_LEVEL
SystemBroadWorksMobileManagerGetRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemBroadWorksMobileManagerModifyRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityAddIMRNListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityAddMobileNetworkIMRNListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityDeleteIMRNListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityDeleteMobileNetworkIMRNListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityGetIMRNListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityGetMobileNetworkIMRNListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityGetRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityGetRequest17sp4	SYSTEM_LEVEL
SystemBroadWorksMobilityGetRequest19sp1	SYSTEM_LEVEL
SystemBroadWorksMobilityGetRequest21	SERVICE_PROVIDER_LEVE
SystemBroadWorksMobilityGetRequest21sp1	SERVICE_PROVIDER_LEVE
SystemBroadWorksMobilityGetRequest21sp1V2	SERVICE_PROVIDER_LEVE
SystemBroadWorksMobilityGetRequest22	SERVICE_PROVIDER_LEVE
SystemBroadWorksMobilityGetRequest22V2	SERVICE_PROVIDER_LEVE
SystemBroadWorksMobilityGetRequest22V3	SERVICE_PROVIDER_LEVE
SystemBroadWorksMobilityMobileNetworkAddRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityMobileNetworkDeleteRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityMobileNetworkGetListRequest	RESELLER_LEVEL
SystemBroadWorksMobilityMobileNetworkGetRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityMobileNetworkModifyRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityMobileSubscriberDirectoryNumberGetSummaryListReq uest	RESELLER_LEVEL
SystemBroadWorksMobilityModifyRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityModifyRequest17sp4	SYSTEM_LEVEL
SystemBroadWorksMobilityModifyRequest21	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeAddRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeAddRequest21	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeDeleteRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeDeleteRequest21	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeGetListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeGetListRequest21	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeListAddRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeListDeleteRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeListGetListRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeListModifyRequest	SYSTEM LEVEL



Transaction	Authorization Level
System Broad Works Mobility Service Access Code List Usage Get Request	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeModifyRequest	SYSTEM_LEVEL
SystemBroadWorksMobilityServiceAccessCodeModifyRequest21	SYSTEM_LEVEL
SystemBroadWorksReceptionistEnterpriseGetRequest	SYSTEM_LEVEL
System Broad Works Reception is tEnter prise Modify Request	SYSTEM_LEVEL
SystemBusyLampFieldGetRequest	SYSTEM_LEVEL
SystemBusyLampFieldGetRequest18	SYSTEM_LEVEL
SystemBusyLampFieldGetRequest23	SYSTEM_LEVEL
SystemBusyLampFieldModifyRequest	SYSTEM_LEVEL
SystemBwDiameterBaseDataGetRequest	SYSTEM_LEVEL
SystemBwDiameterBaseDataGetRequest17sp3	SYSTEM_LEVEL
SystemBwDiameterBaseDataGetRequest22	SYSTEM_LEVEL
SystemBwDiameterBaseDataModifyRequest	SYSTEM_LEVEL
SystemBwDiameterPeerAddRequest	SYSTEM_LEVEL
SystemBwDiameterPeerAddRequest22	SYSTEM_LEVEL
SystemBwDiameterPeerDeleteRequest	SYSTEM_LEVEL
SystemBwDiameterPeerGetListRequest	SYSTEM_LEVEL
SystemBwDiameterPeerModifyRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingPeerAddRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingPeerDeleteRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingPeerGetListRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingPeerModifyRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingRealmAddRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingRealmDeleteRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingRealmGetListRequest	SYSTEM_LEVEL
SystemBwDiameterRoutingRealmModifyRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingBrandingGetRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingBrandingModifyRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingDataTemplateGetListRequest	GROUP_LEVEL
SystemCallCenterEnhancedReportingGetRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingModifyRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingReportTemplateAddRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingReportTemplateDeleteRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingReportTemplateGetListRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingReportTemplateGetRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemCallCenterEnhancedReportingReportTemplateModifyRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingScheduledReportGetActiveListRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingScheduledReportGetCompletedListRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingScheduledReportGetListRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingScheduledReportGetReportTemplateUsageListRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingScheduledTaskParametersGetRequest	SYSTEM_LEVEL
SystemCallCenterEnhancedReportingScheduledTaskParametersModifyRequest	SYSTEM_LEVEL
SystemCallCenterGetRequest	USER_LEVEL
SystemCallCenterGetRequest14sp9	USER_LEVEL
SystemCallCenterGetRequest16	USER_LEVEL
SystemCallCenterGetRequest17	USER_LEVEL
SystemCallCenterGetRequest17sp4	USER_LEVEL
SystemCallCenterGetRequest19	USER_LEVEL
SystemCallCenterGetRequest21	USER_LEVEL
SystemCallCenterModifyRequest	SYSTEM_LEVEL
SystemCallCenterReportingServerGetListRequest	USER_LEVEL
SystemCallingNameRetrievalGetRequest14	SYSTEM_LEVEL
SystemCallingNameRetrievalGetRequest16sp1	SYSTEM_LEVEL
SystemCallingNameRetrievalGetRequest17sp4	SYSTEM_LEVEL
SystemCallingNameRetrievalGetRequest20	SYSTEM_LEVEL
SystemCallingNameRetrievalModifyRequest	SYSTEM_LEVEL
SystemCallingNameRetrievalModifyRequest16sp1	SYSTEM_LEVEL
SystemCallingNameRetrievalModifyRequest20	SYSTEM_LEVEL
SystemCallingPartyCategoryAddRequest	SYSTEM_LEVEL
SystemCallingPartyCategoryDeleteRequest	SYSTEM_LEVEL
SystemCallingPartyCategoryGetListRequest	USER_LEVEL
SystemCallingPartyCategoryGetRequest	SYSTEM_LEVEL
SystemCallingPartyCategoryModifyRequest	SYSTEM_LEVEL
SystemCallMeNowGetRequest	SYSTEM_LEVEL
SystemCallMeNowModifyRequest	SYSTEM_LEVEL
SystemCallNotifyGetRequest	SYSTEM_LEVEL
SystemCallNotifyModifyRequest	SYSTEM_LEVEL
SystemCallProcessingGetPolicyRequest14	USER_LEVEL
SystemCallProcessingGetPolicyRequest14sp1	USER_LEVEL
SystemCallProcessingGetPolicyRequest14sp4	USER LEVEL



Transaction	Authorization Level
SystemCallProcessingGetPolicyRequest14sp7	USER_LEVEL
SystemCallProcessingGetPolicyRequest15	USER_LEVEL
SystemCallProcessingGetPolicyRequest15sp2	USER_LEVEL
SystemCallProcessingGetPolicyRequest16	USER_LEVEL
SystemCallProcessingGetPolicyRequest16sp2	USER_LEVEL
SystemCallProcessingGetPolicyRequest17	USER_LEVEL
SystemCallProcessingGetPolicyRequest17sp3	USER_LEVEL
SystemCallProcessingGetPolicyRequest17sp4	USER_LEVEL
SystemCallProcessingGetPolicyRequest18sp1	USER_LEVEL
SystemCallProcessingGetPolicyRequest19sp1	USER_LEVEL
SystemCallProcessingGetPolicyRequest21sp1	USER_LEVEL
SystemCallProcessingGetPolicyRequest21sp2	USER_LEVEL
SystemCallProcessingGetPolicyRequest22	USER_LEVEL
SystemCallProcessingGetPolicyRequest22V2	USER_LEVEL
SystemCallProcessingGetPolicyRequest23	USER_LEVEL
SystemCallProcessingModifyPolicyRequest14	SYSTEM_LEVEL
SystemCallProcessingModifyPolicyRequest15	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileAddRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileAddRequest20	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileAddRequest21	SYSTEM_LEVEL
System Call Processing Policy Profile Auto Attendant Profile Get Request	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileAutoAttendantProfileGetRequest22	SYSTEM_LEVEL
System Call Processing Policy Profile Auto Attendant Profile Modify Request	SYSTEM_LEVEL
System Call Processing Policy Profile Broad Works Anywhere Profile Get Request	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileBroadWorksAnywhereProfileGetRequest22	SYSTEM_LEVEL
System Call Processing Policy Profile Broad Works Anywhere Profile Modify Request	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileCallCenterProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileCallCenterProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileCallCenterProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileCollaborateProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileCollaborateProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileCollaborateProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileDeleteRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileFindMeFollowMeProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileFindMeFollowMeProfileGetRequest22	SYSTEM_LEVEL



Transaction	Authorization Level
SystemCallProcessingPolicyProfileFindMeFollowMeProfileModifyRequest	SYSTEM_LEVEL
System Call Processing Policy Profile Flexible Seating Host Profile Get Request	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileFlexibleSeatingHostProfileGetRequest22	SYSTEM_LEVEL
System Call Processing Policy Profile Flexible Seating Host Profile Modify Request	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGetAssignedNCOSListRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGetListRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGetRequest20	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGetRequest21	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGroupPagingProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGroupPagingProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileGroupPagingProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileHuntGroupProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileHuntGroupProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileHuntGroupProfileModifyRequest	SYSTEM_LEVEL
System Call Processing Policy Profile Instant Group Call Profile Get Request	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileInstantGroupCallProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileInstantGroupCallProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileMeetMeConferencingProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileMeetMeConferencingProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileMeetMeConferencingProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileModifyRequest20	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileModifyRequest21	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileRoutePointProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileRoutePointProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileRoutePointProfileModifyRequest	SYSTEM_LEVEL
System Call Processing Policy Profile Trunk Group Pilot Profile Get Request	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileTrunkGroupPilotProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileTrunkGroupPilotProfileGetRequest22V2	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileTrunkGroupPilotProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileUserProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileUserProfileGetRequest21sp1	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileUserProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileUserProfileGetRequest22V2	SYSTEM_LEVEL



Transaction	Authorization Level
SystemCallProcessingPolicyProfileUserProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileVoicePortalProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileVoicePortalProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileVoicePortalProfileModifyRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileVoiceXMLProfileGetRequest	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileVoiceXMLProfileGetRequest22	SYSTEM_LEVEL
SystemCallProcessingPolicyProfileVoiceXMLProfileModifyRequest	SYSTEM_LEVEL
SystemCallRecordingAddPlatformRequest	SYSTEM_LEVEL
SystemCallRecordingAddPlatformRequest19	SYSTEM_LEVEL
SystemCallRecordingAddPlatformRequest20	RESELLER_LEVEL
SystemCallRecordingAddPlatformRequest22	RESELLER_LEVEL
SystemCallRecordingDeletePlatformRequest	RESELLER_LEVEL
SystemCallRecordingGetPlatformListRequest	GROUP_LEVEL
SystemCallRecordingGetPlatformListRequest20sp1	GROUP_LEVEL
SystemCallRecordingGetPlatformListRequest22	GROUP_LEVEL
SystemCallRecordingGetPlatformListRequest22V2	GROUP_LEVEL
SystemCallRecordingGetPlatformUsageRequest	SYSTEM_LEVEL
SystemCallRecordingGetPlatformUsageRequest22	RESELLER_LEVEL
SystemCallRecordingGetRequest	SYSTEM_LEVEL
SystemCallRecordingGetRequest22	SYSTEM_LEVEL
SystemCallRecordingGetRequest23	USER_LEVEL
SystemCallRecordingModifyPlatformRequest	RESELLER_LEVEL
SystemCallRecordingModifyPlatformRequest22	RESELLER_LEVEL
SystemCallRecordingModifyRequest	SYSTEM_LEVEL
SystemCallRecordingModifyRequest22	SYSTEM_LEVEL
SystemCallReturnGetRequest	SYSTEM_LEVEL
SystemCallReturnModifyRequest	SYSTEM_LEVEL
SystemCallTypeAddMappingRequest	SYSTEM_LEVEL
SystemCallTypeDeleteMappingRequest	SYSTEM_LEVEL
SystemCallTypeGetListRequest	SYSTEM_LEVEL
SystemCallTypeGetMappingListRequest	SYSTEM_LEVEL
SystemCallWaitingGetRequest	SYSTEM_LEVEL
SystemCallWaitingModifyRequest	SYSTEM_LEVEL
SystemClassmarkAddRequest	SYSTEM_LEVEL
SystemClassmarkDeleteRequest	SYSTEM LEVEL



Transaction	Authorization Level
SystemClassmarkGetListRequest	SERVICE_PROVIDER_LEVE
SystemClassmarkGetUtilizationListRequest	SYSTEM_LEVEL
SystemClassmarkModifyRequest	SYSTEM_LEVEL
SystemCLIDDeliveryPrefixAddListRequest	SYSTEM_LEVEL
SystemCLIDDeliveryPrefixDeleteListRequest	SYSTEM_LEVEL
SystemCLIDDeliveryPrefixGetListRequest	SYSTEM_LEVEL
SystemClientIdentityAddRequest	SYSTEM_LEVEL
SystemClientIdentityDeleteRequest	SYSTEM_LEVEL
SystemClientIdentityGetListRequest	SYSTEM_LEVEL
SystemClientSessionParametersGetRequest	SYSTEM_LEVEL
SystemClientSessionParametersModifyRequest	SYSTEM_LEVEL
SystemCodecAddRequest	SYSTEM_LEVEL
SystemCodecDeleteRequest	SYSTEM_LEVEL
SystemCodecGetListRequest	SYSTEM_LEVEL
SystemCollaborateGetRequest	GROUP_LEVEL
SystemCollaborateGetRequest20sp1	GROUP_LEVEL
SystemCollaborateGetRequest20sp1V2	GROUP_LEVEL
SystemCollaborateModifyRequest	SYSTEM_LEVEL
SystemCollaborateModifyRequest20sp1	SYSTEM_LEVEL
SystemCollaborateModifyRequest20sp1V2	SYSTEM_LEVEL
SystemCommunicationBarringAlternateCallIndicatorAddRequest	SYSTEM_LEVEL
SystemCommunicationBarringAlternateCallIndicatorDeleteRequest	SYSTEM_LEVEL
SystemCommunicationBarringAlternateCallIndicatorGetListRequest	GROUP_LEVEL
SystemCommunicationBarringAlternateCallIndicatorModifyRequest	SYSTEM_LEVEL
SystemCommunicationBarringCallTypeAddRequest	SYSTEM_LEVEL
SystemCommunicationBarringCallTypeDeleteRequest	SYSTEM_LEVEL
SystemCommunicationBarringCallTypeGetListRequest	GROUP_LEVEL
SystemCommunicationBarringCallTypeModifyRequest	SYSTEM_LEVEL
SystemCommunicationBarringCriteriaAddRequest	SYSTEM_LEVEL
SystemCommunicationBarringCriteriaAddRequest17	SYSTEM_LEVEL
SystemCommunicationBarringCriteriaDeleteRequest	SYSTEM_LEVEL
SystemCommunicationBarringCriteriaGetListRequest	SYSTEM_LEVEL
SystemCommunicationBarringCriteriaGetRequest	SYSTEM_LEVEL
SystemCommunicationBarringCriteriaGetRequest17	SYSTEM_LEVEL
SystemCommunicationBarringCriteriaGetRequest19sp1	SYSTEM_LEVEL



Transaction	Authorization Level
SystemCommunicationBarringCriteriaModifyRequest	SYSTEM_LEVEL
SystemCommunicationBarringDigitPatternCriteriaAddRequest	SYSTEM_LEVEL
SystemCommunicationBarringDigitPatternCriteriaDeleteRequest	SYSTEM_LEVEL
SystemCommunicationBarringDigitPatternCriteriaGetListRequest	SYSTEM_LEVEL
System Communication Barring Digit Pattern Criteria Get Pattern List Request	SYSTEM_LEVEL
SystemCommunicationBarringDigitPatternCriteriaGetRequest	SYSTEM_LEVEL
System Communication Barring Digit Pattern Criteria Modify Request	SYSTEM_LEVEL
SystemCommunicationBarringGetRequest	SYSTEM_LEVEL
SystemCommunicationBarringGetRequest21sp1	SYSTEM_LEVEL
SystemCommunicationBarringIncomingCriteriaAddRequest	SYSTEM_LEVEL
SystemCommunicationBarringIncomingCriteriaDeleteRequest	SYSTEM_LEVEL
SystemCommunicationBarringIncomingCriteriaGetListRequest	SYSTEM_LEVEL
SystemCommunicationBarringIncomingCriteriaGetRequest	SYSTEM_LEVEL
SystemCommunicationBarringIncomingCriteriaModifyRequest	SYSTEM_LEVEL
SystemCommunicationBarringModifyRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileAddRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileAddRequest17sp1	SYSTEM_LEVEL
SystemCommunicationBarringProfileAddRequest17sp3	SYSTEM_LEVEL
SystemCommunicationBarringProfileAddRequest19sp1	SYSTEM_LEVEL
SystemCommunicationBarringProfileDeleteRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetCriteriaUsageListRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetDigitPatternCriteriaUsageListRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetIncomingCriteriaUsageListRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetListRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetRequest	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetRequest16	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetRequest17sp1	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetRequest17sp3	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetRequest19sp1	SYSTEM_LEVEL
SystemCommunicationBarringProfileGetRequest19sp1V2	SYSTEM_LEVEL
SystemCommunicationBarringProfileModifyRequest	SYSTEM_LEVEL
System Communication Barring Service Provider Get Criteria Usage List Request	SYSTEM_LEVEL
System Communication Barring Service Provider GetIncoming Criteria Usage List Request	SYSTEM_LEVEL
SystemCommunicationBarringUserControlGetRequest	SYSTEM_LEVEL
SystemCommunicationBarringUserControlModifyRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemConfigurableFileSystemGetRequest	SYSTEM_LEVEL
SystemConfigurableFileSystemGetRequest23	SYSTEM_LEVEL
SystemConfigurableFileSystemModifyRequest	SYSTEM_LEVEL
SystemConfigurableTreatmentAddRequest	SYSTEM_LEVEL
SystemConfigurableTreatmentDeleteRequest	SYSTEM_LEVEL
SystemConfigurableTreatmentGetListRequest	SERVICE_PROVIDER_LEVEL
SystemConfigurableTreatmentGetRequest	SYSTEM_LEVEL
SystemConfigurableTreatmentGetRequest16	SYSTEM_LEVEL
SystemConfigurableTreatmentModifyRequest	SYSTEM_LEVEL
System Connected Line Identification Presentation Get Request	SYSTEM_LEVEL
System Connected Line Identification Presentation Modify Request	SYSTEM_LEVEL
SystemCountryCodeAddRequest	SYSTEM_LEVEL
SystemCountryCodeDeleteRequest	SYSTEM_LEVEL
SystemCountryCodeGetListRequest	GROUP_LEVEL
SystemCountryCodeModifyRequest	SYSTEM_LEVEL
SystemCPEConfigAddFileServerRequest	SYSTEM_LEVEL
SystemCPEConfigAddFileServerRequest14sp6	RESELLER_LEVEL
SystemCPEConfigDeleteFileServerRequest	RESELLER_LEVEL
SystemCPEConfigGetFileServerListRequest	SYSTEM_LEVEL
SystemCPEConfigGetFileServerListRequest14sp6	SYSTEM_LEVEL
SystemCPEConfigModifyFileServerRequest	SYSTEM_LEVEL
SystemCPEConfigModifyFileServerRequest14sp6	RESELLER_LEVEL
SystemCPEConfigParametersGetRequest	SYSTEM_LEVEL
SystemCPEConfigParametersGetRequest14sp6	SYSTEM_LEVEL
SystemCPEConfigParametersGetRequest20	SYSTEM_LEVEL
SystemCPEConfigParametersGetRequest21	SYSTEM_LEVEL
SystemCPEConfigParametersModifyRequest	SYSTEM_LEVEL
SystemCPEConfigParametersModifyRequest20	SYSTEM_LEVEL
SystemCPEConfigParametersModifyRequest21	SYSTEM_LEVEL
SystemCPEConfigRebuildConfigFileRequest	GROUP_LEVEL
SystemCPEConfigRebuildDeviceConfigFileRequest	SYSTEM_LEVEL
SystemCPEConfigReorderDeviceLinePortsRequest	SYSTEM_LEVEL
SystemCPEConfigResetDeviceRequest	SYSTEM_LEVEL
SystemCPEConfigResetDeviceTypeRequest	GROUP_LEVEL
SystemCPEConfigSetConfigFileRequest	RESELLER_LEVEL



Transaction	Authorization Level
SystemCrInterfaceGetRequest	SYSTEM_LEVEL
SystemCrInterfaceGetRequest22	SYSTEM_LEVEL
SystemCrInterfaceModifyRequest	SYSTEM_LEVEL
SystemCustomerOriginatedTraceGetRequest	SYSTEM_LEVEL
SystemCustomerOriginatedTraceModifyRequest	SYSTEM_LEVEL
SystemDeviceManagementAutoRebuildConfigGetListRequest	SYSTEM_LEVEL
SystemDeviceManagementAutoRebuildConfigModifyListRequest	SYSTEM_LEVEL
SystemDeviceManagementEventGetListRequest	SYSTEM_LEVEL
SystemDeviceManagementEventGetListRequest22	SYSTEM_LEVEL
SystemDeviceManagementGetAccessDeviceCountForDeviceTypeRequest	RESELLER_LEVEL
SystemDeviceManagementGetEventStatusSummaryCountRequest	SYSTEM_LEVEL
SystemDeviceManagementInProgressAndPendingEventCancelRequest	SYSTEM_LEVEL
SystemDeviceManagementSwitchDeviceTypeDeviceRequest	SYSTEM_LEVEL
SystemDeviceManagementSwitchDeviceTypeRequest	SYSTEM_LEVEL
SystemDeviceManagementTagAddRequest	RESELLER_LEVEL
SystemDeviceManagementTagAddRequest21sp2	RESELLER_LEVEL
SystemDeviceManagementTagAddRequest22	RESELLER_LEVEL
SystemDeviceManagementTagDeleteListRequest	RESELLER_LEVEL
SystemDeviceManagementTagGetListRequest	RESELLER_LEVEL
SystemDeviceManagementTagModifyRequest	RESELLER_LEVEL
SystemDeviceManagementTagSetAddRequest	RESELLER_LEVEL
SystemDeviceManagementTagSetDeleteRequest	RESELLER_LEVEL
SystemDeviceManagementTagSetGetListRequest	SYSTEM_LEVEL
SystemDeviceManagementTagSetGetListRequest22	GROUP_LEVEL
SystemDeviceManagementTagSetModifyRequest	RESELLER_LEVEL
SystemDeviceProfileAuthenticationLockoutClearAllRequest	SYSTEM_LEVEL
SystemDeviceProfileAuthenticationLockoutClearRequest	SYSTEM_LEVEL
SystemDeviceProfileAuthenticationLockoutGetRequest	SYSTEM_LEVEL
SystemDeviceProfileAuthenticationPasswordRulesGetRequest	GROUP_LEVEL
SystemDeviceProfileAuthenticationPasswordRulesModifyRequest	SYSTEM_LEVEL
SystemDeviceTypeExportRequest	RESELLER_LEVEL
SystemDeviceTypeGetAvailableListRequest	GROUP_LEVEL
SystemDeviceTypeGetAvailableListRequest14sp1	GROUP_LEVEL
SystemDeviceTypeGetAvailableListRequest14sp3	GROUP_LEVEL
SystemDeviceTypeGetAvailableListRequest19	GROUP_LEVEL



Transaction	Authorization Level
SystemDeviceTypeGetAvailableListRequest22	GROUP_LEVEL
SystemDeviceTypeGetRequest	GROUP_LEVEL
SystemDeviceTypeGetRequest14sp3	GROUP_LEVEL
SystemDeviceTypeGetRequest14sp6	GROUP_LEVEL
SystemDeviceTypeGetRequest16	GROUP_LEVEL
SystemDeviceTypeGetRequest16sp1	GROUP_LEVEL
SystemDeviceTypeGetRequest18	GROUP_LEVEL
SystemDeviceTypeGetRequest19	GROUP_LEVEL
SystemDeviceTypeGetRequest21sp1	GROUP_LEVEL
SystemDeviceTypeGetRequest22	GROUP_LEVEL
SystemDeviceTypeGetRequest22V2	GROUP_LEVEL
SystemDeviceTypeImportRequest	RESELLER_LEVEL
SystemDialableCallerIDCriteriaAddRequest	SYSTEM_LEVEL
SystemDialableCallerIDCriteriaDeleteRequest	SYSTEM_LEVEL
SystemDialableCallerIDCriteriaGetRequest	SYSTEM_LEVEL
SystemDialableCallerIDCriteriaModifyRequest	SYSTEM_LEVEL
SystemDialableCallerIDGetRequest	SYSTEM_LEVEL
SystemDialableCallerIDModifyRequest	SYSTEM_LEVEL
SystemDialPlanPolicyAddAccessCodeRequest	SYSTEM_LEVEL
SystemDialPlanPolicyDeleteAccessCodeRequest	SYSTEM_LEVEL
SystemDialPlanPolicyGetAccessCodeListRequest	SYSTEM_LEVEL
SystemDialPlanPolicyGetAccessCodeRequest	SYSTEM_LEVEL
SystemDialPlanPolicyGetRequest	SYSTEM_LEVEL
SystemDialPlanPolicyGetRequest17	SYSTEM_LEVEL
SystemDialPlanPolicyModifyAccessCodeRequest	SYSTEM_LEVEL
SystemDialPlanPolicyModifyRequest	SYSTEM_LEVEL
SystemDigitCollectionGetRequest13mp4	SYSTEM_LEVEL
SystemDigitCollectionModifyRequest	SYSTEM_LEVEL
SystemDnGetSummaryListRequest	RESELLER_LEVEL
SystemDnGetUtilizationListRequest	RESELLER_LEVEL
SystemDnGetUtilizationRequest	SYSTEM_LEVEL
SystemDnGetUtilizationRequest14sp3	RESELLER_LEVEL
SystemDomainAddRequest	RESELLER_LEVEL
SystemDomainDeleteRequest	RESELLER_LEVEL
SystemDomainGetAssignedServiceProviderListRequest	RESELLER_LEVEL



Transaction	Authorization Level
SystemDomainGetListRequest	USER_LEVEL
SystemDomainGetListRequest22	USER_LEVEL
SystemDomainParametersGetRequest	USER_LEVEL
SystemDomainParametersModifyRequest	SYSTEM_LEVEL
SystemDTMFTransmissionGetRequest	SYSTEM_LEVEL
SystemDTMFTransmissionModifyRequest	SYSTEM_LEVEL
SystemEmergencyCallDDoSProtectionGetRequest	SYSTEM_LEVEL
SystemEmergencyCallDDoSProtectionModifyRequest	SYSTEM_LEVEL
SystemEmergencyCallNotificationGetRequest	SYSTEM_LEVEL
SystemEmergencyCallNotificationModifyRequest	SYSTEM_LEVEL
SystemEmergencyZonesGetRequest	SYSTEM_LEVEL
SystemEmergencyZonesModifyRequest	SYSTEM_LEVEL
SystemEndpointGetListRequest	RESELLER_LEVEL
SystemEnhancedCallLogsGetRequest	SYSTEM_LEVEL
SystemEnhancedCallLogsGetRequest17sp4	SYSTEM_LEVEL
SystemEnhancedCallLogsGetRequest20sp1	SYSTEM_LEVEL
SystemEnhancedCallLogsGetRequest22	SYSTEM_LEVEL
SystemEnhancedCallLogsModifyRequest	SYSTEM_LEVEL
SystemEnhancedCallLogsModifyRequest22	SYSTEM_LEVEL
SystemExecutiveGetRequest	SYSTEM_LEVEL
SystemExecutiveModifyRequest	SYSTEM_LEVEL
SystemExpensiveCallNotificationGetRequest	SYSTEM_LEVEL
SystemExpensiveCallNotificationModifyRequest	SYSTEM_LEVEL
SystemExpensiveCallTypeAddRequest	SYSTEM_LEVEL
SystemExpensiveCallTypeDeleteRequest	SYSTEM_LEVEL
SystemExpensiveCallTypeGetListRequest	SYSTEM_LEVEL
SystemExpensiveCallTypeGetListRequest16sp1	SYSTEM_LEVEL
SystemExpensiveCallTypeModifyRequest	SYSTEM_LEVEL
SystemExportAddressingDataRequest	SYSTEM_LEVEL
SystemExportBroadCloudDataRequest	SYSTEM_LEVEL
SystemExportSubscriberRequest	SYSTEM_LEVEL
SystemExtensionLengthGetRequest	GROUP_LEVEL
SystemExtensionLengthModifyRequest	SYSTEM_LEVEL
SystemExternalAuthenticationAddACLEntryRequest	SYSTEM_LEVEL
SystemExternalAuthenticationAddACLEntryRequest14sp2	SYSTEM_LEVEL



Transaction	Authorization Level
SystemExternalAuthenticationDeleteACLEntryRequest	SYSTEM_LEVEL
SystemExternalAuthenticationDeleteACLEntryRequest14sp2	SYSTEM_LEVEL
SystemExternalAuthenticationGetACLListRequest	SYSTEM_LEVEL
SystemExternalAuthenticationModifyACLEntryRequest	SYSTEM_LEVEL
SystemExternalAuthenticationModifyACLEntryRequest14sp2	SYSTEM_LEVEL
SystemExternalEmergencyRoutingParametersGetRequest13mp13	SYSTEM_LEVEL
SystemExternalEmergencyRoutingParametersModifyRequest13mp13	SYSTEM_LEVEL
SystemFaxMessagingGetRequest	SYSTEM_LEVEL
SystemFaxMessagingModifyRequest	SYSTEM_LEVEL
SystemFeatureAccessCodeGetListRequest	SYSTEM_LEVEL
SystemFeatureAccessCodeGetListRequest20	SYSTEM_LEVEL
SystemFeatureAccessCodeGetListRequest21	SYSTEM_LEVEL
SystemFeatureAccessCodeModifyListRequest	SYSTEM_LEVEL
SystemFeatureAccessCodeModifyListRequest20	SYSTEM_LEVEL
SystemFeatureAccessCodeModifyListRequest21	SYSTEM_LEVEL
SystemFileGetContentRequest	GROUP_LEVEL
SystemFileRepositoryDeviceAddRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceAddRequest16	SYSTEM_LEVEL
SystemFileRepositoryDeviceAddRequest20	SYSTEM_LEVEL
SystemFileRepositoryDeviceDeleteRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceGetListRequest	RESELLER_LEVEL
SystemFileRepositoryDeviceGetRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceGetRequest16	SYSTEM_LEVEL
SystemFileRepositoryDeviceGetRequest20	RESELLER_LEVEL
SystemFileRepositoryDeviceGetRequest22	SYSTEM_LEVEL
SystemFileRepositoryDeviceModifyRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceModifyRequest22	SYSTEM_LEVEL
SystemFileRepositoryDeviceUserAddRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceUserDeleteRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceUserGetListRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceUserGetRequest	SYSTEM_LEVEL
SystemFileRepositoryDeviceUserModifyRequest	SYSTEM_LEVEL
SystemGeographicRedundancyPeerSipConnectionMonitoringGetRequest	SYSTEM_LEVEL
SystemGeographicRedundancyPeerSipConnectionMonitoringModifyRequest	SYSTEM_LEVEL
SystemGeographicRedundancyProxyGetRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemGeographicRedundancyProxyModifyRequest	SYSTEM_LEVEL
SystemGeographicRedundancyUnreachableFromPrimaryGetUserListRequest	SYSTEM_LEVEL
SystemGeographicRedundancyUnreachableFromPrimaryGetUserListRequest22	SYSTEM_LEVEL
SystemGetRegistrationContactListRequest	USER_LEVEL
SystemGetRegistrationContactListRequest21sp1	USER_LEVEL
SystemGETSAvpCodeMapAddRequest	SYSTEM_LEVEL
SystemGETSAvpCodeMapDeleteRequest	SYSTEM_LEVEL
SystemGETSAvpCodeMapGetListRequest	SYSTEM_LEVEL
SystemGETSGetRequest	SYSTEM_LEVEL
SystemGETSModifyRequest	SYSTEM_LEVEL
SystemGETSNumberAddRequest	SYSTEM_LEVEL
SystemGETSNumberDeleteRequest	SYSTEM_LEVEL
SystemGETSNumberGetListRequest	SYSTEM_LEVEL
SystemGETSNumberModifyRequest	SYSTEM_LEVEL
SystemGETSReservedFeatureAccessCodeAddRequest	SYSTEM_LEVEL
SystemGETSReservedFeatureAccessCodeDeleteRequest	SYSTEM_LEVEL
SystemGETSReservedFeatureAccessCodeGetListRequest	SYSTEM_LEVEL
SystemGETSReservedFeatureAccessCodeModifyRequest	SYSTEM_LEVEL
SystemGETSResourcePriorityAddRequest	SYSTEM_LEVEL
SystemGETSResourcePriorityDeleteRequest	SYSTEM_LEVEL
SystemGETSResourcePriorityGetListRequest	SYSTEM_LEVEL
SystemGETSResourcePriorityModifyRequest	SYSTEM_LEVEL
SystemGETSSessionPriorityMapAddRequest	SYSTEM_LEVEL
SystemGETSSessionPriorityMapDeleteRequest	SYSTEM_LEVEL
SystemGETSSessionPriorityMapGetListRequest	SYSTEM_LEVEL
SystemGETSSessionPriorityMapModifyRequest	SYSTEM_LEVEL
SystemGroupNightForwardingGetRequest	SYSTEM_LEVEL
SystemGroupNightForwardingModifyRequest	SYSTEM_LEVEL
SystemHolidayScheduleAddRequest	SYSTEM_LEVEL
SystemHolidayScheduleDeleteRequest	SYSTEM_LEVEL
SystemHolidayScheduleGetListRequest	SYSTEM_LEVEL
SystemHolidayScheduleGetRequest	SYSTEM_LEVEL
SystemHolidayScheduleModifyRequest	SYSTEM_LEVEL
SystemHomeNetworkAddRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemHomeNetworkGetListRequest	SYSTEM_LEVEL
SystemHPBXAlternateCarrierSelectionAddCarrierRequest	SYSTEM_LEVEL
SystemHPBXAlternateCarrierSelectionDeleteCarrierRequest	SYSTEM_LEVEL
SystemHPBXAlternateCarrierSelectionGetCarrierListRequest	SERVICE_PROVIDER_LEVE
SystemHPBXAlternateCarrierSelectionModifyCarrierRequest	SYSTEM_LEVEL
SystemHPBXMobileTerminationGetRequest	SYSTEM_LEVEL
SystemHPBXMobileTerminationModifyRequest	SYSTEM_LEVEL
SystemHuntGroupGetRequest	SYSTEM_LEVEL
SystemHuntGroupGetRequest17	USER_LEVEL
SystemHuntGroupGetRequest21	USER_LEVEL
SystemHuntGroupModifyRequest	SYSTEM_LEVEL
SystemHuntGroupModifyRequest21	SYSTEM_LEVEL
SystemInCallServiceActivationGetRequest	SYSTEM_LEVEL
SystemInCallServiceActivationGetRequest17	SYSTEM_LEVEL
SystemInCallServiceActivationModifyRequest	SYSTEM_LEVEL
SystemInCallServiceActivationModifyRequest17	SYSTEM_LEVEL
SystemIntegratedIMPGetRequest	SYSTEM_LEVEL
SystemIntegratedIMPGetRequest19	SYSTEM_LEVEL
SystemIntegratedIMPGetRequest21	SYSTEM_LEVEL
SystemIntegratedIMPModifyRequest	SYSTEM_LEVEL
SystemInterceptUserAddDnListRequest	SYSTEM_LEVEL
SystemInterceptUserDeleteDnListRequest	SYSTEM_LEVEL
SystemInterceptUserGetDnListRequest	SYSTEM_LEVEL
SystemInterceptUserGetRequest	SYSTEM_LEVEL
SystemInterceptUserModifyDnRequest	SYSTEM_LEVEL
SystemInterceptUserModifyRequest	SYSTEM_LEVEL
SystemInventoryReportGetRequest	SYSTEM_LEVEL
SystemInventoryReportModifyRequest	SYSTEM_LEVEL
SystemLanguageAddRequest	SYSTEM_LEVEL
SystemLanguageDeleteRequest	SYSTEM_LEVEL
SystemLanguageGetListRequest	USER_LEVEL
SystemLanguageModifyRequest	SYSTEM_LEVEL
SystemLegacyAutomaticCallbackGetLineTypeListRequest	SYSTEM_LEVEL
SystemLegacyAutomaticCallbackGetRequest	SYSTEM_LEVEL
SystemLegacyAutomaticCallbackModifyLineTypeRequest	SYSTEM_LEVEL



SystemLicensingGetRequest System_LicveL SystemLicensingGetRequest14sp3 System_LicveL SystemLicensingGetRequest14sp3 System_LicveL SystemLicensingGetSystemLicenseListRequest System_LicveL SystemLicensingGetSystemLicenseListRequest21 System_LicveL SystemLicensingGetSystemLicenseListRequest21 System_LicveL SystemLicensingGetSystemLicenseListRequest21sp1 System_LicveL SystemLicensingGetSystemLicenseListRequest22 System_LicveL SystemLicensingGetSystemLicenseListRequest22 System_LicveL SystemLicensingReloadRequest System_LicveL SystemLocationBasedCallingRestrictionsGetRequest System_LicveL SystemLocationBasedCallingRestrictionsGetRequest System_LicveL SystemLocationBasedCallingRestrictionsModifyRequest System_LicveL SystemMailParametersGetRequest2 SystemMailParametersGetRequest2 SystemMailParametersGetRequest2 SystemMailParametersGetRequest2 SystemMailParametersGetRequest3 System_LicveL SystemMailciousCallTraceGetRequest System_LicveL SystemMailciousCallTraceGetRequest System_LicveL SystemMailciousCallTraceGetRequest System_LicveL SystemMediaAddRequest System_Licv	Transaction	Authorization Level
SystemLicensingGetRequest14sp3 SystemLicensingGetSystemLicenseListRequest SystemLicensingGetSystemLicenseListRequest19sp1 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingReloadRequest SystemMediaGetListRequest SystemMediaAdRequest SystemLicensingReloadRequest SystemMediaAdRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecOdedMedifyRequest SystemMediaGroupCodecOdetListRequest SystemMediaGroupCodecOdetListRequest SystemMediaGroupCodecOdetListRequest SystemMediaGroupCodecOdetListRequest SystemMediaGroupCodecOdetListRequest SystemMediaGroupCodecOdetListRequest SystemLicent	SystemLegacyAutomaticCallbackModifyRequest	SYSTEM_LEVEL
SystemLicensingGetSystemLicenseListRequest SystemLicensingGetSystemLicenseListRequest19sp1 SySTEM_LEVEL SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingReloadRequest SystemMailFarametersGetRequest SystemMailFarametersGetRequest SystemMailFarametersGetRequest SystemMailFarametersGetRequest SystemMailciousCallTraceGetRequest SystemMailciousCallTraceGetRequest SystemMediaCousCallTraceGetRequest SystemMediaAddRequest SystemMediaAddRequest SystemLicensingReloadRelo	SystemLicensingGetRequest	SYSTEM_LEVEL
SystemLicensingGetSystemLicenseListRequest19sp1 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLocationBasedCallingRestrictionsGetRequest17sp3 SystemLocationBasedCallingRestrictionsModifyRequest SystemLocationBasedCallingRestrictionsModifyRequest SystemLeveL SystemMailParametersGetRequest System_LeveL SystemMailParametersGetRequest System_LeveL SystemMailParametersGetRequest System_LeveL SystemMailParametersModifyRequest System_LeveL SystemMailciousCallTraceGetRequest System_LeveL SystemMailciousCallTraceGetUserListRequest System_LeveL SystemMailciousCallTraceGetUserListRequest System_LeveL SystemMediaAddRequest System_LeveL SystemMediaAddRequest System_LeveL SystemMediaAddRequest System_LeveL SystemMediaGetListRequest System_LeveL SystemMediaGroupCodecAddRequest System_LeveL SystemMediaGroupCodecAddRequest System_LeveL SystemMediaGroupCodecAddRequest System_LeveL SystemMediaGroupCodecGetListRequest System_LeveL SystemMediaGroupCodecGetListRequest System_LeveL SystemMediaGroupCodecGetListRequest System_LeveL SystemMediaGroupCodecModifyRequest System_LeveL SystemMediaGroupCodecReduest14 System_LeveL SystemMediaServerDeleteRequest System_LeveL System_LeveL	SystemLicensingGetRequest14sp3	SYSTEM_LEVEL
SystemLicensingGetSystemLicenseListRequest21 SystemLicensingGetSystemLicenseListRequest21sp1 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLocationBasedCallingRestrictionsGetRequest SystemLocationBasedCallingRestrictionsGetRequest SystemLocationBasedCallingRestrictionsModifyRequest SystemLocationBasedCallingRestrictionsModifyRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersModifyRequest SystemMailParametersModifyRequest SystemMailCousCallTraceGetRequest SystemMailcousCallTraceGetUserListRequest SystemMaliciousCallTraceGetUserListRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemLicensingGetSystemLicenseListRequest	SYSTEM_LEVEL
SystemLicensingGetSystemLicenseListRequest21sp1 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingGetSystemLicenseListRequest22 SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLocationBasedCallingRestrictionsGetRequest17sp3 SystemLeveL SystemLocationBasedCallingRestrictionsGetRequest17sp3 SystemLeveL SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest2 SystemMailParametersModifyRequest SystemMailParametersModifyRequest SystemMailciousCallTraceGetRequest SystemMailciousCallTraceGetQuest SystemMailciousCallTraceGetUserListRequest SystemMailciousCallTraceGetUserListRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupDeletRequest SystemMediaGeroupDeletRequest SystemM	SystemLicensingGetSystemLicenseListRequest19sp1	SYSTEM_LEVEL
SystemLicensingGetSystemLicenseListRequest22 SystemLicensingReloadRequest SystemLicensingReloadRequest SystemLocationBasedCallingRestrictionsGetRequest SystemLocationBasedCallingRestrictionsGetRequest17sp3 SystemLocationBasedCallingRestrictionsModifyRequest SystemLocationBasedCallingRestrictionsModifyRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersModifyRequest SystemMailiParametersModifyRequest SystemMailiciousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeteRequest SystemMediaGeroupDeteRequest SystemMediaGeroupDeteR	SystemLicensingGetSystemLicenseListRequest21	SYSTEM_LEVEL
SystemLicensingReloadRequest SystemLocationBasedCallingRestrictionsGetRequest SystemLocationBasedCallingRestrictionsGetRequest SystemLocationBasedCallingRestrictionsGetRequest17sp3 System_LeveL SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest2 SystemMailParametersGetRequest2 SystemMailParametersModifyRequest SystemMailParametersModifyRequest SystemMailCousCallTraceGetRequest SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGeroupDeleteRequest SystemMediaGeroupDeleteReq	SystemLicensingGetSystemLicenseListRequest21sp1	SYSTEM_LEVEL
SystemLocationBasedCallingRestrictionsGetRequest SystemLocationBasedCallingRestrictionsGetRequest17sp3 SystemLocationBasedCallingRestrictionsGetRequest17sp3 System_LeveL SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersGetRequest SystemMailParametersModifyRequest SystemMailParametersModifyRequest SystemMailCousCallTraceGetRequest SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGererPeleteRequest SystemMediaGererPeleteRequest SystemMediaGererPeleteRequest SystemMediaGererPeleteRequest SystemMediaGererPeleteRequest SystemMediaGererPeleteRequest SystemMediaGererPeleteRequest SystemMediaGererPeleteRequest	SystemLicensingGetSystemLicenseListRequest22	SYSTEM_LEVEL
SystemLocationBasedCallingRestrictionsGetRequest17sp3 SYSTEM_LEVEL SystemLocationBasedCallingRestrictionsModifyRequest SystemLevel SystemMailParametersGetRequest SystemMailParametersGetRequest22 SystemMailParametersModifyRequest SystemMailParametersModifyRequest SystemMailCiousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupGetListRequest SystemMediaGetListRequest	SystemLicensingReloadRequest	SYSTEM_LEVEL
SystemLocationBasedCallingRestrictionsModifyRequest System_LeVeL SystemMailParametersGetRequest SystemMailParametersGetRequest2 SystemMailParametersGetRequest2 SystemMailParametersModifyRequest SystemMailCousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupGetListRequest SystemMediaGetListRequest SystemMediaGetListReq	SystemLocationBasedCallingRestrictionsGetRequest	SYSTEM_LEVEL
SystemMailParametersGetRequest SystemMailParametersGetRequest22 SystemMailParametersGetRequest22 SystemMaliParametersModifyRequest SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupGetListRequest SystemMediaGroupUsageListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupUsageListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGetListRequest SystemMediaGetLi	SystemLocationBasedCallingRestrictionsGetRequest17sp3	SYSTEM_LEVEL
SystemMailParametersGetRequest22 SystemMailParametersModifyRequest SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGeroupUsageListRequest SystemMediaGeroupUsageListRequest SystemMediaGeroupUsageListRequest SystemMediaGeroupLeveL SystemMediaGeroupLeveLeveL SystemMediaGeroupLeveLeveL SystemMediaGeroupCedLeteRequest SystemLeveL SystemMediaGeroupCedLeteRequest Sys	SystemLocationBasedCallingRestrictionsModifyRequest	SYSTEM_LEVEL
SystemMailParametersModifyRequest SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecCetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCetListRequest SystemMediaGroupGetListRequest SystemMediaGroupDeleteRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGeroupUsageListRequest	SystemMailParametersGetRequest	SYSTEM_LEVEL
SystemMaliciousCallTraceGetRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest16 SystemMediaDeleteRequest SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGeroupCedetRequest Sys	SystemMailParametersGetRequest22	SYSTEM_LEVEL
SystemMaliciousCallTraceGetUserListRequest SystemMaliciousCallTraceGetUserListRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest16 SystemMediaDeleteRequest SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGetListRequest SystemMediaGetListR	SystemMailParametersModifyRequest	SYSTEM_LEVEL
SystemMaliciousCallTraceModifyRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaAddRequest SystemMediaDeleteRequest SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGerverAddRequest14 SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemLeveL	SystemMaliciousCallTraceGetRequest	SYSTEM_LEVEL
SystemMediaAddRequest SYSTEM_LEVEL SystemMediaAddRequest16 SYSTEM_LEVEL SystemMediaDeleteRequest SYSTEM_LEVEL SystemMediaGetListRequest SYSTEM_LEVEL SystemMediaGroupAddRequest SYSTEM_LEVEL SystemMediaGroupCodecAddRequest SYSTEM_LEVEL SystemMediaGroupCodecDeleteRequest SYSTEM_LEVEL SystemMediaGroupCodecGetListRequest SYSTEM_LEVEL SystemMediaGroupCodecGetListRequest SYSTEM_LEVEL SystemMediaGroupCodecModifyRequest SYSTEM_LEVEL SystemMediaGroupDeleteRequest SYSTEM_LEVEL SystemMediaGroupDeleteRequest SYSTEM_LEVEL SystemMediaGroupGetListRequest GROUP_LEVEL SystemMediaGroupModifyRequest SYSTEM_LEVEL SystemMediaGroupUsageListRequest SYSTEM_LEVEL SystemMediaGroupUsageListRequest SYSTEM_LEVEL SystemMediaGroupUsageListRequest SYSTEM_LEVEL SystemMediaServerAddRequest14 SYSTEM_LEVEL SystemMediaServerAddRequest14 SYSTEM_LEVEL	SystemMaliciousCallTraceGetUserListRequest	SYSTEM_LEVEL
SystemMediaAddRequest16 SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupAddRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupGetListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRe	SystemMaliciousCallTraceModifyRequest	SYSTEM_LEVEL
SystemMediaDeleteRequest SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGetVerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaAddRequest	SYSTEM_LEVEL
SystemMediaGetListRequest SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupModifyRequest SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGetVerAddRequest14 SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaAddRequest16	SYSTEM_LEVEL
SystemMediaGroupAddRequest SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupModifyRequest SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaModifyRequest SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaDeleteRequest	SYSTEM_LEVEL
SystemMediaGroupCodecAddRequest SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupGetListRequest SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGerverAddRequest14 SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaGetListRequest	SYSTEM_LEVEL
SystemMediaGroupCodecDeleteRequest SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupModifyRequest SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGetVerAddRequest14 SystemMediaGetVerAddRequest14 SystemMediaGetVerDeleteRequest SystemMediaGetVerDeleteRequest SystemMediaGetVerDeleteRequest	SystemMediaGroupAddRequest	SYSTEM_LEVEL
SystemMediaGroupCodecGetListRequest SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupModifyRequest SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaGroupCodecAddRequest	SYSTEM_LEVEL
SystemMediaGroupCodecModifyRequest SystemMediaGroupDeleteRequest SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupModifyRequest SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaGroupUsageListRequest	SystemMediaGroupCodecDeleteRequest	SYSTEM_LEVEL
SystemMediaGroupDeleteRequest SystemMediaGroupGetListRequest SystemMediaGroupModifyRequest SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaModifyRequest SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaGroupCodecGetListRequest	SYSTEM_LEVEL
SystemMediaGroupGetListRequest GROUP_LEVEL SystemMediaGroupModifyRequest SYSTEM_LEVEL SystemMediaGroupUsageListRequest SYSTEM_LEVEL SystemMediaModifyRequest SYSTEM_LEVEL SystemMediaServerAddRequest14 SYSTEM_LEVEL SystemMediaServerDeleteRequest SYSTEM_LEVEL	SystemMediaGroupCodecModifyRequest	SYSTEM_LEVEL
SystemMediaGroupModifyRequest SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaModifyRequest SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaGroupDeleteRequest	SYSTEM_LEVEL
SystemMediaGroupUsageListRequest SystemMediaModifyRequest SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaGroupGetListRequest	GROUP_LEVEL
SystemMediaModifyRequest SystemMediaServerAddRequest14 SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest SystemMediaServerDeleteRequest	SystemMediaGroupModifyRequest	SYSTEM_LEVEL
SystemMediaServerAddRequest14 SYSTEM_LEVEL SystemMediaServerDeleteRequest SYSTEM_LEVEL	SystemMediaGroupUsageListRequest	SYSTEM_LEVEL
SystemMediaServerDeleteRequest SYSTEM_LEVEL	SystemMediaModifyRequest	SYSTEM_LEVEL
	SystemMediaServerAddRequest14	SYSTEM_LEVEL
SystemMediaServerGetListRequest SYSTEM_LEVEL	SystemMediaServerDeleteRequest	SYSTEM_LEVEL
	SystemMediaServerGetListRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemMediaServerModifyRequest	SYSTEM_LEVEL
SystemMediaServerParametersGetRequest	SYSTEM_LEVEL
SystemMediaServerParametersModifyRequest	SYSTEM_LEVEL
SystemMediaSetAddRequest	SYSTEM_LEVEL
SystemMediaSetDeleteRequest	SYSTEM_LEVEL
SystemMediaSetGetListRequest	SERVICE_PROVIDER_LEVEL
SystemMediaSetGetRequest	SYSTEM_LEVEL
SystemMediaSetModifyRequest	SYSTEM_LEVEL
SystemMeetMeConferencingGetRequest	SYSTEM_LEVEL
SystemMeetMeConferencingGetRequest17sp3	SYSTEM_LEVEL
SystemMeetMeConferencingGetRequest18	USER_LEVEL
SystemMeetMeConferencingGetRequest19	USER_LEVEL
SystemMeetMeConferencingModifyRequest	SYSTEM_LEVEL
SystemMGCPDeviceTypeGetListRequest	SYSTEM_LEVEL
SystemMGCPDeviceTypeGetRequest	SYSTEM_LEVEL
SystemMGCPDeviceTypeModifyRequest	SYSTEM_LEVEL
SystemMigratedUsersGetListRequest	SYSTEM_LEVEL
SystemMigratedUsersGetListRequest22	SYSTEM_LEVEL
SystemMultimediaPolicyGetRequest	SYSTEM_LEVEL
SystemMultimediaPolicyModifyRequest	SYSTEM_LEVEL
SystemMusicOnHoldGetRequest	SYSTEM_LEVEL
SystemMusicOnHoldModifyRequest	SYSTEM_LEVEL
SystemNetworkClassOfServiceAddRequest	SYSTEM_LEVEL
SystemNetworkClassOfServiceDeleteRequest	SYSTEM_LEVEL
System Network Class Of Service Get Assigned Service Provider List Request	SYSTEM_LEVEL
System Network Class Of Service Get Communication Barring Profile Usage List Request	SYSTEM_LEVEL
SystemNetworkClassOfServiceGetListRequest	SYSTEM_LEVEL
SystemNetworkClassOfServiceGetRequest	SYSTEM_LEVEL
SystemNetworkClassOfServiceGetRequest17	SYSTEM_LEVEL
SystemNetworkClassOfServiceGetRequest19sp1	SYSTEM_LEVEL
SystemNetworkClassOfServiceModifyRequest	SYSTEM_LEVEL
SystemNetworkDeviceMonitorParametersGetRequest	SYSTEM_LEVEL
SystemNetworkDeviceMonitorParametersModifyRequest	SYSTEM_LEVEL
SystemNetworkProgressionGetRequest	SYSTEM_LEVEL
SystemNetworkProgressionModifyRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemNetworkRoutingServerAddRequest	SYSTEM_LEVEL
SystemNetworkRoutingServerDeleteRequest	SYSTEM_LEVEL
SystemNetworkRoutingServerGetListRequest	SYSTEM_LEVEL
SystemNetworkRoutingServerModifyRequest	SYSTEM_LEVEL
SystemNetworkServerSyncParametersGetRequest	SYSTEM_LEVEL
SystemNetworkServerSyncParametersGetRequest14sp2	PROVISIONING_LEVEL
SystemNetworkServerSyncParametersGetRequest16	PROVISIONING_LEVEL
SystemNetworkServerSyncParametersGetRequest17sp4	RESELLER_LEVEL
SystemNetworkServerSyncParametersModifyRequest	SYSTEM_LEVEL
SystemNetworkSynchingServerAddRequest	SYSTEM_LEVEL
SystemNetworkSynchingServerAddRequest22	SYSTEM_LEVEL
SystemNetworkSynchingServerAddRequest22V2	SYSTEM_LEVEL
SystemNetworkSynchingServerDeleteRequest	SYSTEM_LEVEL
SystemNetworkSynchingServerGetListRequest	SYSTEM_LEVEL
SystemNetworkSynchingServerModifyRequest	SYSTEM_LEVEL
SystemNetworkSynchingServerModifyRequest22	SYSTEM_LEVEL
SystemNumberActivationGetRequest	USER_LEVEL
SystemNumberActivationGetRequest18sp1	USER_LEVEL
SystemNumberActivationGetRequest21	USER_LEVEL
SystemNumberActivationModifyRequest	SYSTEM_LEVEL
SystemNumberActivationModifyRequest18sp1	SYSTEM_LEVEL
SystemNumberPortabilityQueryDigitPatternAddRequest	SYSTEM_LEVEL
System Number Portability Query Digit Pattern Delete List Request	SYSTEM_LEVEL
SystemNumberPortabilityQueryDigitPatternGetListRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryDigitPatternGetRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryDigitPatternModifyRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryGetRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryModifyRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryStatusAddRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryStatusDeleteListRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryStatusGetListRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryStatusGetRequest	SYSTEM_LEVEL
SystemNumberPortabilityQueryStatusModifyRequest	SYSTEM_LEVEL
SystemOCIAddACLEntryRequest	SYSTEM_LEVEL
SystemOCICallControlAddACLEntryRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemOCICallControlApplicationAddACLEntryRequest	SYSTEM_LEVEL
SystemOCICallControlApplicationAddRequest	SYSTEM_LEVEL
SystemOCICallControlApplicationAddRequest14sp9	SYSTEM_LEVEL
SystemOCICallControlApplicationAddRequest17	SYSTEM_LEVEL
SystemOCICallControlApplicationAddRequest22	SYSTEM_LEVEL
SystemOCICallControlApplicationDeleteACLEntryRequest	SYSTEM_LEVEL
SystemOClCallControlApplicationDeleteRequest	SYSTEM_LEVEL
SystemOCICallControlApplicationGetACLListRequest	SYSTEM_LEVEL
SystemOCICallControlApplicationGetListRequest	USER_LEVEL
SystemOClCallControlApplicationModifyACLEntryRequest	SYSTEM_LEVEL
SystemOCICallControlApplicationModifyRequest	SYSTEM_LEVEL
SystemOCICallControlDeleteACLEntryRequest	SYSTEM_LEVEL
SystemOClCallControlGetACLListRequest	SYSTEM_LEVEL
SystemOClCallControlModifyACLEntryRequest	SYSTEM_LEVEL
SystemOCIDeleteACLEntryRequest	SYSTEM_LEVEL
SystemOCIGetACLListRequest	SYSTEM_LEVEL
SystemOCIModifyACLEntryRequest	SYSTEM_LEVEL
SystemOCIReportingAddACLEntryRequest13mp9	SYSTEM_LEVEL
SystemOCIReportingAddMessageNameListRequest	SYSTEM_LEVEL
SystemOCIReportingDeleteACLEntryRequest	SYSTEM_LEVEL
SystemOCIReportingDeleteMessageNameListRequest	SYSTEM_LEVEL
SystemOCIReportingGetACLListRequest	SYSTEM_LEVEL
SystemOCIReportingGetMessageNameListRequest	SYSTEM_LEVEL
SystemOCIReportingModifyACLEntryRequest	SYSTEM_LEVEL
SystemOCIReportingParametersGetRequest	SYSTEM_LEVEL
SystemOCIReportingParametersGetRequest22	SYSTEM_LEVEL
SystemOCIReportingParametersModifyRequest	SYSTEM_LEVEL
SystemOfficeZoneAddRequest	SYSTEM_LEVEL
SystemOfficeZoneDeleteRequest	SYSTEM_LEVEL
SystemOfficeZoneGetAssignedServiceProviderListRequest	SYSTEM_LEVEL
SystemOfficeZoneGetListRequest	SYSTEM_LEVEL
SystemOfficeZoneGetRequest	GROUP_LEVEL
SystemOfficeZoneGetZoneUsageListRequest	SYSTEM_LEVEL
SystemOfficeZoneModifyRequest	SYSTEM_LEVEL
SystemOutgoingCallingPlanCallTypeAddMappingRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemOutgoingCallingPlanCallTypeDeleteMappingRequest	SYSTEM_LEVEL
SystemOutgoingCallingPlanCallTypeGetListRequest	SYSTEM_LEVEL
SystemOutgoingCallingPlanCallTypeGetMappingListRequest	SYSTEM_LEVEL
SystemOutgoingCallingPlanGetRequest	USER_LEVEL
SystemOutgoingCallingPlanGetRequest17sp3	USER_LEVEL
SystemOutgoingCallingPlanModifyRequest	SYSTEM_LEVEL
SystemPasswordRulesGetRequest13mp2	USER_LEVEL
SystemPasswordRulesGetRequest16	USER_LEVEL
SystemPasswordRulesGetRequest22	USER_LEVEL
SystemPasswordRulesModifyRequest	SYSTEM_LEVEL
SystemPasswordRulesModifyRequest14sp3	SYSTEM_LEVEL
SystemPasswordSecurityParametersGetRequest	SYSTEM_LEVEL
SystemPasswordSecurityParametersModifyRequest	SYSTEM_LEVEL
SystemPerformanceMeasurementGenerateReportRequest	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingAddFileServerRequest	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingAddFileServerRequest22	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingDeleteFileServerRequest	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingDeleteFileServerRequest22	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingGetFileServerListRequest	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingGetFileServerListRequest22	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingGetRequest	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingGetRequest22	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingModifyFileServerRequest	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingModifyFileServerRequest22	SYSTEM_LEVEL
SystemPerformanceMeasurementReportingModifyRequest	SYSTEM_LEVEL
SystemPersonalAssistantGetRequest	SYSTEM_LEVEL
SystemPersonalAssistantModifyRequest	SYSTEM_LEVEL
SystemPhysicalLocationGetRequest	SYSTEM_LEVEL
SystemPhysicalLocationModifyRequest	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest14	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest14sp1	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest14sp4	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest16sp1	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest16sp2	SYSTEM LEVEL
-,	STSTEW_EEVEE



Transaction	Authorization Level
SystemPolicyGetDefaultRequest17sp1	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest17sp3	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest18	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest19sp1	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest20	SYSTEM_LEVEL
SystemPolicyGetDefaultRequest22	SYSTEM_LEVEL
SystemPolicyModifyDefaultRequest14	SYSTEM_LEVEL
SystemPolicyModifyDefaultRequest22	SYSTEM_LEVEL
SystemPortalPasscodeRulesGetRequest	SYSTEM_LEVEL
SystemPortalPasscodeRulesGetRequest19	SYSTEM_LEVEL
SystemPortalPasscodeRulesModifyRequest	SYSTEM_LEVEL
SystemPreferredCarrierAddRequest	PROVISIONING_LEVEL
SystemPreferredCarrierDeleteRequest	PROVISIONING_LEVEL
SystemPreferredCarrierGetGroupListRequest	PROVISIONING_LEVEL
SystemPreferredCarrierGetListRequest	USER_LEVEL
SystemPreferredCarrierGetRequest	PROVISIONING_LEVEL
SystemPreferredCarrierGetUserListRequest	SYSTEM_LEVEL
SystemPreferredCarrierModifyRequest	SYSTEM_LEVEL
SystemProvisioningValidationGetRequest	SYSTEM_LEVEL
SystemProvisioningValidationGetRequest14sp2	SYSTEM_LEVEL
SystemProvisioningValidationGetRequest22	SYSTEM_LEVEL
SystemProvisioningValidationModifyRequest	SYSTEM_LEVEL
SystemPushNotificationAllowedApplicationAddRequest	SYSTEM_LEVEL
SystemPushNotificationAllowedApplicationDeleteRequest	SYSTEM_LEVEL
SystemPushNotificationAllowedApplicationGetListRequest	SYSTEM_LEVEL
SystemPushNotificationAllowedApplicationModifyRequest	SYSTEM_LEVEL
SystemPushNotificationParametersGetRequest	SYSTEM_LEVEL
SystemPushNotificationParametersModifyRequest	SYSTEM_LEVEL
SystemRedundancyParametersGetRequest	SYSTEM_LEVEL
SystemRedundancyParametersGetRequest16sp2	SYSTEM_LEVEL
SystemRedundancyParametersModifyRequest	SYSTEM_LEVEL
SystemResourcePriorityGetRequest	SYSTEM_LEVEL
SystemResourcePriorityModifyRequest	SYSTEM_LEVEL
SystemRoamingNetworkAddRequest	SYSTEM_LEVEL
SystemRoamingNetworkDeleteRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemRoamingNetworkGetListRequest	SYSTEM_LEVEL
SystemRoamingNetworkModifyRequest	SYSTEM_LEVEL
SystemRouteListEnterpriseTrunkNumberPrefixGetSummaryListRequest	RESELLER_LEVEL
SystemRouteListEnterpriseTrunkNumberRangeGetSummaryListRequest	RESELLER_LEVEL
SystemRoutePointExternalSystemAddRequest	PROVISIONING_LEVEL
SystemRoutePointExternalSystemApplicationControllerAddListRequest	PROVISIONING_LEVEL
SystemRoutePointExternalSystemApplicationControllerDeleteListRequest	PROVISIONING_LEVEL
SystemRoutePointExternalSystemApplicationControllerGetRequest	PROVISIONING_LEVEL
SystemRoutePointExternalSystemDeleteRequest	PROVISIONING_LEVEL
SystemRoutePointExternalSystemGetListRequest	RESELLER_LEVEL
SystemRoutePointExternalSystemGetRoutePointListRequest	PROVISIONING_LEVEL
SystemRoutePointExternalSystemModifyRequest	PROVISIONING_LEVEL
SystemRoutingAddRouteDeviceRequest14	SYSTEM_LEVEL
SystemRoutingAddRouteRequest	SYSTEM_LEVEL
SystemRoutingAddTranslationRequest	SYSTEM_LEVEL
SystemRoutingDeleteRouteDeviceRequest	SYSTEM_LEVEL
SystemRoutingDeleteRouteRequest	SYSTEM_LEVEL
SystemRoutingDeleteTranslationRequest	SYSTEM_LEVEL
SystemRoutingGetRequest	SYSTEM_LEVEL
SystemRoutingGetRouteDeviceListRequest	SYSTEM_LEVEL
SystemRoutingGetRouteListRequest	SYSTEM_LEVEL
SystemRoutingGetTranslationListRequest	SYSTEM_LEVEL
SystemRoutingModifyRequest	SYSTEM_LEVEL
SystemRoutingModifyRouteDeviceRequest	SYSTEM_LEVEL
SystemRoutingModifyTranslationRequest	SYSTEM_LEVEL
SystemRoutingProfileGetListRequest	RESELLER_LEVEL
SystemRuntimeDataPublicationGetRequest	SYSTEM_LEVEL
SystemRuntimeDataPublicationModifyRequest	SYSTEM_LEVEL
SystemScheduleAddEventRequest	SYSTEM_LEVEL
SystemScheduleAddRequest	SYSTEM_LEVEL
SystemScheduleDeleteEventListRequest	SYSTEM_LEVEL
SystemScheduleDeleteListRequest	SYSTEM_LEVEL
SystemScheduleGetEventListRequest	SYSTEM_LEVEL
SystemScheduleGetEventRequest	SYSTEM_LEVEL
SystemScheduleGetListRequest	SYSTEM LEVEL



Transaction	Authorization Level
SystemScheduleModifyEventRequest	SYSTEM_LEVEL
SystemScheduleModifyRequest	SYSTEM_LEVEL
SystemSecurityClassificationAddClassificationRequest	SYSTEM_LEVEL
SystemSecurityClassificationDeleteClassificationRequest	SYSTEM_LEVEL
SystemSecurityClassificationGetClassificationRequest	SYSTEM_LEVEL
SystemSecurityClassificationGetClassificationTrunkGroupUsageListRequest	SYSTEM_LEVEL
SystemSecurityClassificationGetClassificationUserUsageListRequest	SYSTEM_LEVEL
SystemSecurityClassificationGetRequest	GROUP_LEVEL
SystemSecurityClassificationGetRequest21	GROUP_LEVEL
SystemSecurityClassificationModifyClassificationRequest	SYSTEM_LEVEL
SystemSecurityClassificationModifyRequest	SYSTEM_LEVEL
SystemSelectiveServicesGetRequest	SYSTEM_LEVEL
SystemSelectiveServicesGetRequest18sp1	SYSTEM_LEVEL
SystemSelectiveServicesGetRequest22	SYSTEM_LEVEL
SystemSelectiveServicesModifyRequest	SYSTEM_LEVEL
SystemServerAddressesGetRequest	SYSTEM_LEVEL
SystemServerAddressesModifyRequest	SYSTEM_LEVEL
SystemServiceActivationAccessCodeGetRequest	SYSTEM_LEVEL
SystemServiceActivationAccessCodeModifyRequest	SYSTEM_LEVEL
SystemServiceAttributeDefaultGetListRequest	SYSTEM_LEVEL
SystemServiceAttributeDefaultModifyListRequest	SYSTEM_LEVEL
SystemServiceCodeAddRequest	SYSTEM_LEVEL
SystemServiceCodeDeleteRequest	SYSTEM_LEVEL
SystemServiceCodeGetListRequest	SYSTEM_LEVEL
SystemServiceCodeModifyRequest	SYSTEM_LEVEL
SystemServicePackMigrationGetRequest	SYSTEM_LEVEL
SystemServicePackMigrationModifyRequest	SYSTEM_LEVEL
SystemServicePhoneNumberLookupRequest	PROVISIONING_LEVEL
SystemSessionAdmissionControlGetRequest	SYSTEM_LEVEL
SystemSessionAdmissionControlGetRequest21sp1	SYSTEM_LEVEL
SystemSessionAdmissionControlGetRequest22	SYSTEM_LEVEL
SystemSessionAdmissionControlModifyRequest	SYSTEM_LEVEL
SystemSessionAuditGetRequest	SYSTEM_LEVEL
SystemSessionAuditGetRequest14sp3	SYSTEM_LEVEL



Transaction	Authorization Level
SystemSessionAuditGetRequest23	SYSTEM_LEVEL
SystemSessionAuditModifyRequest	SYSTEM_LEVEL
SystemSessionAuditModifyRequest14sp3	SYSTEM_LEVEL
SystemShInterfaceParametersGetRequest	SYSTEM_LEVEL
SystemShInterfaceParametersGetRequest17	SYSTEM_LEVEL
SystemShInterfaceParametersModifyRequest	SYSTEM_LEVEL
SystemShInterfaceParametersModifyRequest17	SYSTEM_LEVEL
SystemShInterfaceRefreshTaskGetRequest	SYSTEM_LEVEL
SystemShInterfaceRefreshTaskStartRequest	SYSTEM_LEVEL
SystemShInterfaceRefreshTaskTerminateRequest	SYSTEM_LEVEL
SystemSIPAddACLEntryRequest14	SYSTEM_LEVEL
SystemSIPAddACLEntryRequest14sp2	SYSTEM_LEVEL
SystemSIPAddContentTypeRequest	SYSTEM_LEVEL
SystemSIPAuthenticationEndpointLockoutClearRequest	SYSTEM_LEVEL
SystemSIPAuthenticationEndpointLockoutGetRequest	SYSTEM_LEVEL
SystemSIPAuthenticationLockoutClearAllRequest	SYSTEM_LEVEL
SystemSIPAuthenticationPasswordRulesGetRequest	GROUP_LEVEL
SystemSIPAuthenticationPasswordRulesModifyRequest	SYSTEM_LEVEL
SystemSIPAuthenticationTrunkGroupLockoutClearRequest	SYSTEM_LEVEL
SystemSIPAuthenticationTrunkGroupLockoutGetRequest	SYSTEM_LEVEL
SystemSIPDeleteACLEntryRequest	SYSTEM_LEVEL
SystemSIPDeleteACLEntryRequest14sp2	SYSTEM_LEVEL
SystemSIPDeleteContentTypeRequest	SYSTEM_LEVEL
SystemSIPDeviceFileApplyExtendedCaptureToAllDeviceProfilesRequest	RESELLER_LEVEL
SystemSIPDeviceTypeAddRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest14sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest14sp2	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest14sp3	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest14sp6	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest15	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest16	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest16sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest17	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest17sp4	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest18	SYSTEM LEVEL



Transaction	Authorization Level
SystemSIPDeviceTypeAddRequest18sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest18sp1V2	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest19	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest19sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest20	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest20sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest21	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest21sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest21sp1V2	SYSTEM_LEVEL
SystemSIPDeviceTypeAddRequest22	RESELLER_LEVEL
SystemSIPDeviceTypeAddRequest22V2	RESELLER_LEVEL
SystemSIPDeviceTypeAddRequest22V3	RESELLER_LEVEL
SystemSIPDeviceTypeAddRequest22V4	RESELLER_LEVEL
SystemSIPDeviceTypeAddRequest23	RESELLER_LEVEL
SystemSIPDeviceTypeDeleteRequest	RESELLER_LEVEL
SystemSIPDeviceTypeFileAddRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeFileAddRequest14sp8	SYSTEM_LEVEL
SystemSIPDeviceTypeFileAddRequest16sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeFileAddRequest18	SYSTEM_LEVEL
SystemSIPDeviceTypeFileAddRequest19	SYSTEM_LEVEL
SystemSIPDeviceTypeFileAddRequest20	SYSTEM_LEVEL
SystemSIPDeviceTypeFileAddRequest21sp1	RESELLER_LEVEL
SystemSIPDeviceTypeFileDeleteRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeFileDeleteRequest14sp8	RESELLER_LEVEL
SystemSIPDeviceTypeFileGetListRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeFileGetListRequest14sp8	RESELLER_LEVEL
SystemSIPDeviceTypeFileGetRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeFileGetRequest14sp8	SYSTEM_LEVEL
SystemSIPDeviceTypeFileGetRequest16sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeFileGetRequest18	SYSTEM_LEVEL
SystemSIPDeviceTypeFileGetRequest19	SYSTEM_LEVEL
SystemSIPDeviceTypeFileGetRequest20	GROUP_LEVEL
SystemSIPDeviceTypeFileGetRequest21sp1	GROUP_LEVEL
SystemSIPDeviceTypeFileModifyRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeFileModifyRequest14sp8	SYSTEM_LEVEL



Transaction	Authorization Level
SystemSIPDeviceTypeFileModifyRequest16sp1	RESELLER_LEVEL
SystemSIPDeviceTypeGetListRequest	RESELLER_LEVEL
SystemSIPDeviceTypeGetRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest14sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest14sp2	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest14sp3	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest14sp6	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest15	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest16	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest16sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest17	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest17sp4	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest18	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest18sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest18sp1V2	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest19	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest19sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest20	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest20sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest21	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest21sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest21sp1V2	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest22	SYSTEM_LEVEL
SystemSIPDeviceTypeGetRequest22V2	RESELLER_LEVEL
SystemSIPDeviceTypeGetRequest22V3	RESELLER_LEVEL
SystemSIPDeviceTypeGetRequest22V4	RESELLER_LEVEL
SystemSIPDeviceTypeGetRequest22V5	RESELLER_LEVEL
SystemSIPDeviceTypeGetRequest23	RESELLER_LEVEL
SystemSIPDeviceTypeLanguageMappingGetListRequest	RESELLER_LEVEL
SystemSIPDeviceTypeLanguageMappingModifyRequest	RESELLER_LEVEL
SystemSIPDeviceTypeModifyRequest	SYSTEM_LEVEL
SystemSIPDeviceTypeModifyRequest14sp2	SYSTEM_LEVEL
SystemSIPDeviceTypeModifyRequest15	SYSTEM_LEVEL
SystemSIPDeviceTypeModifyRequest16	SYSTEM_LEVEL
SystemSIPDeviceTypeModifyRequest16sp1	SYSTEM_LEVEL



Transaction	Authorization Level
SystemSIPDeviceTypeModifyRequest17	SYSTEM_LEVEL
SystemSIPDeviceTypeModifyRequest18sp1	SYSTEM_LEVEL
SystemSIPDeviceTypeModifyRequest21	SYSTEM_LEVEL
SystemSIPDeviceTypeModifyRequest22	RESELLER_LEVEL
SystemSIPDeviceTypeModifyRequest22V2	RESELLER_LEVEL
SystemSIPDeviceTypeServiceGetRequest	RESELLER_LEVEL
SystemSIPDeviceTypeServiceModifyRequest	RESELLER_LEVEL
SystemSIPDiversionReasonGetRequest	SYSTEM_LEVEL
SystemSIPDiversionReasonModifyRequest	SYSTEM_LEVEL
SystemSIPGetACLListRequest	SYSTEM_LEVEL
SystemSIPGetContentTypeListRequest	SYSTEM_LEVEL
SystemSIPModifyACLEntryRequest	SYSTEM_LEVEL
SystemSIPModifyACLEntryRequest14sp2	SYSTEM_LEVEL
SystemSIPModifyContentTypeRequest	SYSTEM_LEVEL
SystemSMDIAddACLEntryRequest	SYSTEM_LEVEL
SystemSMDIAddACLEntryRequest14sp2	SYSTEM_LEVEL
SystemSMDIDeleteACLEntryRequest	SYSTEM_LEVEL
SystemSMDIDeleteACLEntryRequest14sp2	SYSTEM_LEVEL
SystemSMDIGetACLListRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskAddServerRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskAddServerRouteRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskDeleteServerRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskDeleteServerRouteRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskGetServerListRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskGetServerRouteListRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskModifyServerRequest	SYSTEM_LEVEL
SystemSMDIMessageDeskModifyServerRouteRequest	SYSTEM_LEVEL
SystemSMDIModifyACLEntryRequest	SYSTEM_LEVEL
SystemSMDIModifyACLEntryRequest14sp2	SYSTEM_LEVEL
SystemSMDIParametersGetRequest	SYSTEM_LEVEL
SystemSMDIParametersModifyRequest	SYSTEM_LEVEL
SystemSMPPGetRequest	SYSTEM_LEVEL
SystemSMPPGetRequest14sp5	SYSTEM_LEVEL
SystemSMPPGetRequest21	GROUP_LEVEL
SystemSMPPGetRequest22	GROUP_LEVEL



Transaction	Authorization Level
SystemSMPPModifyRequest	SYSTEM_LEVEL
SystemSoftwareVersionGetRequest	USER_LEVEL
SystemSpeedDial100GetRequest	SYSTEM_LEVEL
SystemSpeedDial100GetRequest17sp1	SYSTEM_LEVEL
SystemSpeedDial100ModifyRequest	SYSTEM_LEVEL
SystemStateOrProvinceGetListRequest	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest14sp3	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest14sp7	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest15	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest15sp2	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest17	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest17sp3	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest17sp4	USER_LEVEL
SystemSubscriberGetCallProcessingParametersRequest18sp1	USER_LEVEL
SystemSubscriberGetLoginParametersRequest	USER_LEVEL
SystemSubscriberGetProvisioningParametersRequest	USER_LEVEL
SystemSubscriberModifyCallProcessingParametersRequest	SYSTEM_LEVEL
SystemSubscriberModifyCallProcessingParametersRequest14sp7	SYSTEM_LEVEL
SystemSubscriberModifyLoginParametersRequest	USER_LEVEL
SystemSubscriberModifyProvisioningParametersRequest	SYSTEM_LEVEL
SystemSystemServiceCallProcessingPoliciesGetRequest	SYSTEM_LEVEL
SystemSystemServiceCallProcessingPoliciesModifyRequest	SYSTEM_LEVEL
SystemSystemServiceDnAddListRequest	SYSTEM_LEVEL
SystemSystemServiceDnDeleteListRequest	SYSTEM_LEVEL
SystemSystemServiceDnGetAvailableListRequest	SYSTEM_LEVEL
SystemSystemServiceDnGetSummaryListRequest	SYSTEM_LEVEL
SystemSystemServiceDnGetUsageListRequest	SYSTEM_LEVEL
SystemSystemVoicePortalAddRequest	SYSTEM_LEVEL
SystemSystemVoicePortalAddRequest21sp1	SYSTEM_LEVEL
SystemSystemVoicePortalDeleteRequest	SYSTEM_LEVEL
SystemSystemVoicePortalGetListRequest	SYSTEM_LEVEL
SystemSystemVoicePortalGetRequest	SYSTEM_LEVEL
SystemSystemVoicePortalGetRequest21sp1	SYSTEM_LEVEL
SystemSystemVoicePortalModifyRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemThirdPartyIMPGetRequest	SYSTEM_LEVEL
SystemThirdPartyIMPGetRequest19	SYSTEM_LEVEL
SystemThirdPartyIMPModifyRequest	SYSTEM_LEVEL
SystemThirdPartyVoiceMailSupportAddDnRequest	SYSTEM_LEVEL
SystemThirdPartyVoiceMailSupportDeleteDnRequest	SYSTEM_LEVEL
SystemThirdPartyVoiceMailSupportGetDnListRequest	SYSTEM_LEVEL
SystemThirdPartyVoiceMailSupportGetRequest	USER_LEVEL
SystemThirdPartyVoiceMailSupportGetRequest17sp4	USER_LEVEL
SystemThirdPartyVoiceMailSupportModifyDnRequest	SYSTEM_LEVEL
SystemThirdPartyVoiceMailSupportModifyRequest	SYSTEM_LEVEL
SystemTimeScheduleAddRequest	SYSTEM_LEVEL
SystemTimeScheduleDeleteRequest	SYSTEM_LEVEL
SystemTimeScheduleGetListRequest	SYSTEM_LEVEL
SystemTimeScheduleGetRequest	SYSTEM_LEVEL
SystemTimeScheduleModifyRequest	SYSTEM_LEVEL
SystemTimeZoneGetListRequest	USER_LEVEL
SystemTimeZoneGetListRequest20	USER_LEVEL
SystemTreatmentMappingAccessSIPStatusAddRequest	SYSTEM_LEVEL
SystemTreatmentMappingAccessSIPStatusDeleteRequest	SYSTEM_LEVEL
SystemTreatmentMappingAccessSIPStatusGetListRequest	SYSTEM_LEVEL
SystemTreatmentMappingAccessSIPStatusModifyRequest	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceAddRequest	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceAddRequest22	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceAddRequest22V2	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceAddRequest23	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceDeleteRequest	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceDeleteRequest22	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceDeleteRequest22V2	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceDeleteRequest23	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceGetListRequest	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceGetListRequest19sp1	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceGetListRequest22	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceGetListRequest23	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceModifyRequest	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceModifyRequest22	SYSTEM_LEVEL



Transaction	Authorization Level
SystemTreatmentMappingCallBlockingServiceModifyRequest22V2	SYSTEM_LEVEL
SystemTreatmentMappingCallBlockingServiceModifyRequest23	SYSTEM_LEVEL
SystemTreatmentMappingInternalReleaseCauseAddRequest	SYSTEM_LEVEL
SystemTreatmentMappingInternalReleaseCauseDeleteRequest	SYSTEM_LEVEL
SystemTreatmentMappingInternalReleaseCauseGetListRequest	SYSTEM_LEVEL
SystemTreatmentMappingInternalReleaseCauseModifyRequest	SYSTEM_LEVEL
SystemTreatmentMappingNetworkServerTreatmentAddRequest	SYSTEM_LEVEL
SystemTreatmentMappingNetworkServerTreatmentDeleteRequest	SYSTEM_LEVEL
System Treatment Mapping Network Server Treatment Get List Request	SYSTEM_LEVEL
SystemTreatmentMappingNetworkServerTreatmentModifyRequest	SYSTEM_LEVEL
SystemTreatmentMappingNetworkSIPStatusAddRequest	SYSTEM_LEVEL
SystemTreatmentMappingNetworkSIPStatusDeleteRequest	SYSTEM_LEVEL
SystemTreatmentMappingNetworkSIPStatusGetListRequest	SYSTEM_LEVEL
SystemTreatmentMappingNetworkSIPStatusModifyRequest	SYSTEM_LEVEL
SystemTreatmentMappingQ850CauseAddRequest	SYSTEM_LEVEL
SystemTreatmentMappingQ850CauseDeleteRequest	SYSTEM_LEVEL
SystemTreatmentMappingQ850CauseGetListRequest	SYSTEM_LEVEL
SystemTreatmentMappingQ850CauseModifyRequest	SYSTEM_LEVEL
SystemTrunkGroupGetRequest	SYSTEM_LEVEL
SystemTrunkGroupGetRequest19sp1	SYSTEM_LEVEL
SystemTrunkGroupGetRequest21	SYSTEM_LEVEL
SystemTrunkGroupGetRequest22	SYSTEM_LEVEL
SystemTrunkGroupGetRequest23	SYSTEM_LEVEL
SystemTrunkGroupModifyRequest	SYSTEM_LEVEL
SystemTrunkGroupOptionsMessageResponseStatusCodeAddListRequest	SYSTEM_LEVEL
SystemTrunkGroupOptionsMessageResponseStatusCodeDeleteListRequest	SYSTEM_LEVEL
SystemTrunkGroupOptionsMessageResponseStatusCodeGetListRequest	SYSTEM_LEVEL
SystemTrunkGroupUserCreationTaskGetListRequest	SYSTEM_LEVEL
SystemTrunkGroupUserCreationTaskGetListRequest14sp4	SYSTEM_LEVEL
SystemTwoStageDialingAddDnRequest	SYSTEM_LEVEL
SystemTwoStageDialingDeleteDnRequest	SYSTEM_LEVEL
SystemTwoStageDialingGetDnListRequest	USER_LEVEL
SystemTwoStageDialingModifyDnRequest	SYSTEM_LEVEL
SystemVerifyTranslationAndRoutingRequest	GROUP_LEVEL
SystemVideoServerAddRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemVideoServerDeleteRequest	SYSTEM_LEVEL
SystemVideoServerGetListRequest	SYSTEM_LEVEL
SystemVideoServerModifyRequest	SYSTEM_LEVEL
SystemVideoServerParametersGetRequest	SYSTEM_LEVEL
SystemVideoServerParametersModifyRequest	SYSTEM_LEVEL
SystemVirtualOnNetCallTypeAddRequest	SYSTEM_LEVEL
SystemVirtualOnNetCallTypeDeleteRequest	SYSTEM_LEVEL
SystemVirtualOnNetCallTypeGetListRequest	GROUP_LEVEL
SystemVirtualOnNetCallTypeModifyRequest	SYSTEM_LEVEL
SystemVoiceMessageSummaryUpdateGetRequest	SYSTEM_LEVEL
SystemVoiceMessageSummaryUpdateModifyRequest	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetPasscodeRulesRequest14	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetRequest14	USER_LEVEL
SystemVoiceMessagingGroupGetRequest16	USER_LEVEL
SystemVoiceMessagingGroupGetRequest16sp2	USER_LEVEL
SystemVoiceMessagingGroupGetRequest20	USER_LEVEL
SystemVoiceMessagingGroupGetRequest21	USER_LEVEL
SystemVoiceMessagingGroupGetRequest22	USER_LEVEL
SystemVoiceMessagingGroupGetRequest22V2	USER_LEVEL
SystemVoiceMessagingGroupGetVoicePortalMenusRequest14	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetVoicePortalMenusRequest18	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetVoicePortalMenusRequest18sp1	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetVoicePortalMenusRequest19	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetVoicePortalMenusRequest19sp1	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetVoicePortalMenusRequest20	SYSTEM_LEVEL
SystemVoiceMessagingGroupGetVoicePortalMenusRequest21	SYSTEM_LEVEL
SystemVoiceMessagingGroupModifyPasscodeRulesRequest	SYSTEM_LEVEL
SystemVoiceMessagingGroupModifyRequest	SYSTEM_LEVEL
SystemVoiceMessagingGroupModifyRequest16	SYSTEM_LEVEL
SystemVoiceMessagingGroupModifyVoicePortalMenusRequest	SYSTEM_LEVEL
SystemVoiceMessagingGroupModifyVoicePortalMenusRequest19	SYSTEM_LEVEL
SystemZoneAddRequest	SYSTEM_LEVEL
SystemZoneCallingRestrictionsNetAddressAddListRequest	SYSTEM_LEVEL
SystemZoneCallingRestrictionsNetAddressDeleteListRequest	SYSTEM_LEVEL
SystemZoneCallingRestrictionsNetAddressGetListRequest	SYSTEM_LEVEL



Transaction	Authorization Level
SystemZoneCallingRestrictionsZoneAddRequest	SYSTEM_LEVEL
SystemZoneCallingRestrictionsZoneDeleteRequest	SYSTEM_LEVEL
System Zone Calling Restrictions Zone Get List Request	SERVICE_PROVIDER_LEVE
SystemZoneCallingRestrictionsZoneModifyRequest	SYSTEM_LEVEL
SystemZoneCallingZonePhysicalLocationGetRequest	SYSTEM_LEVEL
SystemZoneCallingZonePhysicalLocationModifyRequest	SYSTEM_LEVEL
SystemZoneDeleteRequest	SYSTEM_LEVEL
SystemZoneGetListRequest	SERVICE_PROVIDER_LEVE
SystemZoneLocationBasedPhysicalLocationAddListRequest	SYSTEM_LEVEL
SystemZoneLocationBasedPhysicalLocationDeleteListRequest	SYSTEM_LEVEL
SystemZoneLocationBasedPhysicalLocationGetListRequest	SYSTEM_LEVEL
SystemZoneNetAddressAddListRequest	SYSTEM_LEVEL
SystemZoneNetAddressDeleteListRequest	SYSTEM_LEVEL
SystemZoneNetAddressGetListRequest	SYSTEM_LEVEL
TutorialFlagGetRequest	USER_LEVEL
TutorialFlagModifyRequest	USER_LEVEL
UserAccessDeviceFileGetListRequest	USER_LEVEL
UserAccessDeviceFileGetRequest	USER_LEVEL
UserAccessDeviceFileModifyRequest	USER_LEVEL
UserAccessDeviceResetRequest	USER_LEVEL
UserAccessDeviceTagsGetRequest	USER_LEVEL
UserAddRequest14	GROUP_LEVEL
UserAddRequest14sp9	GROUP_LEVEL
UserAddRequest17sp4	GROUP_LEVEL
UserAddRequest21	GROUP_LEVEL
UserAddRequest22	GROUP_LEVEL
UserAdviceOfChargeGetRequest	USER_LEVEL
UserAdviceOfChargeModifyRequest	USER_LEVEL
UserAlternateNumbersGetRequest	USER_LEVEL
UserAlternateNumbersGetRequest17	USER_LEVEL
UserAlternateNumbersGetRequest21	USER_LEVEL
UserAlternateNumbersModifyRequest	USER_LEVEL
UserAlternateUserIdAddRequest	RESELLER_LEVEL
UserAlternateUserIdDeleteRequest	RESELLER_LEVEL
UserAlternateUserIdGetListRequest	USER_LEVEL



Transaction	Authorization Level
UserAlternateUserIdModifyRequest	RESELLER_LEVEL
UserAnnouncementFileAddRequest	USER_LEVEL
UserAnnouncementFileDeleteListRequest	USER_LEVEL
UserAnnouncementFileGetAvailableListRequest	USER_LEVEL
UserAnnouncementFileGetListRequest	USER_LEVEL
UserAnnouncementFileGetPagedSortedListRequest	USER_LEVEL
UserAnnouncementFileGetRequest	USER_LEVEL
UserAnnouncementFileModifyRequest	USER_LEVEL
UserAnnouncementRepositoryGetSettingsRequest	USER_LEVEL
UserAnonymousCallRejectionGetRequest	USER_LEVEL
UserAnonymousCallRejectionModifyRequest	USER_LEVEL
UserAssignedServicesGetListRequest	USER_LEVEL
UserAuthenticationGetRequest	USER_LEVEL
UserAuthenticationModifyRequest	USER_LEVEL
UserAutomaticCallbackGetRequest	USER_LEVEL
UserAutomaticCallbackModifyRequest	USER_LEVEL
UserAutomaticCollectCallGetRequest	USER_LEVEL
UserAutomaticCollectCallModifyRequest	GROUP_LEVEL
UserAutomaticHoldRetrieveGetRequest	USER_LEVEL
UserAutomaticHoldRetrieveModifyRequest	USER_LEVEL
UserBargeInExemptGetRequest	USER_LEVEL
UserBargeInExemptModifyRequest	USER_LEVEL
UserBasicCallLogsGetListRequest	USER_LEVEL
UserBasicCallLogsGetListRequest14sp4	USER_LEVEL
UserBroadWorksAnywhereAddPhoneNumberRequest	USER_LEVEL
UserBroadWorksAnywhereAddSelectiveCriteriaRequest	USER_LEVEL
UserBroadWorksAnywhereAddSelectiveCriteriaRequest16	USER_LEVEL
UserBroadWorksAnywhereDeletePhoneNumberRequest	USER_LEVEL
UserBroadWorksAnywhereDeleteSelectiveCriteriaRequest	USER_LEVEL
UserBroadWorksAnywhereGetAvailablePortalListRequest	USER_LEVEL
UserBroadWorksAnywhereGetAvailablePortalListRequest21sp1	USER_LEVEL
UserBroadWorksAnywhereGetPhoneNumberPagedSortedListRequest	USER_LEVEL
UserBroadWorksAnywhereGetPhoneNumberRequest	USER_LEVEL
UserBroadWorksAnywhereGetRequest	USER_LEVEL
UserBroadWorksAnywhereGetRequest16sp2	USER_LEVEL



Transaction	Authorization Level
UserBroadWorksAnywhereGetSelectiveCriteriaRequest	USER_LEVEL
UserBroadWorksAnywhereGetSelectiveCriteriaRequest16	USER_LEVEL
UserBroadWorksAnywhereGetSelectiveCriteriaRequest21	USER_LEVEL
UserBroadWorksAnywhereModifyPhoneNumberRequest	USER_LEVEL
UserBroadWorksAnywhereModifyRequest	USER_LEVEL
UserBroadWorksAnywhereModifySelectiveCriteriaRequest	USER_LEVEL
UserBroadWorksCommunicatorGetRequest	USER_LEVEL
UserBroadworksMobilityAddMobileIdentityUsingSharedCallAppearanceRequest	GROUP_LEVEL
UserBroadWorksMobilityGetRequest	USER_LEVEL
UserBroadWorksMobilityGetRequest21	USER_LEVEL
UserBroadWorksMobilityGetRequest21sp1	USER_LEVEL
UserBroadWorksMobilityMobileIdentityAddRequest	GROUP_LEVEL
UserBroadWorksMobilityMobileIdentityAddRequest21sp1	GROUP_LEVEL
UserBroadWorksMobilityMobileIdentityAddRequest22	GROUP_LEVEL
UserBroadWorksMobilityMobileIdentityConsolidatedAddRequest	GROUP_LEVEL
UserBroadWorksMobilityMobileIdentityConsolidatedDeleteRequest	GROUP_LEVEL
UserBroadWorksMobilityMobileIdentityConsolidatedModifyRequest	USER_LEVEL
UserBroadWorksMobilityMobileIdentityDeleteRequest	GROUP_LEVEL
UserBroadWorksMobilityMobileIdentityGetRequest	USER_LEVEL
UserBroadWorksMobilityMobileIdentityGetRequest21sp1	USER_LEVEL
UserBroadWorksMobilityMobileIdentityGetRequest21sp1V2	USER_LEVEL
UserBroadWorksMobilityMobileIdentityGetRequest22	USER_LEVEL
UserBroadWorksMobilityMobileIdentityGetRequest22V2	USER_LEVEL
UserBroadWorksMobilityMobileIdentityModifyRequest	USER_LEVEL
UserBroadWorksMobilityModifyRequest	USER_LEVEL
UserBroadWorksMobilityModifyRequest20	USER_LEVEL
UserBroadWorksMobilityModifyRequest21	USER_LEVEL
UserBroadWorksReceptionistEnterpriseAddUserListRequest	USER_LEVEL
UserBroadWorksReceptionistEnterpriseDeleteUserListRequest	USER_LEVEL
UserBroadWorksReceptionistEnterpriseGetAvailableUserListRequest	USER_LEVEL
UserBroadWorksReceptionistEnterpriseGetRequest	USER_LEVEL
UserBroadWorksReceptionistEnterpriseModifyRequest	USER_LEVEL
UserBroadWorksReceptionistEnterpriseNoteGetRequest	USER_LEVEL
UserBroadWorksReceptionistEnterpriseNoteModifyListRequest	USER_LEVEL
UserBroadWorksReceptionistOfficeGetAvailableUserListRequest	USER_LEVEL



Transaction	Authorization Level
UserBroadWorksReceptionistOfficeGetRequest	USER_LEVEL
UserBroadWorksReceptionistOfficeModifyRequest	USER_LEVEL
UserBroadWorksReceptionistSmallBusinessGetAvailableUserListRequest	USER_LEVEL
UserBroadWorksReceptionistSmallBusinessGetRequest	USER_LEVEL
UserBroadWorksReceptionistSmallBusinessModifyRequest	USER_LEVEL
UserBusyLampFieldGetAvailableUserListRequest	USER_LEVEL
UserBusyLampFieldGetRequest	USER_LEVEL
UserBusyLampFieldGetRequest16sp2	USER_LEVEL
UserBusyLampFieldModifyRequest	USER_LEVEL
UserCallCenterAddSupervisedAgentListRequest	USER_LEVEL
UserCallCenterAgentDetailsGetRequest	USER_LEVEL
UserCallCenterAgentSignOutRequest	USER_LEVEL
UserCallCenterCallDispositionCodeGetAvailableListRequest	USER_LEVEL
UserCallCenterDeleteSupervisedAgentListRequest	USER_LEVEL
UserCallCenterEnhancedReportingReportTemplateParamInfoGetRequest	USER_LEVEL
UserCallCenterEnhancedReportingScheduledReportDeleteRequest	USER_LEVEL
UserCallCenterEnhancedReportingScheduledReportGetRequest	USER_LEVEL
User Call Center Enhanced Reporting Scheduled Report Modify Request	USER_LEVEL
UserCallCenterGetAgentSupervisorListRequest	USER_LEVEL
UserCallCenterGetAvailableCallCenterListRequest	USER_LEVEL
UserCallCenterGetAvailableCallCenterPagedSortedListRequest	USER_LEVEL
UserCallCenterGetAvailableDNISListRequest	USER_LEVEL
UserCallCenterGetListRequest	USER_LEVEL
UserCallCenterGetRequest	USER_LEVEL
UserCallCenterGetRequest16	USER_LEVEL
UserCallCenterGetRequest17	USER_LEVEL
UserCallCenterGetRequest17sp4	USER_LEVEL
UserCallCenterGetRequest19	USER_LEVEL
UserCallCenterGetSupervisedAgentListRequest	USER_LEVEL
UserCallCenterGetSupervisorCallCenterListRequest	USER_LEVEL
UserCallCenterModifyAvailabilityListRequest	USER_LEVEL
UserCallCenterModifyCallCenterListRequest	USER_LEVEL
UserCallCenterModifyRequest	USER_LEVEL
UserCallCenterModifyRequest17sp4	USER_LEVEL
UserCallCenterModifyRequest19	USER_LEVEL



Transaction	Authorization Level
UserCallCenterModifySupervisedAgentListRequest	USER_LEVEL
UserCallCenterMonitoringGetRequest	USER_LEVEL
UserCallCenterMonitoringModifyRequest	USER_LEVEL
UserCallForwardingAlwaysGetRequest	USER_LEVEL
UserCallForwardingAlwaysModifyRequest	USER_LEVEL
UserCallForwardingAlwaysSecondaryGetRequest	USER_LEVEL
UserCallForwardingAlwaysSecondaryModifyRequest	USER_LEVEL
UserCallForwardingBusyGetRequest	USER_LEVEL
UserCallForwardingBusyModifyRequest	USER_LEVEL
UserCallForwardingNoAnswerGetRequest13mp16	USER_LEVEL
UserCallForwardingNoAnswerModifyRequest	USER_LEVEL
UserCallForwardingNotReachableGetRequest	USER_LEVEL
UserCallForwardingNotReachableModifyRequest	USER_LEVEL
UserCallForwardingSelectiveAddCriteriaRequest	USER_LEVEL
UserCallForwardingSelectiveAddCriteriaRequest16	USER_LEVEL
UserCallForwardingSelectiveDeleteCriteriaRequest	USER_LEVEL
UserCallForwardingSelectiveGetCriteriaRequest	USER_LEVEL
UserCallForwardingSelectiveGetCriteriaRequest16	USER_LEVEL
UserCallForwardingSelectiveGetCriteriaRequest21	USER_LEVEL
UserCallForwardingSelectiveGetRequest	USER_LEVEL
UserCallForwardingSelectiveGetRequest16	USER_LEVEL
UserCallForwardingSelectiveModifyCriteriaRequest	USER_LEVEL
UserCallForwardingSelectiveModifyRequest	USER_LEVEL
UserCallingLineIDBlockingOverrideGetRequest	USER_LEVEL
UserCallingLineIDBlockingOverrideModifyRequest	USER_LEVEL
UserCallingLineIDDeliveryBlockingGetRequest	USER_LEVEL
UserCallingLineIDDeliveryBlockingModifyRequest	USER_LEVEL
UserCallingNameDeliveryGetRequest	USER_LEVEL
UserCallingNameDeliveryModifyRequest	USER_LEVEL
UserCallingNameRetrievalGetRequest	USER_LEVEL
UserCallingNameRetrievalModifyRequest	USER_LEVEL
UserCallingNumberDeliveryGetRequest	USER_LEVEL
UserCallingNumberDeliveryModifyRequest	USER_LEVEL
UserCallingPartyCategoryGetRequest	USER_LEVEL
UserCallingPartyCategoryGetRequest16	USER_LEVEL



Transaction	Authorization Level
UserCallingPartyCategoryModifyRequest	USER_LEVEL
UserCallingPartyCategoryModifyRequest16	USER_LEVEL
UserCallLogsClearRequest	USER_LEVEL
UserCallLogsClearRequest14sp4	USER_LEVEL
UserCallMeNowAddCriteriaRequest	USER_LEVEL
UserCallMeNowDeleteCriteriaRequest	USER_LEVEL
UserCallMeNowGetCriteriaRequest	USER_LEVEL
UserCallMeNowGetRequest	USER_LEVEL
UserCallMeNowModifyCriteriaRequest	USER_LEVEL
UserCallMeNowModifyRequest	USER_LEVEL
UserCallNotifyAddCriteriaRequest	USER_LEVEL
UserCallNotifyAddCriteriaRequest16	USER_LEVEL
UserCallNotifyDeleteCriteriaRequest	USER_LEVEL
UserCallNotifyGetCriteriaRequest	USER_LEVEL
UserCallNotifyGetCriteriaRequest16	USER_LEVEL
UserCallNotifyGetCriteriaRequest21	USER_LEVEL
UserCallNotifyGetRequest	USER_LEVEL
UserCallNotifyModifyCriteriaRequest	USER_LEVEL
UserCallNotifyModifyRequest	USER_LEVEL
UserCallParkGetRequest	USER_LEVEL
UserCallPickupGetRequest	USER_LEVEL
UserCallPoliciesGetRequest	USER_LEVEL
UserCallPoliciesGetRequest17	USER_LEVEL
UserCallPoliciesGetRequest19sp1	USER_LEVEL
UserCallPoliciesModifyRequest	USER_LEVEL
UserCallProcessingGetPolicyRequest14	USER_LEVEL
UserCallProcessingGetPolicyRequest14sp1	USER_LEVEL
UserCallProcessingGetPolicyRequest14sp7	USER_LEVEL
UserCallProcessingGetPolicyRequest16	USER_LEVEL
UserCallProcessingGetPolicyRequest16sp2	USER_LEVEL
UserCallProcessingGetPolicyRequest17	USER_LEVEL
UserCallProcessingGetPolicyRequest17sp3	USER_LEVEL
UserCallProcessingGetPolicyRequest17sp4	USER_LEVEL
UserCallProcessingGetPolicyRequest18	USER_LEVEL
UserCallProcessingGetPolicyRequest19sp1	USER_LEVEL



Transaction	Authorization Level
UserCallProcessingGetPolicyRequest21sp1	USER_LEVEL
UserCallProcessingGetPolicyRequest21sp2	USER_LEVEL
UserCallProcessingGetPolicyRequest22	USER_LEVEL
UserCallProcessingGetPolicyRequest22V2	USER_LEVEL
UserCallProcessingModifyPolicyRequest14	USER_LEVEL
UserCallProcessingModifyPolicyRequest14sp7	USER_LEVEL
UserCallRecordingGetRequest	USER_LEVEL
UserCallRecordingGetRequest20	USER_LEVEL
UserCallRecordingModifyRequest	USER_LEVEL
UserCallToNumberGetAvailableListRequest	USER_LEVEL
UserCallTransferGetRequest	USER_LEVEL
UserCallTransferGetRequest14sp4	USER_LEVEL
UserCallTransferModifyRequest	USER_LEVEL
UserCallWaitingGetRequest	USER_LEVEL
UserCallWaitingGetRequest17sp4	USER_LEVEL
UserCallWaitingModifyRequest	USER_LEVEL
UserChargeNumberGetRequest	USER_LEVEL
UserChargeNumberGetRequest14sp9	USER_LEVEL
UserChargeNumberModifyRequest	USER_LEVEL
UserClassmarkGetRequest	SERVICE_PROVIDER_LEVEL
UserClassmarkModifyRequest	SERVICE_PROVIDER_LEVEL
UserCollaborateBridgeGetRequest	USER_LEVEL
UserCollaborateBridgeGetRequest20sp1	USER_LEVEL
UserCollaborateDeleteRoomRequest	USER_LEVEL
UserCollaborateInstantRoomAddRequest	USER_LEVEL
UserCollaborateInstantRoomGetRequest	USER_LEVEL
UserCollaborateInstantRoomParametersGetRequest	USER_LEVEL
UserCollaborateInstantRoomParametersModifyRequest	USER_LEVEL
UserCollaborateMyRoomGetRequest	USER_LEVEL
UserCollaborateMyRoomModifyRequest	USER_LEVEL
UserCollaborateProjectRoomAddRequest	USER_LEVEL
UserCollaborateProjectRoomGetRequest	USER_LEVEL
UserCollaborateProjectRoomModifyRequest	USER_LEVEL
UserCollaborateRoomGetRequest	USER_LEVEL
UserCollaborateRoomIDRegenerateRequest	USER_LEVEL



Transaction	Authorization Level
UserCollaborateRoomListGetRequest	USER_LEVEL
UserCollaborateRoomModifyRequest	USER_LEVEL
UserCommPilotExpressGetRequest	USER_LEVEL
UserCommPilotExpressModifyRequest	USER_LEVEL
UserCommunicationBarringAuthorizationCodeAddListRequest	GROUP_LEVEL
User Communication Barring Authorization Code Delete List Request	GROUP_LEVEL
UserCommunicationBarringAuthorizationCodeGetListRequest	USER_LEVEL
UserCommunicationBarringGetRequest	GROUP_LEVEL
UserCommunicationBarringModifyRequest	GROUP_LEVEL
UserCommunicationBarringUserControlGetRequest	USER_LEVEL
UserCommunicationBarringUserControlModifyRequest	USER_LEVEL
UserConnectedLineIdentificationRestrictionGetRequest	USER_LEVEL
UserConnectedLineIdentificationRestrictionModifyRequest	USER_LEVEL
UserConsolidatedAddRequest	GROUP_LEVEL
UserConsolidatedDeleteRequest	GROUP_LEVEL
UserConsolidatedModifyRequest	USER_LEVEL
UserCustomRingbackUserAddCriteriaRequest	USER_LEVEL
UserCustomRingbackUserAddCriteriaRequest16	USER_LEVEL
UserCustomRingbackUserAddCriteriaRequest20	USER_LEVEL
UserCustomRingbackUserDeleteCriteriaRequest	USER_LEVEL
UserCustomRingbackUserGetCriteriaListRequest	USER_LEVEL
UserCustomRingbackUserGetCriteriaRequest	USER_LEVEL
UserCustomRingbackUserGetCriteriaRequest15sp2	USER_LEVEL
UserCustomRingbackUserGetCriteriaRequest16	USER_LEVEL
UserCustomRingbackUserGetCriteriaRequest20	USER_LEVEL
UserCustomRingbackUserGetCriteriaRequest21	USER_LEVEL
UserCustomRingbackUserModifyActiveCriteriaListRequest	USER_LEVEL
UserCustomRingbackUserModifyCriteriaRequest	USER_LEVEL
UserCustomRingbackUserModifyCriteriaRequest16	USER_LEVEL
UserCustomRingbackUserModifyCriteriaRequest20	USER_LEVEL
UserDeleteRequest	USER_LEVEL
UserDevicePoliciesGetRequest	GROUP_LEVEL
UserDevicePoliciesGetRequest19sp1	GROUP_LEVEL
UserDevicePoliciesGetRequest20	GROUP_LEVEL
UserDevicePoliciesGetRequest21	USER_LEVEL



Transaction	Authorization Level
UserDevicePoliciesModifyRequest	USER_LEVEL
UserDirectedCallPickupWithBargeInGetRequest	USER_LEVEL
UserDirectedCallPickupWithBargeInGetRequest14sp7	USER_LEVEL
UserDirectedCallPickupWithBargeInModifyRequest	USER_LEVEL
UserDirectRouteGetRequest	USER_LEVEL
UserDirectRouteModifyRequest	GROUP_LEVEL
UserDnGetActivationListRequest	USER_LEVEL
UserDoNotDisturbGetRequest	USER_LEVEL
UserDoNotDisturbModifyRequest	USER_LEVEL
UserEnhancedCallLogsGetListRequest	USER_LEVEL
UserEnhancedCallLogsGetListRequest14sp4	USER_LEVEL
UserEnhancedCallLogsGetListRequest16	USER_LEVEL
UserEnhancedCallLogsGetListRequest17sp4	USER_LEVEL
UserEnhancedCallLogsGetListRequest17sp4V2	USER_LEVEL
UserEnhancedCallLogsGetListRequest20	USER_LEVEL
UserEnhancedCallLogsGetListRequest21	USER_LEVEL
UserEnhancedCallLogsGetListRequest21sp1	USER_LEVEL
UserEnhancedCallLogsGetListRequest21sp1V2	USER_LEVEL
UserEnhancedCallLogsGetListRequest22	USER_LEVEL
UserEnterpriseCommonPhoneListGetPagedSortedListRequest	USER_LEVEL
UserExecutiveAddFilteringSelectiveCriteriaRequest	USER_LEVEL
UserExecutiveAssistantGetRequest	USER_LEVEL
UserExecutiveAssistantModifyRequest	USER_LEVEL
UserExecutiveDeleteFilteringSelectiveCriteriaRequest	USER_LEVEL
UserExecutiveGetAssistantRequest	USER_LEVEL
UserExecutiveGetAvailableAssistantListRequest	USER_LEVEL
UserExecutiveGetFilteringRequest	USER_LEVEL
UserExecutiveGetFilteringSelectiveCriteriaRequest	USER_LEVEL
UserExecutiveGetFilteringSelectiveCriteriaRequest21	USER_LEVEL
UserExecutiveGetScreeningAlertingRequest	USER_LEVEL
UserExecutiveModifyAssistantRequest	USER_LEVEL
UserExecutiveModifyFilteringExecutionServerRequest	USER_LEVEL
UserExecutiveModifyFilteringRequest	USER_LEVEL
UserExecutiveModifyFilteringSelectiveCriteriaRequest	USER_LEVEL
UserExecutiveModifyScreeningAlertingRequest	USER_LEVEL



Transaction	Authorization Level
UserExternalCallingLineIDDeliveryGetRequest	USER_LEVEL
UserExternalCallingLineIDDeliveryModifyRequest	USER_LEVEL
UserExternalCustomRingbackGetRequest	USER_LEVEL
UserExternalCustomRingbackModifyRequest	USER_LEVEL
UserFaxMessagingGetRequest	USER_LEVEL
UserFaxMessagingGetRequest17	USER_LEVEL
UserFaxMessagingGetRequest17sp1	USER_LEVEL
UserFaxMessagingModifyRequest	USER_LEVEL
UserFeatureAccessCodeGetListRequest	USER_LEVEL
UserFeatureAccessCodeGetListRequest20	USER_LEVEL
UserFeatureAccessCodeGetListRequest21	USER_LEVEL
UserFeatureAccessCodeModifyListRequest	GROUP_LEVEL
UserFlexibleSeatingGuestGetAvailableHostListRequest	USER_LEVEL
UserFlexibleSeatingGuestGetRequest	USER_LEVEL
UserFlexibleSeatingGuestGetRequest22	USER_LEVEL
UserFlexibleSeatingGuestModifyRequest	USER_LEVEL
UserFlexibleSeatingGuestModifyRequest22	USER_LEVEL
UserGetListInGroupPagedSortedListRequest	GROUP_LEVEL
UserGetListInGroupRequest	GROUP_LEVEL
UserGetListInServiceProviderRequest	GROUP_LEVEL
UserGetListInSystemRequest	RESELLER_LEVEL
UserGetLoginInfoRequest	USER_LEVEL
UserGetLoginInfoRequest21sp1	USER_LEVEL
UserGetLoginInfoRequest22	USER_LEVEL
UserGetLoginInfoRequest22V2	USER_LEVEL
UserGetRegistrationListRequest	USER_LEVEL
UserGetRequest14	USER_LEVEL
UserGetRequest14sp4	USER_LEVEL
UserGetRequest14sp9	USER_LEVEL
UserGetRequest15sp2	USER_LEVEL
UserGetRequest17	USER_LEVEL
UserGetRequest17sp3	USER_LEVEL
UserGetRequest17sp4	USER_LEVEL
UserGetRequest18	USER_LEVEL
UserGetRequest19	USER_LEVEL



Transaction	Authorization Level
UserGetRequest20	USER_LEVEL
UserGetRequest21	USER_LEVEL
UserGetRequest21sp1	USER_LEVEL
UserGetRequest21sp1V2	USER_LEVEL
UserGetRequest22	USER_LEVEL
UserGetRequest22V2	USER_LEVEL
UserGetRequest22V3	USER_LEVEL
UserGetRequest22V4	USER_LEVEL
UserGetRequest22V5	USER_LEVEL
UserGetServiceInstanceListInServiceProviderRequest	SERVICE_PROVIDER_LEVEL
UserGetServiceInstanceListInSystemRequest	RESELLER_LEVEL
UserGroupCommonPhoneListGetPagedSortedListRequest	USER_LEVEL
UserGroupCustomContactDirectoryGetPagedSortedListRequest	USER_LEVEL
UserGroupNightForwardingGetRequest	USER_LEVEL
UserGroupNightForwardingModifyRequest	GROUP_LEVEL
UserGroupPagingGetListRequest	USER_LEVEL
UserHolidayScheduleAddRequest	USER_LEVEL
UserHolidayScheduleDeleteRequest	USER_LEVEL
UserHolidayScheduleGetListRequest	USER_LEVEL
UserHolidayScheduleGetRequest	USER_LEVEL
UserHolidayScheduleModifyRequest	USER_LEVEL
UserHotelingGuestGetAvailableUserListRequest	USER_LEVEL
UserHotelingGuestGetRequest14	USER_LEVEL
UserHotelingGuestGetRequest14sp2	USER_LEVEL
UserHotelingGuestGetRequest14sp4	USER_LEVEL
UserHotelingGuestModifyRequest	USER_LEVEL
UserHotelingGuestModifyRequest21	USER_LEVEL
UserHotelingHostGetRequest14	USER_LEVEL
UserHotelingHostGetRequest14sp4	USER_LEVEL
UserHotelingHostGetRequest17	USER_LEVEL
UserHotelingHostModifyRequest	USER_LEVEL
UserInCallServiceActivationGetRequest	USER_LEVEL
UserInCallServiceActivationModifyRequest	USER_LEVEL
UserIncomingCallingPlanGetRequest	USER_LEVEL
UserIncomingCallingPlanModifyRequest	USER_LEVEL



Transaction	Authorization Level
UserINIntegrationGetRequest	USER_LEVEL
UserINIntegrationModifyRequest	USER_LEVEL
UserIntegratedIMPGeneratePasswordRequest	USER_LEVEL
UserIntegratedIMPGetRequest	USER_LEVEL
UserIntegratedIMPGetRequest21sp1	USER_LEVEL
UserIntegratedIMPModifyRequest	USER_LEVEL
UserInterceptUserGetRequest	USER_LEVEL
UserInterceptUserGetRequest16	USER_LEVEL
UserInterceptUserGetRequest16sp1	USER_LEVEL
UserInterceptUserGetRequest21sp1	USER_LEVEL
UserInterceptUserModifyRequest	USER_LEVEL
UserInterceptUserModifyRequest16	USER_LEVEL
UserInterceptUserModifyRequest21sp1	USER_LEVEL
UserInternalCallingLineIDDeliveryGetRequest	USER_LEVEL
UserInternalCallingLineIDDeliveryModifyRequest	USER_LEVEL
UserLegacyAutomaticCallbackGetRequest	USER_LEVEL
UserLegacyAutomaticCallbackModifyRequest	USER_LEVEL
UserLinePortGetListRequest	USER_LEVEL
UserMaliciousCallTraceGetRequest	SYSTEM_LEVEL
UserMaliciousCallTraceModifyRequest	SYSTEM_LEVEL
UserMeetMeConferencingAddConferenceRequest	USER_LEVEL
UserMeetMeConferencingAddConferenceRequest19	USER_LEVEL
UserMeetMeConferencingAddConferenceRequest23	USER_LEVEL
UserMeetMeConferencingDeleteConferenceListRequest	USER_LEVEL
UserMeetMeConferencingDeleteConferenceRecordingListRequest	USER_LEVEL
UserMeetMeConferencingGetAvailableDelegateListRequest	USER_LEVEL
UserMeetMeConferencingGetBridgeListRequest	USER_LEVEL
UserMeetMeConferencingGetConferenceDelegateListRequest	USER_LEVEL
UserMeetMeConferencingGetConferenceGreetingRequest	USER_LEVEL
UserMeetMeConferencingGetConferenceGreetingRequest20	USER_LEVEL
UserMeetMeConferencingGetConferenceListRequest	USER_LEVEL
UserMeetMeConferencingGetConferenceRecordingListRequest	USER_LEVEL
UserMeetMeConferencingGetConferenceRequest	USER_LEVEL
UserMeetMeConferencingGetConferenceRequest19	USER_LEVEL
UserMeetMeConferencingGetConferenceRequest20	USER LEVEL



Transaction	Authorization Level
UserMeetMeConferencingGetConferenceRequest23	USER_LEVEL
UserMeetMeConferencingModifyConferenceDelegateListRequest	USER_LEVEL
User Meet Me Conferencing Modify Conference Greeting Execution Server Request	USER_LEVEL
UserMeetMeConferencingModifyConferenceGreetingRequest	USER_LEVEL
UserMeetMeConferencingModifyConferenceGreetingRequest20	USER_LEVEL
UserMeetMeConferencingModifyConferenceRequest	USER_LEVEL
UserModifyGroupIdRequest	SERVICE_PROVIDER_LEVEL
UserModifyRequest14	USER_LEVEL
UserModifyRequest14sp9	USER_LEVEL
UserModifyRequest16	USER_LEVEL
UserModifyRequest17sp4	USER_LEVEL
UserModifyRequest21	USER_LEVEL
UserModifyRequest22	USER_LEVEL
UserModifyUserIdRequest	USER_LEVEL
UserMusicOnHoldGetRequest	USER_LEVEL
UserMusicOnHoldModifyRequest	USER_LEVEL
UserMusicOnHoldUserGetRequest	USER_LEVEL
UserMusicOnHoldUserGetRequest16	USER_LEVEL
UserMusicOnHoldUserGetRequest20	USER_LEVEL
UserMusicOnHoldUserModifyRequest	USER_LEVEL
UserMusicOnHoldUserModifyRequest16	USER_LEVEL
UserMusicOnHoldUserModifyRequest20	USER_LEVEL
UserMWIDeliveryToMobileEndpointGetRequest	USER_LEVEL
UserMWIDeliveryToMobileEndpointModifyRequest	USER_LEVEL
UserNetworkConferencingGetRequest	USER_LEVEL
UserNumberPortabilityAnnouncementGetRequest	USER_LEVEL
UserNumberPortabilityAnnouncementModifyRequest	USER_LEVEL
UserOCICallControlApplicationGetListRequest	USER_LEVEL
UserOCICallControlApplicationModifyRequest	GROUP_LEVEL
UserOutgoingCallingPlanAuthorizationCodeAddListRequest	USER_LEVEL
UserOutgoingCallingPlanAuthorizationCodeDeleteListRequest	USER_LEVEL
UserOutgoingCallingPlanAuthorizationCodeGetListRequest	USER_LEVEL
UserOutgoingCallingPlanAuthorizationCodeGetRequest	USER_LEVEL
UserOutgoingCallingPlanAuthorizationCodeModifyRequest	USER_LEVEL
UserOutgoingCallingPlanCallMeNowGetRequest	USER_LEVEL



Transaction	Authorization Level
UserOutgoingCallingPlanCallMeNowModifyRequest	GROUP_LEVEL
UserOutgoingCallingPlanDigitPlanCallMeNowGetRequest	USER_LEVEL
UserOutgoingCallingPlanDigitPlanCallMeNowModifyRequest	GROUP_LEVEL
UserOutgoingCallingPlanDigitPlanOriginatingGetRequest	USER_LEVEL
UserOutgoingCallingPlanDigitPlanOriginatingModifyRequest	USER_LEVEL
UserOutgoingCallingPlanDigitPlanRedirectingGetRequest	USER_LEVEL
UserOutgoingCallingPlanDigitPlanRedirectingModifyRequest	USER_LEVEL
UserOutgoingCallingPlanOriginatingGetRequest	USER_LEVEL
UserOutgoingCallingPlanOriginatingModifyRequest	USER_LEVEL
UserOutgoingCallingPlanPinholeDigitPlanCallMeNowGetRequest	USER_LEVEL
UserOutgoingCallingPlanPinholeDigitPlanCallMeNowModifyRequest	GROUP_LEVEL
UserOutgoingCallingPlanPinholeDigitPlanOriginatingGetRequest	USER_LEVEL
UserOutgoingCallingPlanPinholeDigitPlanOriginatingModifyRequest	GROUP_LEVEL
UserOutgoingCallingPlanPinholeDigitPlanRedirectingGetRequest	USER_LEVEL
UserOutgoingCallingPlanPinholeDigitPlanRedirectingModifyRequest	GROUP_LEVEL
UserOutgoingCallingPlanRedirectedGetRequest	USER_LEVEL
UserOutgoingCallingPlanRedirectedModifyRequest	USER_LEVEL
UserOutgoingCallingPlanRedirectingGetRequest	USER_LEVEL
UserOutgoingCallingPlanRedirectingModifyRequest	USER_LEVEL
UserOutgoingCallingPlanSustainedAuthorizationCodeGetRequest	USER_LEVEL
UserOutgoingCallingPlanSustainedAuthorizationCodeModifyRequest	USER_LEVEL
UserOutgoingCallingPlanTransferNumbersGetRequest	USER_LEVEL
UserOutgoingCallingPlanTransferNumbersModifyRequest	USER_LEVEL
UserPasswordInfoGetRequest	USER_LEVEL
UserPersonalAssistantCallToNumberGetListRequest	USER_LEVEL
UserPersonalAssistantCallToNumberModifyListRequest	USER_LEVEL
UserPersonalAssistantExclusionNumberAddRequest	USER_LEVEL
UserPersonalAssistantExclusionNumberDeleteListRequest	USER_LEVEL
UserPersonalAssistantExclusionNumberGetListRequest	USER_LEVEL
UserPersonalAssistantExclusionNumberGetRequest	USER_LEVEL
UserPersonalAssistantExclusionNumberModifyRequest	USER_LEVEL
UserPersonalAssistantGetRequest	USER_LEVEL
UserPersonalAssistantGetRequest22	USER_LEVEL
UserPersonalAssistantModifyRequest	USER_LEVEL
UserPersonalPhoneListAddListRequest	USER_LEVEL



Transaction	Authorization Level
UserPersonalPhoneListDeleteListRequest	USER_LEVEL
UserPersonalPhoneListGetListRequest	USER_LEVEL
UserPersonalPhoneListGetPagedSortedListRequest	USER_LEVEL
UserPersonalPhoneListModifyRequest	USER_LEVEL
UserPhoneDirectoryGetListRequest	USER_LEVEL
UserPhoneDirectoryGetPagedListRequest	USER_LEVEL
UserPhoneDirectoryGetPagedSortedListRequest	USER_LEVEL
UserPhoneDirectoryGetSearchedListRequest	USER_LEVEL
UserPhysicalLocationGetRequest	USER_LEVEL
UserPhysicalLocationModifyRequest	USER_LEVEL
UserPolycomPhoneServicesGetPrimaryEndpointListRequest	USER_LEVEL
UserPolycomPhoneServicesGetRequest	USER_LEVEL
UserPolycomPhoneServicesModifyRequest	USER_LEVEL
UserPortalPasscodeGetInfoRequest	USER_LEVEL
UserPortalPasscodeModifyRequest	USER_LEVEL
UserPortalPasscodeRulesGetRequest	USER_LEVEL
UserPreAlertingAnnouncementAddCriteriaRequest	USER_LEVEL
UserPreAlertingAnnouncementDeleteCriteriaRequest	USER_LEVEL
UserPreAlertingAnnouncementGetCriteriaRequest	USER_LEVEL
UserPreAlertingAnnouncementGetCriteriaRequest21	USER_LEVEL
UserPreAlertingAnnouncementGetRequest	USER_LEVEL
UserPreAlertingAnnouncementGetRequest20	USER_LEVEL
UserPreAlertingAnnouncementModifyCriteriaRequest	USER_LEVEL
UserPreAlertingAnnouncementModifyRequest	USER_LEVEL
UserPreAlertingAnnouncementModifyRequest20	USER_LEVEL
UserPreferredCarrierUserGetRequest	USER_LEVEL
UserPreferredCarrierUserModifyRequest	USER_LEVEL
UserPrepaidGetRequest	USER_LEVEL
UserPrepaidModifyRequest	SERVICE_PROVIDER_LEVEL
UserPrimaryEndpointAdvancedSettingGetRequest	USER_LEVEL
UserPrimaryEndpointAdvancedSettingModifyRequest	USER_LEVEL
UserPriorityAlertAddCriteriaRequest	USER_LEVEL
UserPriorityAlertAddCriteriaRequest16	USER_LEVEL
UserPriorityAlertDeleteCriteriaRequest	USER_LEVEL



Transaction	Authorization Level
UserPriorityAlertGetCriteriaRequest	USER_LEVEL
UserPriorityAlertGetCriteriaRequest16	USER_LEVEL
UserPriorityAlertGetCriteriaRequest21	USER_LEVEL
UserPriorityAlertModifyActiveCriteriaListRequest	USER_LEVEL
UserPriorityAlertModifyCriteriaRequest	USER_LEVEL
UserPrivacyGetAvailableMonitorsUserListRequest	USER_LEVEL
UserPrivacyGetRequest	USER_LEVEL
UserPrivacyGetRequest13mp17	USER_LEVEL
UserPrivacyModifyRequest	USER_LEVEL
UserPushNotificationGetRequest	USER_LEVEL
UserPushNotificationModifyRequest	USER_LEVEL
UserPushNotificationRegistrationDeleteRequest	SYSTEM_LEVEL
UserPushNotificationRegistrationGetListRequest	USER_LEVEL
UserPushToTalkGetAvailableUserListRequest	USER_LEVEL
UserPushToTalkGetRequest	USER_LEVEL
UserPushToTalkModifyRequest	USER_LEVEL
UserRemoteOfficeGetRequest	USER_LEVEL
UserRemoteOfficeModifyRequest	USER_LEVEL
UserResourcePriorityGetRequest	USER_LEVEL
UserResourcePriorityModifyRequest	GROUP_LEVEL
UserRouteListGetRequest	USER_LEVEL
UserRouteListGetRequest22	USER_LEVEL
UserRouteListModifyRequest	GROUP_LEVEL
UserRoutePointCallDispositionCodeGetAvailableListRequest	USER_LEVEL
UserRoutePointSupervisorGetListRequest	USER_LEVEL
UserRoutePointSupervisorModifyListRequest	USER_LEVEL
UserScheduleAddEventRequest	USER_LEVEL
UserScheduleAddRequest	USER_LEVEL
UserScheduleDeleteEventListRequest	USER_LEVEL
UserScheduleDeleteListRequest	USER_LEVEL
UserScheduleGetEventDetailListRequest	USER_LEVEL
UserScheduleGetEventListRequest	USER_LEVEL
UserScheduleGetEventRequest	USER_LEVEL
UserScheduleGetListRequest	USER_LEVEL
UserScheduleGetListRequest17sp1	USER_LEVEL



Transaction	Authorization Level
UserScheduleModifyEventRequest	USER_LEVEL
UserScheduleModifyRequest	USER_LEVEL
UserSecurityClassificationGetRequest	USER_LEVEL
UserSecurityClassificationGetRequest22	USER_LEVEL
UserSecurityClassificationModifyRequest	GROUP_LEVEL
UserSelectiveCallAcceptanceAddCriteriaRequest	USER_LEVEL
UserSelectiveCallAcceptanceAddCriteriaRequest16	USER_LEVEL
UserSelectiveCallAcceptanceDeleteCriteriaRequest	USER_LEVEL
UserSelectiveCallAcceptanceGetCriteriaListRequest	USER_LEVEL
UserSelectiveCallAcceptanceGetCriteriaRequest	USER_LEVEL
UserSelectiveCallAcceptanceGetCriteriaRequest16	USER_LEVEL
UserSelectiveCallAcceptanceGetCriteriaRequest21	USER_LEVEL
UserSelectiveCallAcceptanceModifyActiveCriteriaListRequest	USER_LEVEL
UserSelectiveCallAcceptanceModifyCriteriaRequest	USER_LEVEL
UserSelectiveCallRejectionAddCriteriaRequest	USER_LEVEL
UserSelectiveCallRejectionAddCriteriaRequest16	USER_LEVEL
UserSelectiveCallRejectionDeleteCriteriaRequest	USER_LEVEL
UserSelectiveCallRejectionGetCriteriaListRequest	USER_LEVEL
UserSelectiveCallRejectionGetCriteriaRequest	USER_LEVEL
UserSelectiveCallRejectionGetCriteriaRequest16	USER_LEVEL
UserSelectiveCallRejectionGetCriteriaRequest16sp1	USER_LEVEL
UserSelectiveCallRejectionGetCriteriaRequest21	USER_LEVEL
UserSelectiveCallRejectionModifyActiveCriteriaListRequest	USER_LEVEL
UserSelectiveCallRejectionModifyCriteriaRequest	USER_LEVEL
UserSelectiveCallRejectionModifyCriteriaRequest16	USER_LEVEL
UserSequentialRingAddCriteriaRequest	USER_LEVEL
UserSequentialRingAddCriteriaRequest16	USER_LEVEL
UserSequentialRingDeleteCriteriaRequest	USER_LEVEL
UserSequentialRingGetCriteriaRequest	USER_LEVEL
UserSequentialRingGetCriteriaRequest16	USER_LEVEL
UserSequentialRingGetRequest13mp16	USER_LEVEL
UserSequentialRingGetRequest14sp4	USER_LEVEL
UserSequentialRingModifyCriteriaRequest	USER_LEVEL
UserSequentialRingModifyRequest	USER_LEVEL
UserSeriesCompletionGetRequest	USER_LEVEL



Transaction	Authorization Level
UserServiceAssignListRequest	GROUP_LEVEL
UserServiceGetAssignmentListRequest	USER_LEVEL
UserServiceIsAssignedRequest	USER_LEVEL
UserServiceUnassignListRequest	GROUP_LEVEL
UserSharedCallAppearanceAddEndpointRequest14	USER_LEVEL
UserSharedCallAppearanceAddEndpointRequest14sp2	USER_LEVEL
UserSharedCallAppearanceDeleteEndpointListRequest14	USER_LEVEL
UserSharedCallAppearanceGetEndpointRequest	USER_LEVEL
UserSharedCallAppearanceGetRequest14	USER_LEVEL
UserSharedCallAppearanceGetRequest14sp2	USER_LEVEL
UserSharedCallAppearanceGetRequest16sp2	USER_LEVEL
UserSharedCallAppearanceGetRequest21sp1	USER_LEVEL
UserSharedCallAppearanceModifyEndpointRequest	USER_LEVEL
UserSharedCallAppearanceModifyRequest	USER_LEVEL
UserShInterfaceGetPublicIdDataRequest	SYSTEM_LEVEL
UserShInterfaceGetPublicIdDataRequest21sp1	SYSTEM_LEVEL
UserShInterfaceGetUserIdDataRequest	SYSTEM_LEVEL
UserShInterfaceGetUserIdDataRequest21sp1	SYSTEM_LEVEL
UserShInterfaceModifyRequest	SYSTEM_LEVEL
UserShInterfacePublicIdentityRefreshTaskStartRequest	SYSTEM_LEVEL
UserSilentAlertingGetRequest	USER_LEVEL
UserSilentAlertingModifyRequest	USER_LEVEL
UserSimultaneousRingFamilyAddCriteriaRequest	USER_LEVEL
UserSimultaneousRingFamilyAddPhoneNumberRequest	USER_LEVEL
UserSimultaneousRingFamilyDeleteCriteriaRequest	USER_LEVEL
UserSimultaneousRingFamilyDeletePhoneNumberRequest	USER_LEVEL
UserSimultaneousRingFamilyGetCriteriaRequest	USER_LEVEL
UserSimultaneousRingFamilyGetPhoneNumberRequest	USER_LEVEL
UserSimultaneousRingFamilyGetRequest	USER_LEVEL
UserSimultaneousRingFamilyGetRequest14sp4	USER_LEVEL
UserSimultaneousRingFamilyGetRequest17	USER_LEVEL
UserSimultaneousRingFamilyModifyCriteriaRequest	USER_LEVEL
UserSimultaneousRingFamilyModifyPhoneNumberRequest	USER_LEVEL
UserSimultaneousRingFamilyModifyRequest	USER_LEVEL
UserSimultaneousRingFamilyModifyRequest14sp4	USER_LEVEL



Transaction	Authorization Level
UserSimultaneousRingFamilyModifyRequest17	USER_LEVEL
UserSimultaneousRingPersonalAddCriteriaRequest	USER_LEVEL
UserSimultaneousRingPersonalAddPhoneNumberRequest	USER_LEVEL
UserSimultaneousRingPersonalDeleteCriteriaRequest	USER_LEVEL
UserSimultaneousRingPersonalDeletePhoneNumberRequest	USER_LEVEL
UserSimultaneousRingPersonalGetCriteriaRequest	USER_LEVEL
UserSimultaneousRingPersonalGetPhoneNumberRequest	USER_LEVEL
UserSimultaneousRingPersonalGetRequest	USER_LEVEL
UserSimultaneousRingPersonalGetRequest14sp4	USER_LEVEL
UserSimultaneousRingPersonalGetRequest17	USER_LEVEL
UserSimultaneousRingPersonalModifyCriteriaRequest	USER_LEVEL
UserSimultaneousRingPersonalModifyPhoneNumberRequest	USER_LEVEL
UserSimultaneousRingPersonalModifyRequest	USER_LEVEL
UserSimultaneousRingPersonalModifyRequest14sp4	USER_LEVEL
UserSimultaneousRingPersonalModifyRequest17	USER_LEVEL
UserSingleSignOnCreateDeviceTokenRequest	USER_LEVEL
UserSMDIMessageDeskAddServerRequest	GROUP_LEVEL
UserSMDIMessageDeskDeleteServerListRequest	GROUP_LEVEL
UserSMDIMessageDeskGetRequest	GROUP_LEVEL
UserSMDIMessageDeskGetServerListRequest	GROUP_LEVEL
UserSMDIMessageDeskModifyRequest	GROUP_LEVEL
UserSpeedDial100AddListRequest	USER_LEVEL
UserSpeedDial100DeleteListRequest	USER_LEVEL
UserSpeedDial100GetListRequest	USER_LEVEL
UserSpeedDial100GetListRequest17sp1	USER_LEVEL
UserSpeedDial100GetRequest	USER_LEVEL
UserSpeedDial100ModifyListRequest	USER_LEVEL
UserSpeedDial8GetListRequest	USER_LEVEL
UserSpeedDial8ModifyListRequest	USER_LEVEL
UserTerminatingAlternateTrunkIdentityGetRequest	USER_LEVEL
UserTerminatingAlternateTrunkIdentityModifyRequest	GROUP_LEVEL
UserThirdPartyVoiceMailSupportGetRequest13mp16	USER_LEVEL
UserThirdPartyVoiceMailSupportGetRequest17	USER_LEVEL
UserThirdPartyVoiceMailSupportModifyRequest	USER_LEVEL
UserTimeScheduleAddRequest	USER LEVEL



Transaction	Authorization Level
UserTimeScheduleDeleteRequest	USER_LEVEL
UserTimeScheduleGetListRequest	USER_LEVEL
UserTimeScheduleGetRequest	USER_LEVEL
UserTimeScheduleModifyRequest	USER_LEVEL
UserTwoStageDialingGetRequest13Mp20	USER_LEVEL
UserTwoStageDialingModifyRequest	USER_LEVEL
UserVideoAddOnGetRequest14	USER_LEVEL
UserVideoAddOnGetRequest19	USER_LEVEL
UserVideoAddOnGetRequest22	USER_LEVEL
UserVideoAddOnModifyRequest14	USER_LEVEL
UserVoiceMessagingUserAddAliasListRequest	USER_LEVEL
UserVoiceMessagingUserDeleteAliasListRequest	USER_LEVEL
UserVoiceMessagingUserGetAdvancedVoiceManagementRequest	USER_LEVEL
UserVoiceMessagingUserGetAdvancedVoiceManagementRequest14sp3	USER_LEVEL
UserVoiceMessagingUserGetAliasListRequest	USER_LEVEL
UserVoiceMessagingUserGetDistributionListRequest	USER_LEVEL
UserVoiceMessagingUserGetGreetingRequest13mp16	USER_LEVEL
UserVoiceMessagingUserGetGreetingRequest16	USER_LEVEL
UserVoiceMessagingUserGetGreetingRequest18	USER_LEVEL
UserVoiceMessagingUserGetGreetingRequest18sp1	USER_LEVEL
UserVoiceMessagingUserGetGreetingRequest20	USER_LEVEL
UserVoiceMessagingUserGetOutgoingSMDIMWIRequest	USER_LEVEL
UserVoiceMessagingUserGetVoiceManagementRequest13mp8	USER_LEVEL
UserVoiceMessagingUserGetVoiceManagementRequest17	USER_LEVEL
UserVoiceMessagingUserGetVoicePortalPasswordInfoRequest	USER_LEVEL
UserVoiceMessagingUserGetVoicePortalRequest	USER_LEVEL
UserVoiceMessagingUserGetVoicePortalRequest16	USER_LEVEL
UserVoiceMessagingUserGetVoicePortalRequest20	USER_LEVEL
UserVoiceMessagingUserModifyAdvancedVoiceManagementRequest	USER_LEVEL
UserVoiceMessagingUserModifyDistributionListRequest	USER_LEVEL
UserVoiceMessagingUserModifyGreetingExecutionServerRequest	USER_LEVEL
UserVoiceMessagingUserModifyGreetingRequest	USER_LEVEL
UserVoiceMessagingUserModifyGreetingRequest16	USER_LEVEL
UserVoiceMessagingUserModifyGreetingRequest20	USER_LEVEL
UserVoiceMessagingUserModifyOutgoingSMDIMWIRequest	USER_LEVEL



T	Audhardardar Laval
Transaction	Authorization Level
UserVoiceMessagingUserModifyRequest	USER_LEVEL
UserVoiceMessagingUserModifyRequest23	USER_LEVEL
UserVoiceMessagingUserModifyVoiceManagementRequest	USER_LEVEL
UserVoiceMessagingUserModifyVoicePortalExecutionServerRequest	USER_LEVEL
UserVoiceMessagingUserModifyVoicePortalPasswordRequest	USER_LEVEL
UserVoiceMessagingUserModifyVoicePortalRequest	USER_LEVEL
UserVoiceMessagingUserModifyVoicePortalRequest16	USER_LEVEL
UserVoiceMessagingUserModifyVoicePortalRequest20	USER_LEVEL
UserVoicePortalCallingGetRequest	USER_LEVEL
UserVoicePortalCallingModifyRequest	USER_LEVEL
UserZoneCallingRestrictionsGetRequest	USER_LEVEL
UserZoneCallingRestrictionsModifyRequest	SERVICE_PROVIDER_LEVEL
VerifySessionIsValidRequest	USER_LEVEL



14 Appendix C: Client Licenses Mapping

This section provides a mapping of the Client Licenses 1 through 21 user services.

License	Service
Client License 1	
Client License 2	
Client License 3	BroadWorks Assistant–Enterprise (until Release 22.0)
Client License 4	BroadWorks Receptionist
Client License 5	Polycom Web Browser
Client License 6	Bria For BroadWorks (until Release 16.0)
Client License 7	
Client License 8	BroadWorks Assistant (until Release 22.0)
Client License 9	BroadWorks Assistant – Mobile
Client License 10	
Client License 11	BroadWorks Communicator
Client License 12	BroadWorks Communicator Multimedia
Client License 13	BroadWorks Communicator G.729
Client License 14	Office Communicator Tab (until Release 17)
Client License 15	
Client License 16	UC Connect (until Release 22.0)
Client License 17	Business Communicator Mobile
Client License 18	Business Communicator Desktop
Client License 19	MobileLink
Client License 20	Lync Softphone – Premium CODECS (starting in 17sp4)
Client License 21	Lync Softphone – Premium CODECS – Lab License (starting in 17sp4)
Client License 22	Reserved
Client License 23	Reserved
Client License 24	Reserved



Acronyms and Abbreviations

API Application Programming Interface

AS **Application Server**

Axis Apache Extensible Interaction System

BroadWorks Common Communication Transport BCCT

CAP Client Application Protocol CLI Command Line Interface **CPL** Call Processing Language

DN **Directory Number**

DTD **Document Type Definition EMS** Element Management System **FAQ** Frequently Asked Question

FTP File Transfer Protocol **GUI** Graphical User Interface HTML

Hypertext Markup Language

HTTPS Hypertext Transfer Protocol Secure Sockets

IAD Integrated Access Device

IΡ Internet Protocol

MD5 Message Digest 5 algorithm MIB Management Information Base

MP Maintenance Patch NS **Network Server**

OCI Open Client Interface

OCI-P Open Client Interface-Provisioning

ocs **Open Client Server**

OSS **Operations Support System** SHA Secure Hash Algorithm

SNAP Subnetwork Access Protocol SOAP Simple Object Access Protocol

SSL Secure Sockets Layer

TCP/IP Transmission Control Protocol/Internet Protocol

TN Telephone Number

URL Uniform Resource Locator

VM Virtual Machine

WSDL Web Service Definition Language

cisco.

WSF Web Server Farm

XML eXtensible Markup LanguageXsi Xtended Services InterfaceXsp Xtended Services Platform