# Data requirements of the R package glatos

Updated: 2019-02-26

# Contents

1	Ove	rview	2
	1.1	Data requirements	. 2
		1.1.1 Detection data	. 2
		1.1.2 Receiver location data	. 3
		1.1.3 Animal tagging and biological data	. 3
		1.1.4 Transmitter specification data	. 4
	1.2	Data objects and classes	. 4
2	App	pendix: GLATOS network standard data files	4
	2.1	Detection file	. 4
	2.2	Receiver location file	. 6
	2.3	Project workbook file	. 7

# 1 Overview

This vignette describes minimum data requirements of the R package glatos to inform loading of data that is not in standard file formats of the Great Lakes Acoustic Telemetry Observation System (GLATOS) or the Ocean Tracking Network (OTN). Strictly speaking, there are no requirements of the glatos package as a whole, but input data are checked within each individual function to determine if requirements are met. The set of data requirements described in this vignette, if followed, will ensure compatibility with all glatos functions.

For data in standard GLATOS and OTN formats, use of built-in data loading functions (see the Data Loading vignette for details) will ensure that resulting data objects meet the requirements of *glatos* functions. For reference, the appendix provides data field definitions (data dictionary) of standard data files obtained from the GLATOS Data Portal.

# 1.1 Data requirements

#### 1.1.1 Detection data

glatos functions that accept detection data as input will typically require a data.frame with one or more of the following columns, named and defined exactly as described below:

- detection\_timestamp\_utc A POSIXct object with detection timestamps (e.g., "2012-04-29 01:48:37").
- receiver\_sn A character vector with unique receiver identifier. This is needed to associate each record with a specific receiver (a physical instrument).
- deploy\_lat A numeric vector with latitude (decimal degrees, NAD83) of geographic location where receiver was deployed. Must be negative for locations in the southern hemishere and positive for locations in the northern hemisphere (e.g., 43.39165).
- deploy\_long A numeric vector with longitude (decimal degrees, NAD83) of geographic location where receiver was deployed. Must be negative for locations in the western hemishere and positive for locations in the eastern hemisphere (e.g., -83.99264).
- transmitter\_codespace A character string with transmitter code space (e.g., "A69-1061" for Vemco PPM coding). In combination with transmiter\_id, this is needed to associate each record with a specific transmitter (a physical instrument).
- transmitter\_id A character string with transmitter ID code (e.g., "1363" for Vemco PPM coding).

  In combination with transmitter\_codespace, this is needed to associate each record with a specific transmitter (a physical instrument).
- sensor\_value A numeric sensor measurement (e.g., an integer for 'raw' Vemco sensor tags).
- sensor\_unit A character string with sensor\_value units (e.g., "ADC"\* for 'raw' Vemco sensor tag detections).\*
- animal\_id A character string with individual animal identifier. This is used to associate each record with an individual animal.

Additionally, some functions will require at least one categorical column to identify location (or group of locations). These can be specified by the user, but examples of such columns in a GLATOS standard detection file are:

• Examples of columns that identify receiver locations (or groups)

```
glatos_array
```

- station
- glatos\_project\_receiver

Any data frame that contains the above columns should be compatible with all glatos functions that accept detection data as input. Use of the data loading functions read\_glatos\_detections and read\_otn\_detections will ensure that these columns are present, but can only be used on data in GLATOS and OTN formats. Data in other formats will need to be loaded using other functions (e.g., read.csv, fread, etc.) and compatibility with glatos functions will need to be carefully checked. For data loading examples, see the Data Loading vignette.

#### 1.1.2 Receiver location data

glatos functions that accept receiver location data as input will typically require a data.frame with one or more of the following columns, named and defined exactly as described below:

- deploy\_lat A numeric vector with latitude (decimal degrees, NAD83) of geographic location where receiver was deployed. Must be negative for locations in the southern hemishere and positive for locations in the northern hemisphere (e.g., 43.39165).
- deploy\_long A numeric vector with longitude (decimal degrees, NAD83) of geographic location where receiver was deployed. Must be negative for locations in the western hemishere and positive for locations in the eastern hemisphere (e.g., -83.99264).
- deploy\_date\_time A POSIXct object with timestamp when receiver was deployed (e.g., "2012-04-29 01:48:37").
- recover\_date\_time A POSIXct object with timestamp when receiver was recovered (e.g., "2012-04-29 01:48:37").

Additionally, some functions will require at least one categorical column to identify location (or group of locations). These can be specified by the user, but examples of such columns in a GLATOS standard receiver locations file are:

- Examples of columns that identify receiver locations (or groups)
  - glatos\_array
  - station
  - $\ glatos\_project\_receiver$

Use of the data loading function read\_glatos\_receivers will ensure that these columns are present, but can only be used on data in GLATOS format. Data in other formats will need to be loaded using other functions (e.g., read.csv, fread, etc.) and compatibility with glatos functions will need to be carefully checked. For data loading examples, see the Data Loading vignette.

# 1.1.3 Animal tagging and biological data

There are currently no *glatos* functions that require animal tagging and biological data other than those columns present in the required *detection* data. Therefore, there are no formal requirements of such data in the package. Nonetheless, the *read\_glatos\_workbook* function can be used to facilitate loading animal tagging and biological data from a standard GLATOS project workbook (\*.xlsm file) into an R session.

Use of the data loading function  $read\_glatos\_workbook$  will ensure that animal data are loaded efficiently and consistently among users, but can only be used on data in GLATOS format. Data in other formats will need to be loaded using other functions (e.g., read.csv, fread, etc.). Although there are currently no glatos requirements of animal data, any future requirements might be expected to be consistent with the  $glatos\_animals$  class.

#### 1.1.4 Transmitter specification data

There are currently no *glatos* functions that require transmitter specification data. Therefore, there are no formal requirements of such data in the package. Nonetheless, the *read\_vemco\_tag\_specs* function can be used to facilitate loading transmitter specification data from a standard VEMCO tag spec (\*.xls) file provided to tag purchasers from VEMCO.

Use of the data loading function  $read\_vemco\_tag\_specs$  will ensure that transmitter specification data are loaded efficiently and consistently among users, but can only be used on data in VEMCO standard format. Data in other formats will need to be loaded using other functions (e.g., read.csv, fread, etc.). Although there are currently no glatos requirements of transmitter specification data, any future requirements might be expected to be consistent with the output of  $read\_vemco\_tag\_specs$ .

# 1.2 Data objects and classes

Most glatos data loading functions return an object with a glatos-specific S3 class name (e.g., glatos\_detections) in addition to a more general class (e.g., data.frame). Currently, no methods exist for glatos classes and such classes are not explicitly required by any function, so glatos classes can merely be thought of as labels showing that the objects were produced by a glatos function and will therefore be compatible with other glatos functions. Beware, as with any S3 class, that it is possible to modify a glatos object to the point that is will no longer be compatible with glatos functions.

# 2 Appendix: GLATOS network standard data files

Detection data from the GLATOS network are queried for each individual project and made available through the project-specific GLATOS Data Portal. Each detection export is a zipped folder that contains multiple files. This appendix describes the structure of two of the comma-separated-value files (.csv) contained in the standard export: detections and receiver locations. These files can be identified by file name. The file that contains "detectionsWithLocs" (e.g., "HECWL\_detectionsWithLocs\_20180627\_172857.csv") contains detections from acoustic receivers in the GLATOS network for all tags in a project. This file contains columns that identify when and where a fish was released and detected, some biological attributes of tagged fish, and tag model and specs. The .csv file with "receiverLocations" in the file name contains deployment and recovery operating schedules for all receivers in the GLATOS network. By combining the information in these two files, researchers are able determine when and where a tagged fish was detected in the GLATOS network and also locations where receivers were deployed that did not detect their tagged fish. Fields (columns) in both files are described below.

#### 2.1 Detection file

A comma-separated-values text file with the following columns:

- animal\_id A field that uniquely identifies tagged animal. This field is used to associate each record with an individual animal.
- detection\_timestamp\_utc An alpha-numeric field in the standard POSIXct format (YYYY-MM-DD HH:MM:SS, i.e., "2012-04-29 01:48:37") that represents the date and time when a tag was detected in UTC timezone.
- glatos\_array Character field identifies subgroup of receivers, usually in close spatial proximity.
- $\bullet \ \ \mathbf{station\_no} \ \ \mathit{Character\ field\ that\ identifies\ receiver\ mooring\ within\ glatos\_array}.$

- transmitter\_codespace A character field with transmitter code space (e.g., "A69-1061" for Vemco PPM coding). In combination with transmiter\_id, this is needed to associate each record with a specific transmitter (a physical instrument).
- transmitter\_id A character field with transmitter ID code (e.g., 1363 for Vemco PPM coding). In combination with transmitter\_codespace, this is needed to associate each record with a specific transmitter (a physical instrument).
- sensor\_value A numeric sensor measurement (e.g., an integer for 'raw' Vemco sensor tags).
- sensor\_unit A character field with sensor\_value units (e.g., ADC for 'raw' Vemco sensor tag detections).
- deploy\_lat A numeric field with latitude (decimal degrees, NAD83) of geographic location where receiver was deployed. Must be negative for locations in the southern hemishere and positive for locations in the northern hemisphere (e.g., 43.39165).
- deploy\_long A numeric field with longitude (decimal degrees, NAD83) of geographic location where receiver was deployed. Must be negative for locations in the western hemishere and positive for locations in the eastern hemisphere (e.g., -83.99264).
- receiver\_sn A character field that uniquely identifies each receiver. This is needed to associate each detection with a specific receiver (a physical instrument).
- tag\_type Character field that identifies type of tag used (e.g., acoustic).
- tag\_model Character field that identifies tag model used.
- tag\_serial\_number Character field that identifies tag serial number.
- common\_name\_e Character field with fish species common name in english.
- capture location Character field with description of where fish were captured (capture location).
- length Numeric field of length of tagged fish.
- weight Numeric field of weight of tagged fish.
- sex Character field that identifies sex of fish released.
- release group Character field that identifies group of released fish (release group)
- release\_location Character field that describes where fish was released.
- release\_latitude A numeric field with latitude (decimal degrees, NAD83) of geographic location where tag was deployed. Must be negative for locations in the southern hemishere and positive for locations in the northern hemisphere (e.g., 43.39165).
- release\_longitude A numeric field with longitude (decimal degrees, NAD83) of geographic location where tag was deployed. Must be negative for locations in the western hemishere and positive for locations in the eastern hemisphere (e.g., 43.39165).
- utc\_release\_date\_time An alpha-numeric field in the standard POSIXct format (YYYY-MM-DD HH:MM:SS, i.e., "2012-04-29 01:48:37") that represents the date and time when a tag was released in UTC timezone.
- glatos\_project\_transmitter GLATOS five-character code of project associated with transmitter.
- glatos\_project\_receiver GLATOS five-character code of project associated with receiver.
- glatos\_tag\_recovered The values of the glatos\_tag\_recovered field is either "yes", or "no". A "yes" value indicates tag was recovered after deployment (e.g., tagged fish caught by angler) and "no" means the tag is still at large.

- glatos\_caught\_date If tag is recovered, the date (in YYYY-MM-DD format) of tag recovery is in the "glatos\_caught\_date" field.
- station Character field that combines glatos\_array and station\_no to identify receiver mooring within project.
- min\_lag minimum time interval (seconds) between current detection and another detection from the same tag on the same receiver. Field is used to identify possible false detections.

### 2.2 Receiver location file

A comma-separated-values text file with the following columns:

- station Character field that combines glatos\_array and station\_no to identify receiver mooring within project.
- glatos\_array Character field identifies subgroup of receivers, usually in close spatial proximity.
- station\_no Character field that identifies receiver mooring within glatos\_array.
- consecutive\_deploy\_no Integer field of the number of times a receiver was deployed at a location.
- intend\_lat Numeric field with intended geographic deployment latitude (decimal degrees, NAD83).

  Must be negative for locations in southern hemisphere and positive for locations in northern hemisphere.
- intend\_long Numeric field with intended geographic deployment longitude (decimal degrees, NAD83).

  Must be positive for values in the eastern hemisphere and negative for locations in the western hemisphere.
- deploy\_lat Numeric field of actual geographic deployment latitude (decimal degrees, NAD83). Must be negative for locations in southern hemisphere and positive for locations in northern hemisphere.
- deploy\_long Numeric fields of actual geographic deployment longitude (decimal degrees, NAD83) must be positive for values in the eastern hemisphere and positive for locations in the western hemisphere.
- recover\_lat Numeric fields of geographic latitude where receivers were recovered (decimal degrees, NAD83). Must be negative for locations in southern hemisphere and positive for locations in northern hemisphere.
- recover\_long Numeric fields of geographic longitude where receivers were recovered (decimal degrees, NAD83). Must be negative for locations in western hemisphere and positive for locations in eastern hemisphere.
- deploy\_date\_time Alpha-numeric fields in standard POSIX format (YYYY-MM-DD HH:MM:SS, i.e., "2012-04-29 01:43:43") that represents the date and time in UTC timezone when a receiver was deployed.
- recover\_date\_time Alpha-numeric fields in standard POSIX format (YYYY-MM-DD HH:MM:SS, i.e., "2012-04-29 01:43:43") that represents the date and time in UTC timezone when a receiver was recovered (recover\_date\_time).
- bottom\_depth Numeric field that represents the water depth (m; between bottom and surface) at location where receiver was deployed.
- riser\_length Numeric field that represents the height of mooring equipment off of bottom (m).

- instrument\_depth Numeric field that represents the distance (m) between the equipment and the water surface.
- ins\_model\_no Character field with user-defined model name of instrument deployed.
- glatos ins frequency Integer field with instrument operating frequency (e.g., 69, 180).
- ins\_serial\_no Character field of instrument model number, uniquely identifies a physical instrument.
- deployed\_by Character field that contain name of person who deployed receiver.
- comments Character fields that contain comments recorded during deployment.
- glatos\_seasonal Character field containing either "yes" or "no". Identifies seasonal ("yes") and annual receiver deployments ("no").
- glatos\_project Character field containing unique 5-letter project identification code. This code is created by user when the project is initiated and submitted to GLATOS.
- glatos\_vps Character field containing either "yes" or "no". If a receiver is part of a Vemco Positioning Study (VPS) then value equals "yes", otherwise field value is "no".

## 2.3 Project workbook file

A macro-enabled Microsoft Excel workbook (\*.xlsm) file containing the following worksheets:

- Locations Contains descriptive data associated with receiver locations.
- Deployment Contains data associated with deployment of telemetry receivers.
- Recovery Contains data associated with recovery of telemetry receivers.
- Tagging Contains data associated with tagging of animals, including data associated with the animal and transmitter.

For more details about the structure of this file, see the Data Submission Package in the GLATOS Data Portal.