
NOMAD

Getting ready to go out and record sites: Uploading Maps onto the Nomad

1. Turn on the Dell computer, the screen should look like this. The tools for uploading are on the left side of the screen.



2. Turn off all programs on the Nomad, then connect it to the Dell with the USB cable and turn the Nomad on (if it is not already). This ActiveSync window will appear. The ActiveSync window should appear like this on the laptop screen showing that the NomadAlpha handheld is connected to the laptop (nothing will show on the handheld, this is normal). If the window shows 'connecting' or takes a very long time to show 'connected' (more than two minutes), then turn off the handheld, unplug the USB cable and reboot the handheld (press and hold the on/off




button for about 5 seconds, until the onscreen boot countdown is complete), restart the laptop and then repeat.

3. Now that the connection is established (it's a good idea to recharge the Nomad battery at this time by plugging in the power plug), we can select the map to put on the Nomad. **Double-click '1. Select Map'** on the desktop, this opens the program with the maps.



Wait a few moments for the program to open, it can take a minute or two.

4. Use the zoom and pan tools to display the area to be surveyed in the map window. The map that is displayed onscreen will be the extent of the map available on the Nomad. To see the scale of the map view, click on the 'layout' button down on the lower left of the screen. You can also use the 'ruler' tool to measure directly on the map. Before the next step, return to the map view by clicking on the 'map' button down on the lower left of the screen, next to the layout button.




5. When you've got the area displayed that you need for the day's survey, click the button 'Get Data for ArcPad 7' on the upper left of the window.




6a. This window will appear. Click 'Select All and the click 'Next'




6b. A similar second window will appear, do the same: Click 'Select All and the click 'Next'





8. Wait. The program will be


busy for some time (up to 5 minutes) and will not always show you that it's working. Best not to attempt to do anything else with the computer at all until you see this window showing that it's finished. Check to see that everything was successful (if not, try again but zoom in further on the map so that the image file will be smaller). Click 'OK'



- 9. **NOTE!** The screen usually freezes and you must click on the hand tool then move the map a fraction to unfreeze it. You will know it worked because the globe at the bottom right will spin then disappear.
- 10. Now **close the program** and click 'Yes' to save.



NOTE: only do this if you have completed step 9 and the globe has disappeared.





'2. Map files to upload to the Nomad'. This will show the map files ready to be uploaded.




Close

- 12. Also on the desktop you should see the ActiveSync window, **click on 'Explore'** to open the Nomad
- 13. **Go to the Root directory** called 'Mobile Device'







14. **Drag and drop** the folder with the new map data (in this example it's NA080419) **from the Dell to the Nomad root directory**



15. This window **may** appear, **click 'OK'** If it doesn't appear, don't panic.




Wait. The files will be converted and transferred. It shouldn't take long. Don't touch anything.




16. On the desktop, double-click the folder '3. Upload recording forms'

Then double-click on the folder Nomad A (or Nomad B)





17. **Select all files** in the **Nomad A** or **Nomad B** folder on the Dell (press Control-A) then **drag and drop** into the folder with the day's survey data in the root directory (in this example it's NA071225). These files contain the archaeological recording forms



Wait. The files will be converted and transferred. It shouldn't take long. Don't touch anything.



18. If you feel confident, to save time for the upload to the second Nomad you can simply change the file name in ODX_GIS_SurveyDataOut from NAxxxxxx to NBxxxxxx (or vice versa) and then drag that folder onto the Nomad root directory. You will still need to put on the recording forms specific to that Nomad, don't change any folder names here!

19. When it's finished, close all windows on the desktop, disconnect the Nomad and turn off the Dell. Ready to go!

