# **Lesson 8 - Gas Optimisation**

## **Gas Optimisation Introduction**



"The real problem is that programmers have spent far too much time worrying about efficiency in the wrong places and at the wrong times; premature optimization is the root of all evil (or at least most of it) in programming. - Donald Knuth

### **Optimisation Process**

Be clear what circumstances you are optimising for, and decide upon an acceptable level of performance. You may have to make trade offs between different scenarios.

The correctness of the code is always the priority.

Assuming your code is correct, and you have a suite of unit tests to confirm that.

### **Optimisation steps**

- 1. Measure the performance (context is important here)
- Pick the change that will have the most impact
- 3. Refactor the code
- 4. Confirm the code correctness using the unit tests
- 5. Go to 1

## **Basic Techniques**

Remove redundant functionality and code

One of the easiest gains is to remove functionality that is excessive, or no longer needed.

Similarly removing redundant code will reduce deployment cost.

#### Take shortcuts

- 1. Break out of loops as early as possible
- 2. For 2 functions as follows

```
a(x) is low cost
```

b(x) is expensive

The ordering should be

```
a(x) | | b(x)
a(x) && b(x)
```

### **Storage**

Since the SSTORE operation is one of the most expensive, there is significant potential for gas savings when using storage.

Saving one slot that is a word of 256 bits to Storage (SSTORE) is 22,100/20,000 gas when

you initially set it from zero to non-zero, depending on whether it is an initial access.

Storage slots are either warm or cold.

- Cold: storage slot hasn't been accessed during this transaction.
- Warm: storage slot has been accessed during this transaction.

5,000/2,900 gas is spent when an already used Storage slot is rewritten.

Reading a storage slot using SLOAD takes 100 gas.

# Consider

- 1. Storing data elsewhere
- 2. Not storing intermediate steps in storage, just the final result.

### **Memory versus Storage**

Memory is generally cheaper than storage but Copying between the memory and storage will cost some gas, so don't copy arrays from storage to memory, use a storage pointer (but beware of subtle bugs when doing this, a

Defi project was recently rekt by this)

Obviously some data needs to persist between function calls

The cost of memory is complicated, you "buy" it in chunks, the cost of which will go up quadratically after the first 724 bytes.

## Avoid repetitive checks

By being sure of the logic of your code, you may be able to remove redundant checks, having a test suite with good coverage will help this.

#### **Refunds**

Free Storage slots by zeroing corresponding variables as soon as you don't need them anymore. This will refund 15000 gas.

Some opcodes can trigger gas refunds, which reduces the gas cost of a transaction.

However the gas refund is applied at the end of a transaction, meaning that a transaction always need enough gas to run as if there was no refunds.

The amount of gas that can be refunded is also limited, to half of the total transaction cost before the hardfork London, otherwise to a fifth. Starting from the hardfork London also, only

SSTORE may trigger refunds. Before that, SELFDESTRUCT could also trigger refunds.

### **Data Types and Packing**

- Use bytes32 whenever possible, because it is the most optimized storage type.
- Type bytes should be used over byte[].
- If the length of bytes can be limited, use the lowest amount possible from bytes1 to bytes32.

#### **Strings**

Using bytes32 is cheaper than using the string type.

### Mapping vs. Array

Most of the time it will be better to use a mapping instead of an array because of its cheaper operations.

However, an array can be the correct choice when using smaller data types. Array elements are packed like other storage variables and the reduced storage space can outweigh the cost of an array's more expensive operations. This is most useful when working with large arrays.

Pack several blocks of information into one Storage slot if they are smaller than a word of 32 bytes. This can give significant savings. Specifically if according to the application logic, they are usually updated and accessed together. For example, a structure of 2 uint128 can be stored in one slot in a mapping instead of storing them separately.

For example take this code

```
language-none
Struct Data {
uint64 a;
uint64 b;
uint128 c;
uint256 d;
}
Data public data
constructor (uint64 _a,uint64 _b, uint128
_c, uint256 _d) public {
    Data.a = _a;
    Data b = b;
    Data c = _c;
```

```
Data.d = _d;
}
```

The SStore instruction is performed twice, once to store a,b,c and a second time to store d (the solc optimiser is able to work out this optimisation)

```
[ a ] [ b language Thone
c ]
[8 bytes / 64 bits] [8 bytes / 64 bits]
[16 bytes / 128 bits ]

[ d
]
[ 32 bytes / 256
bits ]
```

So generally is modifying a uint8 cheaper than modifying a uint256? ....

no...

storing a small number in a uint8 variable is not cheaper than storing it into a uint256 variable, because for storing, any smaller data is padded with zeros to fill the 32 bytes, requiring additional operations from the EVM and additional gas.

#### **Storage and Inheritance**

When we extend a contract, the variables in the child can be packed with the variables in the parent.

The order of variables is determined by C3 linearization. For most applications, all you need to know is that child variables come after parent variables.

### **Memory versus Storage**

Memory is generally cheaper than storage but Copying between the memory and storage will cost some gas, so don't copy arrays from storage to memory, use a storage pointer (but beware of subtle bugs when doing this, a Defi project was recently rekt by this) Obviously some data needs to persist between function calls

The cost of memory is .. complicated, you "buy" it in chunks, the cost of which will go up quadratically after a while. See lesson 3 notes.

Try adjusting the location of your variables playing with the keywords "storage" and "memory". Depending on the size and number of copying operations between Storage and Memory, switching to memory may or may not give improvements. All this is because of varying memory costs. So optimising here is not that obvious, and every case has to be considered individually.

### **Language Features**

#### **Variables**

- Use events rather than storing data
- Avoid public variables
- It may be good to avoid using storage, by employing memory arrays. If the size of the array is exactly known, fixed size memory arrays can be used to save gas.
- A simple optimisation in Solidity consists of naming the return value of a function. It is not needed to create a local variable then.

### **Functions**

Calling functions is relatively cheap (it is just a jump instruction), but it can degrade the compiler's attempts at storage optimisation.

### Memory, calldata and function parameters

Storing the input parameters in memory costs gas. For all public functions, the input parameters are copied to memory automatically. If a function is only called externally, it should be explicitly marked as external, in a way that these parameters are not stored into memory but are read from call data directly.

This can save gas when the function input parameters are huge.

**Function order** 

See Function order article

Each position will have an extra 22 gas, so

- Reduce public variables
- Put often called functions earlier (the order depends on the hash of the function name)

Tool to optimise <u>function name</u>

**Compress Input Data** 

See the example in <u>Compress Input Data Article</u>
they go from these function parameters

```
uint256 amountSell,
uint256 amountBuy,
address tokenSell,
address tokenBuy,
address user,
uint256 nonce,
uint256 gasFee,
uint256 takerFee,
uint256 makerFee,
uint256 joyPrice,
```

```
bool isBuy,
uint8 v,
byte32 r,
byte32 s
```

## to these

```
uint256 amountSell,
uint256 amountBuy,
uint256 data,
uint256 gasFee,
byte32 r,
byte32 s
```

without losing functionality by packing many of the parameters in the data field

#### **View Functions**

You are not paying for view functions that aren't transactions. But this doesn't mean they aren't consuming gas, they do. It is just that it is free when executed on the local EVM. However, if a view function is called in a transaction, all the gas matters.

#### **Modifiers**

Modifiers Increase Code Size you can make them functions instead

When using modifiers, the code of the modifiers is inserted at the start of the function at compile time, which can massively increase code size. So making a modifier a function call instead can help, as only the function call will be inserted at the start of the function.

### Loops

Due to the expensive SLOAD and SSTORE opcodes, managing a variable in storage is much more expensive than managing variables in memory. For this reason, storage variables should not be used in loops.

# For example

```
uint num = 0;
function expensiveLoop(uint x) public {
  for(uint i = 0; i < x; i++) {
    num += 1;
  }
}</pre>
```

do this instead

```
uint num = 0;
function lessExpensiveLoop(uint x) public
{
  uint temp = num;
  for(uint i = 0; i < x; i++) {
    temp += 1;
  }
  num = temp;
}</pre>
```

- Optimise loops to minimise the number and cost of instructions within the loop.
- Take unnecessary values out of the loop
- Predict values if possible
- Reduce the number of iterations by for example breaking out of loop as soon as possible
- Try to avoid unbounded loops

#### **Custom Errors**

Custom Errors Starting from Solidity v0.8.4, there is a convenient and gas-efficient way to explain to users why an operation failed through the use of custom errors. Until now, you could already use strings to give more information about failures (e.g., revert("Insufficient")

funds.");), but they are rather expensive, especially when it comes to deploy cost, and it is difficult to use dynamic information in them. Custom errors are defined using the error statement, which can be used inside and outside of contracts (including interfaces and libraries).

```
language-js
// SPDX-License-Identifier: GPL-3.0
pragma solidity ^0.8.4;
error Unauthorized();
contract VendingMachine {
        address payable owner =
payable(msg_sender);
        function withdraw() public {
                 if (msg.sender != owner){
                         revert
Unauthorized();
                 }
owner_transfer(address(this)_balance);
        }
}
```

#### **Events**

Here's the formula for a LOG gas cost:

k + unindexedBytes a + indexedTopics b where

k = 375

a = 8

b = 375

(Note also that if you use a bigger than 256 bit type for an indexed event topic, like bytes[1000] or something, then you still only pay 375, because in this case, only the Keccak hash of the value is actually indexed.)

## **Miscellaneous Optimisations**

### Use the optimiser

Make sure the optimiser is turned on when compiling your code, you can also adjust the number of runs it will use.

- Remove dead code
- Solidity version, later versions are probably better.
- Use optimization and set the counter to high values or leave the default 200.
   Setting it to 1 can be useful in a rare case when it's important to optimize contract

deployment, but not subsequent functions call.

- Use Libraries (wisely)
   When a public function of a library is called, the bytecode of that function is not made part of a client contract. Thus, complex logic should be put in libraries for keeping the contract size small. But there is a cost for calling the library function.
- Require and Assert
   Use "require" for all runtime conditions
   validations that can't be prevalidated on
   the compile time. And "assert" should be
   used only for static validations that
   normally never fail in a properly functioning
   code.

Reducing error messages text will decrease gas used by the function.

## Hash functions

keccak256: 30 gas + 6 gas for each word of input data

sha256: 60 gas + 12 gas for each word of input data

ripemd160: 600 gas + 120 gas for each word of

## input data

So if you don't have specific reasons to select another hash function, just use keccak256

**Tools and Measurement** 

## Web3:

```
web3.eth.estimateGas(callObject [,
callback])
```

can estimate the gas required for a transaction

There are gas reporter plug ins for Hardhat and Foundry

Sol2UML Visualisation Tool

See repo

It provides visualisation of storage, plus UML diagrams for the contract.

**Advanced Optimisation Techniques** 

**Optimiser details** 

Details about the optimiser **Docs** 

Solidity has 2 optimiser modules

- at opcode level
  - Tries to simplify expressions

- Can inline functions, which may help it simplify bytecode
- uses a rule list : Rules
- removes duplicates
- removes dead code
- Yul IR code level more powerful as it can operate across function calls.
  - Functions have fewer side effects so easier to judge if independent
  - Can remove functions that are multiplied by zero
  - Can reorder functions

#### **Number of runs**

### From the docs

"The number of runs (—optimize—runs) specifies roughly how often each opcode of the deployed code will be executed across the life—time of the contract.

This means it is a trade-off parameter between code size (deploy cost) and code execution cost (cost after deployment). A "runs" parameter of "1" will produce short but expensive code. In contrast, a larger "runs" parameter will produce

longer but more gas efficient code. The maximum value of the parameter is 2\*\*32-1."

Storage Layout

Examples of how different datatypes are stored, including dynamically sized items are illustrated on the sol2uml <u>site</u>

### Miscellaneous Techniques

Since Solidity doesn't perform garbage collection, conserve memory and storage by writing new values over unused old ones.

Keep data in calldata whenever possible, this has already paid for within the transaction, avoid copying unmodified function parameters to memory and simply read the value from calldata.

Inspect Solidity Compiler Yul Output
To see what your Solidity is doing under the hood, add -yul and -ir to your solc compiler options. This can help you understand your code, identify unsafe operation ordering, or compare gas usage between your Yul and Solidity code.

Become familiar with compiler options: <u>Solc</u>
<a href="Mailto:Solc">Solc</a>
<a href="Mailto:Solc">Compiler Options</a>

Utilise vanity addresses with many leading zeroes

If you have 2 addresses - 0x000000a4323... and 0x000000000f38210 because of the leading zeroes you can pack them both into the

same storage slot, then just prepend the necessary amount of zeroes when using them. This saves you storage when doing things such as checking the owner of a contract.

Be aware that using sub-32-byte values doesn't always save gas

Sub-32-byte values can save gas when packing, but decoding them requires extra gas. Use these values on a case-by-case basis.

Writing to an existing storage slot is more costeffective than using a new one
EIP-2200 changed gas dynamics, making it
cheaper to use tokens when holding at least 1
Wei. Learn about EIP-2200 to understand when
to use storage slots and when to leave them
empty. This applies to all Yul+ and Yul contracts
for memory management.

Ottilise iszero() often as the compiler optimises it intelligently Inserting iszero() before some logical pieces can reduce overall gas costs, so test it out before JUMP opcodes.

Using gas() with call() in Yul saves manual gas counting

Use gas() for the gas parameter to forward all available gas when using call() in Yul.

Store storage in code to save gas
Deploy desired storage in a new contract and
read from that address to save gas, particularly
when using SLOAD frequently.

Not all zero address checks in the NFT spec are necessary

Use Solmate's NFT contracts to reduce minting and usage costs, as the standard often needlessly prevents transfers to the void.

Avoid overflow checks if uint256(-1) calls can't cause overflow

Save gas by using unchecked {} in Solidity, avoiding safemath in counters, as the cost of calling a contract billions of times prevents attacks.

Pack structs in Solidity to save read operations Organise structs sequentially so they add up to multiples of 256 bits in size.

So uint112 uint112 uint256 vs uint112

```
uint256 uint112
```

This saves read operations needed to get a value

Make Solidity values constant when possible Replace known and constant values with literals to save gas and comment on their purpose.

Solidity modifiers can increase code size, so sometimes convert them to functions Modifiers' code is inserted at the function's start during compile time, which can significantly increase code size. Converting modifiers to function calls may reduce code size.

Use bitmaps, From bitmaps

For example, rather than

```
// people who showed up: 1, 3, 4,
8, 9
     uint8[] memory a = new uint8[](1,
0, 1, 1, 0, 0, 0, 1, 1, 0);
```

## we can do

```
// people who showed up: 1, 3, 4, 8, 9
```

```
uint16 a = 397; // equals
0110001101 in binary
```

## We can read the bits with

```
uint16 a = 397; // equals

0110001101 in binary

// Read bits at positions 3 and
7.

// Note that bits are 0-indexed,
thus bit 1 is at position 0, bit 2 is at
position 1, etc.

uint8 bit3 = a & (1 << 2)
uint8 bit7 = a & (1 << 6)</pre>
```

## **Example - Optimised Airdrop**

# See gist

### **Testing tips**

When you send ETH or tokens, don't just hardcode a fixed amount, add some random values as well, so you may catch some unpredictable behaviours depending on the amount.

If you enjoy optimising code you might want to try Solidity Gas golf

https://g.solidity.cc/