Search Vaspwiki

Main page Recent changes Random page Help about MediaWiki

What links here Related changes Special pages Printable version Permanent link Page information

Tools

Page Discussion Read View source View history

Requests for technical support from the VASP group should be posted in the VASP-forum.

## Improved Dimer Method

The dimer method<sup>[1]</sup> is a technique for the optimization of transition states. In VASP, the method improved by Heyden et al.(IDM) is implemented, detailed presentation of the method can be found in reference [2]. Algorithm for IDM consists of the following cyclically repeated steps:

- The curvature along the dimer axis is computed using finite diferences The initial dimer direction must be provided by user (see below).
- The dimer is rotated such as its axis is parallel with the direction of the maximal negative curvature.
- An optimization step is taken and the potential energy is maximized along the unstable direction (i.e. dimer axis) while it is minimized in all other directions.

The method is invoked by setting IBRION=44 in the INCAR file.

Furthermore, the user must specify the direction of the unstable mode. The corresponding 3N dimensional vector is defined in the POSCAR file after the lines with atomic coordinates and a separating blank line. Note that the dimer direction is automatically normalized, i.e. the norm of the dimer axis defined by user is irrelevant. An example of a POSCAR file for a simulation with the dimer method is given in the following:

```
ammonia flipping
1.
  0.0.
0.7.0.
0. 0. 8.
H N
3 1
cart
       -0.872954
                                        -0.504000
                                                          ! coordinates for atom 1
                         0.000000
        0.000000
                         0.000000
                                         1.008000
        0.872954
                         0.000000
                                        -0.504000
        0.000000
                         0.000000
                                         0.000000
                                                          ! coordinates for atom N
       ! here we define trial unstable direction:
        0.000001
                     0.522103
                                -0.000009
                                                  ! components for atom 1
                                 0.000000
       -0.000006
                    0.530068
       -0.000005
                    0.522067
                                -0.000007
        0.000001
                    -0.111442
                                 0.000001
                                                  ! components for atom N
```

As in the other structural optimization algorithms in VASP, convergence is controlled through the EDIFFG tag.

Experienced users can affect the performance of the dimer method by modifying the numerical values of the following parameters (the given example values are the default values):

- FINDIFF=1 Use a forward (FINDIFF=1) or central (FINDIFF=2) difference formula for the numerical differentiation to compute the curvature along the dimer direction
- DIMER DIST=0.01 The step size for a numerical differentiation (in Å)
- MINROT=0.01 Dimer is rotated only if the predicted rotation angle is greater than MINROT (rad.)
- STEP\_SIZE=0.01 Trial step size for optimization step (in Å)
- STEP\_MAX=0.1 Trust radius (upper limit) for the optimization step (in Å)

Important information about the progress of optimization is written in the OUTCAR file after the expression DIMER METHOD.

In particular, it is useful to check the curvature along the dimer direction, which should be a negative number (long sequence of positive numbers usually indicates that the algorithm fails to converge to the correct transition state).

IMPORTANT NOTE: The current implementation does not support lattice optimizations (ISIF>2) and can be used only for the relaxation of atomic positions.

## Initial dimer axis

The direction of an unstable vibrational mode can be obtained by performing vibrational analysis (IBRION=5) and taking the x-, y-, and z- components of the imaginary vibrational mode (after division by  $\sqrt{m}$ !) parallel with the reaction coordinate. Note that in order to plot "Eigenvectors after division by SQRT(mass)", NWRITE=3 should be used.

## Practical example

In this example, the transition state for the ammonia flipping is computed. All calculations discussed here were performed using the PBE functional, Brillouin zone sampling was restricted to the gamma point. This practical example can be completed in a few seconds on a standard desktop PC. The starting structure for the IDM simulation should be a reasonable guess for the transition state. A POSCAR file with the initial guess for the ammonia flipping looks like this:

```
ammonia flipping
1.
6. 0. 0.
0.7.0.
0. 0. 8.
H N
3 1
cart
       -0.872954
                        0.000000
                                        -0.504000
        0.000000
                        0.000000
                                        1.008000
        0.872954
                                        -0.504000
                        0.000000
        0.000000
                                         0.000000
                        0.000000
```

As an input for the dimer method, the direction of the unstable mode (dimer axis) is needed. This can be obtained by performing vibrational analysis. The INCAR file should contain the following lines:

```
NSW = 1
Prec = Normal
                           ! perform vibrational analysis
IBRION = 5
                           ! select central differences algorithm
NFREE = 2
POTIM = 0.02
                           ! step for the numerical differenciation
                           ! write down eigenvectors of dynamical matrix after division by SQRT(mass)
NWRITE = 3
```

After completing the vibrational analysis, we look up the hardest imaginary mode (Eigenvectors after division by SQRT(mass)!) in the OUTCAR file:

```
12 f/i= 23.224372 THz 145.923033 2PiTHz 774.681641 cm-1
                                                          96.048317 meV
          Χ
                   Υ
                            Ζ
                                                              dz
                                        dx
                                                  dy
                                             0.522103
    5.127046 0.000000 7.496000
                                                       -0.000009
                                  0.000001
                                             0.530068
                                                        0.000000
    0.000000 0.000000 1.008000
                                 -0.000006
                                 -0.000005
                                             0.522067
    0.872954 0.000000 7.496000
                                                       -0.000007
                                  0.000001 - 0.111442
    0.000000 0.000000 0.000000
                                                        0.000001
```

and use the last three columns to define the dimer axis in the POSCAR file:

```
ammonia flipping
1.
6. 0. 0.
0.7.0.
0. 0. 8.
H N
3 1
cart
       -0.872954
                       0.000000
                                      -0.504000
                                                       ! coordinates for atom 1
        0.000000
                       0.000000
                                       1.008000
        0.872954
                       0.000000
                                      -0.504000
                                       0.000000
        0.000000
                       0.000000
                                                       ! coordinates for atom N
        ! here we define trial unstable direction:
                   0.522103 - 0.000009
        0.000001
                                               ! components for atom 1
       -0.000006
                   0.530068 0.000000
                   0.522067
       -0.000005
                             -0.000007
        0.000001
                  -0.111442
                              0.000001
                                               ! components for atom N
```

In order to perform IDM calculation, the INCAR file should contain the following lines:

```
NSW = 100
Prec=Normal
IBRION=44
                   ! use the dimer method as optimization engine
EDIFFG=-0.03
```

With this setting, the algorithm converges in just a few relaxation steps. Further vibrational analysis can be performed to prove that the relaxed structure is indeed a first order saddle point (one imaginary frequency).

Examples that use this tag

## References

```
6. Henkelman and H. Jónsson, J. Chem. Phys.
```

```
Categories: Transition States | Improved dimer method | Atoms and Molecules | Howto
```

This page was last edited on 24 June 2019, at 14:25.

Privacy policy About Vaspwiki Disclaimers

Content is available under GNU Free Documentation License 1.2 unless otherwise noted.





