untype
hold a key, speak, release.

A Swift-native push-to-talk dictation tool for the macOS menu bar. It streams speech to a realtime STT provider, types it live into whatever you have focused, and lets an LLM clean it, translate it or answer it.

Technical walkthrough · what it is, how it works, how to install and configure it

Version 0.1.0 · build 28 · October 2026



BikS2013

AGENDA

Five parts, from purpose to *daily operation*.

01

What untype is

The problem, the product, who it serves, and the principles it is built on.

02

How it works

Hotkey to audio to transcript to LLM to focused input, the seven operators, and the menu-bar interface.

03

Installation

Install from Homebrew or the notarized disk image, or build, sign and notarize it yourself, then grant the three macOS permissions correctly.

04

Configuration and moving parts

The resolution chain, every setting that matters, the fifteen prompt files, state and log files, and the CLI.

05

Operating and troubleshooting

The daily loop, recipes for Ask, Follow-up and Selection, the logs, common symptoms, and the guardrails.

01

What untype is

A single-user macOS tool for dictating into any application, with a voice protocol designed for talking to coding agents.



01 · THE PROBLEM

Typing is the slowest part of working with an agent.

Prompts, commands and messages are spoken in seconds but typed in minutes. Dictation built into the OS lands raw, unpunctuated text and never reaches the field you are actually working in.

- Raw transcripts carry filler words, false starts and grammar noise.
- Greek and English are mixed in daily work, and the target often needs the other language.
- Text should land at the caret of the frontmost app, not in a separate window.
- A coding agent needs a way to hear "send", "cancel" and "status" without a mouse.



Hold a hotkey, speak, release. Clean text appears at the cursor.

01

Push-to-talk

A global hotkey (default `Control+``) opens the audio gate while held; release finalizes the turn and delivers the output. Push-to-listen mode toggles instead: press to start, press again to stop.

02

Realtime STT

Microphone audio streams over WebSocket to Soniox or ElevenLabs. Partials render live; finals drive the protocol.

03

Refine, translate or ask

An LLM cleans disfluencies, translates between Greek and English, or, with Ask on, answers what you said. Selected text and the previous answer can go along.

04

Live typing at the caret

While you speak, the words are typed straight into the focused control. On release they are replaced in place by the processed text, and optionally copied to the clipboard.

> Two things are treated as non-negotiable: push-to-talk must always work, and processed text must always reach the focused input. Every change is verified against both.

01 · WHO IT SERVES

One person, one Mac, every app.

TYPICAL TARGETS

- Coding agents and chat UIs in the browser or terminal.
- Editors, Notes, Outlook and other rich-text bodies.
- Any macOS control that accepts text through Accessibility or paste.

BILINGUAL BY DESIGN

- Default language hints `el,en`; Greek script detection selects the source language.
- Translation policies `opposite`, `to-en`, `to-el`.
- The default guard phrase is Greek: `τέλος εντολής`.

TWO FRONT ENDS

- The app bundle: a menu-bar icon with a dropdown, a Transcript window, a Settings window, the overlay and the hotkey.
- `untype [options]`: terminal streaming with the same runtime.

VOICE-AGENT PROTOCOL

- Spoken markers such as `command send`, `command cancel` or `command ask on` control sections and operators.
- Machine-readable JSONL events let an agent consume the dictation stream.

The project in numbers.

281

automated Swift Testing tests, all passing at the last recorded run, with zero third-party dependencies.

Platform	macOS 14+
Toolchain	Swift 6 · SwiftPM
Source files / lines	48 · ~17 300
STT providers	2
LLM providers implemented	4 of 10 names
Operators · prompt files	7 · 15
Latest build · released	28 · 28

Three rules shape every decision in the codebase.

01

No fallbacks for configuration

A missing required value raises a typed `missing_configuration` error and exits with code 2. The tool never invents a key, an endpoint or a model.

02

Privacy-safe diagnostics

Logs and events never contain transcript text, processed output, clipboard contents, prompts or secrets. Only names, states, codes and timings.

03

Guarded core features

Push-to-talk and focused-input delivery are protected by explicit guardrails, per-release manual smoke checks, and a latency log that proves delivery worked.

> **Consequence for operators:** most first-run problems are configuration or permission errors that the tool reports precisely, rather than silent degradations.

02

How it works

From the key press to the caret: audio capture, streaming transcription, the voice protocol, LLM processing and delivery.



Six stages, one in-process runtime.

1 · TRIGGER

Hotkey press and release

Quartz event tap with Carbon and NSEvent fallbacks; the audio gate opens on press.

`UntypeHotkeyMonitor` · `HotkeySessionControl`

→

2 · CAPTURE

Microphone to PCM16

AVAudioEngine tap, mono 16-bit at the configured rate, silence while the gate is closed.

`AVFoundationAudioSource` · `PCM16MonoConverter`

→

3 · TRANSCRIBE

Realtime STT stream

WebSocket to Soniox or ElevenLabs; partials and finals flow back to the runtime.

`SonioxTranscriber` · `ElevenLabsTranscriber`

→

4 · PROTOCOL

Markers and sections

Finals are parsed for spoken commands; text is buffered into sections with operator flags.

`VoiceAgentProtocolController` · `VoiceCommandStateMachine`

→

5 · LLM

Refine, translate, ask

One composite call, or one Ask call with selection and conversation; fail-open on error.

`AzureOpenAIRefiner` · `GoogleRefiner` · `AnthropicMessagesRefiner`

→

6 · DELIVER

Live typing, then in place

Typed live while held, edited in place on release; AX, paste or key events otherwise.

`LiveFocusedInputTyper` · `FocusedInputDelivery`

Each stage is timed into one record of `release-latency.jsonl`. The whole chain is assembled by `UntypeRuntimeFactory` into a single `TranscriptionSessionRuntime`, shared by the CLI and the native UI.

The lifecycle of one press.

1

Warm session

Enabling the hotkey starts a hotkey-owned runtime with the gate closed. Idle sessions are recycled every 5 minutes; a session that dies on its own, for example when the provider closes an idle socket, is re-warmed with backoff.

2

Press

The target app and any selected text are captured, the overlay appears, the gate opens and the words start being typed live. A press during the previous delivery is queued, not lost. In push-to-listen mode the first press starts and the next one stops.

3


Release

The gate closes, the provider is asked to commit, and the runtime waits up to 1.5 s for final text. Quick Close submits the latest partial immediately instead.

4

Submit and restart

The LLM runs while the overlay shows a processing wave, the live text is replaced in place, "this turn" operators switch off, and a fresh warm session starts.



Three detection layers share one press/release state.

PRIMARY

Quartz CGEvent tap

System-wide key down and key up, with suppression of the hotkey so it never reaches the frontmost app. Needs Accessibility and Input Monitoring.

Status: `global event tap ready`

FALLBACK 1

Carbon RegisterEventHotKey

A global hotkey registration that fires reliably even when the event tap cannot be installed.

Status:
`carbon global hotkey ready; event tap unavailable`

FALLBACK 2

AppKit NSEvent monitors

Local and global monitors as the last resort; release may be blocked, so the UI asks the user to press again.

Status: `fallback monitor active`

The hotkey monitor is reconfigured only when the hotkey string or its enabled flag changes, so a settings write mid-press can no longer reset a live session. A UI "Push to Talk" button drives the same path when keyboard hooks are unavailable.

Microphone first, provider second.

CAPTURE

- `AVFoundationAudioSource` preflights microphone permission and installs an `AVAudioEngine` input tap with 1 024-frame buffers.
- `PCM16MonoConverter` downmixes to mono 16-bit PCM at the configured sample rate (default 16 000 Hz).
- Errors are typed: `microphone_permission` exits with code 3, `microphone_capture` for engine failures.

GATING AND FORWARDING

- The runtime starts the microphone before connecting the provider socket, so the UI shows audio activity early.
- While the gate is closed, silence is substituted for every chunk; the provider connection stays warm.
- An `AudioActivitySnapshot` (waiting, silent, active, muted) is emitted every 0.25 s for the waveform and status pill.

> Diagnostics trace the order explicitly: starting microphone capture, microphone capture started, connecting realtime stream, realtime stream connected.

Two realtime providers behind one *RuntimeTranscriber* protocol.

SONIOX · DEFAULT

- Model `stt-rt-v5` (v4 is an alias) at `wss://stt-rt.soniox.com/transcribe-websocket`.
- Startup frame carries the key, `pcm_s16le`, sample rate, endpoint detection, language hints or auto identification, and optional context text from prompt file 004.
- Release sends `{"type":"finalize"}` followed by a 250 ms drain. Utterance boundaries arrive as `<end>` and `<fin>` tokens.
- Error frames map 401/403 to `soniox_auth`, 503 to `soniox_network`, the rest to `soniox_protocol`.

ELEVENLABS

- Model `scribe_v2_realtime` at `wss://api.elevenlabs.io/v1/speech-to-text/realtime`.
- Query carries `model_id`, `audio_format=pcm_<rate>`, commit strategy, optional language code and keyterms from prompt file 006.
- Audio is sent as base64 `input_audio_chunk` messages; `previous_text` from file 005 goes with the first chunk only.
- Allowed sample rates: 8 000, 16 000, 22 050, 24 000, 44 100, 48 000 Hz.

Both adapters sit behind a mockable `RealtimeWebSocketClient` and are frame-level tested; live behaviour is covered by manual smoke procedures under `test_scripts/`.

Markers turn speech into sections; sections carry operators.

Marker	A spoken phrase recognised in a final transcript. Four kinds: `state_command`, `section_end`, `section_cancel`, `literal_next`. Matching is case and diacritic insensitive with Greek locale rules and requires word boundaries.
Default phrases	Command phrase `command`, section end `command send`, section cancel `command cancel`, literal next `literal phrase`. The guard phrase `τέλος εντολής` is an alias of section end.
Voice commands on/off	Settings › Protocol › *Voice commands* (default on). Off: no marker is recognised, so everything spoken is dictated text, "command send" included. Turns end on release, operators change with the hotkey letters or the menu.
Section	The dictated text buffered between markers, identified as `sec_000001` and so on. "Command send" submits it with the active operators; "command cancel" discards it; shutdown submits pending text.
Interaction modes	`dictation` (default), `agent-protocol` (JSONL events on stdout, no human status lines) and `hybrid` (both; the CLI requires `--protocol-output`).
Events	Protocol `untype.voice-agent.v1`: session started and ended, state and status, section submitted, processed and cancelled, streaming progress, clipboard copied, input sent, warnings. Every event has a monotonic `seq`.

Seven switches decide what happens to a turn.

OPERATOR	KEY	EFFECT	DEFAULT LIFETIME
refine	**R**	The LLM cleans the transcript, preserving meaning and language.	Until changed
translate	**T**	Translate to the target (opposite, English or Greek) set next to the switch.	Until changed
ask	**A**	What you say is a request to the model; its answer replaces the dictation.	This turn
followup	**F**	Ask also sends the conversation so far, so the model can revise its last answer.	This turn
selection	**S**	The text selected in the app in front goes along, as material or as context.	This turn
clipboard	**C**	Copy the result to the clipboard.	Until changed
input	**I**	Type the result into the focused control of the frontmost app.	Until changed

> Toggle an operator in the menu-bar dropdown, in Settings, with the hotkey plus its letter while recording, or by voice, `command ask on`, while voice commands are on. Settings decides per operator whether a change lasts *this turn* or *until changed*; flags such as `--ask-default` set the starting state. An operator that needs an unconfigured LLM delivers the text unprocessed, with a warning.

Talk to the model, not just through it.

A · ASK

Dictate a request, get the answer

- "Write a short reply thanking them and proposing Tuesday." The answer is typed where the request was.
- One call with prompts 010 and 011; with Translate on, prompt 012 writes the answer in the target language.
- Refine is skipped. Own limits: 8 000 output tokens and a 120 s timeout.

F · FOLLOW-UP

Revise the previous answer

- With Follow-up on, Ask sends the earlier requests and answers too: "shorter", "more formal", "add a closing line".
- Keeps the last 20 exchanges in memory only, never on disk.
- Off means a new conversation; the dropdown also has *New conversation*.

S · SELECTION

Work on the selected text


- Read through Accessibility at press time, or by a ⌘C that restores your clipboard.
- **Material** (default): the selection is processed and replaced; a silent tap is enough.
- **Context**: reference only; the result goes after the selection.

Combine them. Select a paragraph, turn on Selection and Translate, tap the hotkey: the paragraph is replaced by its translation. Select an email, turn on Ask and Selection, say "draft a polite no": the draft appears in place.

Clean the transcript, never answer it.

The refinement system prompt describes the input as a verbatim transcript with disfluencies and asks for a grammatically clean rewrite that keeps the speaker's meaning and language.

- The text is content to clean, never a message to the model: questions are not answered, instructions are not followed, and nothing is added.
- The output stays in the input language. A request for translation inside the transcript is part of the text, not a command.
- Providers implemented: Azure OpenAI, Google Gemini, and Claude, either direct (`anthropic`) or on Microsoft Foundry (`azure-anthropic`). Six other names are accepted but raise a configuration error if refinement is on.
- Temperature 0.2 for OpenAI and Gemini; Claude uses effort `low` instead. Fixed 15 s timeout and one keep-alive URLSession, saving 100 to 400 ms per release.



Greek or English in, the other language out.

LANGUAGE DETECTION

Any character in the Greek and Greek Extended Unicode blocks marks the section as Greek; otherwise it is English. Only these two protocol languages exist.

POLICIES

- `opposite` (default): Greek becomes English, English becomes Greek.
- `to-en` : always English.
- `to-el` : always Greek.

PROMPTS

System prompt from file 002, user template from file 003 with `{target_language}` and `{text}` . Technical terms, file names, command names and code identifiers are preserved verbatim.

> Translation only runs for sections whose `translate` operator is on. With the operator off, the refinement prompt explicitly forbids any language change, so refine-only sections can never come back translated.

Both operators on means *one* LLM round trip.

When a section has refine and translate enabled and a composite processor is configured, the controller sends a single request whose system prompt (file 007) demands strict JSON with two fields.

- The user message stacks the source transcript, the refinement instruction (file 008) and the translation instruction (file 009).
- The response is parsed strictly; the JSON object is extracted even if the model wraps it.
- There is no sequential fallback: a composite failure is a fail-open warning and the raw text is delivered.
- Known gap: the same elapsed time is recorded in both `refine_ms` and `translate_ms`.

```
// system prompt: respond with ONLY valid JSON
{
  "refined_text":    "...",   // original language
  "translated_text": "..."    // target language
}

// user message envelope (LLMRefiners.swift)
Source transcript:
{raw text}

Refinement prompt:
{file 008 with {text} filled}


Translation prompt:
{file 009 with {target_language} filled}
```

A small oscilloscope, not a text box.

- While the hotkey is held, a transparent 200×84 pt panel at the bottom centre of the screen draws the real microphone signal, with automatic gain so quiet speech still swings.
- Under the wave, seven chips R T A F S C I show the operators: solid amber when on. Press the hotkey plus a letter to flip one mid-turn.
- After release a breathing wave stays on screen while the model refines, translates or answers, and the panel hides once the text has been delivered.
- The panel never takes focus, ignores the mouse, joins every Space and is recreated at every appearance.
- The transcript is not in the overlay any more: it is typed into your field. `--llm-streaming` remains, but with nothing to display it only matters for logs.



RECORDING · REFINE, TRANSLATE, CLIPBOARD, INPUT ON



PROCESSING · ASK WITH THE SELECTION

Reaching the caret: live first, three fallbacks.

0 **Live typing while you speak**

With Input on, the transcript is typed into the app that was in front at press time. On release only the differing tail is deleted and retyped; a result with a line break is pasted. These keystrokes carry a marker the hotkey monitors ignore.

1 **AX caret insertion**

For turns without live text: set `kAXSelectedText` at the caret and verify the length changed, which protects rich-text bodies such as Outlook.


2 **Clipboard-preserving paste**

Snapshot the pasteboard, paste with ⌘V, restore the clipboard after 0.8 s. Browsers get this first.

3 **Unicode key events**

Type the text as key events when it is at most 500 UTF-16 units.

> Do not move the caret or type while holding the hotkey: live text is edited relative to where it started. The app delivers in-process, so the grant belongs to `untype.app`; CLI runs use `untype-input-helper`.



Every release writes one privacy-safe latency record.

```
{
  "schema_version": 1,
  "turn_id": "…", "trigger": "ui-hotkey-release",
  "stt_provider": "soniox", "quick_close": false,
  "text_source": "provider_final_text",
  "outcome": "delivered_to_focused_input",
  "total_ms": 1834,
  "durations_ms": {
    "provider_commit_request_ms": 3, "provider_final_wait_ms": 412,
    "runtime_scheduling_ms": 9,      "protocol_submission_ms": 2,
    "refine_ms": 1180, "translate_ms": 0,
    "clipboard_ms": 1,  "focused_input_ms": 210
  },
  "focused_input": { "attempted": true, "ok": true,
    "method": "ax-value", "accessibility_trusted": true,
    "target_role": "AXTextArea" }
}
```

What to read

- `outcome` tells whether text reached the field, was processed without it, or failed.
- `text_source` explains where the text came from: provider final, Quick Close partial, timeout fallback, or none.
- Per-stage durations point at the slow link: provider wait, LLM, or delivery.
- Opt-in via `UNTYPE_RELEASE_LATENCY_LOG`; never contains transcript text.

Two executables, one library, one test target.

Package.swift	swift-tools-version 6.0, macOS 14, no dependencies
Sources/untype/	@main: UI launch or CLI command
Sources/untype-input-helper/	stdin text → focused input, JSON result
Sources/UntypeCore/	46 files, all logic

ConfigResolver · EnvChain · Dotenv · DotenvEditor · EnvTemplate · PromptConfig
TranscriptionSessionRuntime · UntypeRuntimeFactory
AVFoundationAudioSource · PCM16MonoConverter
SonioxTranscriber · ElevenLabsTranscriber
VoiceAgentProtocolController · ProtocolStateMachine · ProtocolMarkerMatcher
LLMRefiners · PromptFileStore · ProtocolJsonlWriter · ReleaseLatencyLogger
FocusedInputDelivery · LiveFocusedInputTyper · SelectedTextReader
NativeUntypeUILauncher (4 093 lines) · UntypeMenuBarController
UntypeMenuBarPanel · UntypeSettingsWindow · UntypePromptSettingsView
WarmSessionRecovery · UntypeTurnContext · UntypeEventLogFile

Tests/UntypeCoreTests/	24 files, 281 tests
scripts/	package-macos-app.sh, update-homebrew-cask.sh
packaging/macos/	icon, entitlements, INSTALL.txt


docs/design/ · docs/reference/ · docs/research/



untype lives in the menu bar.


There is no Dock icon. Click the waveform icon at the top right of the screen for the dropdown; right-click it for a short menu.

- **Header:** the STT and LLM providers and the state: idle, ready, recording, finalizing or listening.
- **Hotkey:** the on/off switch, then *Push-to-talk* (hold) or *Push-to-listen* (press, press again).
- **Mode and Theme:** Dictation, Agent or Hybrid; System, Light or Dark.
- **Operators:** the seven switches with their letters and the translation target. `1×` marks an operator that lasts one turn.
- **Hotkeys:** a reminder of the hotkey and of hotkey + letter.
- **Windows:** Transcript (⌘1), History (⌘2), New conversation, Settings (⌘,) and Quit (⌘Q).



The window shows what was heard and what was delivered.

- Open it with ⌘1 or ⌘2 from the dropdown. Closing it never quits untype.
- **Sidebar:** Transcript, History and Events, plus live status of microphone, Accessibility, the API key and the hotkey.
- **Top bar:** start or stop the session, the push-to-talk switch, refresh, permissions, theme, Settings and compact mode.
- **Chips:** the seven operators, clickable.
- **Turns:** raw and processed text with a copy button each; Copy, Save and Clear for the whole list.




TRANSCRIPT BLURRED FOR PRIVACY

One Settings window, opened with ⌘,

General holds every setting, in groups:

- **Session** with *Edit keys…*, and **Appearance**.
- **Provider:** STT provider, model, languages, sample rate.
- **Protocol:** mode, translation target, and the *Voice commands* switch.
- **Operators:** each switch with a *Lasts* choice, *This turn* or *Until changed*, and whether selected text is material or context.
- **Refinement (LLM):** on/off, provider, model.
- **Push to talk**, **Permissions** and **Credentials**.

Prompts edits the prompt files, covered in section 04. Settings are editable while the session is only warm; during a turn they lock.



03

Installation

Install it with Homebrew or from the notarized disk image, or build and package it yourself, then grant the permissions that make the hotkey and delivery work.



Two ways in, no toolchain required.

HOMEBREW

Tap and install the cask

`brew tap biks2013-tools/untype` then `brew install --cask untype`; later `brew upgrade --cask untype`. The tap `biks2013-tools/homebrew-untype` points at the latest release asset. It is maintained from the repository's `homebrew-tap/` folder and published by `scripts/update-homebrew-cask.sh --push`.

GITHUB RELEASE

Download the notarized disk image

Every build is a release tagged `v0.1.0-b<N>` (first one: `v0.1.0-b8`) with `untype-0.1.0.dmg`, the notarized zip and `SHA256SUMS`. Download it from `github.com/biks2013-tools/untype-s/releases/latest`, open the image, drag untype to Applications, follow `INSTALL.txt`.

Both paths install the same signed and notarized bundle, so permissions survive upgrades. The repository moved from `github.com/BikS2013/untype-s` to `github.com/biks2013-tools/untype-s`: an old tap must be re-tapped. The latest release is build 28, with Ask, Follow-up, Selection and the voice-commands switch.

What you need before the first build.

MACHINE

- macOS 14 or newer (release builds verified on macOS 26).
- Xcode 16+ or Swift 6 command-line tools; full Xcode for `notarytool` and `stapler`.
- A microphone.

SERVICE ACCOUNTS

- A Soniox or ElevenLabs API key for speech-to-text.
- For refinement: an Azure OpenAI resource with a chat deployment, or a Google Gemini API key.
- Optional expiry dates for key-renewal reminders.

RELEASE ONLY

- Apple Developer Program membership.
- A Developer ID Application certificate with its private key in the login keychain.
- An App Store Connect API key stored as the `untype-notary` notarytool profile.

> Check available signing identities with `security find-identity -v -p codesigning` before packaging.

Plain SwiftPM, nothing else.

```
# debug build → .build/debug/untype
swift build

# release build → .build/release/untype + untype-input-helper
swift build -c release

# 281 Swift Testing tests
swift test

# terminal smoke run (no LLM), append mode, verbose diagnostics
.build/debug/untype --no-refine --stt-provider soniox \
  --language en --output-mode append --verbose
```

- No third-party packages: the manifest declares no dependencies, so builds are reproducible offline.
- Release binary is about 4.9 MB; debug about 7.4 MB.
- Stop a terminal session with Control-C: pending provider output is finalized, the pending section submitted, `state.json` persisted, and the socket closed.
- Exit codes: 0 ok, 1 unknown, 2 configuration, 3 microphone, 4 provider auth, 5 provider network, 6 provider protocol.

One script builds, tests, signs, notarizes and staples.

```
scripts/package-macos-app.sh \
  --bundle-id com.local.untype --version 0.1.0 --build 28 \
  --sign-identity "Developer ID Application: GEORGIOS MARINOS (9F9H8NCAUB)" \
  --notary-profile untype-notary \
  --dmg
```

Outputs in `.build/deploy/`

- `untype.app`
- `untype-0.1.0.zip` and `-notarized.zip`
- `untype-0.1.0.dmg` (3.7 MB, distribute this one) and `SHA256SUMS`

FLAG	MEANING
`--bundle-id / --version / --build`	Required. The build number must increase on every run.
`--sign-identity`	Certificate identity; signs helper, main binary and bundle with hardened runtime, timestamp and the microphone entitlement.
`--notary-profile`	Keychain profile for `notarytool submit --wait`, then staple, then Gatekeeper assessment.
`--dmg / --dmg-only`	Also produce a notarized disk image with an Applications symlink and INSTALL.txt.
`--skip-tests / --skip-build / --unsigned`	Development shortcuts. `--unsigned` is for local packaging only, never for a deploy.

Why the signature is a functional requirement, not a formality.

macOS ties Accessibility and Input Monitoring grants to the app's code-signing designated requirement. An ad-hoc signature changes on every build, so each redeploy silently revokes Accessibility and delivery fails with `accessibility_not_trusted`.

- Since build 7 every deploy is signed with the Developer ID Application identity and notarized.
- Grants survive upgrades as long as the same certificate signs the app.
- Grants are lost when the identity changes: certificate renewal, switching certificate type, or an ad-hoc build. The bundle id must also stay fixed.
- The main binary is the bundle executable itself, with no launcher, so the process installing the event tap matches the identity granted in System Settings.

Certificate dates to plan around: Developer ID expires 2027-02-01, Apple Development expires 2027-08-15. Each renewal costs one permission re-grant.



Replace the app in place, verify, relaunch.

```
# 1. quit the running app
osascript -e 'tell application "untype" to quit'

# 2. keep the previous bundle
mv /Applications/untype.app .build/deploy/untype.app.previous

# 3. copy the new bundle and verify it
ditto .build/deploy/untype.app /Applications/untype.app
codesign --verify --deep --strict /Applications/untype.app
spctl --assess --type execute /Applications/untype.app

# 4. launch, and expose the CLI
open -a /Applications/untype.app
ln -sf /Applications/untype.app/Contents/MacOS/untype ~/.local/bin/untype
```

- Install location is `/Applications/untype.app`; the CLI is the same binary through a symlink.
- Publish the DMG, the notarized zip and `SHA256SUMS` as a GitHub Release tagged `v0.1.0-b<N>`, then regenerate the Homebrew cask. Never share a bare app.
- The whole release pipeline takes 5 to 10 minutes; each notarization 2 to 5.
- After every redeploy, perform one push-to-talk release into a text field and confirm `focused_input.ok=true` in the latency log.

Three grants, each with a distinct job.

1. **Microphone**

   Prompted on the first recording. Denial fails fast with `microphone_permission` and exit code 3.


2. **Accessibility**

   Required for the hotkey event tap, for typing into the focused field and for reading the selected text. The entry to check is `untype.app`, not the nested helper.

3. **Input Monitoring**

   Add untype here if the hotkey does not fire while another app is in front.

> Quit and relaunch after changing any permission. Settings › General › Permissions shows the live status; *Open Permission Setup* (or `⌥⌘P`) opens the guide with deep links into System Settings.



SETTINGS › GENERAL · PERMISSIONS AND CREDENTIALS

Where to click in System Settings.

1 · MICROPHONE

- Click *Start Listening* (or hold the hotkey) once. macOS asks "untype would like to access the microphone": click **Allow**.
- No prompt, or *Don't Allow* clicked earlier? **System Settings › Privacy & Security › Microphone**, switch untype on.
- untype appears in that list only after it has asked once, so do the first step first.

2 · ACCESSIBILITY

- **System Settings › Privacy & Security › Accessibility**.
- Click **+** below the list, pick *Applications › untype*, click *Open*, make sure the switch next to untype is on. macOS may ask for your password or Touch ID.
- Quit untype and open it again.
- Switch on but still "not trusted" (typical after an update changed the signature)? Select untype, click **−**, add it again with **+**, quit and reopen.

3 · INPUT MONITORING

- Only if the hotkey does not fire while another app is in front.
- **System Settings › Privacy & Security › Input Monitoring**.
- Click **+**, pick *Applications › untype*, click *Open*, switch it on. An older untype entry there? Remove it with **−** first.
- Quit untype and open it again.

> The welcome screen shows this guide with an *Open … settings* button per pane and a *Re-check status* button; the status is read live from macOS. Each pane lists untype only after it has been added there once, and every change needs a quit and relaunch.

When delivery stops after a redeploy or certificate change.

Symptom

The latency log shows `outcome: focused_input_failed` with `code: accessibility_not_trusted`, or the hotkey stops firing after an install.

Cause

The grant is tied to an older signing identity or bundle id.

```
# reset ONLY the Accessibility grant for the app
tccutil reset Accessibility com.local.untype

# relaunch, then re-add /Applications/untype.app under
# System Settings → Privacy & Security → Accessibility
open -a /Applications/untype.app

# hotkey dead after install? remove the stale entry under
# Input Monitoring, re-add the app, relaunch
```

> **Never reset Input Monitoring when only Accessibility is broken.** That removes the grant the event tap depends on and breaks push-to-talk, which then needs its own re-grant.

Setting up the API keys.

IN THE APP

Welcome screen › *Set keys…*, or Settings › General › Session › *Edit keys…*

- **Speech-to-text, one required:** Soniox API key (the default provider) or ElevenLabs API key (with the provider switched to ElevenLabs).
- **LLM, only for Refine, Translate or Ask:** the Azure OpenAI key, endpoint, deployment and API version; or `GOOGLE_API_KEY`; or Claude: `ANTHROPIC_API_KEY` direct, or `ANTHROPIC_FOUNDRY_API_KEY` with `ANTHROPIC_FOUNDRY_RESOURCE` on Microsoft Foundry.
- Secrets are masked; a *Show* switch reveals them while editing. *Save* writes only the fields you changed; an emptied field unsets that key.
- Keys are stored in `~/.tool-agents/untype/.env`, readable only by you, and never appear in logs or diagnostics.

IN THE FILE

Edit `~/.tool-agents/untype/.env` directly

- The first session start creates it as a fully commented template: every variable as `# NAME=` with its description, allowed values and default.
- Remove the leading `#` and fill the value, for example `SONIOX_API_KEY=…` or `AZURE_OPENAI_API_KEY=…`; comments and order are preserved, and later duplicates of a key are removed by the editor.
- Optional expiry dates, `SONIOX_API_KEY_EXPIRES_AT` and `ELEVENLABS_API_KEY_EXPIRES_AT`, make the UI warn 14 days before a key expires.
- Settings › General › Credentials shows each key's name, source tier and expiry, never the value. Pick the LLM provider and model in Settings › Refinement (LLM).

> **Nothing is defaulted.** A required key that is missing everywhere is a configuration error that names the variable and the four places it may be set; the onboarding checklist stays open until a speech-to-text key is present.

From launch to the first delivered sentence.

1. **Launch from Applications or Spotlight**

   The waveform icon appears in the menu bar. While microphone, Accessibility or a speech-to-text key is missing, the window opens with the onboarding checklist.

2. **Set the provider keys**

   Set keys… writes them to `~/.tool-agents/untype/.env`. Editing by hand works too: the first session start provisions that file as a fully commented template, and the fifteen prompt files under `prompts/`.

3. **Grant the permissions**

   Microphone, Accessibility and, if the hotkey stays silent, Input Monitoring; quit and relaunch after each change.

4. **Switcht the hotkey on in the dropdown**

   Pick Push-to-talk or Push-to-listen and the operators you want: Refine and Input are a good start. Click into a text field, hold `Control+`` , speak, release.

5. **Verify**

   The words appear while you speak and are replaced by the refined text on release. With the latency log on, the newest record reads `focused_input.ok=true`.

04

Configuration and moving parts

Where every setting lives, how the four tiers resolve, and what the state, prompt and log files contain.



Four tiers, highest priority first, and no invented values.

TIER 1 · HIGHEST

CLI flag

Explicit arguments such as `--stt-provider`. UI settings are converted into the equivalent flags, so what the UI sets behaves like a flag.

→

TIER 2

Local `.env`

The `.env` file in the current working directory, useful for per-project overrides when running the CLI.

→

TIER 3

User `.env`

`~/.tool-agents/untype/.env` : the normal home of API keys and provider settings for the app bundle. Provisioned as a commented template on first start; the UI credentials editor writes here.

→

TIER 4 · LOWEST

Shell environment

Exported variables of the launching shell. The UI shows which tier supplied the API key.

PARSER RULES

Comments and blank lines skipped, `export` prefix stripped, quotes handled, inline comments removed, last duplicate wins, blank values fall through to the next tier. Booleans accept true/false, yes/no, on/off, 1/0.

NO-FALLBACK RULE

A required value that is missing everywhere raises a typed error naming the variable and the four places it may be set. Nothing is defaulted silently, and startup stops with exit code 2.

Everything user-specific sits in one folder.

```
~/.tool-agents/untype/                  mode 0700
├── .env                                keys and settings, 0600 (template)
├── prompts/                            15 files, hot-reloaded
│   ├── 001 … 003                       refinement, translation
│   ├── 004 … 006                       STT provider context
│   ├── 007 … 009                       composite refine + translate
│   ├── 010 … 012                       Ask
│   ├── 013 · 014                       selected text
│   └── 015                             Follow-up conversation
├── state.json                          operators + policy
├── ui-state.json                       window, hotkey, settings
├── events.log                          session events, 0600, 1 MB
├── release-latency.jsonl               opt-in, + .previous
└── AuthKey_<KEYID>.p8                  notarization key
```

- The tool never writes secrets anywhere else, and never logs transcript text, selections or answers into this folder.
- Prompt files are provisioned with defaults if missing, validated on every start, and editable in Settings › Prompts.
- The Developer ID certificate lives in the login keychain, not here.
- Repository copies of the prompts under `prompts/` are for review only; the runtime reads this folder.
- A legacy `~/.tool-agents/mic-tool-ts/` folder without this one triggers a migration hint at startup.

Provider, credentials and audio parameters.

ENVIRONMENT VARIABLE	CLI FLAG	PURPOSE AND DEFAULT
UNTYPE_STT_PROVIDER	**--stt-provider**	`soniox` (default) or `elevenlabs`.
SONIOX_API_KEY	**--api-key**	Required when the provider is Soniox.
SONIOX_API_KEY_EXPIRES_AT	**--api-key-expires-at**	YYYY-MM-DD; warns when 14 days or fewer remain.
ELEVENLABS_API_KEY	**--elevenlabs-api-key**	Required when the provider is ElevenLabs.
ELEVENLABS_API_KEY_EXPIRES_AT	**--elevenlabs-api-key-expires-at**	Same reminder behaviour.
UNTYPE_MODEL	**--model**	Realtime model; `stt-rt-v5` or `scribe_v2_realtime` by provider.
UNTYPE_ENDPOINT	**--endpoint**	WebSocket URL; provider default when unset.
UNTYPE_LANGUAGES	**--language (repeatable)**	Hints such as `el,en`, or `auto` alone.
UNTYPE_SAMPLE_RATE	**--sample-rate**	16 000 Hz default; ElevenLabs accepts a fixed set.
UNTYPE_ENABLE_ENDPOINT_DETECTION	**--[no-]endpoint-detection**	Provider utterance detection, on by default.
UNTYPE_QUICK_CLOSE	**--[no-]quick-close**	Submit the latest partial on release instead of waiting; off by default.

Refinement provider, model and tuning.

ENVIRONMENT VARIABLE	CLI FLAG	PURPOSE AND DEFAULT
UNTYPE_REFINE	**--refine / --no-refine**	Master switch for LLM processing, which Refine, Translate and Ask need; on by default.
UNTYPE_LLM_PROVIDER	**--llm-provider**	`azure-openai` (default), `google`, `anthropic`, `azure-anthropic`; six other names are accepted but not implemented.
UNTYPE_LLM_MODEL	**--llm-model**	Model name, default `gpt-5.4`; for Foundry the deployment name, such as `claude-opus-5-5`.
AZURE_OPENAI_API_KEY · _ENDPOINT	env only	Required for `azure-openai`.
AZURE_OPENAI_DEPLOYMENT · _API_VERSION	env only	Deployment (falls back to the model name) and API version, default `2024-10-21`.
GOOGLE_API_KEY	env only	Required for `google`.
UNTYPE_LLM_MAX_OUTPUT_TOKENS	**--llm-max-output-tokens**	Caps refine and translate output; omitted when unset (Claude: 4 096).
UNTYPE_LLM_REASONING_EFFORT	**--llm-reasoning-effort**	`none|minimal|low|medium|high`; drops temperature. Claude maps none and minimal to `low`.
UNTYPE_LLM_STREAMING	**--[no-]llm-streaming**	Token streaming of the LLM response; off by default.

Claude direct or on Microsoft Foundry, and the Ask limits.

VARIABLE	APPLIES TO	MEANING AND HOW TO OBTAIN IT
ANTHROPIC_API_KEY	anthropic	Claude API key from the Claude Console.
ANTHROPIC_FOUNDRY_API_KEY	azure-anthropic	Foundry portal › Build › Models › your deployment › Details › Key. Set it even if it equals the Azure OpenAI key: nothing falls back.
ANTHROPIC_FOUNDRY_RESOURCE	azure-anthropic	Resource name; the endpoint becomes `https://<resource>.services.ai.azure.com/anthropic`.
ANTHROPIC_FOUNDRY_BASE_URL	azure-anthropic	A full base URL instead of the resource name. Setting both is an error.
UNTYPE_ASK_DEFAULT	Ask	`--ask-default on|off`, default off. Also `UNTYPE_FOLLOWUP_DEFAULT` and `UNTYPE_SELECTION_DEFAULT`.
UNTYPE_ASK_MAX_OUTPUT_TOKENS	Ask	`--ask-max-output-tokens`, default 8 000. Answers are full texts, so they do not share the refine cap.

> Claude requests use `x-api-key`, effort `low` by default and no temperature. A refusal or a `max_tokens` stop counts as a failure, so the raw text is delivered rather than a fragment. Ask has a fixed 120 s timeout; refine and translate keep 15 s.

Modes, marker phrases and initial operator states.

ENVIRONMENT VARIABLE	CLI FLAG	PURPOSE AND DEFAULT
UNTYPE_INTERACTION_MODE	**--interaction-mode**	`dictation` (default), `agent-protocol`, `hybrid`.
UNTYPE_PROTOCOL_OUTPUT	**--protocol-output**	JSONL event file; required for hybrid mode on the CLI.
UNTYPE_OUTPUT_MODE	**--output-mode**	`overwrite` (default, TTY), `append`, `final-only`.
UNTYPE_COMMAND_PHRASE	**--command-phrase**	Default `command`.
UNTYPE_SECTION_END_PHRASE	**--section-end-phrase**	Default `command send`.
UNTYPE_SECTION_CANCEL_PHRASE	**--section-cancel-phrase**	Default `command cancel`.
UNTYPE_LITERAL_NEXT_PHRASE	**--literal-next-phrase**	Default `literal phrase`; the next marker is dictated as text.
UNTYPE_GUARD_PHRASE	**--guard-phrase**	Default `τέλος εντολής`, an alias of section end.
UNTYPE_VOICE_COMMANDS	**--[no-]voice-commands**	On by default; off ignores every spoken marker above. In the app, the Settings switch decides.
UNTYPE_<OPERATOR>_DEFAULT	**--<operator>-default on|off**	Starting state of refine, translate, ask, followup, selection, clipboard, input; unset means `state.json` applies.
UNTYPE_TRANSLATION_POLICY	**--translation-policy**	`opposite` (default), `to-en`, `to-el`.


Fifteen files, twelve required, all editable.

FILE	REQUIRED	PURPOSE
001-refinement-system.txt	Yes	Refinement; keeps the language, never answers the text.
002 · 003 translation system / user template	Yes	Translation; 003 needs `{target_language}` and `{text}`.
004 · 005 · 006 Soniox / ElevenLabs context	No	Recognition hints sent to the STT provider: context text, previous text, keyterms.
007 · 008 · 009 composite	Yes	One-call refine + translate as JSON; 008 needs `{text}`, 009 `{target_language}`.
010-ask-system.txt	Yes	Ask: fulfil the dictated request and return only the requested text.
011-ask-user-template.txt	Yes	The Ask message; needs `{text}`.
012-ask-translated-user-template.txt	Yes	Ask with Translate on; needs `{target_language}` and `{text}`.
013-selection-context-template.txt	Yes	Selection as reference only; needs `{selection}`.
014-ask-selection-template.txt	Yes	Selection put before an Ask request; needs `{selection}`.
015-ask-conversation-template.txt	Yes	Follow-up history before an Ask request; needs `{history}`.

Violations raise typed configuration errors before a session starts, and the Settings editor refuses to save them. Prompt contents are never logged.

Edit, save, and the next turn already uses it.

- Settings › **Prompts** lists the files by group: Refinement, Translation, Refine + translate, Ask, Selected text, Transcription context.
- Edit, then **Save** (⌘S). *Revert* drops unsaved edits; *Reset to Default* loads the built-in text for you to save.
- A save is validated with the same rules as session start, so a missing placeholder cannot be written.
- untype checks the files every second, including edits from another editor. The Events tab shows `prompts.reloaded` and an idle warm session restarts at once; a turn in progress is never interrupted.
- Keep two invariants: refinement must not change the language, and only Ask may answer the dictated text.



Latency logging, verbosity and timing constants.

SETTING	MEANING
UNTYPE_RELEASE_LATENCY_LOG	Enable the per-release JSONL log; off by default. Flag `--[no-]release-latency-log`.
UNTYPE_RELEASE_LATENCY_LOG_PATH	Default `~/.tool-agents/untype/release-latency.jsonl`.
UNTYPE_RELEASE_LATENCY_LOG_RESET_ON_START	Clear the log once per process start, keeping the previous run as `.previous`; env only.
events.log (fixed path)	Session and diagnostic events of the app, kept across relaunches; no transcripts.
UNTYPE_VERBOSE / -v	State transitions and operator diagnostics on stderr; never text.

Final-text wait after release	1.5 s
Soniox finalize drain	250 ms
LLM timeout: refine · Ask	15 s · 120 s
Selection ⌘C fallback wait	≤ 300 ms
Warm-session idle recycle	5 min
Pasteboard restore after paste	0.8 s
Follow-up memory	20 exchanges

The timings on the right are compiled constants, not settings. They explain what you see: a processing wave that lasts 15 s is a hung LLM call, not a stuck hotkey; with Ask, long answers can take 30 s.

Two small JSON files, no secrets, no transcripts.

```jsonc
// state.json — written at runtime shutdown
{
  "version": 1,
  "saved_at": "2026-09-11T23:52:00Z",
  "protocol": {
    "operators": { "refine": true, "translate": false,
      "ask": false, "followup": false, "selection": false,
      "clipboard": true, "input": true },
    "translation_policy": "opposite"
  }
}
```

```jsonc
// ui-state.json — window and settings
{
  "version": 1, "saved_at": "…",
  "settings": { "provider": "soniox", "model": "stt-rt-v5",
    "languages": ["el","en"], "protocolMode": "dictation",
    "llmEnabled": true, "llmProvider": "azure-anthropic",
    "llmModel": "claude-opus-5-5",
    "hotkeyEnabled": true, "hotkeyHoldToTalk": true,
    "hotkey": "Control+`", "appearance": "light",
    "perTurnOperators": ["ask","followup","selection"],
    "selectionRole": "material", … },
  "push_to_talk": { "enabled": true, "hotkey": "Control+`" }
}
```

> Persisted operator values apply only when the corresponding flag or environment variable is not set. An invalid file is a typed error that names the file to fix or delete, never a silent reset.

One command, one subcommand, one helper.

UNTYPE [OPTIONS]

- Streams transcripts to stdout; diagnostics and warnings to stderr.
- Ready line: `[untype] Ready to listen.`
- `-h`, `--version` print and exit 0.
- Unknown options raise `invalid_configuration`.

UNTYPE UI

- Opens the native window; the same as double-clicking the bundle.
- Runs the identical runtime in-process, so no terminal parsing.

UNTYPE-INPUT-HELPER


- `diagnose` reports Accessibility trust and focused-element capabilities.
- `send --method auto|ax-value|unicode-events|paste-keycode` with text on stdin; one JSON line out; exit 2 on expected failure.

```
untype --api-key sk_... --language el --language en
SONIOX_API_KEY=sk_... untype --output-mode append
untype --stt-provider elevenlabs --elevenlabs-api-key xi_... --language auto
untype --no-refine --interaction-mode hybrid --protocol-output ./events.jsonl
```

05

Operating and troubleshooting

The daily loop, what the logs say, the symptoms you will meet, and the rules that keep the two core features intact.



Focus a field, hold, speak, release.

01

Set the turn

In the menu-bar dropdown, switch on what this turn needs: Ask, Follow-up or Selection. Refine, Translate, Clipboard and Input usually stay on.

02

Focus and hold

Click into the target field, or select the text to work on. Hold the hotkey, or press once in push-to-listen mode, and speak. Your words appear as you say them.

03

Flip mid-turn

Still holding, press R, T, A, F, S, C or I to switch an operator. The overlay chips show the result. Keep the caret where it is.

04

Release

The wave breathes while the model works, then the live text is replaced in place. Operators set to *this turn* switch off again.

> Quick Close trades accuracy for speed: it submits the latest partial the moment you release. With voice commands on, say "command send", "command cancel", "command status" or "command ask on". Switch them off in Settings › Protocol if you dictate text containing those words.

Five things to try in the first week.

GOAL	SWITCH ON	DO THIS
Clean dictation	R I	Hold, speak naturally with ums and restarts, release. A tidy sentence replaces the raw words.
Write in the other language	R T I	Speak Greek, get English, or the reverse. Pick the target next to Translate in the dropdown.
Translate existing text	T S I	Select a paragraph and tap the hotkey without speaking. The paragraph is replaced by its translation.
Draft a reply	A S I	Set *Selected text is* to Context, select the message, say "reply that I agree and propose Tuesday at ten". The draft goes after the message, not over it.
Refine the draft	A F I	Right after an Ask, say "shorter and more formal". The model revises its previous answer.

One line tells you which link is slow or broken.

```
tail -1 ~/.tool-agents/untype/release-latency.jsonl | python3 -c \
  'import sys,json; r=json.load(sys.stdin); print(r.get("outcome"), r.get("focused_input"))'
# expected: delivered_to_focused_input {'attempted': True, 'ok': True, ...}
```

SIGNAL	INTERPRETATION
provider_final_wait_ms high	Provider finalization or voice activity detection is slow; consider Quick Close for short commands.
runtime_scheduling_ms high	UI or runtime scheduling contention on the main thread.
refine_ms / translate_ms / ask_ms high	The LLM is the bottleneck: model choice, reasoning effort, answer length, or network.
focused_input ok=false	Accessibility, target application or paste problems; check `code`. `method=live-typed` means live typing delivered the turn.
events.log after a relaunch	Shows what happened before: `push-to-talk session ended unexpectedly`, then the re-warm attempts.
text_source=timeout_fallback_partial	The provider did not finalize within 1.5 s; the latest partial was used with a warning.

What you see, why, and what to do.

SYMPTOM	CAUSE	FIX
`focused_input_failed`, `accessibility_not_trusted`	Accessibility grant tied to an older signing identity.	`tccutil reset Accessibility com.local.untype`, relaunch, re-add the app.
Hotkey does nothing after an install	Input Monitoring grant belongs to the previous identity.	Remove the stale entry, re-add `/Applications/untype.app`, relaunch.
Text processed but not inserted; untype was frontmost	No external target to restore.	Focus the target edit control before release.
Processing wave lasts 15 s, raw text delivered	Hung LLM request hitting the fixed timeout.	Check the endpoint and deployment; delivery is fail-open.
Refinement silently skipped, HTTP 400	`UNTYPE_LLM_REASONING_EFFORT` set on a non-reasoning deployment.	Unset it for that deployment.
UI shows one Azure deployment, requests use another	Duplicate `AZURE_OPENAI_DEPLOYMENT` lines; last one wins.	Keep a single definition in `.env`.
Warm session keeps restarting after a provider error	Fatal provider error such as an exhausted balance.	Auto-restart is skipped after fatal errors; fix the account, restart the session.
Notarization `status: Invalid`	Signing or entitlement problem in the bundle.	`xcrun notarytool log <id> --keychain-profile untype-notary`.

Live typing, Ask and Selection have their own pitfalls.

SYMPTOM	CAUSE	FIX
Final text lands in the wrong place or garbled	The caret moved, or you typed, while the hotkey was held.	Keep hands off the field until the text settles.
Live words stay after "command cancel"	Only a delivered result replaces live text.	Undo or delete them by hand.
Ask returns your words, with "ask operator failed"	LLM off or misconfigured, or the request failed.	Turn on Refinement (LLM) and check the provider keys.
Ask answer cut off, "stop_reason max_tokens"	The answer exceeded the Ask output cap.	Raise `UNTYPE_ASK_MAX_OUTPUT_TOKENS` above 8 000.
Selection ignored	The app exposes no selection and the ⌘C fallback copied nothing.	Check Accessibility; some editors copy the whole line when nothing is selected.
Translated selection overwrote text you wanted to keep	The Material role replaces the selection.	Switch *Selected text is* to Context.
Ask switched itself off	Ask, Follow-up and Selection last one turn by default.	Set *Lasts* to Until changed in Settings › Operators.
An operator flips, or the turn ends, while you dictate	Your text contained a command phrase such as "command translate on".	Switch off Settings › Protocol › *Voice commands*.
"command send" does nothing and is typed as text	Voice commands are off.	Switch them on, or end the turn with the hotkey.
First press after a long idle did nothing (older builds)	The provider closed the idle socket.	Build 25 and later re-warm the session automatically; see `events.log`.

Two features may never regress.

Do not break push-to-talk.


Any change to the UI, session controls, hotkey configuration, permission flow, overlay or runtime lifecycle must keep the whole chain: listening stays active, press and release reach the hotkey-owned session, the gate opens and closes, the overlay shows and hides, and delivery runs after release. Verify in `NativeUntypeUILauncher`, `UntypeHotkeyMonitor`, `HotkeySessionControl` and `TranscriptionSessionRuntime`.

Do not break focused-input delivery.

Any change touching delivery, live typing, the protocol controller, the packaging script, or any redeploy must be followed by a real release into a text field with `focused_input.ok=true` in the log. untype's own keystrokes must keep the marker that the hotkey monitors ignore.

Never redeploy an ad-hoc bundle.

Always package with the Developer ID identity and notarize; an unsigned build silently revokes Accessibility.



untype

Where it stands, and what is next.

Build 28, on GitHub Releases and Homebrew, is a menu-bar app with live typing at the caret, a text-free oscilloscope overlay, seven operators including Ask, Follow-up and Selection, a voice-commands switch, a Settings window with hot-reloaded prompts, and Claude on Microsoft Foundry.

Open items: synchronise runtime state across execution contexts, await provider handshakes and trailing finals, reduce UI main-thread writes, and replace the placeholder bundle id in one deliberate build.

Docs: `docs/design/project-design.md`, `configuration-guide.md`, `deployment-guide.md`, `release-runbook.md` and the issue register in `Issues - Pending Items.md`.

