OpenWay Group Operation Manual

# **Currency Conversion**

# Contents

INTRODUCTION	1
CHAPTER 1. GENERAL PROPERTIES	2
CHAPTER 2. DETERMINING THE CURRENCY AND FX RATE IN WAY4  Currency Table Redefining Currency Parameters Redefining Currency for Online Redefining Currency for clearing documents Viewing and Editing Currency Redefinitions Transaction Switch Setup Entering Local to Foreign Currency Rates FX Rate History Loading Channel Rates Copying FX Rates to a New Financial Institution Using Channel Rates for Internal Conversion	4 4 5 5 6 7 7 8 10 11 14 14
CHAPTER 3. CURRENCY CONVERSION IN WAY4  Setting up Main FX Schemes  Main FX Schemes  "FX Scheme" Form  Adding an FX Scheme for a New Currency Deleting FX Schemes  FX Types  "FX Types" Form Independent FX Types Dependent FX Types Configuring Multicurrency FX Schemes Base Cross Rates Configuring Special Cross Rate Schemes Configuring Explicit Cross Rate Schemes Migrating FX Schemes Manually Configuring Explicit Cross Rate Schemes Configuring the FX Rate Difference Configuring the FX Rate Difference Showing the FX Rate Difference in WAY4 Currency Conversion Global Parameters Additional Parameters	18 18 18 19 21 22 22 23 24 24 25 26 26 28 29 30 33 34 35 35
CHAPTER 4. SOLVING TYPICAL PROBLEMS IN CURRENCY CONVERSION	۱36
Messages Confirming the Accounting Scheme CDB.CHECK_SCHEME:E001 CDB.CHECK_SCHEME:E034 Messages Created While Checking the Financial Institution CDBC.CHECK_FI_SPC:E002 CDBC.CHECK_FI_SPC:E003 CDBC.CHECK_FI_SPC:E009 Messages Created when Checking the FX Scheme FX.CHECK_FX:E001 FX.CHECK_FX:E005 FX.CHECK_FX:E006 FX.CHECK_FX:E010 FX.CHECK_FX:E011 FX.CHECK_FX:E012 FX.CHECK_FX:E013 FX.CHECK_FX:E014	36 36 37 37 37 37 37 38 38 38 39 39

FX.CHECK_FX:E017	40
FX.CHECK_FX:E018	40
FX.CHECK_FX:E020	40
FX.CHECK_FX:E021	40
FX.CHECK_FX:E022	41
FX.CHECK_FX:W001	41
Messages Created when Processing Documents	41
CHCK.BASE:E02	41
CHCK.BASE:E03	42
CHCK.ROUTING:E10	42
CHCK.TRANSF:E004	42

# Introduction

Multicurrency support can be considered as one of the most important functions needed for the accounting and processing of card transactions through WAY4<sup>TM</sup>.

This document is intended for WAY4 system administrators (bank or processing centre employees) and describes the specifics of setting up and working with a multicurrency system.

While working with this document, it is recommended that users refer to the following reference material from OpenWay's documentation series:

- DB Manager Administrator Manual
- Interchange Routing
- Daily Procedures
- WAY4<sup>TM</sup> Accounting Schemes
- WAY4<sup>TM</sup> Service Packages
- Usage Limiters
- Standing Payment Orders
- Documents
- Scheduler
- Menu Editor
- FX Rates
- Financial Institutions
- Housekeeping

The following conventions are used throughout this document:

- Field labels in screen forms are typed in *italics*.
- Button labels used in screen forms are placed in square brackets, such as [Approve].
- Menu selection sequences are shown with the use of arrows, such as Full →
  Issuing → Contracts Input & Update.
- Item selection sequences, in the system menu, are shown with the use of different arrows, such as Database => Change password.
- Key combinations used while working with DB Manager are shown in angular brackets, such as <Ctrl>+<F3>.
- Warnings of possible erroneous actions are marked with the \( \frac{\( \)}{\( \)} \) sign.
- Messages marked with the isign contain information about important features, additional facilities, or the optimal use of certain functions of the system.

# Chapter 1. General Properties

Currency conversion occurs in the WAY4 system in the following situations:

- When determining the amount available in an issuing contract having accounts in different currencies
- During authorization when the currency of the authorization request differs from the currency of the contract
- When determining the balance of a contract having accounts in various currencies
- When determining a contract's usage limiter parameters (see the Usage Limiters Administrator Manual) during authorization when the currency of the authorization request differs from the currency specified by the usage limiter
- When posting macrotransactions that include contractor accounts in differing currencies
- When charging a fee, when the account currency differs from the fee currency indicated in the service involved (see section "Full Information about a Service" in the WAY4<sup>TM</sup> Service Packages Administrator Manual)
- While processing outward clearing files when comparing transaction amounts with the maximum transaction amount set by the payment system that can be executed without authorization (floor limit) if the transaction currency differs from the currency in which the floor limit is set
- When creating reports, for example, client statements

For currency conversion the WAY4 system uses the following tools and procedures:

- FX schemes
- FX types
- FX contract of a financial institution (FI), used by default for posting currency conversion operations and containing a set of conversion accounts
- Additional global parameters that define currency conversion rules
- A currency system dictionary that can be refreshed partly by loading data from the payment system
- Entering FIs and types of local to foreign currency rates during daily procedures (entering of the bank date); different rate types may be entered, such as FX buy rates, FX sell rates, and FX middle rates. The system will convert currency based on the middle rate, excluding these cases where the service sets another buy/sell rate for the transaction (see section "Full Information about a Service" in the WAY4<sup>TM</sup> Service Packages Administrator Manual)
- Loading of currency rates from the payment system

Note that in most cases WAY4 converts currency using the rate of the local to foreign currency and a conversion account pair, one account in the local and the other in the foreign currency. The local currency is defined when configuring the FI (see the "Changing the Local Currency" section of the Financial Institutions Administrator Manual). A foreign currency may be converted to another foreign currency without using accounts in the local currency (see the description of the global parameter USE\_CROSS\_FX in the document WAY4<sup>TM</sup> Global Parameters ).

# Chapter 2. Determining the Currency and FX Rate in WAY4

Currencies are accounted in the system using forms "Currency Table", used to keep a dictionary of currencies, and "FX Rates", used to enter rates of currencies to a local currency used for conversion.

The system allows for importing payment systems daily currency conversion rates in clearing files.

# **Currency Table**

The table of currencies (see Fig. 1) can be accessed through the user menu path "Full  $\rightarrow$  Configuration Setup  $\rightarrow$  Main Tables  $\rightarrow$  Currency Table".




Fig. 1. System currency table

Users must manually enter in data from payment system directories and load data from MasterCard files (Full → Daily Procedures → Load BIN Tables and Handbooks → MC Load BIN Table and Handbooks → MC. Full Replacement → Load MPE Replacement Files). When loading file data, currency entries that have the *Use in Bank* field set to value "Yes" will not be refreshed. If a conflicting situation arises, for example, if a discrepancy is found in parameter values for the same currency in different payment systems, consult with the WAY4 system vendor's representatives.

The currency table contains the following fields:

- Full Name currency name.
- *Name* alphabet currency code in ISO.
- *Code* currency code number in ISO.
- *Exponent* number of decimal places used in the currency.

- *FX Range* the amount of currency units used when setting the rate value; for example, when entering the value "For 100" for the Japanese yen, a rate of 0,77EUR/JPY means that the rate is 0,77 euros to 100 Japanese yen.
- *Use in Bank* when this parameter is set to "Yes", conversion and entry of currency rates in the FI's local currency can take place in daily procedures in WAY4.

# Redefining Currency Parameters

In the "Currency Table" dictionary, it is possible to redefine a currency – its code and/or number of decimal places used in the currency (the exponent) according to IPS requirements. For example, according to an IPS requirement, from a certain point in time the exponent in a certain currency must have a null value. A currency can be redefined when processing authorization documents (Online) or when processing clearing documents (Clearing).

For one currency, several redefinition variants can be specified, that are effective at different times. Redefinition effective periods must not overlap.

For online processing, a currency is redefined through the user interface, if Transaction Switch is used for data exchange with external systems. If NetServer is used, settings to redefine currencies for online processing are made by the WAY4 vendor.

If a currency must be redefined for settlements (Clearing, Settlement), this is done through the user interface.

# Redefining Currency for Online

To redefine the currency used for online processing, click on the [Add Redef] button in the "Currency Table" form (see Fig. 1) and select the "OnLine" context menu item to open the "Currency Overrides – Edit OnLine" form (see Fig. 2).




Fig. 2. Creating a redefinition for Icelandic Krona, used for online processing Fill in the following fields:

- *GMT Date From* date and time (GMT) from which the currency redefinition used for processing online is effective.
- *GMT Date To* date and time (GMT) until which the currency redefinition used for processing online is effective. If the field is empty, the redefinition will be effective indefinitely.
- Channel name of the transaction channel. The value is selected from a list registered in the "Message Channels" dictionary (menu item "Full → Configuration Setup → Main Tables → Message Channels"). Transaction Switch must be set up to provide an interface with external systems (see the section "Transaction Switch Setup").
- *Numeric Code* the currency's numeric code after redefinition.
- *Name* the currency's name after redefinition.
- *Exponent* number of decimal places for amounts in this currency after the currency has been redefined.

# Redefining Currency for clearing documents

To redefine the currency used when processing clearing documents, click on the [Add Redef] button in the "Currency Table" form (see Fig. 1) and select the "Clearing" context menu item to open the "Currency Overrides – Edit Clearing" form (see Fig. 3).




Fig. 3. Creating a redefinition for Icelandic Krona used when processing clearing documents Fill in the following fields:

- Bank Date From bank date and time the currency redefinition for processing clearing documents is effective.
- Bank Date To bank date and time until which the currency redefinition for processing clearing documents is effective. If the field is empty, the redefinition is effective indefinitely.

The remaining fields in the "Currency Overrides – Edit Clearing" form are the same as those in the "Currency Overrides – Edit OnLine" form (see the section "Redefining Currency for Online").

If the "CHANGE\_CURR", "CHANGE\_CURR\_OUT", "CHANGE\_CURR\_IN", "EXT\_CURR\_EXP" parameters are set in document import/export pipes, they have a higher priority than the settings made in the user interface.

# Viewing and Editing Currency Redefinitions

To view and edit currency redefinitions that were created earlier, click on the [Redefinition] button in the "Currency Table" form (see Fig. 1) to open the "Redefinition for <...>" form (see Fig. 4).



Fig. 4. List of redefinitions for Icelandic Krona

Select the redefinition that must be changed using the [Action] button and the "Edit" context menu item to open the edit form. The edit form is the same as the form for creating a redefinition (see Fig. 2, Fig. 3); all fields are editable.

Use the [Action] button and the "Delete" context menu to delete a redefinition.

# **Transaction Switch Setup**

Set up services for interacting with payment systems:

#### For example:

Where the *currencyOverrides channel* parameter is a channel code from the *Code* field of the "Message Channels" dictionary (menu item "Full  $\rightarrow$  Configuration Setup  $\rightarrow$  Main Tables  $\rightarrow$  Message Channels").

# **Entering Local to Foreign Currency Rates**

The rate of a certain currency to a local currency used in conversion can be entered as part of the daily procedures for opening a new banking day (see section "Setting Banking Date" in the Daily Procedures User Manual) when a new banking date is set.

Depending on how the user menu item "Full  $\rightarrow$  Daily Procedures  $\rightarrow$  Default Start of Day" and "Full  $\rightarrow$  Daily Procedures  $\rightarrow$  Start of Day Step By Step  $\rightarrow$  Set Banking Date" is configured, users can be invited to enter the currency rate according to one of the following ways:

- "Set FX Rates (Full)" Enter the buy, sell, and middle rate values for each FI registered in the system.
- "Set FX Rates (Middle Rates)" Enter the middle currency rate for each FI registered in the system; entered values will automatically be copied to the buy/sell rate value fields.
- "Set FX Rates (HeadOffice)" Enter all currency rates for the FI's head office; entered values are automatically copied to rate fields for all remaining FIs.
- "Set FX Rates (HeadOffice, Middle Rates)" Enter the middle currency rate for the FI's head office; entered values are automatically copied to the buy/sell rate of the head FI, and to the rate value fields for all remaining FIs.

To enter the currency rate value, use the table form "FX Rates..." (see Fig. 5).




Fig. 5. Table for entering FX rates

This table contains the following fields:

- *Currency* name of currency
- *Institution* name of FI, for which the rate is indicated
- FX Type field that shows (if filled) that this particular rate is associated with an additional conversion type (see "FX Types")

It should be kept in mind that a new rate can only be entered for independent additional FX types; for dependent additional FX types the rate value is the basic rate value used by default (see "FX Types").

- Range quantity of currency units used when determining the rate
- FX Middle middle rate value
- FX Buy buy rate; this value is used when the FX Rate Type field of the service through which a document is processed contains the "Buy/Sell" value,

the contract has no account in the transaction currency with the type specified in the Service, and either of the following conditions is met:

- An account with a foreign currency is credited
- An account with the local currency is debited
- FX Sell sell rate; this value is used when the FX Rate Type field of the service through which a document is processed contains the "Buy/Sell" value, the contract has no account in the transaction currency with the type specified in the Service, and either of the following conditions is met:
  - An account with a foreign currency is debited
  - An account with the local currency is credited
- *CB Rate* rate set by the Central Bank (the national bank) of the country; by default this field is set to the middle rate. For example, the rate value set in this field can be used for report generation.
- Auth Sell Mult sell rate factor used during authorisation to calculate the blocked amount converted from a local currency. This value may be used to compensate the difference between the blocked amount and the amount posted to contract accounts, which arises because of the difference in the conversion rates on the authorisation date and the financial document processing date. In this case, blocked amounts are calculated by the following formula:

 $Blocked\ amount\ (FC) = \frac{Transaction\ amount\ (LC)}{Local\ currency\ rate\cdot Auth\ Sell\ mult}$ 

For example, to increase blocked amounts by 2%, specify value "0.98" in this field; the default value is "1" (blocked amounts are not changed).

 Auth Buy Mult – buy rate factor used during authorisation to calculate the blocked amount converted to a local currency. This value may be used to compensate the difference between the blocked amount and the amount posted to contract accounts, which arises because of the difference in the conversion rates on the authorisation date and the financial document processing date. In this case, block amounts are calculated by the following formula:

Blocked amount (LC) = Transaction amount (FC)  $\cdot$  Local currency rate  $\cdot$  Auth Buy mult

For example, to increate blocked amounts by 2%, specify value "1.02" in this field; the default value is "1" (blocked amounts are not changed).

It should be kept in mind that when entering a new rate value, the system checks whether the new value differs from the current value more than the permissible fluctuation value indicated for the currency in the *Max Fluctuation* field in the currency table (see "Setting up Main FX Scheme"). If this limit is exceeded, the system will create an error message and interrupt the loading of rates. In this case, the system will use previously entered rate values (see "FX Rate History"); therefore, if new values need to be entered, enter the rate again after making the necessary corrections.

Currency rates can entered several times a day if necessary through the user menu path "Full → Daily Procedures → Start of Day Step By Step → Reset FX Rates" without changing the current banking date.

Setup through this menu item will allow currency rates to be loaded from files, as well as through Scheduler (see the Scheduler Administrator Manual). Loading currency rates from files makes it possible to optimise the process of entering currency rate values. To load currency rates from files, use the user menu path "Full  $\rightarrow$  DB Administrator Utilities  $\rightarrow$  Special OpenWay Utilities  $\rightarrow$  FX Rates Import  $\rightarrow$  RBS FX Rates Import". The format for currency rate files is described in the "FX Rates" manual.

# **FX Rate History**

Users can access the history of currency rates and the current rate through the user menu path "Full  $\rightarrow$  Daily Procedures  $\rightarrow$  FX Rate History". After selecting the indicated menu item, the screen will display the table grid "FX Rate History" (see Fig. 6).




Fig. 6. Table of rate values last entered by the user

This grid is the same type as the FX Rates table (see Fig. 5 in section "Entering Local to Foreign Currency Rates") and contains the last currency rates entered by the user.

It should be kept in mind that data presented in the "FX Rate History" table may not correspond to current rate values used by the system for conversion. A similar situation is possible, for example, after entering a value that differs from the current rate by an amount exceeding a set limit (see "Entering Local to Foreign Currency Rates").

To access current values and rate history of any currency, select the row containing the currency and conversion type in the "FX Rate History" table (see Fig. 6) and click on the [FX History] button.

The screen will display the table grid "FX History for <name of currency>" (see Fig. 7).




Fig. 7. FX history for selected currency

This grid contains the rate history for a given currency with the date and the name of the user who entered the data.

Note that the form "FX History for <name of currency>" displays the current rate in the row containing the most recent date in the *Date To* field or, if rates

were entered several times over the same day, the highest value in the *Seqv N* field. The field contains a number unique within a day.

Clicking the [Seqv N Info] button opens a form containing information about the time the rate was set. This information may be useful when a rate changes several times a day.

# **Loading Channel Rates**

Channel rates are loaded as follows:

- For Visa, information for updating FX channel rates is loaded when the BIN table is updated (see the sections "Loading the VISA BIN / ARDEF Table" and "Loading the VISA PLUS BIN Tables" of the document "Interchange Routing").
- For MasterCard, FX channel rates are updated using the menu item "MasterCard → MC.Daily Procedures → MC.Load Bin Table and Handbooks → Load MC Rates". Before executing this menu item, copy the file received from MasterCard with the name mask "T05???.?" to the "<OWS\_WORK>\Data\Interchange\MPE\_Inc" directory.

Rates are loaded to the CHANNEL\_CURRENCY table.

Information about loaded FX rates from a payment channel can be viewed through the user menu item path "Full →Daily Procedures →Load BIN Tables and Handbooks → FX Channel Rates".

This group contains the following user menu items:

- "Channel Rates on Date" access to channel rates for a certain date.
- "Channel Rates Last" access to the last entered channel rates.
- "Cross Rates on Date" access to cross rates calculated from the channel rate.

To access channel rates for a given date, select the menu item path "Full  $\rightarrow$  Daily Procedures  $\rightarrow$  Load BIN Tables and Handbooks  $\rightarrow$  FX Channel Rates  $\rightarrow$  Channel Rates on Date".

This will invoke the dialog box "Get Rate Type and Date" (see Fig. 8).




Fig. 8. Dialog box for selecting the FX type and date

Select the desired channel rate type from the drop-down list in the FX Type field. Rate types are registered in the "FX Types" form (Full  $\rightarrow$  Configuration Setup  $\rightarrow$  Accounting Setup  $\rightarrow$  FX Types). In the *Is Internal* field of the form, specify "No" for FX rate types imported from payment systems.

For Visa, a single "Visa Daily" rate is registered (unlike, for instance, for Master Card, for which Buy, Sell and Middle rates are registered).

The *Date* field is used to enter the date on which the channel rate was established by the payment system. After setting up these fields, click on the [Proceed] button.

The table grid "Channel Rates on Date" will appear on the screen (see Fig. 9).



Fig. 9. Table of channel rates

This table contains the following fields:

- Amnd Date date when file was loaded from the payment system
- FX Type additional conversion type (see "FX Types")
- Base Currency base currency for settlement with the payment system in US dollars or euros
  - Rates for currency to the payment system settlement currency and "direct" rates between different currencies can be loaded for MasterCard. When searching for FX rates, "direct" rates have a higher priority (i.e. they will be used first).
- Currency currency of rate shown
- 1 Base = value of currency rate to WAY4 settlement currency (rounded value)
- FX String rate value loaded from the payment system
- Date date when channel rate was set

The [History] button will invoke a table grid containing a list of all rate values for a selected currency, set up in the WAY4 system.

Channel rates are used for conversion transactions when comparing the transaction amount of inward clearing files with the payment channel's floor limit, if the transaction currency differs from the floor limit currency. Indicated rates, if set up accordingly in the Service Packages of the Interchange routing

contracts, can be used for calculating fees charged by the payment system on acquirer inward clearing documents.

To access the last rate entered into the system from any channel, select the user menu item path "Full  $\rightarrow$  Daily Procedures  $\rightarrow$  Load BIN Tables and Handbooks  $\rightarrow$  FX Channel Rates  $\rightarrow$  Channel Rates Last". After the desired channel rate is selected, the screen will display a table grid similar to the "Channel Rates on Date" table (see Fig. 9).

WAY4 will determine the currency cross rate based on the channel rates and the base currency rate.

To access data on cross rates, select the following user menu path: "Full  $\rightarrow$  Daily Procedures  $\rightarrow$  Load BIN Tables and Handbooks  $\rightarrow$  FX Channel Rates  $\rightarrow$  Cross Rates on Date".

This will display the dialog box "Get Rate Type and Date" (see Fig. 8) which indicates the channel rate type used for calculating the cross rate and the date on which the channel rates were set. After setting up the indicated fields, click on the [Proceed] button.

This will display the "Cross Rates" grid form (see Fig. 10).



Fig. 10. Table of currency cross rates

The "Cross Rates" table is used in the WAY4 system exclusively for user information purposes.

This table contains the following fields:

- FX Type additional conversion type (see "FX Types")
- Base Currency settlement currency used to determine the cross rate
- From Currency currency, rate of which determines the rate of currency indicated in the To Currency field
- *To Currency* currency, rate of which determines the rate of currency indicated in the *From Currency* field
- 1 From = rate of currency indicated in the To Currency field to one unit of the currency indicated in the From Currency field
- Date date when the channel rate was set
- Imported rates can also be accessed from the following menu folders:
- For MasterCard in the menu "MasterCard →MC. Daily Procedures →MC. Load Bin Table and Handbooks".
- For VISA in the menu "VISA → VISA. Daily Procedures → VISA. Inward Procedures".

In addition to import of channel rates, WAY4 supports import of arbitrary rates from other external sources. Processing centres can use this import for internal conversion for a number of operations at arbitrary rates. This is done using the menu item "Full → DB Administrator Utilities → Special OpenWay Utilities → External FX Rates Import". For more information, see the document "Importing External (Arbitrary) FX Rates".

# Copying FX Rates to a New Financial Institution

If contracts are being copied to a new financial institution, FX rates can be copied from the old institution to the new one (for example, to use the appropriate rates when reversing a transaction). To do so, execute the menu item "Full  $\rightarrow$  DB Administrator Utilities  $\rightarrow$  Special OpenWay Utilities  $\rightarrow$  FX Rates copy for FI". A form will open to choose the date for which the rates are being copies, the institution from which they are being copied and the target institution (see Fig. 11).




Fig. 11. "Date From. Fi from and FI to" form

Fill in this form's fields and click the [Proceed] button.

# Using Channel Rates for Internal Conversion

Processing centres can use channel rates for internal conversion. This means not setting their own rates, but converting for all operations (or for a number of operations) using channel rates.

To use channel rates for internal conversion, do as follows:

• Channel rates are imported in the standard way to the CHANNEL CURRENCY table (see the section "Loading Channel Rates).

Each record in the CHANNEL\_CURRENCY table (as an example, see the "Channel Rates on Date" form in Fig. 12) contains the rate of a certain currency (*Currency* field) to the payment system settlement currency (*Base Currency* field; this is usually *USD* (US dollars).



Fig. 12. Channel rates

- In the "FX Types" form ("Full → Configuration Setup → Accounting Setup → FX Types"; for more information, see the section "FX Types"), register a specific FX type with the following parameters, see Fig. 13.
  - Set the value of the *Is Internal* parameter to "Yes".
  - This FX Type's code (*Code* field) should have the following format:

CR\_<BUY\_FX\_TYPE\_CODE>;<SELL\_FX\_TYPE\_CODE>;<MIDDLE\_FX\_TYPE\_CODE>

#### Where

<BUY\_FX\_TYPE\_CODE> – is the FX Type code (*Code* field in the "FX Types" form) that corresponds to the buy rate in the CHANNEL\_CURRENCY table.

<SELL\_FX\_TYPE\_CODE> – is the FX Type code (*Code* field in the "FX Types" form) that corresponds to the sell rate in the CHANNEL\_CURRENCY table.

<MIDDLE\_FX\_TYPE\_CODE> – is the FX Type code (*Code* field in the "FX Types" form) that corresponds to the middle value of the rate in the CHANNEL\_CURRENCY table




Fig. 13. Configuring an FX Type

Configure an FX Scheme for this FX Type (specify the configured FX type in the FX Type field), see Fig. 14. The FX Scheme determines which currency is converted to the local currency.

FX Schemes can be configured for direct conversion (conversion from/to a local currency) and for multicurrency conversion.

For more information about FX Schemes, see the sections "Main FX Schemes" and "Configuring Multicurrency FX Schemes".



Fig. 14. Configuring an FX Scheme using a configured FX Type

- Execute the menu item "RBS FX Rates Copy To Internal" (Full → DB Administrator Utilities → Special OpenWay Utilities → RBS FX Rates Copy for Internal"). Based on channel rates, FX rates to the local currency will be calculated. These rates are calculated and registered with a link to FX Schemes with a specific FX Type rates are registered in the FX\_SCHEMES table. When searching for an FX Scheme, a record from the CHANNEL\_CURRENCY table is analysed as follows:
  - The currency from the *Base Currency* field in the CHANNEL\_CURRENCY table is matched with the financial institution's currency. If they match, a search is made for an FX Scheme whose currency (the Scheme's *Currency* field) matches the currency in the *Currency* field of the record in the CHANNEL\_CURRENCY table.
  - If the record's *Base Currency* currency does not match the financial institution's currency (or no FX Scheme was found in the previous step), the currency from the *Currency* field of the CHANNEL\_CURRENCY table is matched with the financial institution's currency. If they match, a search is made for an FX Scheme whose currency (the Scheme's *Currency* field) matches the currency in the *Currency* field of the record in the CHANNEL\_CURRENCY table.
    - I.e. in the aforementioned cases (conditions), one of the currencies for a record in the CHANNEL\_CURRENCY table (*Base Currency* or *Currency* channel rate) must match the financial institution's local currency, and the other currency must match the FX Scheme's currency. If this condition is observed, the "direct" rate from the CHANNEL\_CURRENCY table is used for calculation.
  - If the search according to the previous conditions did not provide a result, a search is made for two FX Schemes with the same currency in the *Base Currency* field and currencies in the *Currency* field corresponding to the *Currency* and *Base Currency* currencies of a record from the CHANNEL\_CURRENCY table.

## Example.

♦ In the CHANNEL\_CURRENCY table there is a record with Base Curr=USD, Currency=JPY, financial institution's local currency – EUR. I.e. there is no "direct" rate of JPY to EUR in the CHANNEL\_CURRENCY table.

- ◆ For an FX Scheme with *Currency*=JPY (scheme for converting JPY to EUR) rates will be calculated based on two records from the CHANNEL\_CURRENCY table: 1. Base Curr=USD, Currency=JPY; 2. Base Curr=USD, Currency=EUR.
- If errors occur when running the menu item "RBS FX Rates Copy To Internal", the process is not terminated. The number of records processed (registered) successfully and records with errors, as well as error messages can be viewed in the process log when the "Copy Channel Rates" process is finished.
- To use calculated FX rates (to activate rates), execute the menu item
   "Full → Daily Procedures → Start of Day Step By Step → Reset FX
   Rates". FX rates will be moved from the FX\_SCHEMES table to the
   FX\_RATES table.
- These rates can be used, for example, in Services. The appropriate FX Type should be set in the Service's FX Type field. When a transaction is made using this Service, the corresponding rates will be used in conversion.

# Chapter 3. Currency Conversion in WAY4

The way currency conversion is performed is determined by main FX scheme settings, FX type settings, multicurrency FX scheme settings, and global system parameters.

To convert currency in WAY4, the following needs to be set up for the FI:

- An FX contract that will be used as default for conversion operations.
- Main FX schemes, defining basic default FX types.
- If necessary, an FX type.
- If necessary, multicurrency FX schemes.
- Global parameters

# Setting up Main FX Schemes

# Main FX Schemes

A main FX scheme is a scheme registered in WAY4 for converting a foreign currency into a local currency. A main FX scheme record specifies a bank contract accounts pair used by default to record currency conversion for the corresponding FI and set currency. These accounts (or their pairs from an asset-liability pair of accounts) are used as FX accounts when converting this currency to the local currency

## "FX Scheme" Form

Main FX schemes are accessed in the "FX Scheme" form ("Full  $\rightarrow$  Configuration Setup  $\rightarrow$  Accounting Setup  $\rightarrow$  FX Scheme"), see Fig. 15.



Fig. 15. Table for configuring FX schemes

The "FX Scheme" form contains the following fields:

- *Currency* field contains a drop-down list of currencies; only the currencies from the system currency table for which "Yes" is set in the *Use in Bank* field are displayed (see "Currency Table").
- Financial Institution field for selecting the name of FI from a list.
- Base Curr, Is Cross Rate these fields are used when configuring multicurrency FX schemes, see the section "Configuring Multicurrency FX Schemes". They are not filled in for main FX schemes.

- *Trade Account* field for selecting an assets or liabilities account in the currency belonging to the FX contract; this account should be of type "Incoming Active"/"Incoming Passive" and category "Other".
- Reval Account field containing a drop-down list for indicating the assets or liabilities account in the local currency belonging to the FX contract; this account should be of type "Outgoing Active"/"Outgoing Passive" and category "Other" (for details on account parameters, see section "Account Types" in the WAY4<sup>TM</sup> Accounting Schemes Administrator Manual).
- *Is Local* this field can have the following values:
  - "Local" for local FI currency.
  - "Foreign" for foreign currency.
  - "Invalid" used if the FX scheme for that currency could not be authenticated due to a setup error.
- *Max Fluctuation* field for indicating the maximum fluctuation permissible in the currency rate; if this value is exceeded when a new rate value is entered for a currency the system will not accept the new data and create an error message (see "FX Rate History")
- FX Type for main FX types used by default, this field is left blank; the field is filled in when independent additional FX types are set up (see "FX Types")

An empty FX Type field for the main FX type does not mean that the parameters of this main FX type will be used for all additional FX types. Each additional FX type is set up separately: to set up an independent additional FX type, a new record containing a specific additional FX type is added to the "FX Scheme" form; to set up a dependent additional FX type, a new record containing a specific additional FX type is added to the "Additional for <name of currency>" form (see the section "FX Types").

## Adding an FX Scheme for a New Currency

The procedure for adding FX schemes for a new currency contains the following steps:

- In the currency table (see "Currency Table") add the currency (if absent in the list) and set its *Use in Bank* field to "Yes".
- In the "FX Scheme" table grid, select a template row for the FX scheme configured for the FI for a foreign currency, and click on the [Add Currency] button. This will display the "Add Currency" form indicating the names of the FI to which the FX scheme for the new currency will be added. In this form, click on the [Add] button and in the "Get Currency" form that opens, select the currency for the FX scheme, and click the [Proceed] button.
- If necessary, add account templates in the new currency to the Accounting Schemes of the cardholder contract and merchant client contract.
- In Service Packages (if necessary) select the new currency used for calculating the fee and usage limiter parameters.

As a result of this procedure, the system adds to the "FX Scheme" table a row including the FX scheme of a new currency and an FX type (see "FX Types") if one is configured for the FI. It also adds account templates in that currency to the FI bank contract's Accounting Scheme. The added account templates are of the same type as the template of the account currency being copied, or applied. The whole process of adding accounting templates for a new currency to the Accounting Schemes of cardholder and merchant client contracts must be accomplished manually.

Because adding a new FX scheme for a new currency changes the bank contract's Accounting Schemes, run a renew procedure afterward by selecting the user menu item path "Full → Configuration Setup → Main Tables → Renew All For Institution" in order to verify all the changes made (see the Financial Institutions Administrator Manual).

To enable the system to perform a check on changes made to the FX Scheme table, click on the [Check] button in the table (see Fig. 15). If the check is successful, the *Is Local* field in the FX Scheme will indicate "Foreign" for the FI's foreign currencies and "Local" for its local currencies. If check turns up an error in the FX scheme, the *Is Local* field will contain "Invalid".

If a new currency must be added to a subordinate financial institution (i.e. to an institution created by copying settings from a parent institution; see the section "Copying Basic FI Configurations" of the document "Financial Institutions"), do as follows:

- Add a currency in the parent institution (add a new currency, add an FX scheme for this currency, check settings by clicking on the [Check] button in the "FX Scheme" form; see the above description of steps for adding an FX scheme for a new currency).
- Synchronise settings of the subordinate institution (Refresh), see the sections "Partial Copying of Configurations for a Specific FI" and "Selective Copying of Parent FI Settings for all Child FIs" of the document "Financial Institutions". FX schemes for child financial institutions will be created automatically.

In configuring the FX Scheme for a financial institution, the following requirements must be met:

- The FX scheme for a local currency should not indicate the currency conversion accounts, i.e. fields *Trade Acount* and *Reval Account* should not be filled;
- The currency table should contain only one entry for each FI currency for each value in the *FX Type* field.

It is not recommended that users add an FX scheme to a new currency by clicking [Ins] to add a new row to the "FX Scheme" table. This button is only used to add independent FX Types (see "FX Types").


After adding an FX scheme, enter an FX rate value for the new currency. Otherwise, an error may occur during authorisation request processing if the necessary FX rate is missing, and the request will be declined.

# Deleting FX Schemes

To delete an FX scheme, select the record in the "FX Scheme" form, click the [Do] button and execute the "Delete with Additional" context menu command.

The scheme will be marked for deletion – the value "For Delete" is inserted in the *Is Local* field. The record is not immediately deleted, since active rates may exist for the scheme. When entering new FX rates (when executing the procedure "Full  $\rightarrow$  Daily Procedures  $\rightarrow$  Start of Day Step by Step  $\rightarrow$  Reset FX Rates") the rates will be marked as inactive and the scheme will be archived.

When deleting FX schemes for which FX Types are configured, all subordinate records (schemes) are also marked for deletion.



# **FX Types**

In order to widen user options around currency conversion according to bank requirements, WAY4 uses additional conversion types, called FX types, in addition to the basic types of conversion provided through the FX scheme.

By using FX types, foreign currency can be converted to local currency according to a special rate and/or using accounts other than the default ones for carrying out currency conversion.

The system distinguishes between two kinds of FX types:

- Independent allows special rate values to be set for FX from a foreign currency to a local currency (for example, different conversion rates for individuals and legal entities) and/or special FX accounts (for example, accounts for balance and off-balance accounting). For more information, see the section "Independent FX Types".
- Dependent allows redefinition of FX accounts. For more information, see the section "Dependent FX Types").

FX types can be used in the following situations:

- When indicating an FX type in the Accounting Scheme:
  - when processing operations affecting accounts of the same contract but in different currencies, for instance, to change parameters of multicurrency normalization accounts (see the "Multicurrency Normalisation" section of the Standing Payment Orders Administrator Manual);
- When indicating an FX type in the Service Package (see the "Full Information about a Service" section of the WAY4<sup>TM</sup> Service Packages Administrator Manual):
  - to change the parameters of transactions converting operation amounts and fees defined by a service; in this case, the FX type is defined in the service's parameters;
- When processing outward clearing files and comparing transaction amounts with the floor limit, if the transaction currency differs from the currency in which the limit is set.

# "FX Types" Form

FX Types are registered using the user menu item "Full  $\rightarrow$  Configuration Setup  $\rightarrow$  Accounting Setup  $\rightarrow$  FX Types". This displays the "FX Types" grid form (see Fig. 16).




Fig. 16. Table for registering FX Types

This form contains the following fields"

- *Name* FX Type name.
- *Code* FX Type code that is unique within the table.
- Is Internal when the "Yes" value is set in this field, a currency rate for this FX Type can be entered according to the rate entry procedure (see the section "Entering Local to Foreign Currency Rates"); for FX Types with the "No" value in this field, the system uses rates imported from payment systems.

# Independent FX Types

An independent FX Type for a foreign currency is set up by adding a new record to the "FX Scheme" table of FX schemes (see Fig. 17).

- In the *FX Type* field, specify the FX Type. The value is selected from a list of FX Types configured in the "FX Type" form with the value of the parameter *Is Internal* = "Yes" (see the section ""FX Types" Form").
- In the *Currency* field, specify the name of the currency for which special FX rates and/or accounts must be set.
- In the *Trade Account* and *Reval Account* fields, if necessary, specify special FX accounts for the selected currency.



Fig. 17. Configuring FX Type parameters

if FX schemes are used with independent FX Types, the procedure for entering currency rates includes entry of FX Type values along with entry of the main rate (see the section "Entering Local to Foreign Currency Rates").

For WAY4 to validate changes made to the table of FX schemes, click on the [Check] button in the "FX Scheme" form (see Fig. 15 in the section ""FX Scheme" Form"). If the check is successful, the *Is Local* field for FX schemes

will contain "Foreign" for foreign currencies and "Local" for the financial institution's local currency. If errors in FX scheme setup are found, the *Is Local* field will contain the "Invalid" value.

# Dependent FX Types

Only special FX accounts can be redefined using a dependent FX Type; the currency rate for this conversion type corresponds with the value of the main rate used by default.

Dependent FX Types are configured for each main FX scheme, with the exception of schemes belonging to the FI's local currency.

To configure dependent FX types in the FX scheme, select in the "FX Scheme" table (see Fig. 15 in the section ""FX Scheme" Form") the desired scheme and click on the [Additional] button. This will invoke the form "Additional for <name of currency>" to the screen (see Fig. 18).




Fig. 18. Configuring dependent FX Types

This form is filled out as follows:

- FX Type field for selecting a list of FX types having parameter Is Internal = "Yes".
- *Trade Account* field with a drop-down list for selecting an assets or liabilities account in a given foreign currency associated with the FX contract; by default this field should contain the value indicated in the field of the same name in the main FX scheme (see ""FX Scheme" Form").
- Reval Account field with a drop-down list for selecting an assets or liabilities account in a local currency associated with the FX contract; by default this field should contain the value indicated in the field of the same name in the main FX scheme (see "FX Scheme" Form").
- *Individual Accounting* if value "No" or an empty value is set in this field, the bank contract accounts indicated in fields *Trade Account* and *Reval Account* are used for currency conversion. If this field is set to "Yes", the system uses the accounts of the client contract of the same type as the bank contract accounts indicated in fields *Trade Account* and *Reval Account*.
- Base Curr and Is Cross Rate fields in the "Additional for <currency name>" form are used when configuring technical schemes that are subordinate to explicit cross-rate schemes (see the section "Configuring Explicit Cross Rate Schemes").

If using several FX types, the "Additional for <name of currency>" form should contain a corresponding number of rows.

For WAY4 to validate changes made to the "Additional for..." table, click on the [Check] button (see Fig. 18). If the check is successful, the dependent FX Type's *Is Local* field will contain the "Foreign" value.

When filling out the fields of this form, it should be kept in mind that no two entries in this table should have the same value in the *FX Type* field.

To delete a dependent FX type, select the record in the "Additional for..." form, click the [Do] button and execute the "Delete" context menu command.

# Configuring Multicurrency FX Schemes

Multicurrency FX Schemes are schemes for conversion from one foreign currency into another foreign currency.

if multicurrency FX schemes are not set up in the system, one foreign currency will be converted to another foreign currency using the main rates of these foreign currencies to the local rate (see the section "Base Cross Rates").

Multicurrency FX schemes are configured when one foreign currency must be converted to another using special rates or accounts. Ways of configuring multicurrency FX schemes:

- Creation of special FX schemes for converting local currency to those foreign
  currencies between which a special FX rate must be set. Rates of local
  currency to the foreign currencies specified using such FX schemes will be
  used when calculating special cross rates for the given foreign currencies. For
  more information, see the section "Configuring Special Cross Rate Schemes".
- Setting up a special FX scheme for converting one foreign currency into another for explicit cross rates. For more information, see the section "Configuring Explicit Cross Rate Schemes".

## **Base Cross Rates**

If multicurrency FX Rates are not set up in the system when converting currency from one foreign currency to another, the system calculates a cross rate using the basic local currency rate to the currency in question.

For example, if the local FI currency is Danish kroner, then conversion from US dollars to euros takes place according to this rate:

$$R_{USD/EUR} = \frac{R_{DKK/EUR}}{R_{DKK/USD}}$$
, where:

 $R_{DKK/EUR}$  – local currency rate in euros,

 $R_{DKK/USD}$  – local currency rate in US dollars.

In the same way, conversion from Japanese yen to euros will occur by through this rate:

$$R_{JPY/EUR} = \frac{R_{DKK/EUR}}{R_{DKK/JPY}}, \text{where:}$$

 $R_{DKK/EUR}$  – rate of local currency to euro,

 $R_{DKK/JPY}$  – rate of local currency to Japanese yen.

# Configuring Special Cross Rate Schemes

If the cross rates specified in the section "Base Cross Rates" differ from the rates desired, such as official rates, it is necessary to use special rates of the local currency to those of the foreign currency which are to be converted to another foreign currency.

In the case cited in the section "Base Cross Rates", the cross rate for converting US dollars to euros will be calculated as follows:

$$R_{USD/EUR}^{I} = \frac{R_{DKK/EUR}^{I}}{R_{DKK/USD}^{I}}$$
, where:

 $R_{DKK/USD}^{I}$  and  $R_{DKK/EUR}^{I}$  – special local currency rates to the foreign currency.

In the same way, the cross rate for converting Japanese yen to euros will be calculated as follows:

$$R_{JPY/EUR}^{I} = \frac{R_{DKK/EUR}^{I}}{R_{DKK/JPY}^{I}}$$
, where:

 $R_{DKK/IPY}^{I}$  and  $R_{DKK/EUR}^{I}$  – special local currency rates to the foreign currency.

To enter these special rates of local currency to the foreign currency,  $(R_{DKK/USD}^{I} \text{ и } R_{DKK/EUR}^{I})$  special FX schemes are used (see Fig. 19).

The rates  $(R_{DKK/USD}^{I} \cup R_{DKK/EUR}^{I})$  are independently calculated by the user to obtain correct FX cross rate values  $(R_{USD/EUR}^{I})$  according to the formulae specified above.

To configure special FX schemes:

- Add special FX schemes to the "FX Scheme" table for the foreign currencies being converted into another foreign currency; this, for the examples cited above, is US dollars, euros, and Japanese yen.
- When adding these FX schemes, the names of the foreign currencies between which conversion is being performed are selected in the *Currency* and *Base Currency* fields of the "FX Scheme" form (see Fig. 19).
  - Base Currency the foreign currency into which the other currency is being converted.
  - Currency the foreign currency that is being converted into the currency in the Base Currency
    - If two foreign currencies are specified in the FX scheme, during daily rate entry, rates of the local currency to the currency in the *Currency* field will be set for this scheme. These rates will be used during conversion from the *Currency* field currency to the *Base Currency* currency.
- The *Is Cross Rate* field should be left empty.

Fig. 19. Configuring FX Schemes for special cross rates

After this setup is confirmed, the system will allow users to enter special local currency rates during daily rate entry that may be used in calculating a cross rate for converting from these foreign currencies to another foreign currency.

- If a special cross rate scheme was created for only one foreign currency, the rate of the other foreign currency participating in conversion will be determined by the system through main rates of the local currency to the corresponding foreign currency.
- When setting up a special cross rate scheme, FX Types can be used in the same way as with main FX schemes (see the section "FX Types").
- Beginning with version 03.35.00, special cross rates are configured without the participation of independent FX types. In upgrading to this version, special cross rates scheme parameters change automatically:
- The *FX Type* field is cleared (the corresponding FX Type becomes history).
- The *Base Currency* field is filled in. The name of the currency corresponding to the code of the currency from the FX Type *Code* field is automatically filled in (from the "FX Types" form).
- An empty value is automatically specified in the *Is Cross Rate* field. Cross rates are calculated as in earlier versions.

# Configuring Explicit Cross Rate Schemes

Beginning with version 03.35.00 it is possible to explicitly set cross rates. Explicit cross rate schemes can be configured in one of the following ways:

- Migrate FX schemes set up using independent FX Types for calculating special cross rates. In migration, schemes are reconfigured and are further used for setting explicit cross rates (see the section "Migrating FX Schemes").
- Create special FX schemes manually for setting explicit cross rates. See the section "Manually Configuring Explicit Cross Rate".

## Migrating FX Schemes

To migrate FX schemes, do as follows:

 Execute the menu command "Full → Configuration Setup → Accounting Setup → FX Move to Cross Rate". The "FX Move to Cross-Rate" form will open, see Fig. 20.




Fig. 20. Updating FX schemes

If before installing version 03.35.00, special cross rates were used, this form shows additional FX schemes used earlier to calculate special cross rates.

i If special cross rates were not used before installation of version 03.35.00, this form does not contain records. In this case, FX schemes for working with explicit cross rates should be configured manually. See the section "Manually Configuring Explicit Cross Rate".

- To reconfigure an FX scheme for it to set explicit cross rates, specify its main foreign currency (*Code* field) and base foreign currency (*Base Curr* field). The cross rate will be set as the rate of conversion from the main foreign currency to the base one. In the example shown in Fig. 20, if USD are selected as the main currency (this is a scheme with the "USD" value in the *Code* field), cross rates will be specified for conversion of US dollars to Euros (for example, USD/EUR middle rate 0,6750). The inverse cross rate (EUR/USD) will be automatically calculated based on the USD to EUR rate entered.
- To start the migration process for a selected scheme, click the [Move] button. The following will occur:
  - In the "FX Scheme" form a new special FX scheme is generated, for which:
    - ♦ The "Yes" value is specified in the *Is Cross Rate* field (see Fig. 21). This means that during daily entry of rates, explicit cross rates will be set for the currency from the *Currency* field to the *Base Curr* field (and not the rate of the local currency to the *Currency* field currency, see the section "Configuring Special Cross Rate").
    - ♦ In the *Currency* field, the main foreign currency for the cross rate is specified: the foreign currency that is being converted into the foreign currency in the *Base Curr* field.
    - ♦ In the *Base Curr* field, the base foreign currency is specified. This is the foreign currency to which conversion is being made.
    - ◆ The *Trade Account* and *Reval Account* fields in the "FX Scheme" form remain empty. FX accounts for explicit cross rate schemes are specified in the form "Additional for <name of main currency>" (see below).
  - The "Additional for <name of currency>" form is automatically filled in, see Fig. 21. In this form, two additional technical schemes (with the "Technical" value in the *Is Cross Rate* field) are created that specify FX accounts:

- ♦ One technical scheme is created on the basis of the original FX scheme for which migration is being performed.
- ♦ The second scheme is generated in the following way: the system automatically searches for a paired FX scheme for calculating a special cross rate (the inverse of the scheme for which migration is being performed). In the example in Fig. 20, migration is performed for a scheme to convert USD to Euros (a scheme with the "USD" value in the *Code* field). The paired scheme is that to convert Euros to USD (a scheme with the "EUR" value in the *Code* field). On its basis, an additional technical FX scheme is generated in the form "Additional for <name of main currency>, see Fig. 21.

Original FX schemes for calculating special cross rates based on which technical schemes are created become history.

If a paired FX scheme for calculating a special cross rate does not exist, the second technical FX scheme is created using FX accounts from the main FX scheme for the corresponding currency.




Fig. 21. Explicit cross rate scheme generated during migration

Changes to FX schemes enter into force during the next entry of rates when daily opening procedures are executed.

## Manually Configuring Explicit Cross Rate Schemes

Explicit cross rate schemes are manually configured in the "FX Scheme" form (Full  $\rightarrow$  Configuration Setup  $\rightarrow$  Accounting Setup  $\rightarrow$  FX Scheme).

See the section "Migrating FX Schemes" for information on filling in "FX Scheme" form fields.

After filling in "FX Scheme" form fields, click the [Check] button. In the form "Additional for <name of main currency>" two technical FX schemes used to specify FX settlement accounts are generated automatically.

Accounts from main FX schemes for the corresponding currencies are used as FX accounts. If necessary, the accounts in the *Reval Account* and *Trade Account* fields can be changed.

FX Types can be used when configuring explicit cross rate schemes, in the same way as with main FX schemes (see the section "FX Types").

To delete a technical FX scheme, the parent FX scheme must be specified. Deletion of a technical scheme without the parent scheme is not accessible.

# Configuring the FX Rate Difference

This section describes basic configuration of the FX rate difference. For questions on configuring complex schemes for recording the FX rate difference, please contact the WAY4 vendor's customer support.

The FX rate difference is revenue and expenses from transactions to buy and sell foreign currency (for the local currency) or from FX transactions (buying and selling foreign currency for another foreign currency).

The FX rate difference (FeeAmount) is calculated as the difference between a country's Central Bank (National Bank) rate (CB Rate) for the date the transaction is made and the actual transaction rate expressed in a local currency.

Calculation of the FX rate difference depends on the transaction's direction – purchase or sale of currency (i.e. on whether the bank is buying or selling currency).

If the bank is selling currency (for example, if the client withdraws an amount in a foreign currency from his account in a local currency):

$$Fee Amount = Transaction Amount \left( \frac{Local Amount}{Transaction Amount} - CBRate \right)$$

If the bank is buying currency (for example, when depositing an amount in a foreign currency to a client account in a local currency):

$$FeeAmount = TransactionAmount \left(CBRate - \frac{LocalAmount}{TransactionAmount}\right)$$

The actual transaction rate is calculated as the relation of the amount in the financial institution's local currency (LocalAmount) to the amount in the foreign currency (TransactionAmount).

When the mode for recording (withholding) the FX rate difference is enabled (see the section "Configuring the FX Rate Difference") macrotransactions are analysed whose source contract account currency and target contract account currency differ. The FX rate difference is withheld if the FX rate according to which the amount was calculated in the financial institution's local currency (Local Amount/Transaction Amount) differs from the *CB Rate* rate. It follows that if the amount in the local currency (LocalAmount) differs from the amount in the foreign currency (TransactionAmount) converted at the *CB Rate* rate, the FX rate difference will be withheld.

If conversion was made according to a rate equal to the *CB Rate* rate, the FX rate difference will not be withheld, even if there was a rounding error.

The FX rate difference is recorded as a separate entry (GL\_TRACE) under the main (parent) macrotransaction generated when processing the transaction.

Example.

Deposit of 100 USD to an account in the local currency (Czech koruna (CZK)) according to the FX middle rate, equal to 1 USD= 29 CZK, which differs from the CB Rate rate (1 USD= 30 CZK).

The FX rate difference of 100 CZK will be withheld.

$$100\left(\frac{3000}{100}-29\right)$$

# Configuring the FX Rate Difference

To configure the FX rate difference, do as follows:

- Set the value of the FX\_MARGIN\_MODE global parameter to "Y".
- For the FX rate difference, set up a new transaction type (Full → Configuration Setup → Transaction Types) with the "None" value in the *DR/CR* field and transaction subtype (Full → Configuration Setup → Transaction Types → [Sub Types]). Usually, it is sufficient to set up one transaction type and one transaction subtype.
  - Several transaction types are set up if the FX rate difference must be configured differently for different FX Types.
  - Usually, the FX rate difference is recorded in the bank FX contract account (the conversion account where the *Trade* and *Revaluation* accounts specified in FX schemes are maintained). In this case, on the transaction subtype level in the *Source Cat* and *Target Cat* fields, the "Account" values is selected, in the *Source Type* and *Target Type* fields, the "Bank Account" value is selected (see Fig. 22). If in FX schemes *Trade* and *Revaluation* accounts are maintained in a client contract, it is necessary to create a separate transaction subtype. In this subtype's properties, in the *Source Cat* and *Target Cat* fields select the "Account" value, and in the *Source Type* and *Target Type* fields, select the "Client Account" value (see Fig. 22).




Fig. 22. Configuring transaction types and subtypes for the FX rate difference

- In the "FX Margin Transaction Types" form (Full → Configuration Setup →Transaction Types → FX Margin Transaction Types):
  - Configure a record specifying a common transaction type used for the FX rate difference (see Fig. 23).

• If necessary, configure the relation of transaction types with additional FX types (FX Type) and the financial institution. That is, if in the previous step several transaction types were set up for separate recording of the FX rate difference for different FX types, they should be specified in this form. The financial institution is specified if one financial institution shows FX rate differences differently depending on the FX type while other financial institutions use one common transaction type.




Fig. 23. "FX Margin Transaction Types" form

- Services must be configured for the FX rate difference.
  - Services are configured in those Service Packages that are used for the financial institution's FX contracts (usually, for the bank FX contract; if the *Trade* and *Revaluation* accounts are maintained in a client contract, the Service for the FX rate difference must be configured in the client Service Package).
  - Usually one main Service is configured for the FX rate difference, under which Custom Fees are configured that specify the main parameters for recording the FX rate difference. On the Custom Fee level correspondence of accounts, separation according to the director of the FX rate difference

     buy or sell currency, separation according to currency, etc. is set.

Several main Services can be created if the FX rate difference is recorded separately for different FX Types. In this case, Services are created for transaction subtypes corresponding to the given FX Types.

This section describes basic setup (see Fig. 24): creation of one main Service and one Custom Fee, without separation by currency, FX rate difference direction, etc.

- If complex schemes are required for recording the FX rate difference with separation according to currency, it is recommended to contact the WAY4 vendor's customer support service.
- One main Service is configured for the FX rate difference this is arbitrarily a Source Service or a Target Service. It is recommended to configure a Source Service.
- When configuring the main Service for the FX rate difference:
  - ◆ In the *Source Type* field, the corresponding FX contract type for the FX rate difference is specified ("Bank Account" or "Client Account".)
  - ♦ In the *Transaction Type* field, the transaction subtype is selected that is configured for the FX rate difference for the specified contract type.
  - ♦ The "None" value is set in the *Fee Dir* field.
- When configuring a Custom Fee:

- ♦ Set the "Debit" value in the *Direction* field.
- ♦ In the *Fee Code* field, specify a code that does not correspond to the code of the main Service.
- ♦ In the *FEE* % field specify the value "100"; this allows the entire amount of the FX rate difference to be transferred to the specified account.
- ◆ In the *Fee Curr* field, set the FI's local currency in explicit form (in addition to the tag FEE\_CURR\_TAG=FX\_MARGIN\_CURR;).
- ♦ In the *Account Type* field, specify the type of account from which the FX rate difference will be charged. If the *Account Type* field is not filled in, the Revaluation Account will be used that was used during conversion (the account from the FX Scheme's *Reval Account* field).
- ♦ In the *Fee Contract* and *Fee Account* fields, the contract is specified to which the FX rate difference will be transferred and the contract account (account from the Expenses/Revenue asset-liability pair for the FX rate difference). If these fields are not filled in, the FX rate difference will not be considered.
- The FX rate difference is always recorded in the local currency, therefore, when selecting the account in which the FX rate difference will be recorded and the account from which the FX rate difference is withheld, an account in a local currency must be specified.
- ♦ In the *Service Details* field, specify the tag FEE\_CURR\_TAG=FX\_MARGIN\_CURR; this tag sets calculation of the FX rate difference in the local currency, other settings are not supported).
- ♦ In the *Service Details* field, specify the tag FEE\_AMOUNT\_TAG=<value>; to specify the amount of the FX rate difference. Possible tag values:
  - FX\_MARGIN\_FULL full FX rate difference of a macrotransaction. This value is used if it is not necessary to separately consider the FX rate difference for currency buying and selling transactions (including when converting from one foreign currency into another foreign currency).
  - FX\_MARGIN\_BUY FX rate difference from buying currency (may be equal to "0" if this was a sale). In the case of conversion between two foreign currencies, only that part of the FX rate difference will be charged that relates to the purchase).
  - FX\_MARGIN\_SELL the FX rate difference from selling currency (may be equal to "0" if this was a purchase). In the case of conversion between two foreign currencies, only that part of the FX rate difference will be charged that relates to the sale).




Fig. 24. Configuring Services for recording the FX rate difference on a bank account (basic settings), the local currency is USD (US dollars)

If an FX rate difference was generated for a macrotransaction, a Service is searched for with consideration of the FX rate difference in the Service Package of the contract on which conversion was made (the search is made by transaction type, FX Type, etc.).

When entering FX rates (in execution of the daily opening procedure), it is necessary to correctly specify the country's Central Bank (National Bank) rate (CB Rate).

# Showing the FX Rate Difference in WAY4

Example: a transaction in US dollars with a card in the local currency (Czech koruna (CZK)) is shown in WAY4:

The document (see Fig. 25) contains the following data: transaction amount

 − 10 USD, settlement amount − 10 USD.




Fig. 25. Document

• Macrotransaction generated according to the document.



Fig. 26. Macrotransaction generated according to the document

- Journal entries generated when posting the macrotransaction, (see
- Fig. 27).




Fig. 27. Journal entries generated when posting the macrotransaction

• GL Entry in which the FX rate difference is recorded (see Fig. 28).




Fig. 28. GL Entry

# **Currency Conversion**

The actual currency conversion in the WAY4 system takes place in conversion accounts. Indicated accounts and their contracts are defined in the FX scheme configuration (see the section "Setting up Main FX Schemes") or their definitions may depend on additional global parameters (see "Global Parameters").

Currency conversion with conversion accounts takes place when the system processes macrotransactions created as a result of posting financial documents to transactions and non-transaction fees, during those cases when the contractor account currencies differ from one another.

In a simple scenario, currency conversion takes place according to the following transaction scheme (see Fig. 29):




Fig. 29. Accounting transactions when converting currency

As a rule, the FI's FX contract accounts are used as currency conversion accounts. It is possible to redefine these accounts through FX types (see "FX Types") and additional global parameters (see "Global Parameters").

# **Global Parameters**

When converting currency in the WAY4 system, the following global parameters are used:

- FX\_RATE\_INVERSE,
- CHANGE CURRENCY,
- AUTH\_USE\_DOMESTIC,
- USE\_AUTH\_FX,
- USE\_CROSS\_FX,
- MULTICURRENCY\_NORMALIZATION,
- FX\_MARGIN\_CURRENT\_RATE

(see the document "WAY4<sup>TM</sup> Global Parameters User Manual").

# **Additional Parameters**

When converting currency in the WAY4 system, the following additional parameters are used:

- Tag "USE\_TRANS\_AMOUNT=Y/N;" can be set on the financial institution, Product or Service Package level. For more information, see the description of the USE\_TRANS\_AMOUNT tag in the section "Additional FI Parameters" of the "Financial Institutions" document.
- *FX in HO* field of the "Details for <name of financial institution>" form. For more information, see the section "Additional FI Parameters" of the "Financial Institutions" document.

# Chapter 4. Solving Typical Problems in Currency Conversion

To solve problems that arise during currency conversion setup and implementation, it is recommended that users analyze messages generated by the system while these processes are being executed. To access these messages, users may access the system process  $\log$  ("Full  $\rightarrow$  Process  $\log$   $\rightarrow$  Process  $\log$ "). To analyze messages created by the system during document processing, find the desired document in the list of registered documents (Full  $\rightarrow$  Documents Input & Update  $\rightarrow$  Docs - General Form  $\rightarrow$  Doc - General") and click on the [Message] button.

# Messages Confirming the Accounting Scheme

CDB.CHECK\_SCHEME:E001

## **Message Text**

"Invalid template currency detected"

# **Message Description**

When checking the Accounting Scheme, the system found that the account template does not contain a currency, or that there is no FX scheme indicated for the FI in the account template for the currency.

#### **Recommended Actions**

Specify the account template currency or configure the FX scheme for the FI (see "Setting up Main FX Schemes Main FX Schemes").

# CDB.CHECK SCHEME:E034

## **Message Text**

"Invalid scheme currency"

#### **Message Description**

While checking the Accounting Scheme, the system either discovered that the Accounting Scheme has no specified currency, or found that no FX scheme is specified for the FI in the Accounting Scheme's currency.

#### **Recommended Actions**

Specify the Accounting Scheme currency or configure an FX scheme for the FI (see "Setting up Main FX Schemes Main FX Schemes").

# Messages Created While Checking the Financial Institution CDBC.CHECK FI SPC:E002

#### **Message Text**

"Entry of FX Schemes is not allowed for this institution"

#### **Message Description**

This message is created for a financial institution with a reference to another FI in the *Clearing In* field of the table ("Full  $\rightarrow$  Configuration Setup  $\rightarrow$  Main Tables  $\rightarrow$  Financial Institutions") and for which FX schemes are set up, despite the fact that this FI does not have its own General Ledger.

#### **Recommended Actions**

FX schemes for this FI must be deleted.

# CDBC.CHECK\_FI\_SPC:E003

## **Message Text**

"Entry of FX Scheme is required for this institution"

## **Message Description**

While checking the FI, the system did not find any entries pertaining to it in the FX Scheme table.

#### **Recommended Actions**

Configure the FI's FX scheme (see "Setting up Main FX Schemes Main FX Schemes"). In the FX scheme table, a minimum of one entry for the FI should be present, created for the FI's local currency.

# CDBC.CHECK\_FI\_SPC:E009

#### **Message Text**

"Local Currency not found in FX Scheme"

#### **Message Description**

When checking the FI, the system did not find an FX scheme for the financial institution's local currency.

# **Recommended Actions**

Set up an FX scheme for the FI's local currency (see "Setting up Main FX Schemes Main FX Schemes").

# Messages Created when Checking the FX Scheme

## FX.CHECK FX:E001

## **Message Text**

"Currency FX scheme already defined"

#### **Message Description**

While checking the FX scheme, the system found more than one entry for the same currency for one FI.

#### **Recommended Actions**

Delete duplicate entries from the FX Scheme table (see "Setting up Main FX Schemes Main FX Schemes").

# FX.CHECK FX:E005

## **Message Text**

"Invalid FX revaluation account"

#### **Message Description**

While checking the FX scheme, the system found a reference in the *Reval Account* field to a bank contract account that does not exist, or the *Reval Account* field is not filled in.

#### **Recommended Actions**

Correct the reference to the appropriate bank contract account in the FX scheme (see "Setting up Main FX Schemes Main FX Schemes").

# FX.CHECK\_FX:E006

## **Message Text**

"Invalid FX trade account"

## **Message Description**

While checking the FX scheme, the system found a reference in the *Trade Account* field to a bank contract account that does not exist.

#### **Recommended Actions**

Correct the reference to the appropriate bank contract account in the FX scheme (see "Setting up Main FX Schemes Main FX Schemes").

# FX.CHECK FX:E010

## **Message Text**

"Base currency is not defined for Cross-rate scheme"

# **Message Description**

While checking, the system discovered that in the "FX Scheme" form for an additional FX scheme used for explicit cross rates, the *Base Curr* field is not filled in...

#### **Recommended Actions**

Change the FX scheme (see "Configuring Explicit Cross Rate Schemes").

# FX.CHECK FX:E011

## **Message Text**

"Base currency is equal to FI Local Currency for Cross-rate scheme"

#### **Message Description**

While checking, it is discovered that in the "FX Scheme" form for an additional FX scheme used for explicit cross rates, the FI's local currency is specified in the *Base Curr* field.

#### **Recommended Actions**

Correct FX scheme settings. The FI's local currency is not used when configuring explicit cross rate schemes (see the section "Configuring Explicit Cross Rate Schemes").

# FX.CHECK\_FX:E012

#### **Message Text**

"Base currency is equal to Scheme Currency for Cross-rate scheme"

# **Message Description**

While checking, it is discovered that for a cross rate scheme, a currency corresponding to the scheme's main foreign currency is specified in the *Base Curr* field of the "FX Scheme" form.

#### **Recommended Actions**

Correct FX Scheme settings (see the section "FX Types").

# FX.CHECK FX:E013

## **Message Text**

"Wrong number of additional technical cross-rate schemes"

# **Message Description**

While checking, it is discovered that an incorrect set of technical schemes was generated for an explicit cross rate scheme. An incorrect value is set in the *Base Curr* field for one or both technical schemes.

#### **Recommended Actions**

Correct the technical scheme configuration in the form "Additional for <name of main currency>" (see the section "Configuring Explicit Cross Rate Schemes").

# FX.CHECK FX:E014

#### **Message Text**

"Old and New Cross-rate definitions are present in FX Schemes"

#### **Message Description**

While checking, it was discovered that in the "FX Scheme" form, more than one cross rate scheme was created for one currency. This situation arises if after migration of schemes to explicit cross rates a user creates cross rate schemes the old way (using an additional FX type, setting a base currency).

#### **Recommended Actions**

Correct FX scheme settings; delete duplicate records of cross rate schemes created using FX types (see the section "Configuring Multicurrency FX Schemes").

# FX.CHECK\_FX:E017

# **Message Text**

"Is Cross Rate must be Yes or No for parent scheme"

## **Message Description**

When checking a record in the "Additional for <name of main currency>" it was discovered that for the parent FX scheme, the value "Technical" is specified in the *Is Cross Rate* field of the "FX Scheme" field.

#### **Recommended Actions**

Correct the FX scheme settings in the "FX Scheme" form, specifying the "Yes" value in the *Is Cross Rate* field (if the scheme is being configured for explicit cross rates), or "No".

# FX.CHECK FX:E018

#### **Message Text**

"Parent and child schemes have different Is Cross Rate attributes"

# **Message Description**

When checking, a discrepancy in the values in the *Is cross Rate* field of the FX scheme in the "FX Scheme" form and child FX schemes in the "Additional for <name of main currency>" form is discovered.

This error does not occur when checking an explicit cross rate scheme and its child technical explicit cross rate schemes.

#### **Recommended Actions**

Correct FX scheme settings.

## FX.CHECK FX:E020

# **Message Text**

"Technical Cross-rate scheme have wrong Base Currency"

# **Message Description**

When checking the technical FX scheme in the form "Additional for <name of main currency>" it was discovered that in this scheme's *Base Curr* field, an incorrect value is specified that does not correspond to the main or base currency of the parent explicit cross rate scheme.

#### **Recommended Actions**

Correct FX scheme settings. For a explicit cross rate scheme, two child technical schemes are created: for one, the value of the *Base Curr* field of the parent scheme is specified in the *Base Curr* field, and for the other technical scheme, the value of the parent scheme's *Currency* (main currency) field.

# FX.CHECK FX:E021

# **Message Text**

"Technical Cross-rate scheme have wrong Code"

# **Message Description**

When checking, it was discovered that an incorrect value is specified in the *Code* field for the technical FX scheme.

#### **Recommended Actions**

Correct FX scheme settings

# FX.CHECK FX:E022

#### **Message Text**

"Parent Scheme is missing for the Technical Cross-rate scheme"

## **Message Description**

When checking, it was discovered that the parent cross rate scheme is missing for a technical scheme.

This situation may occur when the value "Technical" is specified in the *Is cross Rate* field of the "FX Scheme" form. This value may be set only in the form "Additional for <name of main currency> when configuring technical schemes for explicit cross rate schemes.

#### **Recommended Actions**

Correct FX scheme settings in the "FX Scheme" form, correct the value of the *Is cross Rate* field.

# FX.CHECK FX:W001

# **Message Text**

"FX Rates history missing for currency"

# **Message Description**

This is a warning that FX rate history is missing for the configured FX scheme.

#### **Recommended Actions**

Enter in the rate of local to foreign currency (see "Entering Local to Foreign Currency Rates").

# Messages Created when Processing Documents

# CHCK.BASE:E02

## **Message Text**

"Invalid Settlement Currency".

## **Response Code**

96

# **Message Description**

The settlement currency is not indicated in the document or is not specified in the FX scheme for the source contract FI.

Upon posting the document was declined.

#### **Recommended Actions**

Check the settlement currency and/or the fee currency in the document. If this currency is absent from the FX scheme of the source contract FI, it should be added.

# CHCK.BASE:E03

#### **Message Text**

"Invalid Fee currency".

## **Response Code**

96

## **Message Description**

The fee currency value is not indicated in the document or undefined in the FX scheme for the FI of the source contract and/or target contract.

Upon processing the document was declined.

#### **Recommended Actions**

Check the fee currencies in the document (Source Fee Currency, Target Fee Currency). If the fee currency is absent from the FX scheme, add it.

## CHCK.ROUTING:E10

#### **Message Text**

"Invalid Settlement Currency".

## **Response Code**

96

#### **Message Description**

The settlement currency is not indicated in the interbranch transaction document or is not specified in the FX scheme for the FI associated with the macrotransaction.

The currency is selected according to the document currency and interbranch routing properties. Upon posting the document was declined.

## **Recommended Actions**

Check the settlement currency and if needed make corrections to the FX scheme.

## CHCK.TRANSF:E004

# **Message Text**

"Invalid Settlement Currency".

## **Response Code**

12

## **Message Description**

The settlement currency is not indicated in the transfer amount document or in the FX scheme for the source contract and target contract FI. Upon posting the document was declined.

## **Recommended Actions**

Check the settlement currency in the document and if necessary make corrections to the FX scheme.