BioTuring System - GPU enterprise version installation guide

This edition of the installation guide describes the installation process of BioTuring® System for container runtime (Docker/Containerd), K8S, and standalone Linux machine.

1. Introduction

BioTuring System is a GPU-accelerated single-cell and spatial platform developed by BioTuring®. It dramatically increases the computing performance of singlecell and spatial analysis by harnessing the power of the graphics processing unit (GPU).

1.1. Pre-Installation Requirements

Before installing the BioTuring System on Linux/K8S, some pre-installation steps are required: - Container runtime (Docker, Containerd) - The system has one or multiple NVIDIA GPU(s) (at least 16 GB memory per GPU) - SSL certificate and a domain name for users to securely access the platform on the web browser - A token obtained from BioTuring - At least 64 GB of root partition. - At least 32 GB of RAM - At least 16 CPU cores. - Operating system: Ubuntu 18.04.x, Ubuntu 20.04.x, Ubuntu 22.04.x, RHEL 7.x, RHEL 8.x, RHEL 9.x

1.2. Self-Signed CA Certificate installation (If you have problem with curl https):

Adding self-signed certificates as trusted to your proxy agent/server

bash ./cert/install.sh

2. Docker Installation:

We support container runtime: Docker, Containerd.

Note: The ideal system that we recommend for most companies is AWS g5.8xlarge

1. Simple installation (Recommended):

bash ./install.docker.sh

2. Manual Installation:

For GPU version

```
docker container run -d -t -i \
```

- -e WEB DOMAIN='CHANGE THIS TO YOUR DOMAIN' \
- -e BIOTURING_TOKEN='USE TOKEN OBTAINED FROM BIOTURING' \
- -e ADMIN_USERNAME='admin' \

```
-e ADMIN_PASSWORD='CHANGE YOUR PASSWORD IF NECESSARY' \
    -e LC_ALL='C.UTF-8' \
    -e LC_LANG='C.UTF-8' \
    -p 80:80 \
    -p 443:443 \
    -v '/path/to/persistent/storage/':/data/user_data \
    -v '/path/to/stateful/storage/':/data/app_data \
    -v '/path/to/ssl/storage/':/config/ssl \
    --gpus all \
    --link bioturing-ecosystem:latest \
    --name bioturing-ecosystem
For GPU version
docker container run -d -t -i \
    -e WEB_DOMAIN='CHANGE THIS TO YOUR DOMAIN' \
    -e BIOTURING TOKEN='USE TOKEN OBTAINED FROM BIOTURING' \
    -e ADMIN_USERNAME='admin' \
    -e ADMIN_PASSWORD='CHANGE YOUR PASSWORD IF NECESSARY' \
    -e LC_ALL='C.UTF-8' \
    -e LC LANG='C.UTF-8' \
    -p 80:80 \
    -p 443:443 \
    -v '/path/to/persistent/storage/':/data/user_data \
    -v '/path/to/stateful/storage/':/data/app_data \
    -v '/path/to/ssl/storage/':/config/ssl \
    --link bioturing-ecosystem-cpu:latest \
    --name bioturing-ecosystem-cpu
'/path/to/ssl/storage/': must contain two files: tls.crt and tls.key
```

3. Notices

3.1. Security

- BioTuring System uses HTTPS protocol to securely communicate over the network.
- All of the users need to authenticate using a BioTuring account or the company's SSO to access the platform.
- We highly recommend setting up a private VPC network for IP restriction.
- The data stays behind the company firewall.
- BioTuring System does not track any usage logs.

3.2. Data visibility

- Data can be uploaded to Personal Workspace or Data Sharing group.
- In the Personal Workspace, only the owner can see and manipulate the data she/he uploaded.

- In the Data Sharing group, only people in the group can see the data.
 In the Data Sharing group, only people with sufficient permissions can manipulate the data.