libzerocoin User Guide

Ian Miers, Christina Garman and Matthew Green

This manual describes libzerocoin, an implementation of the cryptographic components of the Zerocoin protocol.

The libzerocoinlibrary is designed to integrate with a Bitcoin/Litecoin style client, and performs the base cryptographic operations necessary to integrate Zerocoin with the client. These operations include generation/veri cation of coins, as well as generation/veri cation of spend signatures. Roughly speaking, the use of Zerocoin proceeds according to the following steps:

- 1. All Zerocoin clients in a deployment must share a single parameter N where N is a 2048-3072 bit modulus such that N=p*q where p and q are large safe prime numbers (i.e., p=2p'+1, q=2q'+1 for primes p',q'). Once N has been generated, the underlying values p,q,p',q' can and should be destroyed.
 - In addition to N, all clients must agree on a security level k (an integer \geq 80), as well as a canonical value of one zerocoin (measured in the underlying currency).
- 2. To Mint a zerocoin, a client rst generates a new coin c using operations in the libzerocoin library.

Once the coin is Minted, the client must now format and transmit a ZEROCOIN_MINT transaction to the network, using routines not present in libzerocoin. This transaction is similar to a normal Bitcoin/Litecoin transaction: it consists of inputs combining to the value of one zerocoin. Unlike a standard transaction, this transaction does not provide any outputs. Instead it simply embeds the Zerocoin value c.