

TMS Bridge: Database Objects

Date: 2026-04-29
TMS Database Version: release/7.0.0.8+NEW-DISP0 (commit 6543ffd9)

Schema Convention

- tms** = runtime-resolved TMS tenant schema (e.g., `tms01001` on PostgreSQL, `TMS01001` on Oracle)
- public** = PostgreSQL default schema (Bridge-local objects)
- pdis_transportorder**, **pdis_tourpoint**, **pdis_leg**, **disp_mde_ah**, **disp_mde_eb**, **cal_uniface**, **pdis_transportorderdto** = fixed routine schemas

1. Tables (11)

All accessed READ-only via Entity Framework Core. No `SaveChanges` calls exist in the application layer.

Classification principle: Objects are classified by their **actual database type** (TABLE or VIEW), not by the EF Core mapping directive. `ToView()` in EF Core means "treat as read-only entity" — it does not imply the database object is a view. `ToTable()` means "treat as writable entity". When `ToView()` targets a database TABLE, the object is classified here as a TABLE with read-only access.

#	Object Name	Type	Schema	EF Mapping	Access	Required Permission
1	bordero	TABLE	tms	ToTable	READ	SELECT
2	fahrer	TABLE	tms	ToTable	READ	SELECT
3	ort	TABLE	tms	ToTable	READ	SELECT
4	person	TABLE	tms	ToTable	READ	SELECT
5	pst_hst	TABLE	tms	ToTable	READ	SELECT
6	rollkart	TABLE	tms	ToTable	READ	SELECT
7	sendung	TABLE	tms	ToTable	READ	SELECT
8	sen_ls_pst	TABLE	tms	ToTable	READ	SELECT
9	sen_ls_ref	TABLE	tms	ToTable	READ	SELECT
10	sen_zuord	TABLE	tms	ToTable	READ	SELECT
11	sen_ref	TABLE	tms	ToView	READ (read-only)	SELECT

Note on #11: `sen_ref` is a TABLE in the TMS database, mapped via `ToView("sen_ref")` in `SenRefEntityConfiguration.cs`. The `ToView()` directive enforces read-only access at the EF level — it does not change the underlying database object type. A `v_sen_ref` VIEW exists in the database (unions `sen_ref` + `sen_ls_ref`) but is **not used** by the TMS Bridge.

Note: Entity configurations for `transportorder`, `shipment`, `tourpoint`, `presettemp`, `freightexchange_tourpoint`, `transportorder_pickupplanning`, and `transportordercut` declare `ToTable(...)` but `BranchDbContext.OnModelCreating` overrides all of them with `ToView(...)`. These are listed in section 2 (Views).

2. Views (20)

All accessed READ-only via Entity Framework Core.

2a. Disposition Views

#	Object Name	Type	Schema	Access	Required Permission	Notes
1	v_dis_transportorder	VIEW	public	READ	SELECT	
2	v_dis_to_filter	VIEW	public	READ	SELECT	Renamed from v_dis_transportorder_filter
3	v_dis_to_pickupplanning	VIEW	public	READ	SELECT	Renamed from v_dis_transportorder_pickupplanning
4	v_dis_shipment_all	VIEW	public	READ	SELECT	
5	v_dis_to_tourpoint	VIEW	public	READ	SELECT	
6	v_dis_freight_exchange_tp	VIEW	public	READ	SELECT	Renamed from v_dis_freight_exchange_tourpoints
7	v_dis_to_presettemp	VIEW	public	READ	SELECT	Renamed from v_dis_transportorder_presettemp
8	v_dis_branch_address	VIEW	public	READ	SELECT	
9	v_dis_leg	VIEW	public	READ	SELECT	
10	v_dis_to_features	VIEW	tms	READ	SELECT	Renamed from v_dis_transportorder_features
11	v_dis_contact_details	VIEW	tms	READ	SELECT	
12	v_dis_to_tp_target_dates	VIEW	tms	READ	SELECT	Renamed from v_dis_to_tourpoint_target_dates
13	v_dis_tp_client_comm	VIEW	tms	READ	SELECT	Renamed from v_dis_tourpoint_client_communication
14	v_pers_tb	VIEW	tms	READ	SELECT	

2b. EBV Views

#	Object Name	Type	Schema	Access	Required Permission	Notes
15	v_ebv_shipment	VIEW	tms	READ	SELECT	
16	v_ebv_delivery_note	VIEW	tms	READ	SELECT	Navigation-only (no own DbSet)
17	v_ebv_leg	VIEW	tms	READ	SELECT	Navigation-only (no own DbSet)
18	v_ebv_participant	VIEW	tms	READ	SELECT	Navigation-only (no own DbSet)
19	v_ebv_service	VIEW	tms	READ	SELECT	Navigation-only (no own DbSet)

2c. Sendung (Consignment) Views

#	Object Name	Type	Schema	Access	Required Permission	Notes
20	v_sen_ls	VIEW	tms	READ	SELECT	

3. Functions (11)

Called via IRoutineExecutor . Functions return data; some also mutate state (marked WRITE).

#	Object Name	Type	Schema	Access	Required Permission	
1	pdis_transportorderdto.get	FUNCTION	pdis_transportorderdto	READ	EXECUTE	Transport0

#	Object Name	Type	Schema	Access	Required Permission	
2	pdis_transportorder.getxserverdto	FUNCTION	pdis_transportorder	READ	EXECUTE	GetXserver
3	pdis_transportorder.getdriver	FUNCTION	pdis_transportorder	READ	EXECUTE	GetDriverM
4	pdis_transportorder.geterrormessage	FUNCTION	pdis_transportorder	READ	EXECUTE	Internal erro
5	pdis_transportorder.setxserverdto	FUNCTION	pdis_transportorder	WRITE	EXECUTE	SetXServer
6	pdis_transportorder.createtransportorderfromleg	FUNCTION	pdis_transportorder	WRITE	EXECUTE	CreateTran
7	pdis_transportorder.createtransportorderfromshipment	FUNCTION	pdis_transportorder	WRITE	EXECUTE	CreateTran (obsolete)
8	pdis_transportorder.addshipment	FUNCTION	pdis_transportorder	WRITE	EXECUTE	CreateTran (obsolete)
9	pdis_leg.getstaysloadedstatus	FUNCTION	pdis_leg	READ	EXECUTE	GetStaysLo
10	cal_uniface.item	FUNCTION	cal_uniface	READ	EXECUTE	ItemMutati PstHstMeta
11	cal_uniface.list2dbtt	TABLE FUNCTION	cal_uniface	READ	EXECUTE	List2DbttM PstHstMeta

Note on #10 + #11: PstHstMetaDataResolver chains cal_uniface.item followed by cal_uniface.list2dbtt automatically when a pst_hst GraphQL query includes the decodedMetaData field. These are triggered server-side without an explicit mutation call.

Note on #11: cal_uniface.list2dbtt is a table function. Only an Oracle builder exists (OracleTableBuilder , generates SELECT * FROM TABLE(...)). No PostgreSQL equivalent is implemented.

4. Stored Procedures (35)

Called via IRoutineExecutor . All are WRITE operations (mutate database state).

4a. pdis_transportorder Schema — Transport Order Management (22)

#	Object Name	Type	Schema	Access	Required Permission	Called
1	pdis_transportorder.delete	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	DeleteTransportOderMut
2	pdis_transportorder.addtourpoint	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	AddTourpointMutation
3	pdis_transportorder.edittourpoint	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	EditTourpointMutation
4	pdis_transportorder.deletetourpoint	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	DeleteTourpointMutatic
5	pdis_transportorder.movetourpoint	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	MoveTourpointMutation
6	pdis_transportorder.removeleg	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	RemoveLegMutation
7	pdis_transportorder.createandaddleg	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	CreateAndAddLegMutatic
8	pdis_transportorder.removeshipment	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	RemoveShipmentFromTran
9	pdis_transportorder.addvehicle	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	AssignVehicleMutation
10	pdis_transportorder.removevehicle	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	RemoveVehicleMutation
11	pdis_transportorder.addtrailer	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	AddTrailerMutation
12	pdis_transportorder.removetrailer	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	RemoveTrailerMutation

#	Object Name	Type	Schema	Access	Required Permission	Called
13	pdis_transportorder.setparticipant	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetParticipantMutation
14	pdis_transportorder.removeparticipant	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	RemoveParticipantMutat
15	pdis_transportorder.setpresettemp	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetPresetTempMutation
16	pdis_transportorder.settransportmode	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetTransportModeMutati
17	pdis_transportorder.setvehicleattributes	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetVehicleAttributesMu
18	pdis_transportorder.setequipmenthired	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetEquipmentHiredMutat
19	pdis_transportorder.setloadingaidsoptions	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetLoadingAidsOptionMu
20	pdis_transportorder.setcomment	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetCommentMutation
21	pdis_transportorder.setdriver	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	SetDriverMutation
22	pdis_transportorder.removedriver	PROCEDURE	pdis_transportorder	WRITE	EXECUTE	RemoveDriverMutation

4b. pdis_tourpoint Schema – Tourpoint Management (6)

#	Object Name	Type	Schema	Access	Required Permission	Called By
23	pdis_tourpoint.setcustomertournumber	PROCEDURE	pdis_tourpoint	WRITE	EXECUTE	SetCustomerTourNumberMutatio
24	pdis_tourpoint.setloadinginterval	PROCEDURE	pdis_tourpoint	WRITE	EXECUTE	SetLoadingIntervalMutation
25	pdis_tourpoint.settargetloadingstarttime	PROCEDURE	pdis_tourpoint	WRITE	EXECUTE	SetTargetLoadingStartTimeMut
26	pdis_tourpoint.settargetloadingendtime	PROCEDURE	pdis_tourpoint	WRITE	EXECUTE	SetTargetLoadingEndTimeMutat
27	pdis_tourpoint.removeloadintervals	PROCEDURE	pdis_tourpoint	WRITE	EXECUTE	RemoveLoadingIntervalsMutat:
28	pdis_tourpoint.setloadingreference	PROCEDURE	pdis_tourpoint	WRITE	EXECUTE	SetLoadingReferenceMutation

4c. pdis_leg Schema – Leg Management (1)

#	Object Name	Type	Schema	Access	Required Permission	Called By
29	pdis_leg.staysloaded	PROCEDURE	pdis_leg	WRITE	EXECUTE	StaysLoadedMutation

4d. disp_mde_ah Schema – MDE Arrival Hub (4)

#	Object Name	Type	Schema	Access	Required Permission	Called By
30	disp_mde_ah.scanbarcode	PROCEDURE	disp_mde_ah	WRITE	EXECUTE	DispMdeAhScanBarcodeMutation
31	disp_mde_ah.startentladung	PROCEDURE	disp_mde_ah	WRITE	EXECUTE	DispMdeAhStartEntladungMutation
32	disp_mde_ah.endeentladung	PROCEDURE	disp_mde_ah	WRITE	EXECUTE	DispMdeAhEndeEntladungMutation
33	disp_mde_ah.abschlnve	PROCEDURE	disp_mde_ah	WRITE	EXECUTE	DispMdeAhAbschlnVEMutation

4e. disp_mde_eb Schema – MDE Departure Hub (2)

#	Object Name	Type	Schema	Access	Required Permission	Called By
34	disp_mde_eb.endeentladung	PROCEDURE	disp_mde_eb	WRITE	EXECUTE	DispMdeEbEndeEntladungMutation
35	disp_mde_eb.abschlnve	PROCEDURE	disp_mde_eb	WRITE	EXECUTE	DispMdeEbAbschlnVEMutation

5. Custom Types (1)

#	Object Name	Type	Schema	Required Permission	Values	Notes
1	legtype	ENUM	pdis_transportorder	USAGE	VL, HL, NL	Registered via HasPostgresEnum (PostgreSQL only). Used as input parameter in createtransportorderfromleg , createandaddleg , removeshipment , and obsolete lot mutations.

Summary: Permission Scope

By Access Pattern

Access	Count	Required Permission
READ (Tables)	11	SELECT
READ (Views)	20	SELECT
READ (Functions)	5	EXECUTE
WRITE (Functions)	4	EXECUTE
READ (Table Functions)	1	EXECUTE
WRITE (Procedures)	35	EXECUTE
USAGE (Custom Types)	1	USAGE
Total	77	

By Schema

Schema	SELECT	EXECUTE	USAGE	Total
tms (tenant)	16 (11 tables + 5 views)	—	—	16
public	9 (9 views)	—	—	9
pdis_transportorder	—	31 (9 functions + 22 procedures)	1 (legtype)	32
pdis_tourpoint	—	6 procedures	—	6
pdis_leg	—	2 (1 function + 1 procedure)	—	2
pdis_transportorderdto	—	1 function	—	1
disp_mde_ah	—	4 procedures	—	4
disp_mde_eb	—	2 procedures	—	2
cal_uniface	—	2 functions	—	2
Total	25	48	1	77

View Rename Reference

The following 7 views were renamed in TMS Database `release/7.0.0.8+NEW-DISPO` (commit `6543ffd9`). This document uses the **new names**. The TMS Bridge code must be updated to reference these new names before deployment.

Old Name	New Name
v_dis_transportorder_filter	v_dis_to_filter
v_dis_transportorder_pickupplanning	v_dis_to_pickupplanning
v_dis_freight_exchange_tourpoints	v_dis_freight_exchange_tp
v_dis_transportorder_presettemp	v_dis_to_presettemp
v_dis_transportorder_features	v_dis_to_features
v_dis_to_tourpoint_target_dates	v_dis_to_tp_target_dates
v_dis_tourpoint_client_communication	v_dis_tp_client_comm

Not renamed: v_dis_transportorder_count -> v_dis_to_count (not used by TMS Bridge).

Version History

Version	Date	Author	Changes
1.0	2026-04-29	Matthias Max	Initial inventory: 10 tables, 21 views, 11 functions, 35 procedures, 1 custom type. View names updated to post-rename state (7 views renamed in TMS DB commit 6543ffd9).
1.1	2026-04-29	Matthias Max	Reclassified sen_ref from VIEW to TABLE (read-only via ToView). Added EF Mapping column to tables section. Added classification principle: objects classified by actual DB type, not EF mapping directive. Counts: 11 tables, 20 views. Triggered by Eric Meijers' review feedback.

Created and maintained by **Virtual Architect**