

Is this implementation correct?

```
schedule1() {
acquire(struct lock *I) {
                                                                       status = disable_interrupt();
 status = interrupt disable();
                                                                       push_list(ready_list, cur_thread);
                                                                      schedule();
 while (I->value == 0) {
                                                                      set_interrupt_status(status);
    schedule1();
 l->value = 0;
                                                                      lock is initialized with 1.
 set_interrupt_status(status);
                                                                      Yes, but not good because
                                                                      there is no point in scheduling
                                                                      waiting threads until the lock
release(struct lock *I) {
                                                                      holder releases the lock
  I->value = 1;
}
```

The schedule1 routine puts the waiting threads to the ready list such that it can be scheduled later (say on timer interrupt). However, it doesn't make sense to let these waiting threads getting scheduled until the lock holder releases the lock. A better solution would be to put these threads in some other list (not ready list). During release, the lock holder can remove a thread from the waiting list and add them to the ready list.

```
acquire(struct lock *I) {
    status = interrupt_disable();
    while (I->value == 0) {
        list_push(I->wait_list, cur_thread);
        schedule();
    }
    I->value = 0;
    set_interrupt_status(status);
}

struct lock {
    int value;
        struct list *wait_list;
    };

Instead of putting the threads in the
    ready list, the lock implementation puts
    them in another list, thus preventing
    them from getting scheduled.
```

The lock structure contains a list that contains all the threads that are waiting for acquiring the corresponding lock. In acquire routine, if a thread is unable to acquire a lock, it puts itself to the waiting list of the corresponding lock and call schedule. Notice, schedule is different from schedule1. schedule doesn't put the current thread to the ready list. Also, schedule assumes that the caller must have disabled the interrupt before calling schedule. If interrupts are enabled, then schedule may call itself (unless we implement some other logic to prevent that) and thus end up putting the ready list in an inconsistent state.

```
A > schedule 1 > sobetale > context switch
B > context-switch > schedule > sechedule 1
acquire
                                                                schedule1() {
                                                              status = disable_interrupt();
                                                                 push_list(ready_list, cur_thread);
acquire(struct lock *I) {
                                                                 schedule();
intstatus = interrupt_disable();
                                                                 set interrupt status(status);
  while (I->value == 0) {
     list_push(l->wait_list, cur_thread);
     schedule(); _
                                                               Is it okay to call schedule with
                                                               interrupts disabled? Does this mean
                                                               that the new thread will be running
  l->value = 0;
                                                               with interrupts disabled?
  set_interrupt_status(status);
```

Even if we are disabling interrupts while calling schedule, it will be enabled after the schedule returns.

acquire schedule1() { status = disable_interrupt(); push_list(ready_list, cur_thread); acquire(struct lock *I) { schedule(); status = interrupt_disable(); set_interrupt_status(status); while (I->value == 0) { list_push(I->wait_list, cur_thread); schedule(); Is it okay to call schedule with interrupts disabled? Does this mean that the new thread will be running I->value = 0; with interrupts disabled? set_interrupt_status(status); No, if the new thread was preempted using schedule1 routine, then the interrupts will be enabled in the schedule1 method, after returning from the schedule.

acquire

```
acquire(struct lock *I) {
  status = interrupt_disable();
  while (I->value == 0) {
     list_push(I->wait_list, cur_thread);
     schedule();
  }
  I->value = 0;
  set_interrupt_status(status);
}
```

Is it okay to call schedule with interrupts disabled? Does this mean that the new thread will be running with interrupts disabled?

If the schedule (for the new thread) was called from the acquire routine, then the interrupt will be enabled at the end of the acquire routine.

release

```
release(struct lock *I) {
    t = list_pop(I->wait_list);
    if (t)
        list_push(ready_list, t);
        I->value = 1;
}
```

```
acquire(struct lock *I) {
    status = interrupt_disable();
    while (I->value == 0) {
        list_push(I->wait_list, cur_thread);
        schedule();
    }
    I->value = 0;
    set_interrupt_status(status);
    }

What is the problem with the release implementation?
```

release

```
release(struct lock *I) {
    t = list_pop(I->wait_list);
    if (t)
        list_push(ready_list, t);
    I->value = 1;
}
```

```
acquire(struct lock *I) {
  status = interrupt_disable();
  while (I->value == 0) {
    list_push(I->wait_list, cur_thread);
    schedule();
  }
  I->value = 0;
  set_interrupt_status(status);
}
```

What is the problem with the release implementation?

The release is modifying the wait_list without disabling interrupts. An interrupt may schedule the current thread after the partial update of wait_list, and new thread may call the acquire routine. In the acquire routine, list_push may cause wait_list to go into an inconsistent state.

release

```
release(struct lock *I) {
    t = list_pop(I->wait_list);
    if (t)
        list_push(ready_list, t);
    I->value = 1;
}
```

```
schedule1() {
   status = disable_interrupt();
   push_list(ready_list, cur_thread);
   schedule();
   set_interrupt_status(status);
}
```

What is the problem with the release implementation?

The release is modifying the ready_list without disabling interrupts. An interrupt may call schedule1 after the partial update of the ready_list. In schedule1 routine, the list_push may cause the ready_list to go into an inconsistent state.

```
acquire(struct lock *I) {
release
                                                                    status = interrupt_disable();
                                                                    while (I->value == 0) {
                                                                      list_push(I->wait_list, cur_thread);
                                                                      schedule();
release(struct lock *I) {
                                                                    I->value = 0;
  t = list_pop(l->wait_list);
                                                                    set_interrupt_status(status);
  if (t)
     list_push(ready_list, t);
                                                               What is the problem with the release
  I->value = 1;
                                                               implementation?
                                                               Let us say that list_pop returns NULL. At
                                                               this point, an interrupt may schedule a new
                                                               thread (T2) that may call the acquire
                                                               routine and add itself to wait_list. Thread
                                                               T2 will never be woken up unless a new
                                                               thread tries to acquire the same lock.
```

This case is described on the next slide.

```
acquire(struct lock *I) {
                                                                 status = interrupt_disable();
release
                                                                 while (I->value == 0) {
                                                                   list_push(l->wait_list, cur_thread);
                                                         A
                                                                   schedule();
T1: try to acquire lock A
                                                                 I->value = 0;
T1: acquired lock A
                                                                 set_interrupt_status(status);
T1: try to release lock A
T1: list_pop returns NULL
                                                                release(struct lock *I) {
                                                       t = list_pop(l->wait_list);

t = list_pop(l->wait_list);
                                                                                             schedule
T1: schedule1 is called
T2: try to acquire lock A
                                                                   list_push(ready_list, t);
T2: added to wait_list, schedule1 was called
                                                                 I->value = 1;
                                                                }
T1: released lock A
T2: is still in the wait list ..
T3: try to acquire lock A, acquired lock A, try to release lock A, add T2 to ready list
```

```
release
release(struct lock *I) {
    status = interrupt_disable();
    t = list_pop(I->wait_list);
    if (t)
        list_push(ready_list, t);
        I->value = 1;
    set_interrupt_status(status);
}
```

The correct implementation of release disables the interrupts throughout the function body.

acquire(struct lock *I) { release status = interrupt_disable(); while (I->value == 0) { list_push(I->wait_list, cur_thread); schedule(); release(struct lock *I) { I->value = 0; status = interrupt_disable(); set_interrupt_status(status); t = list_pop(l->wait_list); if (t) list_push(ready_list, t); What is the scenario in which the thread that was added to the ready list (i.e., t) may not I->value = 1; get the lock after getting schedule? set_interrupt_status(status);

```
acquire(struct lock *I) {
release
                                                                 status = interrupt_disable();
                                                                 while (I->value == 0) {
                                                                   list_push(I->wait_list, cur_thread);
                                                                   schedule();
release(struct lock *I) {
                                                                 l->value = 0;
  status = interrupt disable();
                                                                 set interrupt status(status);
  t = list_pop(l->wait_list);
  if (t)
                                                             What is the scenario in which the thread
     list_push(ready_list, t);
                                                             that was added to the ready list (i.e., t) may
  I->value = 1;
                                                             not get the lock after getting schedule?
  set_interrupt_status(status);
                                                             If another thread acquires the lock between
                                                             the release of lock and scheduling of t.
```

Let us say thread T1 was releasing the lock. In release, T1 found T2 on the waiting list, added them to the ready list, and then released the lock (returned from the release routine). Now, before T2 gets CPU, another thread T3 was scheduled and acquired the lock. After this, T3 was preempted (before releasing the lock), and T2 was scheduled. In this case, T2 will not get the lock, and it waits again by putting itself to the waiting list and calling schedule.

Locks

- Locks are an example of synchronization primitive
- Another example of synchronization primitive is a semaphore

Semaphores

- A semaphore consists of an integer (value) with two operators down and up that manipulates the value in a critical section
- down
 - wait until the value becomes positive
 - decrement the value
- up
 - increment the value

Semaphores are the same as locks, just that the value of semaphore can be more than one. Semaphores can be used to implement locks and may be used in other scenarios as well.

down(struct semaphore *s) { status = interrupt_disable(); while (s->value <= 0) { list_push(s->wait_list, cur_thread); schedule(); } s->value--; set_interrupt_status(status); } struct semaphore { int value; struct list *wait_list; }; Same as acquire, except the value can be more than 1.

```
up(struct semaphore *s) {
    status = interrupt_disable();
    t = list_pop(s->wait_list);
    if (t)
        list_push(ready_list, t);
    s->value++;
    set_interrupt_status(status);
}

struct semaphore {
    int value;
    struct list *wait_list;
};

Same as release, except the
    value can be more than 1.
```

Locking using semaphore

```
lock_init(semaphore *s) {
   s->value = 1;
}
lock_acquire(semaphore *s) {
   down(s);
}
lock_release(semaphore *s) {
   up(s);
}
```

We can implement locks by initializing the semaphore to 1.

Semaphores

• Parent wait for child to get scheduled

Semaphores can also be used to implement wait and signal. If a thread initializes the semaphore with zero and calls down, then it will wait until somebody signals by calling up. In this example, a parent thread creates a child thread and passes a semaphore to the child. The semaphore is initialized with zero. The parent is waiting for the child to send a signal when it gets a chance to run.

```
/* GLOBALS */
                                                  int counter = 0;
Condition variables
                                                  char buffer[BUFFER SIZE];
                                                  int in = 0, out = 0;
                                       char get() {
void put(char ch) {
                                          while (counter == 0);
  while (counter == BUFFER_SIZE);
                                          char ch = buffer[out];
   buffer[in] = ch;
                                          out = (out + 1) % BUFFER_SIZE;
   in = (in + 1) % BUFFER_SIZE;
                                          counter--;
   counter++;
                                          return ch;
}
                                       }
```

This is the same example that we have discussed before. buffer is a circular queue. If the queue is not full, the put routine inserts a character to the buffer. If the buffer is not empty, the get routine removes a character from the queue. Multiple threads can be in the get and put routines at the same time.

```
/* GLOBALS */
                                                    int counter = 0;
Condition variables
                                                    char buffer[BUFFER SIZE];
                                                    int in = 0, out = 0;
                                                    struct condition not full, not empty;
                                         char get() {
void put(char ch) {
                                           while (counter == 0);
  while (counter == BUFFER SIZE);
                                            char ch = buffer[out];
  buffer[in] = ch;
                                            out = (out + 1) % BUFFER SIZE;
  in = (in + 1) % BUFFER SIZE;
                                            counter--;
   counter++;
                                            return ch;
}
                                         }
```

One of the problems with this code is waiting for the buffer to become not empty or not full in a busy loop. Notice that rather than waiting in the while loop in the put routine, it is better to call yield because the buffer can only become not full if the get routine gets a chance to run. The put routine should not be scheduled until a thread executing get routine decrements the counter. In this case, the condition variables can be used instead of waiting for a condition to be true in a busy loop.

Condition variables

- cond_wait(struct condition *cond)
 - sleep if the condition is not true
- cond_signal(struct condition *cond)
 - wakeup a thread that is sleeping on this condition

cond_wait and cond_signal take a condition variable as input. cond_wait is called when a condition is not true. It puts the current thread to sleep. cond_signal wakes up a thread that is sleeping on the input condition variable. After a thread (waiting on condition variable) wakes up, it rechecks the condition. If the condition is not true, it goes to sleep mode again.

```
/* GLOBALS */
                                                       int counter = 0;
Condition variables
                                                       char buffer[BUFFER_SIZE];
                                                       int in = 0, out = 0;
                                                       struct condition not_full, not_empty;
void put(char ch) {
                                           char get() {
  while (counter == BUFFER_SIZE)
                                              while (counter == 0)
     cond_wait(&not_full);
                                                cond_wait(&not_empty); -
  buffer[in] = ch;
                                              char ch = buffer[out];
  in = (in + 1) % BUFFER_SIZE;
                                              out = (out + 1) % BUFFER_SIZE;
  counter++;
                                              counter--;
  cond_signal(&not_empty);
                                              cond_signal(&not_full);
}
                                              return ch;
                                           }
```

This example can be rewritten using cond_wait and cond_signal like this.

```
/* GLOBALS */
                                                        int counter = 0;
 Condition variables
                                                        char buffer[BUFFER SIZE];
                                                        int in = 0, out = 0;
                                                        struct condition not full, not empty;
                                     char get() {
void put(char ch) {
                                    —acquire(&lock);
acquire(&lock);
                                       while (counter == 0)
  while (counter == BUFFER SIZE)
                                          cond_wait(&not_empty);
     cond wait(&not full);
                                        char ch = buffer[out];
  buffer[in] = ch;
                                        out = (out + 1) % BUFFER_SIZE;
  in = (in + 1) % BUFFER_SIZE;
                                        counter--;
  counter++;
                                        cond signal(&not full);
  cond signal(&not empty);
                                     release(&lock)
  release(&lock);
                                        return ch;
                                     }
```

There is another problem with this code. We need locks before accessing the counters, as we have discussed earlier. If we add locks at the start and end of put and get routines, there could be a deadlock. For example, a thread that is calling the put routine can go to sleep if the buffer is full while holding the lock.

```
/* GLOBALS */
                                                            int counter = 0;
 Condition variables
                                                            char buffer[BUFFER SIZE];
                                                            int in = 0, out = 0;
                                                            struct condition not full, not empty;
void put(char ch) {
                                        char get() {
  acquire(&lock);
                                          acquire(&lock);
  while (counter == BUFFER SIZE) {
                                          while (counter == 0) {
                                                                             if (counter=0)
    release(&lock);
                                             release(&lock);
                                            cond wait(&not empty);
    cond_wait(&not_full);
                                             acquire(&lock);
     acquire(&lock);
                                           char ch = buffer[out];
  buffer[in] = ch;
  in = (in + 1) % BUFFER_SIZE;
                                           out = (out + 1) % BUFFER_SIZE;
  counter++;
                                          counter --;
  cond_signal(&not_empty);
                                          cond_signal(&not_full);
  release(&lock);
                                           release(&lock)
                                           return ch;
                                        }
```

To eliminate the deadlocks, we can release the lock before sleeping and acquire it back after waking up. But this could lead to the lost wakeup problem. For instance, if a thread (say T1) got preempted just before the cond_wait in get, and some other thread (say T2) starts executing the put routine and inserts a character in the buffer. Now the cond_signal in T2 is not going to wake up any thread (because T1 hasn't called the cond_wait yet). If the scheduler schedules T1 after some time, it would put itself to the sleeping list even though the buffer is not empty. This is also called the lost wakeup problem. One of the reasons why T2 got scheduled before T1 was added to the sleeping list because T2 has released the lock before calling cond_wait. To solve this problem, cond_wait takes a lock as an argument and expects the caller to acquire the lock before the call. cond_wait releases the lock after adding the current thread to the sleeping list. cond_signal expects the caller to acquire the same lock (as in cond_wait) before the call. cond_signal moves a thread from the sleeping list to the ready list.

Condition variables

- cond_wait(struct condition *cond, struct lock *lock)
 - sleep if the condition is not true
 - the lock must be acquired before calling this routine
 - releases the lock after adding the thread to the sleeping list
 - reacquires the lock before returning
- cond_signal(struct condition *cond, struct lock *lock)
 - wakeup a thread that is sleeping on this condition
 - the lock must be acquired before calling this routine

```
/* GLOBALS */
                                                         int counter = 0;
  Condition variables
                                                         char buffer[BUFFER_SIZE];
                                                         int in = 0, out = 0;
                                                         struct condition not_full, not_empty;
                                      char get() {
void put(char ch) {
  acquire(&lock);
                                        acquire(&lock);
  while (counter == BUFFER SIZE) {
                                        while (counter == 0) {
   cond_wait(&not_full, &lock);
                                           cond_wait(&not_empty, &lock); ->
                                         }
   buffer[in] = ch;
                                         char ch = buffer[out];
   in = (in + 1) % BUFFER_SIZE;
                                         out = (out + 1) % BUFFER_SIZE;
   counter++;
                                         counter--;
cond_signal(&not_empty, &lock);
                                         cond_signal(&not_full, &lock); ->
   release(&lock);
}
                                         release(&lock)
                                         return ch;
                                      }
```

The final correct code looks like this.

Condition variables


- cond_wait
 - called while the lock is held
 - releases the lock after adding itself to wait_list
 - yields CPU
 - reacquires the lock after getting rescheduled
- cond_signal
 - called while the lock is held
 - move a thread from the wait_list to ready_list

Isolation

- A thread can access data of other threads
- We don't want an application to see data of other applications
 - Otherwise, a malicious application can steal our sensitive data
 - e.g., password from a banking application
- We need a different abstraction for isolating applications

Process


- A process is a container that contains one or more threads
- Processes can't see data of each other
- OS is shared between all the processes
 - As of now, we know that the interrupt handler is the part of OS
 - Processes can't see the data of OS



Applications

- An application is a group of processes
 - E.g., each tab in the Firefox application could be a process
- Applications can have multiple threads
 - E.g., each tab in the Firefox application could be a thread
- Developers can choose between multiple threads, multiple processes, and a combination of both
 - multiple threads enable faster communication
 - multiple processes enable stronger isolation

If we have to choose between multiple processes vs. multiple threads for developing an application, no choice is better than another in all aspects. Threads may be better for performance (because of faster communication using shared memory), but not for bug isolation. If a thread crashes, everything else (other threads) crashes. This may not be true for processes. But processes may end up using more system resources than threads.



Memory isolation

• Will discuss later

OS

- So far we have discussed that an application thread can yield a CPU
 - by calling a yield routine in OS
- Interrupt handler is automatically invoked by the hardware after a timer interrupt
- Can we allow an application to call yield but disallow other routines?
 - What can go wrong if the application can call schedule directly?

OS

- So far we have discussed that an application thread can yield a CPU
 - by calling a yield routine in OS
- Interrupt handler is automatically invoked by the hardware after a timer interrupt
- Can we allow an application to call yield but disallow other routines?
 - What can go wrong if the application can call schedule directly?
 - If it happens, the schedule function will run with interrupts enabled and could potentially make the ready list inconsistent

How can we restrict applications from calling schedule directly?

- No way, using jmp instruction application can jump to anywhere
- What if we disallow assembly code?
 - We can compile OS as a library that only exports the yield routine
 - The loader (OS) can patch the call to yield in the application binary with the real address of yield at load time

Function pointers in C

```
typedef int (*fooptr)(int, int);
int foo(int x, int y) {
  return x + y;
}
int main() {
  fooptr ptr = foo;
  return ptr(10, 11);
}
```

A function pointer is a variable that stores the address of a function. A function can be indirectly called using the address stored in a function pointer. Along with other usage, function pointers are used in the generic implementation of library routines. For example, a generic implementation of the quicksort algorithm can take a user-defined function as an argument to compare two inputs.

Function pointers in C

```
typedef int (*fooptr)(int, int);
int foo(int x, int y) {
  return x + y;
}
int main() {
  fooptr ptr = (fooptr)0x10123;
  return ptr(10, 11);
}
```

In the C language, any address can be stored in a function pointer. C applications can jump to any address by storing it to a function pointer and calling it indirectly.

How can we restrict applications from calling schedule directly?

• What if we disallow the function pointers?

Applications can modify the return address on the stack

```
foo() {
 unsigned *a = (unsigned*)&a;
 a[2] = 0 \times 100123;
}
```

The application can overwrite the return address on the stack to jump to any address. In this example, when foo returns, the CPU will jump to address 0x100123.

How about Java?

- No pointers
- No out of bounds array accesses
- Automatic memory management
- No arbitrary typecasts
- Yes, for Java applications we can enforce this restriction

How can we restrict applications from calling schedule directly?

- The goal of the OS to allow all kind of languages including assembly
- We need some sort of hardware support for this
- Let us assume for now that if an application directly jumps to OS routines, the OS kills the application