## LDM DSC Dylibs

- PrivacySettingsUI
- PreferencesUI
- WebKit
- PhotoLibraryServicesCore
- •IMSharedUtilities
- MessagesBlastDoorSupport
- SoftwareUpdateServices
- StatusKitAgentCore
- FaceTime
- TelephonyUtilities
- •Email

## FaceTime

The LDMGlobalEnabled setting is read in the ObjC function:

```
-[FaceTimePushHandler
handler:didReceiveMessage:forTopic:fromID:messageContext:]
```

I believe this is FaceTime dropping incoming FaceTime calls unless you have previously called that person or contact.

```
if ( LDMGlobalEnabled )
  if ( os_log_type_enabled_68(v13, OS_LOG_TYPE_DEFAULT) )
    _os_log_impl_61(
     &dword_20A04C000,
     (NSObject *)OSLogHandleForIDSCategory("FTMessageDelivery"),
     OS_LOG_TYPE_DEFAULT,
      "dropping push message: %@ for IMAV because lockdown mode is enabled",
      (uint8_t *)&138412290,
     0xC);
    ( (unsigned int)os_log_shim_legacy_logging_enabled() )
    if ( MarcoShouldLog(CFSTR("Service")) )
     MarcoLog(
       CFSTR("Service"),
       CFSTR("IMAV Lockdown Mode"),
       CFSTR("dropping push message: %@ for IMAV because lockdown mode is enabled"));
   if ( IMShouldLog_0(CFSTR("IDS"), 0) )
      IMLogString(
       CFSTR("IDS"),
       CFSTR("Service"),
       CFSTR("FTMessageDelivery"),
       CFSTR("dropping push message: %@ for IMAV because lockdown mode is enabled"));
```