# Chapter 2 Creating Arrays

# An *array* is MATLAB's basic data structure

- Can have any number of dimensions.
   Most common are
  - vector one dimension (a single row or column)
  - matrix two or more dimensions
- Arrays can have numbers or letters

To create a row vector from known numbers, type variable name, then equal sign, then inside square brackets, numbers separated by spaces and/or commas

Note MATLAB displays row vector horizontally

### To create a column vector from known numbers

 Method 1 - same as row vector but put semicolon after all but last number

- Method 2 same as row vector but put apostrophe (') after closing bracket
  - Apostrophe interchanges rows and columns. Will study later

```
variable_name = [ n1 n2 n3 ]'
>> yr = [1984 1986 1988 ]'
yr =
1984
1986
1988
```

# To create a vector with specified constant spacing between elements

- m is first number
- n is last number
- q is difference between consecutive numbers

$$v = m:q:n$$

### means

$$v = [m m+q m+2q m+3q ... n]$$

### If omit q, spacing is one

v = m:n

### means

$$v = [m m+1 m+2 m+3 ... n]$$

```
>> x = 1:2:13

x = 1 3 5 7 9 11 13

>> y = 1.5:0.1:2.1 Non-integer spacing

y = 1.5000 1.6000 1.7000

1.8000 1.9000 2.0000 2.1000
```

>> 
$$z = -3:7$$
  
 $z = -3 - 2 - 1 \ 0 \ 1 \ 2 \ 3 \ 4 \ 5 \ 6 \ 7$   
>>  $xa = 21:-3:6$  Negative spacing  
 $xa = 21 \ 18 \ 15 \ 12 \ 9 \ 6$ 

# To create a vector with specified number of terms between first and last

```
v = linspace(xi, xf, n)
```

- xi is first number
- xf is last number
- n is number of terms (= 100 if omitted)

```
>> va = linspace(0, 8, 6) Six elements
va = 0 \ 1.6000 \ 3.2000 \ 4.8000 \ 6.4000 \ 8.0000
>> va = linspace( 30, 10, 11 ) Decreasing elements
va=30 28 26 24 22 20 18 16 14 12 10
```



m:q:n lets you directly specify spacing. linspace() lets you directly specify number of terms

### Create a two-dimensional matrix like this

```
m = [ row 1 numbers; row 2 numbers;
...; last row numbers ]
```

- Each row separated by semicolon
- All rows have same number of columns

```
>> a=[ 5 35 43; 4 76 81; 21 32 40]
a =

5 35 43
4 76 81
21 32 40
```

```
>> cd=6; e=3; h=4;
          Commas optional
>> Mat=[e, cd*h, cos(pi/3);...
h^2 \operatorname{sqrt}(h^*h/cd) 14]
Mat
    3.0000 24.0000
                             0.5000
                           14.0000
   16.0000
                 1.6330
```

### Can also use m:p:n or linspace() to make rows

 Make sure each row has same number of columns

```
>> A=[1:2:11; 0:5:25;...
linspace(10,60,6); 67 2 43 68 4 13]
                    5
             3
                                        11
                  10
                                 20
                                        25
                         15
    10
           20
                  30
                          40
                                 50
                                        60
    67
                  43
                          68
                                        13
```

# What if number of columns different?

```
>> B= [1:4; linspace(1,4,5)]
??? Error using ==> vertcat

CAT arguments dimensions are
not consistent.
```

zeros (m, n) - makes matrix of m rows and n columns, all with zeros ones (m, n) - makes matrix of m rows and n columns, all with ones eye (n) - makes square matrix of n rows and columns. Main diagonal (upper left to lower right) has ones, all other elements are zero

### 2.2.1 The zeros, ones and, eye Commands

```
>> idn=eye(5)
idn = 1
```



# To make a matrix filled with a particular number, multiply ones (m, n) by that number

- All variables are arrays
  - Scalar array with only one element
  - Vector array with only one row or column
  - Matrix array with multiple rows and columns
- Assigning to variable specifies its dimension
  - Don't have to define variable size before assigning to it, as you do in many programming languages
- Reassigning to variable changes its dimension to that of assignment

# Transpose a variable by putting a single quote after it, e.g., x'

- In math, transpose usually denoted by superscript "T", e.g.,  $x^T$
- Converts a row vector to a column vector and vice-versa
- Switches rows and columns of a matrix, i.e., first row of original becomes first column of transposed, second row of original becomes second column of transposed, etc.

### 2.4 THE TRANSPOSE OPERATOR

#### 2.4 THE TRANSPOSE OPERATOR

Can access (read from or write to) elements in array (vector or matrix) individually or in groups

- Useful for changing subset of elements
- Useful for making new variable from subset of elements

# Address of element is its position in the vector

- "address" often called index
- Addresses always start at 1 (not o)
  - Address 1 of row vector is leftmost element
  - Address 1 of column vector is topmost element
- To access element of a vector represented by a variable, follow variables name by address inside parentheses, e.g., v(2) = 20 sets second element of vector v to 20

```
>> VCT=[35 46 78 23 5 14 81 3 55]
VCT = 35 \ 46 \ 78 \ 23 \ 5 \ 14 \ 81 \ 3 \ 5
>> VCT (4)
ans = 23
>> VCT(6) = 273
VCT = 35 \ 46 \ 78 \ 23 \ 5 \ 273 \ 81 \ 3 \ 5
>> VCT(2)+VCT(8)
ans = 49
>> VCT(5)^VCT(8)+sqrt(VCT(7))
ans = 134
```

Address of element in a matrix is given by row number and column number. Address often called *index* or *subscript* 

- Addresses always start at 1 (not o)
  - Row 1 is top row
  - Column 1 is left column
- If variable ma is a matrix, ma(k,p) is element in row k and column p



In MATLAB, left index always refers to row, right index to column

```
>> MAT=[3 11 6 5; 4 7 10 2; 13 9 0 8]
         Column 1
 MAT =
                   11
Element in
                           10
row 3 and
                    9
                                          Row 3
column 1
  >> MAT(3,1)
  ans = 13
  \rightarrow MAT (3, 1) = 20 Assign new value to element in row 3 and column 1
  MAT = 3
                 11
                           6
                                   5
Only this
                         10
element
                   9
changed
  >> MAT(2,4)-MAT(1,2)
  ans = -9
```

### The colon: lets you address a range of elements

- Vector (row or column)
  - va (:) all elements
  - va (m:n) elements m through n

### Matrix

- A(:, n) all rows of column n
- A (m,:) all columns of row m
- A(:,m:n) all rows of columns m through n
- A (m:n,:) all columns of rows m through n
- A (m:n,p:q) columns p through q of rows m through n

#### 2.6 USING A COLON: IN ADDRESSING ARRAYS

```
>> A=[1:2:11; 2:2:12; 3:3:18; 4:4:24; 5:5:30]
             3
                    5
                                         11
A =
                           8
                                 10
                                         12
                    6
      3
                    9
             6
                          12
                                 15
                                         18
                   12
                          16
                                 20
                                         24
      5
            10
                          20
                                 25
                   15
                                         30
>> B=A(:,3) All rows of column 3
B =
     5
      6
     12
     15
```

- >> C=A(2, :) All columns of row 2
- C = 2

- >> E=A (2:4,:) All columns of rows two through four
- E = 2

- >> F=A (1:3,2:4) Columns two through four of rows one through three
- F = 3

Can replace vector index or matrix indices by vectors in order to pick out specific elements. For example, for vector v and matrix m

- v([a b c:d]) returns elements a, b, and c through d
- m([a b], [c:d e]) returns columns c through d and column e of rows a and b

```
>> v=4:3:34

v = 4 7 10 13 16 19 22 25 28 31 34
```

>> 
$$u=v([3, 5, 7:10])$$
  
 $u = 10 16 22 25 28 31$ 

#### 2.6 USING A COLON: IN ADDRESSING ARRAYS

### Two ways to add elements to existing variables

- 1. Assign values to indices that don't exist
  - MATLAB expands array to include indices, puts specified values in assigned elements, fills any unassigned new elements with zeros
- 2. Add values to ends of variables
  - Adding to ends of variables is called appending or concatenating
  - "end" of vector is right side of row vector or bottom of column vector
  - "end" of matrix is right column or bottom row

## Assigning to undefined indices of vectors

```
>> DF=1:4
DF = 1 2 3 4
>> DF(5:10)=10:5:35
DF = 1 2 3 4 10 15 20 25 30 35
>> AD = [5 7 2]
AD = 5 7 2
>> AD(8) = 4
AD = 5 7 2 0 0 0 4
>> AR(5) = 24
              Unassigned elements set to zero
```

### Appending to vectors

- Can only append row vectors to row vectors and column vectors to column vectors
  - If r1 and r2 are any row vectors, r3 = [r1 r2] is a row vector whose left part is r1 and right part is r2
  - If c1 and c2 are any column vectors, c3 = [c1; c2] is a column vector whose top part is c1 and bottom part is c2

```
>> RE=[3 8 1 24];
>> GT=4:3:16;
>> KNH=[RE GT]
KNH = 3 \ 8 \ 1 \ 24 \ 4 \ 7 \ 10 \ 13 \ 16
>> KNV=[RE'; GT']
KNV = 3
       8
      24
      10
      13
      16
```

#### Assigning to undefined indices of matrices

### Appending to matrices

- If appending one matrix to right side of other matrix, both must have same number of rows
- If appending one matrix to bottom of other matrix, both must have same number of columns

#### 2.7 ADDING ELEMENTS TO EXISTING VARIABLES

# To delete elements in a vector or matrix, set range to be deleted to empty brackets

```
>> kt=[2 8 40 65 3 55 23 15 75 80]
kt = 2 8 40 65 3 55 23 15 75 80

>> kt(6)=[]

Delete sixth element (55)
kt = 2 8 40 65 3 23 15 75 80 55 gone

>> kt(3:6)=[]

Delete elements 3 through 6 of current kt, not original kt
kt = 2 8 15 75 80
```

## To delete elements in a vector or matrix, set range to be deleted to empty brackets

```
>> mtr=[5 78 4 24 9; 4 0 36 60 12; 56 13 5
89 3]
mtr = 5 78
                         24
                  36
                         60
                               12
     56
          13
                         89
>> mtr(:, 2:4) = []
mtr = 5
          12
     56
```

MATLAB has many built-in functions for working with arrays. Some common ones are:

- length (v) number of elements in a vector
- size (A) number of rows and columns in a matrix or vector
- reshape (A, m, n) changes number of rows and columns of a matrix or vector while keeping total number of elements the same. For example, changes 4x4 matrix to 2x8 matrix

- diag(v) makes a square matrix of zeroes with vector in main diagonal
- diag(A) creates vector equal to main diagonal of matrix

For more functions, click on the Help icon, then in the Help window click on MATLAB, then on "MATLAB functions", then on "By Category", then scroll down to the section labeled "Matrices and Arrays"

# A *string* is an array of characters Strings have many uses in MATLAB

- Display text output
- Specify formatting for plots
- Input arguments for some functions
- Text input from user or data files

 Create a string by typing characters within single quotes (')



- Many programming languages use the quotation mark (") for strings. Not MATLAB!
- When typing in string
  - Color of text changes to maroon when type first single quote
  - Color of text changes to purple when type last single quote

- Can have letters, digits, symbols, spaces
  - To type single quote in string, use two consecutive single quotes, e.g., make the string of English "Greg's car" by typing
     'Greg''s car'
  - Examples: 'ad ef', '3%fr2', 'edcba:21!', 'MATLAB'

### Can assign string to a variable, just like numbers

```
>> name = 'Sting'
name =
    Sting
>> police = 'New York''s
finest'
police =
    New York's finest
```

#### In a string variable

- Numbers are stored as an array
- A one-line string is a row vector
  - Number of elements in vector is number of characters in string

```
>> name = 'Howard the Duck';
>> size( name )
ans =
1 15
```

### Strings are indexed the same way as vectors and matrices

- Can read by index
- Can write by index
- Can delete by index

### Example

```
>> word = 'dale';
\gg word(1)
ans = d
>> word(1) = 'v'
word = vale
>> word(end) = []
word = val
>> word (end+1:end+3) = 'ley'
word = valley
```

MATLAB stores strings with multiple lines as an array. This means each line must have the same number of columns (characters)

```
>> names = [ 'Greg'; 'John' ]
names =
    Greg
    John
>> size( names )
ans =
    2 4
```


Must put in extra characters (usually spaces) by hand so that all rows have same number of characters

Making sure each line of text has the same number of characters is a big pain. MATLAB solves problem with char function, which pads each line on the right with enough spaces so that all lines have the same number of characters

```
char('string 1', 'string 2', 'string 3')
```

#### **EXAMPLE**

```
>> question=char('Romeo,
Romeo, ', . . .
'Wherefore art thou', 'Romeo?')
question =
    Romeo, Romeo,
    Wherefore art thou
    Romeo?
>> size ( question )
ans
    3 18
```



Three lines of text stored in a 3x18 array MATLAB makes all rows as long as longest row

 First and third rows above have enough space characters added on ends to make each row 18 characters long