1986	130	
1988	136	The tableYP array is displayed.
1990	145	
1992	158	
1994	178	
1996	211	

Another example of displaying a table is shown in Sample Problem 4-3. Tables can also be created and displayed with the fprintf command, which is explained in the next section.

# 4.3.2 The fprintf Command

The fprintf command can be used to display output (text and data) on the screen or to save it to a file. With this command (unlike with the disp command) the output can be formatted. For example, text and numerical values of variables can be intermixed and displayed in the same line. In addition, the format of the numbers can be controlled.

With many available options, the fprintf command can be long and complicated. To avoid confusion, the command is presented gradually. First, this section shows how to use the command to display text messages, then how to mix numerical data and text, next how to format the display of numbers, and finally how to save the output to a file.

# Using the fprintf command to display text:

To display text, the fprintf command has the form:

```
fprintf('text typed in as a string')
```

For example:

```
fprintf('The problem, as entered, has no solution. Please
check the input data.')
```

If this line is part of a script file, then when the line is executed, the following is displayed in the Command Window:

```
The problem, as entered, has no solution. Please check the input data.
```

With the fprintf command it is possible to start a new line in the middle of the string. This is done by inserting \n before the character that will start the new line. For example, inserting \n after the first sentence in the previous example gives:

```
fprintf('The problem, as entered, has no solution.\nPlease check the input data.')
```

When this line executes, the display in the Command Window is:

```
The problem, as entered, has no solution.
Please check the input data.
```

The \n is called an escape character. It is used to control the display. Other escape characters that can be inserted within the string are:

```
\b Backspace. \t Horizontal tab.
```

When a program has more than one fprintf command, the display generated is continuous (the fprintf command does not automatically start a new line). This is true even if there are other commands between the fprintf commands. An example is the following script file:

```
fprintf('The problem, as entered, has no solution. Please
check the input data.')
x = 6; d = 19 + 5*x;
fprintf('Try to run the program later.')
y = d + x;
fprintf('Use different input values.')
```


When this file is executed the display in the Command Window is:

The problem, as entered, has no solution. Please check the input data. Try to run the program later. Use different input values.


To start a new line with the fprintf command, \n must be typed at the start of the string.

## Using the fprintf command to display a mix of text and numerical data:

To display a mix of text and a number (value of a variable), the fprintf command has the form:



The formatting elements are:



The flag, which is optional, can be one of the following three characters:

Character used	<u>Description</u>					
for flag						
<ul><li>(minus sign)</li></ul>	Left-justifies the number within the field.					
+ (plus sign)	Prints a sign character (+ or –) in front of the number.					
0 (zero)	Adds zeros if the number is shorter than the field.					


The field width and precision (5.2 in the previous example) are optional. The first number (5 in the example) is the field width, which specifies the minimum number of digits in the display. If the number to be displayed is shorter than the field width, spaces or zeros are added in front of the number. The precision is the second number (2 in the example). It specifies the number of digits to be displayed to the right of the decimal point.

The last element in the formatting elements, which is required, is the conversion character, which specifies the notation in which the number is displayed. Some of the common notations are:

- e Exponential notation using lowercase e (e.g., 1.709098e+001).
- E Exponential notation using uppercase E (e.g., 1.709098E+001).
- f Fixed-point notation (e.g., 17.090980).
- g The shorter of e or f notations.
- G The shorter of E or f notations.
- i Integer.

Information about additional notation is available in the help menu of MAT-LAB. As an example, the fprintf command with a mix of text and a number is used in the script file that calculates the average points scored in three games.

```
% This script file calculates the average points scored in three games.
% The values are assigned to the variables by using the input command.
% The fprintf command is used to display the output.
game(1) = input('Enter the points scored in the first game ');
game(2) = input('Enter the points scored in the second game ');
game(3) = input('Enter the points scored in the third game ');
ave_points = mean(game);
```



Notice that, besides using the fprintf command, this file differs from the ones shown earlier in the chapter in that the scores are stored in the first three elements of a vector named game, and the average of the scores is calculated by using the mean function. The Command Window where the script file above (saved as Chapter4Example6) was run is shown below.

```
>> Chapter4Example6
Enter the points scored in the first game 75
Enter the points scored in the second game 60
Enter the points scored in the third game 81
An average of 72.000000 points was scored in the three games.
>>
The display generated by the fprintf command combines text and a number (value of a variable).
```

With the fprintf command it is possible to insert more than one number (value of a variable) within the text. This is done by typing %g (or % followed by any formatting elements) at the places in the text where the numbers are to be inserted. Then, after the string argument of the command (following the comma), the names of the variables are typed in the order in which they are inserted in the text. In general the command looks like:

```
fprintf('..text...%g...%g...%f...', variable1, variable2, variable3)
```

An example is shown in the following script file:

```
fprintf('A projectile shot at %3.2f degrees with a velocity
of %4.2f km/h will travel a distance of %g km.\n',theta,v,d)
```

When this script file (saved as Chapter4Example7) is executed, the display in the Command Window is:

```
>> Chapter4Example7
A projectile shot at 30.00 degrees with a velocity of
1584.00 km/h will travel a distance of 17.091 km.
>>
```

# Additional remarks about the fprintf command:

- To place a single quotation mark in the displayed text, type two single quotation marks in the string inside the command.
- To display the % character in the text, type %%.
- The fprintf command is vectorized. This means that when a variable that is a vector or a matrix is included in the command, the command repeats itself until all the elements are displayed. If the variable is a matrix, the data is used column by column.

For example, the script file below creates a  $2 \times 5$  matrix T in which the first row contains the numbers 1 through 5, and the second row shows the corresponding square roots.

```
x=1:5;
y=sqrt(x);

Create a vector x.

T=[x; y]
Create 2 × 5 matrix T, first row is x, second row is y.

fprintf('If the number is: %i, its square root is: %f\n',T)

The fprintf command displays two numbers from T in every line.
```

When this script file is executed, the display in the Command Window is:

```
T =
    1.0000
              2.0000
                         3.0000
                                   4.0000
                                              5.0000
                                                      The 2 \times 5 matrix T.
    1.0000
              1.4142
                         1.7321
                                   2,0000
                                              2.2361
                                                      The fprintf
If the number is: 1, its square root is: 1.000000
                                                      command repeats
                                                      five times, using the
If the number is: 2, its square root is: 1.414214
                                                      numbers from the
If the number is: 3, its square root is: 1.732051
                                                      matrix T column
                                                      after column.
If the number is: 4, its square root is: 2.000000
If the number is: 5, its square root is: 2.236068
```

## Using the fprintf command to save output to a file:

In addition to displaying output in the Command Window, the fprintf command can be used for writing the output to a file when it is necessary to save the output. The data that is saved can subsequently be displayed or used in MATLAB and in other applications.

Writing output to a file requires three steps:

- a) Opening a file using the fopen command.
- b) Writing the output to the open file using the fprintf command.
- c) Closing the file using the fclose command.

#### Step a:

Before data can be written to a file, the file must be opened. This is done with the fopen command, which creates a new file or opens an existing file. The fopen command has the form:

fid is a variable called the file identifier. A scalar value is assigned to fid when fopen is executed. The file name is written (including its extension) within single quotes as a string. The permission is a code (also written as a string) that tells how the file is opened. Some of the more common permission codes are:

۱r′ Open file for reading (default). Open file for writing. If the file already exists, its content is deleted. If the file does not exist, a new file is created. Same as 'w', except that if the file exists the written `a' data is appended to the end of the file. Open (do not create) file for reading and writing. 'r+' Open file for reading and writing. If the file already 'w+' exists, its content is deleted. If the file does not exist, a new file is created. Same as 'w+', except that if the file exists the writ-'a+' ten data is appended to the end of the file.

If a permission code is not included in the command, the file opens with the default code 'r'. Additional permission codes are described in the help menu.

# Step b:

Once the file is open, the fprintf command can be used to write output to the file. The fprintf command is used in exactly the same way as it is used to display output in the Command Window, except that the variable fid is inserted inside the command. The fprintf command then has the form:

```
fprintf(fid, 'text %-5.2f additional text', vari able_name)

fid is added to the fprintf command.
```

## Step *c*:

When the writing of data to the file is complete, the file is closed using the fclose command. The fclose command has the form:

fclose(fid)

## Additional notes on using the fprintf command for saving output to a file:

- The created file is saved in the current directory.
- It is possible to use the fprintf command to write to several different files. This is done by first opening the files, assigning a different fid to each (e.g. fid1, fid2, fid3, etc.), and then using the fid of a specific file in the fprintf command to write to that file.

An example of using fprintf commands for saving output to two files is shown in the following script file. The program in the file generates two unit conversion tables. One table converts velocity units from miles per hour to kilometers per hour, and the other table converts force units from pounds to newtons. Each conversion table is saved to a different text file (extension .txt).

```
% Script file in which fprintf is used to write output to files.
% Two conversion tables are created and saved to two different files.
% One converts mi/h to km/h, the other converts 1b to N.
clear all
Vmph=10:10:100;
                                   Creating a vector of velocities in mi/h.
Vkmh=Vmph.*1.609;
                                              Converting mph to km/h.
TBL1=[Vmph; Vkmh];
                                  Creating a table (matrix) with two rows.
F1b=200:200:2000;
                                        Creating a vector of forces in lb.
FN=Flb.*4.448;
                                                    Converting lb to N.
                                  Creating a table (matrix) with two rows.
TBL2=[Flb; FN];
fid1=fopen('VmphtoVkm.txt','w'); Open a .txt file named VmphtoVkm.
fid2=fopen('FlbtoFN.txt','w');
                                          Open a .txt file named FlbtoFN.
fprintf(fid1, 'Velocity Conversion Table \n \n');
                           Writing a title and an empty line to the file fid1.
fprintf(fid1,'
                        mi/h
                                          km/h
                                                    \n');
                              Writing two column headings to the file fid1.
fprintf(fid1,'
                    %8.2f
                                   %8.2f\n',TBL1);
                    Writing the data from the variable TBL1 to the file fid1.
```

```
fprintf(fid2,'Force Conversion Table\n \n');
fprintf(fid2,' Pounds Newtons \n');
fprintf(fid2,' %8.2f %8.2f\n',TBL2);
fclose(fid1);
fclose(fid2);

Writing the force conversion table (data in variable TBL2) to the file fid2.

Closing the files fid1 and fid2.
```

When the script file above is executed two new .txt files, named VmphtoVkm and FlbtoFN, are created and saved in the current directory. These files can be opened with any application that can read .txt files. Figures 4-3 and 4-4 show how the two files appear when they are opened with Microsoft Word.




Figure 4-3: The VmphtoVkm.txt file opened in Word.

Flbto	FN.txt - Mic	rosoft Word													
Elle E	dit <u>V</u> iew <u>I</u> r	nsert F <u>o</u> rmat	<u>T</u> ools	T <u>a</u> ble	<u>W</u> indow	<u>H</u> elp	Ado <u>b</u> e	PDF	Acroba	at <u>C</u> omr	nents				×
: D 3	8818	Q   45° (1)	X =		3 10 -	(21 v	9.			43	¶	100%	<b>+</b>	III <u>R</u> ea	ad ;
· 为 伊	Plain Text	t 🔻 Courie	r New	<b>v</b> 1	0 - B	I	<u>n</u>   <u>≡</u>	≣ :		P⁴	¶4	i= ::	<u>A</u>	- "; -	<b>4</b>
	1		. 2		. 3		4 .			. 5 .			. 6 .		<u>۸</u>
Ford	ce Convers	ion Table													3
	Pounds	New	tons												
	200.00	88	9.60												
	400.00	177	9.20												
	600.00	266	8.80												
	800.00	355	B.40												
	1000.00	444	B.00												
	1200.00	533	7.60												_
	1400.00	622	7.20												~
	1600.00	711	6.80												<b>±</b>
	1800.00	800	6.40												•
	2000.00	889	6.00												Ŧ
■ 🙃 🗉	<b>□</b> 🖾 🕻 📖														>
Page 1	Sec 1	1/1	At 1"	Ln 1	Col 1	RE	C TRK	EXT	OVR I	English	(U.S				

Figure 4-4: The FlbtoFN.txt file opened in Word.