

Dynace Windows Development System

User Manual
April 6, 2026

by Blake McBride

Copyright © 1996 Blake McBride All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Windows and Microsoft are registered trademarks of Microsoft Corporation. T_EX is a trademark of the American Mathematical Society. Other brand and product names are trademarks or registered trademarks of their respective holders.

This manual was typeset with the T_EX typesetting system developed by Donald Knuth.

Short Contents

1	Introduction	1
2	Concepts	9
3	Mechanics	17
4	Library Reference	21
	Method Index	311

Table of Contents

1	Introduction	1
1.1	Overview	1
1.2	Benefits	2
1.3	A Short Example	2
1.4	Features	3
1.5	Reasons to use WDS	3
1.6	Installation	4
1.7	Contents	4
1.8	Learning The System	5
1.9	Examples & Tutorial	5
1.10	Manual Organization	7
1.11	Support, Contact & Upgrades	7
1.12	Use, Copyrights & Trademarks	7
1.13	Credits	8
2	Concepts	9
2.1	Windows	9
2.1.1	Main Window	9
2.1.2	Child Window	9
2.1.3	Popup Window	9
2.2	Menus	10
2.3	Dialogs	10
2.3.1	Modal Dialogs	10
2.3.2	Modeless Dialogs	10
2.4	Controls	10
2.4.1	Text Control	10
2.4.2	Numeric Control	10
2.4.3	Date Control	11
2.4.4	Push Button	11
2.4.5	Check Box	11
2.4.6	Radio Button	11
2.4.7	List Box	11
2.4.8	Combo Box	11
2.4.9	Scroll Bar	11
2.5	Help System	11
2.6	Cursors	11
2.6.1	System Cursors	11
2.6.2	External Cursors	12
2.7	Icons	12
2.7.1	System Icons	12
2.7.2	External Icons	12
2.8	Fonts	12

2.8.1	System Fonts	12
2.8.2	External Fonts	12
2.9	Brushes	12
2.9.1	System Brushes	12
2.9.2	Stock Brushes	13
2.9.3	Solid Brushes	13
2.9.4	Hatch Brushes	13
2.10	Pens	13
2.10.1	Stock Pens	13
2.10.2	Custom Pens	13
2.11	Common Dialogs	13
2.11.1	Color Dialog	13
2.11.2	Font Dialog	13
2.11.3	File Dialog	13
2.11.4	Print Dialog	13
2.12	Printing	14
2.13	Resources	14
2.14	Dynamic Link Libraries (DLL)	14
2.15	Windows API	15
2.16	Message Passing Architecture	15
3	Mechanics	17
3.1	Build Methods	17
3.2	Build Environment Setup	17
3.2.1	Linux / macOS (Wine)	17
3.2.2	Windows (MSVC)	17
3.3	Building WDS From Scratch	17
3.3.1	Linux / macOS	17
3.3.2	Windows	18
3.4	Examples Setup	18
3.4.1	Linux / macOS	18
3.4.2	Windows	18
3.5	Example Files	18
3.6	Building The Examples	19
3.7	Debugging	19
3.8	Building Your Own Application	19
3.9	DPP	19
4	Library Reference	21
4.1	A Note To Dynace Language Users	21
4.2	Class Hierarchy	21
4.3	Application	23
4.4	Windows	42
4.4.1	Main Window	88
4.4.2	Child Windows	89

4.4.3	Popup Windows	90
4.5	Printing	90
4.6	Menus	106
4.6.1	External Menus	111
4.6.2	Internal Menus	112
4.7	Popup Menus	115
4.8	Dialogs	117
4.8.1	Standard Dialog Method Arguments	118
4.8.2	Dialog Methods	118
4.8.3	Modal Dialogs	149
4.8.4	Modeless Dialogs	151
4.9	Controls	153
4.9.1	Standard Control Method Arguments	153
4.9.2	Control Methods	154
4.9.3	Text Control	164
4.9.4	Numeric Control	170
4.9.5	Date Control	178
4.9.6	Push Buttons	182
4.9.7	Check Boxes	186
4.9.8	Radio Buttons	189
4.9.9	List Boxes	194
4.9.10	Combo Boxes	205
4.9.11	Scroll Bars	218
4.9.12	Custom Controls	223
4.10	Cursors	223
4.10.1	System Cursors	224
4.10.2	External Cursors	225
4.11	Icons	226
4.11.1	System Icons	228
4.11.2	External Icons	229
4.12	Fonts	230
4.12.1	System Fonts	234
4.12.2	External Fonts	234
4.13	Brushes	236
4.13.1	Stock Brushes	238
4.13.2	Solid Brushes	238
4.13.3	System Brushes	239
4.13.4	Hatch Brushes	240
4.14	Pens	241
4.14.1	Stock Pens	243
4.14.2	Custom Pens	243
4.15	Help System	244
4.16	Common Dialogs	247
4.16.1	File Selection Dialog	247
4.16.2	Printer Selection and Configuration Dialog	252
4.16.3	Color Selection Dialog	255

4.16.4 Font Selection Dialog	258
4.17 Dynamic Link Libraries	262
4.18 Tree Views	264
4.18.1 TreeView Methods	264
4.18.2 TreeViewItem Methods	269
4.19 Tool Bar	274
4.19.1 ToolBar Methods	274
4.20 Status Bar	278
4.20.1 StatusBar Methods	279
4.21 Image Control	280
4.21.1 ImageControl Methods	280
4.22 Time Control	282
4.22.1 TimeControl Methods	282
4.23 Shortcut Menu	285
4.23.1 ShortcutMenu Methods	285
4.24 Static Control	287
4.24.1 StaticControl Methods	287
4.24.2 StaticTextControl Methods	288
4.25 Bitmap	289
4.25.1 Bitmap Methods	290
4.26 Spin Control	291
4.26.1 SpinControl Methods	291
4.27 Task List	291
4.27.1 TaskList Methods	291
4.27.2 Task Methods	296
4.28 HTTP Request	297
4.28.1 HttpRequest Methods	298
4.28.2 WebService Methods	301
4.29 Line Control	303
4.29.1 LineControl Methods	303
4.30 Rectangle Control	304
4.30.1 RectControl Methods	304
Method Index	311

1 Introduction

The Dynace Windows Development System (WDS) is a Dynace class library which enables a C programmer with no knowledge of C++, Dynace, the Windows API or message-driven architecture to write real Windows applications with an absolute minimum learning curve and number of lines of code. In fact, it is possible to become familiar enough with windows, menus, dialogs and controls using WDS to write a Windows application after just one day!

The programmer is able to write the application using familiar C in a familiar procedural fashion. Instead of taking the usual fifty plus lines of code necessary to implement a typical “Hello World” program, with WDS it takes four lines of code! Fully functional menus and dialogs can be implemented with WDS in a handful of lines instead of the hundreds it takes using the Windows API or other available tools.

WDS applications are portable across 64-bit Windows and Linux/macOS via Wine.

Dynace (pronounced *dī-ne-sē*), what WDS is based upon, stands for a “DYNAmic C language Extension”. It is an object oriented extension to the C or C++ languages. Dynace is written in the C language and designed to be as portable as possible. It solves many problems associated with C++ and adds features previously only available in languages such as CLOS or Smalltalk without their overhead. Dynace is fully documented in another manual.

1.1 Overview

The C language is the most popular and well known among the language choices available for the PC and Unix environments. Therefore, there are many more programmers who know and feel comfortable with the C language than any other. All the popular tools available for software development under Windows use the C++ language. C++ is a complex superset of the C language with questionable benefits. There is a significant learning curve associated with going from proficient C ability to C++.

Although the currently available tools for Windows development, which work in association with C++, provide a very high degree of flexibility and power, they are tremendously complex to learn and use effectively. Given the tremendous complexity of both the Windows development tools currently available on the market and the fact that these tools are all based on C++, the time necessary for a normal C programmer to become knowledgeable and proficient in Windows development, including both C++ and the Windows tools, is an absolute minimum of six months. This time may vary to a period exceeding a year.

The currently available tools require an enormous amount of code (lines of program text) in order to achieve the most fundamental functionality. Although the current tools actually generate most of this code, the bottom line is that any real life application will end up having an enormous amount of code. There is a clear relationship between lines of code and a) how maintainable a program is for finding bugs or making enhancements, and b) how difficult it is for new programmers to get up to speed with respect to the new tools and application. Given the cost of software development and the tremendous backlog, this issue is of paramount importance.

The focus of WDS is to enable a normal C programmer to learn and be able to write and understand a fundamental Windows program in one day. Given just a little more time with WDS (in terms of days), the programmer will be able to write and understand real Windows applications in a minimum amount of time and with a very minimum amount of code. There's no need to learn a new language, such as C++. The programmer may use his existing knowledge in C and just needs to learn a very high level and simple to understand set of tools. Instead of taking hundreds of lines of code to add a new dialog, as required by the existing tools, WDS can accomplish the same task in half a dozen lines. Instead of taking up to one hundred lines of code just to bring up the main application window, WDS just requires four lines!

1.2 Benefits

There are three main benefits to using WDS over the other available options. The first is that the learning curve associated with Dynace for Windows allows a programmer or programming team to get up-to-speed with respect to Windows programming in an absolute minimum amount of time. The difference in time is days instead of six months or more. This directly translates into saved dollars and increases the success of projects.

The second main benefit is that since application features may be implemented in tens of lines of program code, instead of the hundreds or thousands of lines required by existing tools, applications may be developed in a drastically reduced time frame.

The third main benefit is that since WDS is so easy to learn and requires so few lines of code for application development, applications developed with WDS are much easier to debug, maintain and enhance. Programmer turnover is much less a problem due to the fact that new programmers can get up-to-speed in a minimum amount of time.

With WDS there is never a need for a code generator or wizard since so few lines are needed to create the application. All your code is application specific.

In short, WDS is an invaluable tool for Windows application development during the learning, development, and maintenance phases of application development. WDS is also portable to Linux and Mac via the Wine package.

1.3 A Short Example

The following complete example illustrates how easy it is to get started with WDS. Implementing this exact functionality using the Windows API would take more than fifty lines of code!

```
#include "generics.h"

int      start()
{
    object win;

    win = vNew(MainWindow, "My Test Application");

    vPrintf(win, "Hello, World!\n");

    return gProcessMessages(win);
}
```

1.4 Features

This section enumerates some of the key features of The Dynace Windows Development System (WDS).

- Drastically reduces the learning curve associated with Windows development
- Drastically reduces the lines of code necessary to build Windows apps
- Applications are portable across 64-bit Windows and Linux/macOS via Wine
- Applications are easier to debug, enhance and pass off to new programmers since it is straight C and so few lines
- Full support for main, popup and child windows, menus, modal and modeless dialogs, cursors, icons, fonts, brushes, and pens
- Support for all standard Windows controls as well as several supplied controls
- Easy to use routines for printing reports
- Support for most of the Windows common dialogs
- Compiles with a regular C or C++ compiler – not an interpreter – runs FAST!
- Full support for the Windows help system at all levels of context
- Support for external DLL access
- Full source code to WDS is included
- Applications are royalty free

1.5 Reasons to use WDS

The following lists several reasons to use the Dynace Windows Development System:

1. Drastically reduce the learning curve associated with learning to write for Windows – be able to write real Windows applications in a few days instead of the normal 6 months to a year learning curve.
2. Be able to write Windows apps fast using only a few lines of code – do “Hello World” in 4 lines, menus and dialog in a few lines – write completely functional dialogs in a handful of lines instead of the hundreds it normally takes.

3. Drastically reduce the time necessary to debug, maintain and enhance the app since it's so few lines of code.
4. Write apps which are portable across 64-bit Windows and Linux/macOS via Wine.
5. Be much less dependent on a few "expert" programmers since the code is much easier to follow and learn.
6. No need to learn a new language since WDS apps are normal C code.
7. Don't be the victim of a vendor since WDS comes with full source code.
8. Be able to take advantage of the very advanced object oriented capabilities of the Dynace Object Oriented Extension to C, which WDS is built on top of.
9. Your apps will run very fast since they are compiled into optimized machine code by your compiler.
10. Integrates well with existing compiler vendor's IDEs. No need to learn a new set of tools.
11. It's easier to port non-Windows apps to Windows with WDS since WDS encapsulates much of the message-driven architecture associated with Windows programming.
12. WDS applications are royalty free.

1.6 Installation

WDS is available from the GitHub repository at <https://github.com/blakemcbride/WDS>. Clone the repository and follow the build instructions in `docs/BUILD.txt`.

1.7 Contents

Once the system has been installed there will exist a series of directories under the WDS root directory. The system will contain the following directories:

Windows	Source code to the Windows GUI class library (the core of WDS).
ODBC	Source code to the ODBC/SQL class library.
Resources	Source code to the resource compilation library.
Registry	Source code to Windows registry access.
generics	Generic function infrastructure.
cld	Source to a GUI resource editor and dialog designer.
include	Header files required by WDS applications (<code>dynwin.h</code> , <code>generics.h</code> , etc.).
lib	Built WDS libraries.
bin	Various executables and utilities associated with the system.
WinExam	GUI examples and tutorial (exam01 through exam25).
examples	Dynace language tutorial examples (not required for WDS).
Java	Source to a Java/Dynace interface.
OLE	COM/OLE integration.

scheme Runtime source files for the MzScheme/Dynace interface.
docs Various documentation files to help orient a new user.
manual WDS manuals along with source to them.

WDS depends on Dynace, which must be built separately. The `include` and `lib` directories contain the files needed to compile and link WDS applications.

1.8 Learning The System

This manual contains a description of the WDS concepts, a detailed description of the WDS system and complete reference to all WDS classes. It is designed for a programmer who is proficient in the C language, but has little or no knowledge of Windows programming or Dynace.

In addition to this manual, the accompanying example programs will be needed in order to learn how to use the system. The example programs included with WDS provide a step-by-step tutorial to getting started.

A proficient C programmer with a pre-existing compiler environment should be able to install this package and feel comfortable enough with the system to write a simple Windows application in one day.

The best approach to learning WDS would be to start by reading chapters 1 (Introduction) and 2 (Concepts). Then refer to chapter 3 (Mechanics) while working through the WDS example programs.

If you wish to dive right in and get a feel for the system you may perform the setup procedure described in chapter 3 and then go directly to the example programs.

While working through the examples you may refer to the index (located in the back of the manual) to locate information on all WDS functions.

Although it is not necessary, you may also learn and incorporate the many powerful object oriented features of the Dynace object oriented extension to C, which is what this library is based on. Dynace is fully documented in a separate manual.

1.9 Examples & Tutorial

The WDS system includes a series of examples which serve both as a Quick Start and a Tutorial. These examples are located under the `WinExam` directory. The examples located under the `examples` directory are strictly for the Dynace object oriented extension to C and are not needed to use WDS.

Each example is contained in its entirety in an independent directory. This is done in order to illustrate the exact files and steps necessary to create a single application.

The example programs are contained in sub-directories under the `WINEXAM` directory and are named `EXAMnn` (where the `nn` is a two digit number). These numbers are significant in that they describe the correct order that the examples should be followed. Each example depends on knowledge built up in previous examples and is not repeated.

Each example contains a *readme* file which describes information relating to the purpose of the example and build instructions. These files should be read first. Each example also includes makefiles which are associated with the compiler vendor being used. Full source is included.

Each example program contains source (.c) files. There is also a mirror of each source file with a .txt file extension. These text files contain duplicates of the source file with extensive documentation in the form of comments. These files should be viewed in order to understand the code in the application.

Complete setup and build instructions are contained in Chapter 3.

The example programs are tutorial in nature and should be considered the main source of information used to get started. The manual augments the examples with introductory material, concepts and a complete reference.

The following is a list of the enclosed examples:

- 01 Illustrates the steps necessary to compile and link a bare bones Windows application.
- 02 Illustrates the use of menus and message boxes.
- 03 Illustrates the minimum steps necessary for the creation of a modal dialog.
- 04 Illustrates the addition of text controls to a dialog.
- 05 Illustrates the addition of numeric and date controls to a dialog.
- 06 Illustrates the addition of push button controls to a dialog.
- 07 Illustrates the addition of radio buttons and check boxes to a dialog.
- 08 Illustrates the addition of a combo box and list box to a dialog.
- 09 Illustrates the addition of a scroll bar to a dialog.
- 10 Illustrates a modal dialog with all control types initialized and used.
- 11 Illustrates the process of printing to the default printer.
- 12 Illustrates the process of printing to a user selected and configured printer.
- 13 Illustrates various methods of outputting text to the printer and changing pages.
- 14 Illustrates printer output utilizing different fonts.
- 15 Illustrates printer graphics output, output scaling, brushes and pens.
- 16 Illustrates the use of modeless dialogs.
- 17 Illustrates the use of a modeless dialog which isn't associated with a parent window.
- 18 Illustrates the use of the context sensitive help system.
- 19 Illustrates the creation of Dynace classes in conjunction with a WDS application.

See the file `WinExam/list` for the most up-to-date list of example programs.

1.10 Manual Organization

This manual serves as both a user manual and a complete reference manual to the WDS system. The Dynace object oriented extension to C is documented in a separate manual.

Chapter 1 (Introduction) covers background material needed to orient a new user.

Chapter 2 (Concepts) covers fundamental concepts associated with the Windows environment. It does this without introducing very much syntax or other mechanics.

Chapter 3 (Mechanics) documents the exact procedures necessary to setup and use the WDS system. The example programs should be viewed subsequent to setting the system up.

Chapter 4 (Class Reference) provides a detailed reference to all classes and methods associated with the class library included with the WDS system.

The index (located in the back) provides a complete alphabetical listing of all classes, methods, and macros described in chapter 4.

1.11 Support, Contact & Upgrades

WDS is open source software hosted at <https://github.com/blakemcbride/WDS>. Bug reports, questions, and feature requests may be submitted via the GitHub issue tracker.

Internet blake@mcbride.name

GitHub <https://github.com/blakemcbride/WDS>

1.12 Use, Copyrights & Trademarks

Copyright © 1996 Blake McBride All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE

OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

1.13 Credits

The Dynace Object Oriented Extension to C, Windows Development System and their associated documentation were written by Blake McBride (blake@mcbride.name).

2 Concepts

The Windows environment has its own lexicon and way of doing things. This chapter is designed to explain that lexicon and give the programmer a certain comfort level with respect to elements of Windows programming.

2.1 Windows

Windows are the rectangular region on your screen where a user interacts with the application. There are many things which may be done with a window. Typically, a user may move, resize or change a window into an icon. Actually, dialogs and controls (discussed further down) are actually little windows located inside bigger windows. Therefore, it is also possible for a user to interact in a variety of ways with a specific window.

There are many attributes which may be associated with a window. Each window may have a system menu associated with it, a title bar, a minimize/maximize buttons, various colors, sizes, positions, and border types.

There are three main window types: main, child and popup.

2.1.1 Main Window

There is normally exactly one main window associated with any given application. This is the first window which comes up when an application starts up, the one which acts as the fulcrum for all the facilities of the application, and the one which contains the main menu associated with the application. This is also the window which has the application icon associated with it. This is so when the application is iconized the appropriate icon will be displayed.

2.1.2 Child Window

In addition to the main window, there are child windows. A child window is a rectangular region or window which is directly associated with some other (parent) window. Child windows are always restricted to being located inside its parent window. It can't be moved outside its parent. Also, when a parent window gets iconized (minimized into an icon), its child windows follow suit. When a parent window gets moved across the screen, the child windows will follow such that their relative position in their parent remains constant. When a child window is created it is positioned relative to its parent.

2.1.3 Popup Window

In addition to child windows, the system also supports popup windows. A popup window is a rectangular region which acts, to a greater or lesser extent, independently of any other window. A popup window may exist outside of any other window and be moved or resized independent of any other window. Popup windows may or may not have a parent. If a parent window is associated with a popup and the parent gets iconized, the popup will follow suit. If no parent is associated with a popup it can be iconized independent of any other window. Since popup windows are independent of other windows, they are created with positions which are relative to the entire screen.

2.2 Menus

Menus are the words or labels which typically appear at the top of the main window associated with an application. The user is able to select various application functions by selecting the appropriate menu option. Each menu option may also present the user with additional menu options down to a number of levels.

2.3 Dialogs

Once a user selects a particular application function through the application menu, an applications principal method of providing the user with information, or obtaining information from, is through dialogs. A dialog is a rectangular region (or more precisely, a window) which contains various display information and input fields (controls).

There are two fundamental dialog types: modal and modeless.

2.3.1 Modal Dialogs

A modal dialog is one which must be completed or canceled prior to accessing any other part of a given application. If the user is presented with a modal dialog and attempts to activate another window within the same application, the system will just beep. This dialog type, however, does not restrict the user from accessing other applications.

Modal dialogs are used most often because the complexity of an application would grow tremendously if the user were allowed to be in multiple parts of the same application at the same time.

2.3.2 Modeless Dialogs

Modeless dialogs allow the user to switch from one part of a particular application to another without completing or canceling the modeless dialog. The user may switch to another part of an application, obtain additional information, and then return to any portion of the modeless dialog to complete it. The user may even iconize the dialog for another time.

Modeless dialogs are more complex and less frequently used than modal dialogs.

2.4 Controls

Controls are the primary method of obtaining information from the user. They are the input fields, push buttons, selection boxes, scroll bars, etc. Although Windows supports a group of standard controls, there is an endless number of possible types of controls. WDS supports all standard Windows controls in addition to providing several additional ones and enhancements to the standard ones.

2.4.1 Text Control

Text controls are used to obtain textual information in the form of character strings. WDS provides a variety of enhancements to the standard Windows text controls.

2.4.2 Numeric Control

Numeric controls are a WDS supplied control used to obtain numeric data from the user.

2.4.3 Date Control

Date controls are a WDS supplied control used to obtain date information from the user.

2.4.4 Push Button

Push buttons are Windows supplied, WDS enhanced, controls which allow the user to evoke an immediate action function. For example, the common “OK” and “CANCEL” buttons are push buttons. The user clicks on the button and some action gets evoked.

2.4.5 Check Box

Check boxes are Windows supplied, WDS enhanced, controls which allow the user to select among non-exclusive yes/no, on/off type options.

2.4.6 Radio Button

Radio buttons are Windows supplied, WDS enhanced, controls which allow the user to select one option among a group of mutually exclusive options.

2.4.7 List Box

List boxes allow the user to select items from a list of options. The list may be fully displayed, scrollable or drop down in nature.

2.4.8 Combo Box

Combo boxes are a combination of the text control and the list box. With combo boxes, a user may select among a list of options or type in a new item.

2.4.9 Scroll Bar

Scroll bars allow the user to visually select a position within some application specific range via the mouse.

2.5 Help System

Windows provides a powerful help system which enables the user to obtain interactive application specific help information via a “Help” menu option or within a specific context via the “F1” key. WDS supports and makes it easy to use all capabilities of the Windows help system.

2.6 Cursors

Cursors are the visual elements which indicate where a user’s input focus is or where he wishes it to be. Cursors can also be used to indicate something about the input mode or system status (for example the hour glass is used to indicate that the system is busy). Common cursors are the underscore, the arrow, the ibeam, and the hour glass.

2.6.1 System Cursors

System cursors are common cursors which are predefined by the system. These include most of the cursors most applications would need (such as the underscore, the arrow, the ibeam, and the hour glass) and are easy to select and use.

2.6.2 External Cursors

External cursors are cursors which are application specific and created by the programmer. These cursors may look like virtually anything.

2.7 Icons

Icons are those little picture boxes which are left when an application is minimized. It is normally something the user can identify the application with in order to reactive it.

2.7.1 System Icons

System icons are those generic icons which are predefined by Windows. These system defined icons are easy to select and use, but are of a bit less value since they have little to do with any specific application.

2.7.2 External Icons

External icons are application specific and programmer created icons. They must be designed by the programmer prior to use, but are very flexible, easy to design, and help the user identify the application.

2.8 Fonts

Fonts are the types (such as Helvetica or Times) and size (i.e. 10pt) of the characters which appear within an application. There are literally thousands to choose from. Fortunately, however, the system defaults are often sufficient.

2.8.1 System Fonts

The system fonts are those fonts which the user has configured his system to use on a global basis. Use of these fonts makes an application have a familiar look and feel when compared to the rest of the apps on the users machine.

2.8.2 External Fonts

External fonts are programmer selectable fonts and may be any of the many fonts available to the Windows system.

2.9 Brushes

Brushes specify the color and pattern which appears in a window background, in text and graphics.

2.9.1 System Brushes

System brushes are those colors which were selected by the user as global to their Windows environment. The programmer may select, for example, the color the user chose for background windows. The new brush will then have the same colors that the user is used to seeing in other applications on their system. System brushes are used most often.

2.9.2 Stock Brushes

Stock brushes allow the programmer to select from a number of common, Windows defined, brushes.

2.9.3 Solid Brushes

Solid brushes are arbitrary color solid brushes which may be selected by the programmer.

2.9.4 Hatch Brushes

Hatch brushes enable the programmer to select from any color and any of a number of Windows defined hatch patterns.

2.10 Pens

Pens are used, principally in graphics, for drawing lines or providing the outline of a figure. The attributes associated with a pen includes color of the line, width of the line, and its style. Common styles include solid, dashed, dotted, etc.

2.10.1 Stock Pens

Stock pens allow a programmer to select among a few, common, Windows defined pens.

2.10.2 Custom Pens

Using a custom pen allows the programmer to specify the exact attributes associated with a particular pen.

2.11 Common Dialogs

Windows provides a few common dialogs in order to obtain frequently needed information in a uniform format. Use of these dialogs when appropriate eases the programming normally associated with dialog creation and provides the user with a familiar interface.

2.11.1 Color Dialog

The color dialog provides a convenient method of requesting detailed color selection information from the user.

2.11.2 Font Dialog

The font dialog provides a convenient method of requesting detailed font selection information from the user.

2.11.3 File Dialog

The file dialog provides a convenient method of allowing the user to view and select files.

2.11.4 Print Dialog

The print dialog provides a convenient method of selecting and configuring the printer.

2.12 Printing

WDS provides many convenient and easy to use methods of selecting and configuring printers as well creating reports with a variety of fonts and graphics.

2.13 Resources

Windows programs may use application specific icons, dialogs, menus and cursors. These items are referred to as resources. Each resource has a name and may be accessed by the application program. Resources are created with a graphically oriented tool called a *resource editor*.

Once the needed resources are created, the resource editor saves them to a file called the resource file. The contents of the resource file are then compiled into a binary form using a *resource compiler*. Finally, the compiled resource file is combined with the executable file at link time.

Resource editors and compilers are included and documented along with your C compiler package. The resource editor included with Microsoft Visual Studio can be used to create and edit standard `.rc` files. Any resource editor that produces standard Windows resource files will work with WDS.

2.14 Dynamic Link Libraries (DLL)

Normally, when a program is linked, all of the library code which is accessed gets copied to the executable being created. Therefore, when the program is run, all the necessary routines are readily available in the executable file. This is called static linking.

When using DLLs, at link time the linker copies very small stub functions instead of the real routines into the executable file. These stub functions, when called by the application code, automatically access the real routines at run time which exist in external DLL files. This is called dynamic linking because it happens dynamically at run time.

The actual code which uses statically or dynamically linked routines is exactly the same. In other words, the process of writing code doesn't change. The only difference is the link commands used and the fact that dynamic linking requires that the DLLs be available at run time.

There are three advantages to using DLLs. The first is that if you have several apps which use the same library routines, you can save disk space by only requiring one copy of the routines on disk (in the DLL instead of a copy in each executable file).

The second is that since Windows knows that both apps are sharing the exact same code (because they use the same DLL), if the user activates both apps, Windows only needs to load one copy of the routines in memory and share the same code for both apps. This saves memory space.

The third advantage of using DLLs is that if you have several apps which use the same routine, and a bug is discovered in that routine, only the DLL needs to be updated. None of the apps will have to be re-linked. The next time any of the apps are run, it will load the new, and repaired, routine.

There are also a couple of drawbacks associated with the use of DLLs. First, instead of just using an executable file (as is the case with statically linked executables) you must make sure to install the appropriate DLLs. This complicates the installation process.

The second, and more troublesome, problem associated with DLLs has to do with versions. Lets say you have some app which uses some common DLL. Everything is compiled and linked and runs well. Several months go by and you start working on a new project. While developing the new app you decide to use some routine in your common DLL which is used by the first app. While using the routine located in the DLL you discover a bug or anomaly in the routine, you therefore decide to correct it. Now the second app works fine. A month later you try to use the first app again and it now has all sorts of bugs! How could this happen? It always worked before and you haven't changed it.

What happened is that the first app depended on a particular anomaly associated with the original version of the routine located in the DLL. When the anomaly was corrected, it mysteriously broke the first app. This scenario is more common and troublesome than it may appear!

2.15 Windows API

WDS targets the Windows API (64-bit) and builds as a native 64-bit application on Windows using MSVC. WDS is also portable to Linux and macOS via the Wine library, where it likewise builds and runs as a 64-bit application using GCC/winegcc.

2.16 Message Passing Architecture

Most character based applications are pretty simple in the sense that they (in one form or another) basically get a key, perform some processing, get the next key, perform some more processing, etc. In a graphical environment (such as Windows) this model doesn't work. At any point (like in the middle of entering data in a field) the user may decide to move or resize a window and the application has to be able to handle a myriad of possible input requests (messages) at any point. In order to accommodate this fact, Windows programming uses a different programming model called *Message Driven Architecture* (MDA).

MDA is tremendously more complex and requires much more code to handle than the old get-key model. The main benefit of the Dynace Windows Development System is that WDS encapsulates and hides most of the aspects of MDA. With WDS you can code in a simple, familiar way and produce full featured Windows applications.

3 Mechanics

This chapter, in concert with the WDS examples, describes the tools and actual steps necessary to create WDS application programs. The best method of learning is to go through the example programs located under the **WinExam** directory in the order in which they appear.

3.1 Build Methods

There are two supported build methods for WDS applications:

- **Linux/macOS:** GNU Make with GCC/winegcc (via Wine).
- **Windows:** NMAKE with Microsoft Visual C++ (MSVC).

Both methods are command-line based. WDS builds as a native 64-bit application on both platforms.

3.2 Build Environment Setup

3.2.1 Linux / macOS (Wine)

The following must be in place before building:

1. Install Wine and the Wine development headers (e.g. **wine-devel** on Fedora, **libwine-dev** on Debian/Ubuntu).
2. Build Dynace (a separate package). See <https://github.com/blakemcbride/Dynace>.
3. Edit the file **makefile.inc** in the WDS root directory and set **DYNACE_PATH** to point to your Dynace installation directory. Verify **WINEINCPATH** is correct (default is **/usr/include/wine**).

3.2.2 Windows (MSVC)

The following must be in place before building:

1. Install Visual Studio with C/C++ command-line tools.
2. Build Dynace (a separate package). See <https://github.com/blakemcbride/Dynace>.
3. Edit the file **setupenv.bat** in the WDS root directory and set **DYNACE_PATH** to point to your Dynace installation directory.
4. Run **setupenv.bat** from a Visual Studio Developer Command Prompt.

3.3 Building WDS From Scratch

The procedure used to build WDS from scratch is fully described in **docs/BUILD.txt**. A brief summary follows.

3.3.1 Linux / macOS

From the WDS root directory:

```
make makegens
make
```

3.3.2 Windows

From the WDS root directory (in a Developer Command Prompt after running `setupenv.bat`):

```
nmake -f makefile.msc makegens
nmake -f makefile.msc all-scratch
```

New users will want to read all the files in the `docs` directory.

3.4 Examples Setup

3.4.1 Linux / macOS

Each example directory contains a GNU `makefile`. Simply `cd` into the example directory and run `make`.

3.4.2 Windows

The Windows NMAKE makefiles (`makefile.msc`) are not installed in the example directories by default. To install them, run the following from the `WinExam\setup` directory:

```
windows
```

This copies the appropriate `makefile.msc` into each example directory. You can then build any example with:

```
nmake -f makefile.msc
```

The `WinExam\setup` directory also contains:

<code>clean</code>	Deletes build artifacts from all example directories.
<code>cleanxx</code>	Removes the installed <code>makefile.msc</code> files from all example directories (returns to as-shipped state).

3.5 Example Files

This section documents the files which are contained in each example program.

<code>readme</code>	This file describes the purpose of the example. It should be read first.
<code>main.c</code>	This file is the complete source code to the example program.
<code>main.txt</code>	This is a fully commented version of <code>main.c</code> . It describes all aspects of the current example which are unique.
<code>main.rc</code>	This is the resource script describing the resources used by the application. It is created and edited via a resource editor.
<code>resource.h</code>	This file is created by the resource editor. It is used by the application code to associate resources defined in <code>main.rc</code> to macro names.
<code>makefile</code>	GNU makefile for building under Linux/macOS (Wine).

makefile.msc

NMAKE makefile for building under Windows (MSVC). Installed by running `WinExam\setup\windows` (see Examples Setup above).

Once an application is built, the only file needed to run it is `main` (Linux) or `main.exe` (Windows).

3.6 Building The Examples

To build an example under Linux/macOS, `cd` into the example directory and run:

```
make
```

To build a debug version:

```
make DEBUG=1
```

To build an example under Windows, `cd` into the example directory and run:

```
nmake -f makefile.msc
```

3.7 Debugging

Due to the fact that WDS is the first thing which Windows sees when it executes an application and the fact that WDS is not normally built with debugging information, the following procedure will make it easier to debug your application code.

First compile your application with debugging information. Then when you wish to debug the application, set a break point at “start”. You can then debug your application by telling the debugger to run to the first break point. You will then see the initial function of your application and may debug as usual from that point.

Since WDS comes with full source code, you may compile it with debugging information and debug through the WDS code as well as your application specific code.

3.8 Building Your Own Application

The best method of building your own application would be to start with one of the example programs and proceed from there. This way all the compiler, linker and other options will be preset.

If you plan to create your own Dynace classes along with your WDS application, it would be best for you to start with the WDS example which illustrates the creation of a Dynace class along with the WDS application. This example has the appropriate make file logic to handle custom classes along with a WDS application.

3.9 DPP

DPP is the pre-processor used by Dynace to convert class definition files into C source files. It is also used to generate generic files and perform generic/method argument checking. This utility is only needed when creating new classes and is only used by more advanced WDS users who wish to create their own Dynace classes.

This utility is fully documented in the Dynace language manual.

4 Library Reference

This chapter gives a detailed description of each WDS class. It is organized by facility so that in order to look something up, you would first go to the section which deals with the facility you are interested in. And then the functions are in alphabetical order.

There is a naming convention used with Dynace generics. All generics start with either a lower case “g”, “v” or “m”, and are always followed by an upper case letter. The ones which start with “g” are normal generics and may be treated like normal C functions. The ones which begin with “v” use the variable argument facilities of C and you should, therefore, take a bit extra care when using them since there is no compile time argument checking being done with these functions.

Since all generics start with either “g”, “v” or “m” and in order to avoid the difficulty associated with grouping all the generics under three letters, the first letter is dropped for indexing or heading purposes. Therefore if you are looking up a generic, it will always appear in the index or header with its first letter missing. The syntax description and example code, however, will show the entire name.

There is one thing about Dynace which you must be aware of, however. Dynace generic functions (which is what most of these functions are) allow the same function to be called in many circumstances. These generic functions dynamically dispatch to the appropriate procedures based on the type of the first argument to the generic function (or “generic” for short). So even though you are calling the same function name, entirely different functionality may occur based on the type of the first argument. This fact is seldom, if ever, a problem since you know whether you are dealing with an icon or a dialog, for example, at any given point. Just be sure to look up the generic in the appropriate section.

4.1 A Note To Dynace Language Users

In an effort to hide unnecessary details associated with class vs. instance methods from WDS users who don’t care about the differences, these differences are not discussed or grouped as they are in the Dynace manual. You can always distinguish between the two by what the method takes as its first argument. If it’s a class, then you have a class method, otherwise it’s an instance method.

If you are a WDS user with interest in the Dynace object oriented extension to C, it is fully documented in its associated manual.

4.2 Class Hierarchy

This Dynace Windows Development System contains the following class hierarchy:

Dynace Windows Development System Class Hierarchy

(Object)

Application

(Stream)

Window

MainWindow

PopupWindow

DisplayWindow

StatusWindow

SplashWindow

ChildWindow

ToolBar

StatusBar

ButtonWindow

Control

SpinControl

TextControl

NumericControl

DateControl

PushButton

CheckBox

RadioButton

ListBox

DirListBox

ComboBox

ScrollBar

StaticControl

CustomControl

Printer

Menu

ExternalMenu

InternalMenu

PopupMenu

Dialog

ModalDialog

ModelessDialog

HelpSystem

Cursor

SystemCursor

ExternalCursor

TaskList

Task

DialogTask

Icon

SystemIcon

ExternalIcon

Font

SystemFont

ExternalFont

Brush

StockBrush

SolidBrush

SystemBrush

HatchBrush

Pen

StockPen

CustomPen

CommonDialog

FileDialog

PrintDialog

ColorDialog

FontDialog

DynamicLibrary

Database (ODBC)

Statement

StatementInfo

TableInfo

ColumnInfo

TableListbox

VirtualListbox

ComClient (COM/DCOM/OLE)

ComInstance

ComInterface

ComServer

OLEDispatch

4.3 Application

The **Application** class is the class used to control application wide defaults such as fonts, cursors, brushes and so on. It is also the class which gets executed by Windows first and executes your application specific **start** function.

There are no instance methods associated with the **Application** class. All access to this class is through class methods via the global class object **Application**.

AddGlobal::Application

[AddGlobal]

```
r = gAddGlobal(Application, key, val);

char    *key;    /* dictionary key    */
object  val;     /* value to store    */
object  r;       /* val on success, NULL if key exists */
```

This class method adds an object to the application-wide global dictionary under **key**. If **key** already exists, the call fails and returns **NULL**; the existing entry is not modified.

Example:

```
gAddGlobal(Application, "config", configObj);
```

See also: **GetGlobal**, **ChangeGlobal**, **RemoveGlobal**, **DisposeGlobal**

ChangeGlobal::Application

[ChangeGlobal]

```
r = gChangeGlobal(Application, key, val);

char    *key;    /* dictionary key    */
object  val;     /* new value to store */
object  r;       /* result            */
```

This class method replaces the value associated with an existing **key** in the application-wide global dictionary. The previous value is not disposed.

Example:

```
gChangeGlobal(Application, "config", newConfigObj);
```

See also: **AddGlobal**, **GetGlobal**, **RemoveGlobal**, **DisposeGlobal**

CheckMessages::Application

[CheckMessages]

```

r = gCheckMessages(Application);

object r;      /* Application */

```

This class method pumps the Windows message queue for timer, cursor, and paint messages. This is useful during long-running operations to keep the UI responsive.

Example:

```
gCheckMessages(Application);
```

CmdLine::Application

[CmdLine]

```

cl = gCmdLine(Application);

char *cl;      /* command line */

```

This method is used to gain access to command line which was used when the application was launched.

Example:

```

int cl;

cl = gCmdLine(Application);

```

See also: Instance, Show, PrevInstance

DisallowMultipleInstances::Application

[DisallowMultipleInstances]

```

r = gDisallowMultipleInstances(Application, tag, msg);

char *tag;      /* unique application identifier */
char *msg;      /* message to show, or NULL */
int r;          /* non-zero if another instance is running */

```

This class method checks whether another instance of the application is already running, using **tag** as a system-wide identifier. If another instance is found and **msg** is non-NULL, the message is displayed. Returns non-zero if a duplicate is detected.

Example:

```

if (gDisallowMultipleInstances(Application, "MyApp", "Already running."))
    return 1;

```


DisposeAtExit::Application

[DisposeAtExit]

```

r = gDisposeAtExit(Application, obj);

object  obj;    /* object to dispose at exit */
object  r;      /* Application                */

```

This class method registers `obj` to be automatically disposed when the application exits.

Example:

```
gDisposeAtExit(Application, myResource);
```

See also: `RemoveAtExit`

DisposeGlobal::Application

[DisposeGlobal]

```

r = gDisposeGlobal(Application, key);

char    *key;    /* dictionary key */
object  r;      /* Application on success, NULL if not found */

```

This class method removes an entry from the application-wide global dictionary and deep-disposes both the key and the value object.

Example:

```
gDisposeGlobal(Application, "config");
```

See also: `AddGlobal`, `GetGlobal`, `ChangeGlobal`, `RemoveGlobal`

ErrorMessage::Application

[ErrorMessage]

```

r = gErrorMessage(Application, msg);

char    *msg;    /* error message text */
object  r;      /* Application        */

```

This class method displays `msg` in a modal error message box.

Example:

```
gErrorMessage(Application, "File not found.");
```

See also: `Message`, `MessageMode`

GetArg::Application

[GetArg]

```
s = gGetArg(Application, num);

int    num;    /* argument index (0-based) */
char   *s;     /* argument string          */
```

This class method returns the command-line argument at index `num` (0-based). Returns an empty string if `num` is out of range.

Example:

```
char *prog = gGetArg(Application, 0);
```

See also: `NumArgs`

GetBackBrush::Application

[GetBackBrush]

```
bo = gGetBackBrush(Application);

object bo;    /* brush object */
```

This method is used to obtain a copy of the default background brush object associated with the application. The returned object will be an instance of one of the subclasses of the `Brush` class.

The object returned must, either explicitly or implicitly, be disposed when it is no longer needed. This is normally done automatically by WDS when it is associated with a window.

See the `Brush` class and its subclasses for further details.

Example:

```
object bo;

bo = gGetBackBrush(Application);
```

See also: `GetTextBrush`, `SetBackBrush`

GetColorTheme::Application

[GetColorTheme]

```

r = gGetColorTheme(Application, rp, gp, bp);

int    *rp;    /* pointer to receive red value    */
int    *gp;    /* pointer to receive green value */
int    *bp;    /* pointer to receive blue value  */
int     r;     /* non-zero if a theme is active  */

```

This class method retrieves the current color theme RGB values. Returns non-zero if a color theme has been set.

Example:

```

int r, g, b;
if (gGetColorTheme(Application, &r, &g, &b))
    /* theme is active */;

```

See also: **SetColorTheme**

GetCursor::Application

[GetCursor]

```

co = gGetCursor(Application);

object co;    /* cursor object */

```

This method is used to obtain a copy of the default cursor object associated with the application. The returned object will be an instance of one of the subclasses of the **Cursor** class.

The object returned must, either explicitly or implicitly, be disposed when it is no longer needed. This is normally done automatically by WDS when it is associated with a window.

See the **Cursor** class and its subclasses for further details.

Example:

```

object co;

co = gGetCursor(Application);

```

See also: **SetCursor**

GetFont::Application

[GetFont]

```
fo = gGetFont(Application);

object fo;    /* font object */
```

This method is used to obtain a copy of the default font object associated with the application. The returned object will be an instance of one of the subclasses of the **Font** class.

The object returned must, either explicitly or implicitly, be disposed when it is no longer needed. This is normally done automatically by WDS when it is associated with a window.

See the **Font** class and its subclasses for further details.

Example:

```
object fo;

fo = gGetFont(Application);
```

See also: **SetFont**

GetGlobal::Application

[GetGlobal]

```
r = gGetGlobal(Application, key);

char    *key;    /* dictionary key */
object  r;       /* stored object, or NULL */
```

This class method retrieves an object previously stored in the application-wide global dictionary under **key**. Returns **NULL** if **key** is not found.

Example:

```
object cfg = gGetGlobal(Application, "config");
```

See also: **AddGlobal**, **ChangeGlobal**, **RemoveGlobal**, **DisposeGlobal**

GetIcon::Application

[GetIcon]

```
io = gGetIcon(Application);

object io;    /* icon object */
```

This method is used to obtain a copy of the default icon object associated with the application. The returned object will be an instance of one of the subclasses of the `Icon` class.

The object returned must, either explicitly or implicitly, be disposed when it is no longer needed. This is normally done automatically by WDS when it is associated with a window.

See the `Icon` class and its subclasses for further details.

Example:

```
object io;

io = gGetIcon(Application);
```

See also: `SetIcon`

`GetName::Application`

[`GetName`]

```
nm = gGetName(Application);

char *nm; /* application name */
```

This method is used to obtain the global name associated with the application.

Example:

```
char *nm;

nm = gGetName(Application);
```

See also: `SetName`

`GetScalingMode::Application`

[`GetScalingMode`]

```
m = gGetScalingMode(Application);

int m; /* scaling mode */
```

This method is used to get the current scaling mode in effect. See `SetScalingMode` for further details.

Example:

```
int mode;

mode = gGetScalingMode(Application);
```

See also: `SetScalingMode`, `ScaleToPixels`, `ScaleToCurrentMode`

`GetSize::Application`

[`GetSize`]

```
r = gGetSize(Application, vert, horz);

int    *vert;    /* vertical size */
int    *horz;    /* horizontal size */
object r;        /* Application */
```

This method is used to get the total size of the user's screen. `vert` and `horz` are in increments dictated by the mode selected by `SetScalingMode`.

Example:

```
int      y, x;

gGetSize(Application, &y, &x);
```

See also: `SetScalingMode`, `GetSize::Window`

`GetTextBrush::Application`

[`GetTextBrush`]

```
bo = gGetTextBrush(Application);

object bo;    /* brush object */
```

This method is used to obtain a copy of the default text brush object associated with the application. The returned object will be an instance of one of the subclasses of the `Brush` class.

The object returned must, either explicitly or implicitly, be disposed when it is no longer needed. This is normally done automatically by WDS when it is associated with a window.

See the `Brush` class and its subclasses for further details.

Example:

```
object bo;

bo = gGetTextBrush(Application);
```

See also: `GetBackBrush`, `SetTextBrush`

Instance::Application

[Instance]

```

    ins = gInstance(Application);

    HINSTANCE  ins;    /* instance handle */

```

This method is used to gain access to the Windows instance handle associated with the application. This handle is mainly used internally by Windows and WDS, and should not normally be needed by a WDS programmer.

Example:

```

    HINSTANCE  h;

    h = gInstance(Application);

```

See also: `PrevInstance`, `CmdLine`, `Show`

IsExiting::Application

[IsExiting]

```

    r = gIsExiting(Application);

    int      r;    /* 1 if exiting, 0 otherwise */

```

This class method returns 1 if the application is in the process of exiting, 0 otherwise.

Example:

```

    if (gIsExiting(Application))
        return;

```

Language::Application

[Language]

```

    lang = gLanguage(Application);

    int      lang;    /* current language index */

```

This class method returns the current language index previously set by `SetLanguage`. The default is 0 (English).

Example:

```

    int lang = gLanguage(Application);

```

See also: `SetLanguage`

Message::Application

[Message]

```

r = gMessage(Application, msg);

char    *msg;    /* message text */
object  r;       /* Application */

```

This class method displays `msg` in a message box, provided message mode is enabled. If message mode is disabled, no dialog appears.

Example:

```
gMessage(Application, "Operation complete.");
```

See also: `ErrorMessage`, `MessageMode`

MessageMode::Application

[MessageMode]

```

prev = gMessageMode(Application, mode);

int    mode;    /* >= 0 to set, < 0 to query */
int    prev;    /* previous mode value */

```

This class method gets or sets whether `gMessage` shows a message box. Pass a non-negative value to set the mode, or a negative value to query without changing it. Returns the previous mode.

Example:

```
int old = gMessageMode(Application, 0); /* disable messages */
```

See also: `Message`, `ErrorMessage`

NumArgs::Application

[NumArgs]

```

n = gNumArgs(Application);

int    n;       /* number of command-line arguments */

```

This class method returns the number of command-line arguments passed to the application.

Example:

```
int n = gNumArgs(Application);
```


See also: `GetArg`

`OpenURL::Application`

[`OpenURL`]

```
r = gOpenURL(Application, url);

char    *url;    /* URL or file path */
object  r;       /* Application      */
```

This class method opens a URL or file using the system default handler via `ShellExecute`. Control returns immediately.

Example:

```
gOpenURL(Application, "https://example.com");
```

See also: `OpenURLWait`

`OpenURLWait::Application`

[`OpenURLWait`]

```
r = gOpenURLWait(Application, url);

char    *url;    /* URL or file path */
object  r;       /* Application      */
```

This class method opens a URL or file using the system default handler and blocks until the spawned process finishes.

Example:

```
gOpenURLWait(Application, "report.pdf");
```

See also: `OpenURL`

`PrevInstance::Application`

[`PrevInstance`]

```
ins = gPrevInstance(Application);

HINSTANCE ins;    /* instance handle */
```

This method is used to gain access to the Windows instance handle associated with the previous instance of this application, should more than one be running. This handle is mainly used internally by Windows and WDS, and should not normally be needed by a WDS programmer.

This value will always be `NULL` under Windows NT.

Example:

```
HINSTANCE  h;

h = gPrevInstance(Application);
```

See also: `Instance`, `CmdLine`, `Show`

`QuitApplication::Application`

[QuitApplication]

```
r = gQuitApplication(Application, ret);

int      ret;      /* app return value */
object   r;        /* Application      */
```

This method is used to terminate an application. The value passed will be used as the return value of the application.

Example:

```
gQuitApplication(Application, 0);
```

See also: `Error`

`RemoveAtExit::Application`

[RemoveAtExit]

```
r = gRemoveAtExit(Application, obj);

object  obj;      /* object to remove from exit set */
object  r;        /* Application                  */
```

This class method removes `obj` from the set of objects that will be disposed at application exit. The object itself is not disposed.

Example:

```
gRemoveAtExit(Application, myResource);
```

See also: `DisposeAtExit`

RemoveGlobal::Application

[RemoveGlobal]

```

r = gRemoveGlobal(Application, key);

char    *key;    /* dictionary key */
object  r;       /* Application on success, NULL if not found */

```

This class method removes an entry from the application-wide global dictionary without disposing the value object. Use this when you want to retain the value after removal.

Example:

```
gRemoveGlobal(Application, "config");
```

See also: AddGlobal, GetGlobal, ChangeGlobal, DisposeGlobal

ReturnAsTab::Application

[ReturnAsTab]

```

prev = gReturnAsTab(Application, mode);

int    mode;    /* >= 0 to set, < 0 to query */
int    prev;    /* previous mode value */

```

This class method gets or sets whether the Return key acts like the Tab key for dialog navigation. Pass a non-negative value to set the mode, or a negative value to query without changing it. Returns the previous mode.

Example:

```
gReturnAsTab(Application, 1); /* enable Return-as-Tab */
```

ScaleToCurrentMode::Application

[ScaleToCurrentMode]

```

r = gScaleToCurrentMode(Application, y, x, fnt);

int    *y;      /* row position */
int    *x;      /* column position */
object fnt;     /* current font object */
object r;       /* Application */

```

This method is used to convert coordinates from pixels to the current scaling mode. It is mainly used internally by WDS in order to convert Window's standard pixel positions into the current scaling mode.

On entry `x` and `y` point to values which are coordinates in terms of pixels. After this method returns, their value will be changed to be in terms of the current scaling mode (see `SetScalingMode`).

`fnt` is a font object which is used only if the current scaling mode is relative to a font. If so, the font it will be related to will be the one passed.

Example:

```
int      y, x;
object   fnt;

y = some position;
x = some position;
fnt = some font object;
gScaleToCurrentMode(Application, &y, &x, fnt);
```

See also: `SetScalingMode`, `GetScalingMode`, `ScaleToPixels`

`ScaleToPixels::Application`

[`ScaleToPixels`]

```
r = gScaleToPixels(Application, y, x, fnt);

int      *y;      /* row position          */
int      *x;      /* column position       */
object   fnt;     /* current font object   */
object   r;       /* Application            */
```

This method is used to convert coordinates from the current scaling mode to pixels. It is mainly used internally by WDS in order to convert your coordinates into standard pixel positions.

On entry `x` and `y` point to values which are coordinates in terms of the current scaling mode (see `SetScalingMode`). After this method returns, their value will be changed to be in terms of pixels.

`fnt` is a font object which is used only if the current scaling mode is relative to a font. If so, the font it will be related to will be the one passed.

Example:

```
int      y, x;
object   fnt;

y = some position;
x = some position;
fnt = some font object;
gScaleToPixels(Application, &y, &x, fnt);
```

See also: `SetScalingMode`, `GetScalingMode`, `ScaleToCurrentMode`

`SetBackBrush::Application`

[`SetBackBrush`]

```
r = gSetBackBrush(Application, bo);

object bo;      /* brush object      */
object r;      /* brush object passed */
```

This method is used to set the application wide default background brush. This is the brush used to color everything except the text that appears on windows and dialogs. `bo` must be an instance of one of the subclasses of `Brush`. All windows and dialogs will use the application wide default brush which is in effect when they are created unless a specific brush object is specified for a particular window.

When a new default brush object is set, any previous default object will be disposed. If no default is set, WDS uses the system brush identified as `COLOR_WINDOW`.

See the `Brush` class and its subclasses for further details.

Example:

```
gSetBackBrush(Application, vNew(SystemBrush, COLOR_WINDOW));
```

See also: `GetBackBrush`, `SetTextBrush`

`SetColorTheme::Application`

[`SetColorTheme`]

```
gSetColorTheme(Application, r, g, b);

int    r;      /* red component (0-255) */
int    g;      /* green component (0-255) */
int    b;      /* blue component (0-255) */
```

This class method sets the application background color theme using RGB values.

Example:

```
gSetColorTheme(Application, 220, 220, 255);
```

See also: `GetColorTheme`

SetCursor::Application

[SetCursor]

```

r = gSetCursor(Application, co);

object co;      /* cursor object      */
object r;       /* cursor object passed */

```

This method is used to set the application wide default cursor. `co` must be an instance of one of the subclasses of **Cursor**. All windows will use the application wide default cursor which is in effect when they are created unless a specific cursor object is specified for a particular window.

When a new default cursor object is set, any previous default object will be disposed. If no default is set, WDS uses the system cursor identified as `IDC_ARROW`.

See the **Cursor** class and its subclasses for further details.

Example:

```
gSetCursor(Application, gLoadSys(SystemCursor, IDC_ARROW));
```

See also: `GetCursor`, `LoadSys::SystemCursor`, `Load::ExternalCursor`

SetFont::Application

[SetFont]

```

r = gSetFont(Application, fo);

object fo;      /* font object      */
object r;       /* font object passed */

```

This method is used to set the application wide default font. `fo` must be an instance of one of the subclasses of **Font**. All windows will use the application wide default font which is in effect when they are created unless a specific font object is specified for a particular window.

When a new default font object is set, any previous default object will be disposed. If no default is set, WDS uses the system font identified as `SYSTEM_FONT`.

See the **Font** class and its subclasses for further details.

Example:

```
gSetFont(Application, vNew(SystemFont, SYSTEM_FONT));
```

See also: `GetFont`, `Load::SystemFont`, `New::ExternalFont`

SetIcon::Application

[SetIcon]

```

r = gSetIcon(Application, io);

object io;      /* icon object      */
object r;       /* icon object passed */

```

This method is used to set the application wide default icon. An icon associated to a window is the one which is displayed when the window is iconized. `io` must be an instance of one of the subclasses of `Icon`. All windows will use the application wide default icon which is in effect when they are created unless a specific icon object is specified for a particular window.

When a new default icon object is set, any previous default object will be disposed. If no default is set, WDS uses the system icon identified as `IDI_APPLICATION`.

See the `Icon` class and its subclasses for further details.

Example:

```
gSetIcon(Application, gLoadSys(SystemIcon, IDI_APPLICATION));
```

See also: `GetIcon`, `LoadSys::SystemIcon`, `Load::ExternalIcon`

SetLanguage::Application

[SetLanguage]

```

r = gSetLanguage(Application, lang);

int    lang;    /* language index (0 = English) */
object r;       /* Application                  */

```

This class method sets the current application language. Language index 0 is English; other indices are application-defined.

Example:

```
gSetLanguage(Application, 1); /* Spanish */
```

See also: `Language`

SetName::Application

[SetName]

```

gSetName(Application, nm);

char    *nm;    /* application name */

```

This method is used to give the application a globally accessible name. This name is accessible via `GetName`. There is no other use made of this information.

Example:

```
gSetName(Application, "My App");
```

See also: `GetName`

`SetScalingMode::Application`

[`SetScalingMode`]

```
r = gSetScalingMode(Application, m);

int      m;      /* scaling mode */
int      r;      /* previous mode */
```

This method is used to set the scaling mode used by all other WDS methods which take coordinate positions. Valid modes are as follows:

`SM_1_PER_CHAR`

This mode causes each position to be in increments determined by the size of the current font. For example row 7 would mean 7 times the height of the current font. Similar to line positions.

`SM_10_PER_SYSCHAR`

This mode causes each position to be in increments determined by one tenth the size of the system font declared globally to the user's Windows environment. For example row 70 would mean 7 times the height of the Windows global system font. This allows positioning relative to a scaling factor determined by the user.

`SM_PIXELS`

This mode performs no conversion. The application is able to use pixel coordinated directly.

The default value is `SM_1_PER_CHAR`.

The value returned is the mode which was previously set.

Example:

```
gSetScalingMode(Application, SM_PIXELS);
```

See also: `GetScalingMode`, `ScaleToPixels`, `ScaleToCurrentMode`

SetTextBrush::Application

[SetTextBrush]

```

r = gSetTextBrush(Application, bo);

object bo;      /* brush object      */
object r;       /* brush object passed */

```

This method is used to set the application wide default text brush. This is the brush used by all text output (or foreground) to windows or dialogs. **bo** must be an instance of one of the subclasses of **Brush**. All windows and dialogs will use the application wide default brush which is in effect when they are created unless a specific brush object is specified for a particular window.

When a new default brush object is set, any previous default object will be disposed. If no default is set, WDS uses the system brush identified as **COLOR_WINDOWTEXT**.

See the **Brush** class and its subclasses for further details.

Example:

```
gSetTextBrush(Application, vNew(SystemBrush, COLOR_WINDOWTEXT));
```

See also: **GetTextBrush**, **SetBackBrush**

Show::Application

[Show]

```

sv = gShow(Application);

int    sv;      /* show value */

```

This method is used to gain access to the show value supplied by Windows when an application starts. It is normally used to determine how an initial application's main window should be shown. The available options are Windows macros which begin with **SW_** and are fully documented by the Windows documentation under the **WinMain** function.

Example:

```

int    sv;

sv = gShow(Application);

```

See also: **Instance**, **CmdLine**, **PrevInstance**

4.4 Windows

This section documents the `Window` class which contains all the functionality which is common to Main, Child, and Popup windows. See chapter 2 of this manual for a description of the different window types.

`AddCompletionFunctionAfter::Window` [AddCompletionFunctionAfter]

```
r = gAddCompletionFunctionAfter(wind, fun);

object wind;      /* a window object    */
int      (*fun)(); /* completion function */
object r;         /* wind                */
```

This method adds a completion function `fun` to the end of the list of completion functions associated with window `wind`. The completion function is called when the window is closed. `fun` receives the window object as its argument and should return 0 to cancel the close or non-zero to allow it.

The window object passed is returned.

Example:

```
gAddCompletionFunctionAfter(myWind, my_cleanup);
```

See also: `CompletionFunction`, `AddCompletionFunctionBefore`

`AddCompletionFunctionBefore::Window` [AddCompletionFunctionBefore]

```
r = gAddCompletionFunctionBefore(wind, fun);

object wind;      /* a window object    */
int      (*fun)(); /* completion function */
object r;         /* wind                */
```

This method adds a completion function `fun` to the beginning of the list of completion functions associated with window `wind`. See `AddCompletionFunctionAfter` for full details.

The window object passed is returned.

See also: `CompletionFunction`, `AddCompletionFunctionAfter`

AddHandlerAfter::Window

[AddHandlerAfter]

```

r = gAddHandlerAfter(wind, msg, func);

object    wind;      /* a window object */
unsigned msg;        /* message          */
long      (*func)(); /* function pointer */
object    r;         /* the window obj  */

```

This method is used to associate function **func** with Windows window message **msg** for window **wind**. Whenever window **wind** receives message **msg**, **func** will be called.

wind is the window object who's messages you wish to process. **msg** is the particular message you wish to trap. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with **WM_**.

func is the function which gets called whenever the specified message gets received and takes the following form:

```

long      func(object    wind,
                  HWND     hwnd,
                  UINT     mMsg,
                  WPARAM   wParam,
                  LPARAM   lParam)
{
    .
    .
    .
    return 0L; /* or whatever is appropriate */
}

```

Where **wind** is the window being sent the message. The remaining arguments and return value is fully documented in the Windows documentation under the **WindowProc** function and the Windows Messages documentation.

WDS keeps a list of functions associated with each message associated with each window. When a particular message is received the appropriate list of handler functions gets executed sequentially. **AddHandlerAfter** appends the new function to the end of this list, and **AddHandlerBefore** adds the new function to the beginning of the list.

WDS may also, and optionally, execute the Windows default procedure associated with a given message either before or after the user added list of functions. This behavior may be controlled via **DefaultProcessingMode**.

Windows will only see the return value of the last message handler executed including, if applicable, the default.

Example:

```

int      hSize, vSize;

static long  process_wm_size(object wind,
                                HWND    hwnd,
                                UINT     mMsg,
                                WPARAM   wParam,
                                LPARAM   lParam)
{
    hSize = LOWORD(lParam);
    vSize = HIWORD(lParam);
    return OL;
}

.
.
gAddHandlerAfter(wind, (unsigned) WM_SIZE, process_wm_size);
.
.
```

See also: DefaultProcessingMode, AddHandlerBefore

AddHandlerBefore::Window

[AddHandlerBefore]

```

r = gAddHandlerBefore(wind, msg, func);

object  wind;      /* a window object */
unsigned msg;      /* message          */
long    (*func)(); /* function pointer */
object  r;         /* the window obj  */
```

This function is fully documented under AddHandlerAfter.

See also: AddHandlerAfter

AddInitFunctionAfter::Window

[AddInitFunctionAfter]

```

r = gAddInitFunctionAfter(wind, fun);

object  wind;      /* a window object      */
int     (*fun)();  /* initialization function */
object  r;         /* wind                  */
```

This method adds an initialization function `fun` to the end of the list of init functions associated with window `wind`. Init functions are called when the window is initialized. `fun` receives the window object as its argument.

The window object passed is returned.

See also: `InitFunction`, `AddInitFunctionBefore`

`AddInitFunctionBefore::Window`

[`AddInitFunctionBefore`]

```
r = gAddInitFunctionBefore(wind, fun);

object  wind;      /* a window object      */
int      (*fun)();  /* initialization function */
object  r;          /* wind                */
```

This method adds an initialization function `fun` to the beginning of the list of init functions associated with window `wind`. See `AddInitFunctionAfter` for full details.

The window object passed is returned.

See also: `InitFunction`, `AddInitFunctionAfter`

`AddTimer::Window`

[`AddTimer`]

```
r = gAddTimer(wind, interval, fun);

object  wind;      /* a window object      */
int      interval; /* timer interval in ms */
int      (*fun)();  /* timer callback function */
int      r;         /* timer ID              */
```

This method adds a recurring timer to window `wind`. The function `fun` will be called every `interval` milliseconds. The value returned is a timer ID which can be passed to `KillTimer` to remove the timer.

Example:

```
int  timerID;

timerID = gAddTimer(myWind, 1000, my_timer_func);
```

See also: `KillTimer`

Associate::Window

[Associate]

```

r = mAssociate(wind, itm, fun);

object wind; /* a window object */
int itm; /* menu item */
long (*fun)(); /* function */
object r; /* the menu */

```

This method is used to associate an application specific function (**fun**) with a menu item (**itm**) associated with the current menu attached to window **wind**. Once this is done, if the user selects the menu option identified by **itm**, then the function **fun** will be executed.

itm is a programmer defined macro which identifies one particular choice among those available within the menu which is currently attached to window **wind**. This macro is defined while the programmer defines the entire menu using the resource editor.

fun is the function which will be executed when the user selects menu option **itm** and has the following form:

```

long fun(object wind, unsigned id)
{
    .
    .
    .
    return 0L;
}

```

The function executed (**fun**) is passed the window object and the specific menu id which the user selected and returns a long. The return value is documented in the Windows documentation under the message named **WM_COMMAND**. It should normally be 0L.

Example:

```

static long file_message(object wind)
{
    gMessage(wind, "File_Message");
    return 0L;
}

.
.
mLoadMenu(win, IDR_MENU1);
mAssociate(win, ID_FILE_MESSAGE, file_message);

```

See also: LoadMenu, MenuItemMode

AutoDispose::Window

[AutoDispose]

```
r = gAutoDispose(wind, mode);

object  wind;      /* a window object    */
int     mode;      /* auto dispose mode */
int     r;         /* previous value     */
```

This method is used to enable or disable the auto dispose mechanism associated with a window. This feature, when enabled, causes WDS to automatically dispose of the WDS object associated with a window whenever the user closes the window (**wind**). Normally, when this feature is disabled, if the user closes a window, WDS removes the window from the display, but the WDS object remains intact until the program manually disposes of the window object (via **Dispose**). This feature is most commonly used with asynchronous, popup windows.

Note that it is invalid to attempt to use a WDS object subsequent to it being disposed, and each unneeded WDS object must be deleted.

mode is set to 1 to enable the feature and 0 to disable it. The value returned is the prior mode.

Example:

```
gAutoDispose(wind, 1);
```

See also: **Dispose**

AutoShow::Window

[AutoShow]

```
r = gAutoShow(wind, mode);

object  wind;      /* a window object    */
int     mode;      /* auto show mode     */
int     r;         /* previous value     */
```

This method is used to enable or disable the auto show mechanism associated with a window. This feature, when enabled, causes WDS to automatically display (execute **Show**) on a window which is written to. This enables the programmer to create a window which will automatically popup the first time the program displays text to it.

mode is set to 1 to enable the feature and 0 to disable it. The value returned is the prior mode.

Example:

```
gAutoShow(wind, 1);
```

See also: [Show](#)

BackBrush::Window

[BackBrush]

```
r = gBackBrush(wind, brsh);

object wind;    /* a window object */
object brsh;    /* brush object      */
object r;       /* wind                */
```

This method is used to determine what brush object is used for the background of window **wind** and performs the same function as the **Use** method when used with a **Brush** object. Any previously associated brush object will be disposed. This brush object will also be automatically disposed when the window is disposed.

The window passed is returned.

Example:

```
object myWind;

gBackBrush(myWind, vNew(SolidBrush, 0, 0, 255));
```

See also: [TextBrush](#), [Use](#), [SetTextBrush::Application](#) and the [Brush](#) classes

Center::Window

[Center]

```
r = gCenter(wind);

object wind;    /* a window object */
object r;       /* wind                */
```

This method centers window **wind** on the screen. If the window is already shown, it is centered immediately; otherwise it will be centered when shown.

The window object passed is returned.

Example:

```
object myWind;

myWind = vNew(MainWindow, "My App");
gCenter(myWind);
```


CompletionFunction::Window

[CompletionFunction]

```

r = gCompletionFunction(wind, fun);

object  wind;      /* a window object      */
int      (*fun)();  /* completion function */
object  r;          /* wind                */

```

This method sets the completion function associated with window **wind** to **fun**. The completion function is called when the window is closed. **fun** receives the window object as its argument and should return 0 to cancel the close or non-zero to allow it.

Any previously set completion function is replaced.

The window object passed is returned.

Example:

```

static int my_completion(object wind)
{
    /* perform cleanup */
    return 1; /* allow close */
}

.
.
gCompletionFunction(myWind, my_completion);

```

See also: **AddCompletionFunctionAfter**, **AddCompletionFunctionBefore**

DefaultProcessingMode::Window

[DefaultProcessingMode]

```

r = gDefaultProcessingMode(wind, msg, mode);

object  wind;      /* a window object      */
unsigned msg;      /* message              */
int      mode;     /* default processing mode */
object  r;          /* the window obj       */

```

This method is used to determine when or if the Windows default message procedure is processed for a given message (**msg**) associated with a particular window (**wind**).

WDS allows a programmer to specify an arbitrary number of functions to be executed whenever a window receives a specific message (via **AddHandlerAfter** and **AddHandlerBefore**). Windows has default procedures associated with many window messages. At times it is necessary to replace or augment this default functionality. **DefaultProcessingMode** gives the programmer control over when and if this default

Windows functionality. `mode` is used to specify the desired mode. The following table indicates the valid modes:

- | | |
|---|--|
| 0 | Do not execute the Windows default processing |
| 1 | Execute default processing <i>after</i> programmer defined handlers |
| 2 | Execute default processing <i>before</i> programmer defined handlers |

Note that the default mode is always 1, and must be explicitly changed, if desired, for each message associated with each window.

`msg` is the particular message you wish to affect. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with `WM_`.

Example:

```
gDefaultProcessingMode(wind, (unsigned) WM_SIZE, 0);
```

See also: `AddHandlerAfter`

`Disable::Window`

[Disable]

```
r = gDisable(wind);

object wind;    /* a window object */
object r;       /* wind           */
```

This method disables window `wind` for user input. A disabled window is grayed out and does not accept keyboard or mouse input.

The window object passed is returned.

Example:

```
gDisable(myWind);
```

See also: `Enable`

`DisableAll::Window`

[DisableAll]

```
r = gDisableAll(wind);

object wind;    /* a window object */
object r;       /* wind           */
```

This method disables all controls contained within window `wind`.

The window object passed is returned.

Example:

```
gDisableAll(myWind);
```

See also: `EnableAll`, `Disable`

`Dispose::Window`

[Dispose]

```
r = gDispose(wind);

object wind; /* a window object */
object r;    /* NULL */
```

This method is used to remove and dispose of a window object when it is no longer needed. This method should be called on all windows when they are no longer needed.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object myWind;

myWind = gDispose(myWind);
```

See also: `AutoDispose`, `New::ChildWindow`, `New::PopupWindow`

`DrawText::Window`

[DrawText]

```
r = gDrawText(wind, str, rect, fmt);

object wind; /* a window object */
char *str;   /* text to draw */
RECT *rect;  /* bounding rectangle */
int fmt;     /* format flags */
object r;    /* wind */
```

This method draws text `str` in window `wind` at the position and size specified by `rect`. The `fmt` argument specifies formatting flags as defined by the Windows `DrawText` API (e.g. `DT_CENTER`, `DT_WORDBREAK`).

Example:

```
RECT rc = {10, 10, 200, 50};

gDrawText(myWind, "Hello", &rc, DT_CENTER);
```

Enable::Window

[Enable]

```
r = gEnable(wind);

object wind; /* a window object */
object r;    /* wind           */
```

This method enables window **wind** for user input, reversing a prior call to **Disable**.

The window object passed is returned.

Example:

```
gEnable(myWind);
```

See also: **Disable**

EnableAll::Window

[EnableAll]

```
r = gEnableAll(wind);

object wind; /* a window object */
object r;    /* wind           */
```

This method enables all controls contained within window **wind**.

The window object passed is returned.

Example:

```
gEnableAll(myWind);
```

See also: **DisableAll**, **Enable**

Erase::Window

[Erase]

```
r = gErase(wind, brow, erow, bcol, ecol);

object wind;    /* a window object    */
int     brow;   /* beginning row      */
int     erow;   /* ending row        */
int     bcol;   /* beginning column   */
int     ecol;   /* ending column     */
object r;       /* the window object  */
```

This method is used to delete all text vectors which intersect the rectangle defined by the parameters. These parameters are adjusted according to the current scaling mode (set with `SetScalingMode::Application`). All coordinates are measured from the upper left hand corner of the window and start with 0,0.

The object returned is the window object passed.

Example:

```
gErase(win, 3, 10, 0, 200);
```

See also: `EraseLines`, `EraseAll`

EraseAll::Window

[EraseAll]

```
r = gEraseAll(wind);

object wind;    /* a window object    */
object r;       /* the window object  */
```

This method is used to erase all text lines associated with a window.

The object returned is the window object passed.

Example:

```
gEraseAll(win);
```

See also: `EraseLines`, `Erase`

EraseLines::Window

[EraseLines]

```

r = gEraseLines(wind, blin, elin);

object  wind;    /* a window object    */
int     blin;    /* beginning line    */
int     elin;    /* ending line       */
object  r;        /* the window object */

```

This method is used to delete all text lines from a starting line number (**blin**) to an ending line number (**elin**). All lines are measured from the upper left hand corner of the window and start with 0,0. Lines positions are calculated based on the current font.

The object returned is the window object passed.

Example:

```
gEraseLines(win, 3, 10);
```

See also: **Erase**, **EraseAll**

Getch::Window

[Getch]

```

ch = gGetch(wind);

object  wind;    /* a window object    */
int     ch;       /* character read      */

```

This method is used to obtain the next input character struck by the user. The **SetBlock** method may be used to determine whether or not **Getch** waits if a character is not available. The value returned is the character struck by the user or 0 if no character was available and the input was non-blocking.

Example:

```

object  myWind;
int     ch;

ch = gGetch(myWind);

```

See also: **Kbhit**, **SetBlock**, **Gets**

GetParent::Window

[GetParent]

```
prnt = gGetParent(wind);

object  wind;    /* child window object */
object  prnt;    /* parent window object */
```

This method is used to obtain the parent window object associated with window `wind`.

Example:

```
object  myWind, parentWind;

parentWind = gGetParent(myWind);
```

See also: `SetParent`, `New::ChildWindow`

GetPosition::Window

[GetPosition]

```
r = gGetPosition(wind, vert, horz);

object  wind;    /* a window object */
int      *vert;   /* vertical position */
int      *horz;   /* horizontal position */
object  r;        /* wind arg passed */
```

This method is used to get the current position of a window. `vert` and `horz` are in increments dictated by the mode selected by `SetScalingMode::Application`. The window object passed is returned.

Example:

```
int      y, x;

gGetPosition(myWind, &y, &x);
```

See also: `SetScalingMode::Application`, `GetSize`, `SetPosition`

Gets::Window**[Gets]**

```

r = gGets(wind, buf, len);

object  wind; /* a window object      */
char    *buf; /* input buffer          */
unsigned len; /* length of buffer                  */
char    *r;   /* buf                                */

```

This method is used to read (accept) a single line of text from a user until a return is hit or `len-1` key strokes have been entered and place them in `buf`.

This method returns a pointer to the buffer passed unless there is an error, in which case `NULL` is returned. The input accepted will a return terminated line entered by the user up to `len-1` characters. However, the number of characters may be less if non-blocking io is selected (via `SetBlock`) and there aren't enough characters available. `SetRaw` may also be used to control whether backspace processing will be performed.

Example:

```

object  myWind;
char    buf[80];

gGets(myWind, buf, sizeof(buf));

```

See also: `SetBlock`, `SetRaw`, `Gets`, `Getch`

GetSize::Window**[GetSize]**

```

r = gGetSize(wind, vert, horz);

object  wind; /* a window object      */
int     *vert; /* vertical size        */
int     *horz; /* horizontal size      */
object  r;     /* wind arg passed      */

```

This method is used to get the current size of a window. `vert` and `horz` are in increments dictated by the mode selected by `SetScalingMode::Application`. The window object passed is returned.

Example:

```

int     y, x;

gGetSize(myWind, &y, &x);

```


See also: `SetScalingMode::Application`, `GetPosition`, `SetSize`,
`GetSize::Application`

`GetStyle::Window`

[`GetStyle`]

```
r = gGetStyle(wind);

object  wind;    /* a window object */
DWORD   r;       /* current style   */
```

This method returns the current Win32 window style associated with window `wind`. The style values are as defined by the Windows documentation under `CreateWindow`.

Example:

```
DWORD   style;

style = gGetStyle(myWind);
```

See also: `SetStyle`

`GetTag::Window`

[`GetTag`]

```
r = gGetTag(wind);

object  wind;    /* a window object */
object  r;       /* tag           */
```

This method is used to obtain a Dynace object which has been associated with a window via `SetTag`. The value return is the object which has been associated with the window object `wind`. If there is no object associated with the window, `NULL` will be returned.

Example:

```
object  myWind, someObj;

someObj = gGetTag(myWind);
```

See also: `SetTag`, `SetTag::Dialog`

GetTask::Window**[GetTask]**

```
r = gGetTask(wind);

object  wind;    /* a window object */
object  r;       /* task object      */
```

This method returns the Task object associated with window `wind`, or NULL if no task has been set.

Example:

```
object  task;

task = gGetTask(myWind);
```

See also: `SetTask`

GetTopic::Window**[GetTopic]**

```
r = gGetTopic(wind);

object  wind;    /* a window object */
char    *r;      /* help topic      */
```

This method returns the help topic string associated with window `wind`, or NULL if no topic has been set.

Example:

```
char    *topic;

topic = gGetTopic(myWind);
```

See also: `SetTopic`

Handle::Window**[Handle]**

```
h = gHandle(wind);

object  wind;    /* window object */
HANDLE  h;       /* Windows handle */
```

This method is used to obtain the Windows internal handle associated with a window object. Note that this will be 0 prior to executing `Show` on the window because that is the point where Windows creates the handle.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```
object myWind;
HANDLE h;

h = gHandle(myWind);
```

InitFunction::Window

[InitFunction]

```
r = gInitFunction(wind, fun);

object wind;      /* a window object      */
int (*fun)();      /* initialization function */
object r;          /* wind                      */
```

This method sets the initialization function associated with window *wind* to *fun*. The init function is called when the window is initialized. *fun* receives the window object as its argument.

Any previously set init function is replaced.

The window object passed is returned.

Example:

```
static int my_init(object wind)
{
    /* perform initialization */
    return 0;
}

.
.
gInitFunction(myWind, my_init);
```

See also: `AddInitFunctionAfter`, `AddInitFunctionBefore`

IsIconic::Window

[IsIconic]

```
r = gIsIconic(wind);

object wind; /* a window object */
int r;       /* 1 if minimized */
```

This method returns 1 if window `wind` is currently minimized (iconic), or 0 otherwise.

Example:

```
if (gIsIconic(myWind))
    /* window is minimized */
```

See also: `IsMaximized`, `IsNormal`

`IsMaximized::Window`

[`IsMaximized`]

```
r = gIsMaximized(wind);

object wind; /* a window object */
int     r;    /* 1 if maximized */
```

This method returns 1 if window `wind` is currently maximized, or 0 otherwise.

Example:

```
if (gIsMaximized(myWind))
    /* window is maximized */
```

See also: `IsIconic`, `IsNormal`

`IsNormal::Window`

[`IsNormal`]

```
r = gIsNormal(wind);

object wind; /* a window object */
int     r;    /* 1 if normal state */
```

This method returns 1 if window `wind` is in the normal (restored) state — that is, neither minimized nor maximized.

Example:

```
if (gIsNormal(myWind))
    /* window is in normal state */
```

See also: `IsIconic`, `IsMaximized`

Kbhit::Window**[Kbhit]**

```
r = gKbhit(wind);

object  wind;    /* a window object */
int     r;       /* characters ready */
```

This method is used to determine if and how many characters are waiting in the character input queue. This method is used in an attempt to provide a familiar character based user input mechanism.

The value returned is the number of characters ready for input or zero if none are available.

Example:

```
object  myWind;
int     n;

n = gKbhit(myWind);
```

See also: `Getch`, `SetBlock`, `Gets`

KillTimer::Window**[KillTimer]**

```
r = gKillTimer(wind, timerID);

object  wind;    /* a window object */
int     timerID; /* timer ID */
int     r;       /* result */
```

This method removes a timer previously created with `AddTimer`. `timerID` is the value returned by `AddTimer`.

Example:

```
gKillTimer(myWind, timerID);
```

See also: `AddTimer`

LoadCursor::Window

[LoadCursor]

```

r = mLoadCursor(wind, csr);

object   wind; /* a window object */
unsigned csr; /* cursor identifier */
object   r;    /* cursor object   */

```

This method is used to load a programmer defined cursor and associate it with window **wind**. The cursor would then be displayed any time the pointer was placed in the window.

csr is a programmer defined unsigned integer which identifies the cursor. This identifier is normally a macro and defined through the resource editor. The cursor object will be automatically destroyed whenever the window is destroyed or if a new cursor is loaded.

The value returned is an object representing the cursor loaded, or NULL if the cursor was not found.

Example:

```

object myWind;

mLoadCursor(myWind, MY_CURSOR);

```

See also: LoadSystemCursor, Load::ExternalCursor, Use

LoadFont::Window

[LoadFont]

```

r = gLoadFont(wind, fname, sz);

object   wind; /* a window object */
char     *fname; /* font name      */
int      sz;    /* point size   */
object   r;     /* font object  */

```

This method is used to load an arbitrary font by name at any point size and associate it as the default font for future text output to window **wind**. **fname** is the full name of the font as it appears when you list the available fonts via the control-panel / fonts Windows utility, minus the font type in parentheses. **sz** indicates the desired point size.

All font objects associated with a window will be automatically destroyed whenever the window is destroyed.

The value returned is an object representing the font loaded, or NULL if the font was not found.

Note that **fname** may also be a Dynace object cast as a **(char *)**.

Example:

```
object myWind;

gLoadFont(myWind, "Times New Roman", 12);
```

See also: **LoadSystemFont**, **Indirect::ExternalFont**, **Use**

LoadIcon::Window

[LoadIcon]

```
r = mLoadIcon(wind, icn);

object wind; /* a window object */
unsigned icn; /* icon identifier */
object r; /* icon object */
```

This method is used to load a programmer defined icon and associate it with window **wind**. The icon would then be displayed if window **wind** was iconized.

icn is a programmer defined unsigned integer which identifies the icon. This identifier is normally a macro and defined through the resource editor. The icon object will be automatically destroyed whenever the window is destroyed or if a new icon is loaded.

The value returned is an object representing the icon loaded, or **NULL** if the icon was not found.

Example:

```
object myWind;

mLoadIcon(myWind, ALGOCORP_ICON);
```

See also: **LoadSystemIcon**, **Load::ExternalIcon**, **Use**

LoadMenu::Window

[LoadMenu]

```
r = mLoadMenu(wind, mnu);

object wind; /* a window object */
unsigned mnu; /* menu identifier */
object r; /* menu object */
```

This method is used to load a programmer defined menu and associate it with window **wind**. The menu would be displayed at the top of the window.

`mnu` is a programmer defined unsigned integer which identifies the menu. This identifier is normally a macro and defined through the resource editor. Any menu previously associated with the window is pushed on a stack so that previous menus may be easily returned to in a last-in-first-out basis using the `PopMenu` method. All menus associated with a window will be destroyed when the window is destroyed.

The value returned is an object representing the menu loaded, or `NULL` if the menu was not found.

Example:

```
object myWind;

mLoadMenu(myWind, MY_MENU);
```

See also: `Associate`, `PopMenu`, `LoadMenuStr`, `Load::ExternalMenu`, `Use`

`LoadMenuStr::Window`

[`LoadMenuStr`]

```
r = gLoadMenuStr(wind, mnu);

object wind; /* a window object */
char *mnu; /* menu identifier */
object r; /* menu object */
```

This method is used to load a programmer defined menu and associate it with window `wind`. The menu would be displayed at the top of the window.

`mnu` is a programmer defined name which identifies the menu. This name is defined through the resource editor. Any menu previously associated with the window is pushed on a stack so that previous menus may be easily returned to in a last-in-first-out basis using the `PopMenu` method. All menus associated with a window will be destroyed when the window is destroyed.

Note that the `LoadMenu` method is used more frequently since the resource editors assign macros to each menu name.

The value returned is an object representing the menu loaded, or `NULL` if the menu was not found.

Example:

```
object myWind;

gLoadMenuStr(myWind, "mymenu");
```

See also: `Associate`, `LoadMenu`, `LoadStr::ExternalMenu`, `Use`

LoadSystemCursor::Window

[LoadSystemCursor]

```

r = gLoadSystemCursor(wind, csr);

object    wind; /* a window object */
LPCSTR    csr;  /* cursor identifier */
object    r;    /* cursor object   */

```

This method is used to load a Windows predefined cursor and associate it with window **wind**. The cursor would then be displayed if the pointer was positioned over the window.

csr is a Windows defined macro which identifies the cursor. The available options are defined in the Windows documentation under the function named **LoadCursor** and normally begin with **IDC_**. The cursor object will be automatically destroyed whenever the window is destroyed or if a new cursor is loaded.

The value returned is an object representing the cursor loaded, or **NULL** if the cursor was not found.

Example:

```

object    myWind;

gLoadSystemCursor(myWind, IDC_CROSS);

```

See also: **LoadCursor**, **LoadSys::SystemCursor**, **Use**

LoadSystemFont::Window

[LoadSystemFont]

```

r = gLoadSystemFont(wind, fnt);

object    wind; /* a window object */
unsigned fnt; /* font identifier */
object    r;    /* font object   */

```

This method is used to load a Windows predefined font and associate it with window **wind**. The last font associated with a window is the one which will be used when any text is output to the window.

fnt is a Windows defined macro which identifies the font. The available options are defined in the Windows documentation under the function named **GetStockObject** and normally end with **_FONT**. The font object will be automatically destroyed whenever the window is destroyed.

The value returned is an object representing the font, or **NULL** if the font was not found.

Example:

```
object myWind;

gLoadSystemFont(myWind, SYSTEM_FONT);
```

See also: LoadFont, Load::SystemFont, Use

LoadSystemIcon::Window

[LoadSystemIcon]

```
r = gLoadSystemIcon(wind, icn);

object wind; /* a window object */
LPCSTR icn; /* icon identifier */
object r; /* icon object */
```

This method is used to load a Windows predefined icon and associate it with window **wind**. The icon would then be displayed if window **wind** was iconized.

icn is a Windows defined macro which identifies the icon. The available options are defined in the Windows documentation under the function named **LoadIcon** and normally begin with **IDI_**. The icon object will be automatically destroyed whenever the window is destroyed or if a new icon is loaded.

The value returned is an object representing the icon loaded, or **NULL** if the icon was not found.

Example:

```
object myWind;

gLoadSystemIcon(myWind, IDI_APPLICATION);
```

See also: LoadIcon, LoadSys::SystemIcon, Use

Maximize::Window

[Maximize]

```
r = gMaximize(wind);

object wind; /* a window object */
object r; /* wind */
```

This method maximizes window **wind** so that it fills the entire screen.

The window object passed is returned.

Example:

```
gMaximize(myWind);
```

Menu::Window

[Menu]

```
r = gMenu(wind);
```

```
object wind;    /* a window object */
object r;       /* menu object    */
```

This method returns the menu object associated with window `wind`, or `NULL` if no menu has been loaded.

Example:

```
object menu;
```

```
menu = gMenu(myWind);
```

See also: `LoadMenu`, `LoadMenuStr`

MenuItemMode::Window

[MenuItemMode]

```
r = mMenuItemMode(wind, itm, mod);
```

```
object wind;    /* a window object    */
unsigned itm;    /* menu item          */
unsigned mod;    /* menu item mode     */
object r;       /* the menu           */
```

This method is used to set the mode associated with a particular item in the menu which is currently attached to window `wind`.

`itm` is a programmer defined macro which identifies one particular choice among those available within the menu which is currently attached to window `wind`. This macro is defined while the programmer defines the entire menu using the resource editor.

`mod` may be one of `MF_DISABLED`, `MF_ENABLED` or `MF_GRAYED` and is documented in the Windows documentation under the function `EnableMenuItem`.

The menu object associated with the window is returned.

Example:

```
mMenuItemMode(win, ID_FILE_MESSAGE, MF_GRAYED);
```

See also: LoadMenu, Associate

Message::Window

[Message]

```
r = gMessage(wind, msg);

object wind;    /* window object */
char    *msg;   /* message      */
object  r;      /* window object */
```

This method is used to open up a temporary informational window. The window will contain the message given by `msg` and the user must acknowledge the window prior to continuing by hitting an OK button.

The value returned is the window passed.

Example:

```
object myWind;

gMessage(myWind, "Press OK to continue.");
```

See also: MessageWithTopic

MessageWithTopic::Window

[MessageWithTopic]

```
r = gMessageWithTopic(wind, msg, tpc);

object wind;    /* window object */
char    *msg;   /* message      */
char    *tpc;   /* help topic   */
object  r;      /* window object */
```

This method is used to open up a temporary informational window. The window will contain the message given by `msg` and the user must acknowledge the window prior to continuing by hitting an OK button.

If the user hits the F1 key while presented with the message, the help topic identified by `tpc` will get displayed via the Windows help system.

The value returned is the window passed.

Example:

```
object myWind;

gMessageWithTopic(myWind, "Press OK to continue.", "mytopic");
```

See also: `Message` and the `HelpSystem` class.

`MoveToTop::Window`

[`MoveToTop`]

```
r = gMoveToTop(wind);

object wind; /* a window object */
object r;    /* wind           */
```

This method brings window `wind` to the top of the Z-order, making it the foreground window.

The window object passed is returned.

Example:

```
gMoveToTop(myWind);
```

See also: `SetZOrder`

`New::Window`

[`New`]

```
r = vNew(Window);

object r; /* new window */
```

This class method is used to create a basic window object. It is used by all the subclasses of `Window` and would not normally be used by a programmer.

The value returned is the new window created.

Example:

```
object myWind;

myWind = vNew(Window);
```

See also: `New::MainWindow`, `New::ChildWindow`, `New::PopupWindow`, `Show`
`Dispose`

`NewBuiltIn::Window`

[`NewBuiltIn`]

```
r = gNewBuiltIn(Window, class, parent);

char *class; /* Windows built in class designation */
object parent; /* parent window object           */
object r;      /* new child window                 */
```

This class method is used to create a child window which is used as a Windows-built-in control. `Window` represents the `Window` class and is typed in as shown. `class` is a string representing one of the window classes build into Windows. This string is defined and documented by Windows under the function named `CreateWindow`. `parent` represents the parent window object and must be specified.

The value returned is the new child window (control) created.

Example:

```
object myWind, ctl;

myWind = vNew(MainWindow, "App Name");
ctl = gNewBuiltIn(Window, "button", myWind);
```

See also: `New::ButtonWindow`

`NextControl::Window`

[NextControl]

```
r = gNextControl(wind, ctl);

object wind; /* a window object */
object ctl; /* current control */
object r; /* next control or NULL */
```

This method returns the next focusable control in window `wind` after control `ctl`. If `ctl` is `NULL`, the first focusable control in the window is returned.

Example:

```
object next;

next = gNextControl(myWind, NULL); /* get first */
```

See also: `PreviousControl`

`Perform::Window`

[Perform]

```
r = gPerform(wind);

object wind; /* a window object */
int r; /* result */
```

This method sets up controls and shows window `wind` in a non-blocking manner. Control returns to the caller immediately. The window remains visible and active until closed by the user or programmatically.

Example:

```
gPerform(myWind);
```

See also: `PerformModal`, `Show`

`PerformModal::Window`

[`PerformModal`]

```
r = gPerformModal(wind);
```

```
object  wind;  /* a window object */
int     r;      /* result           */
```

This method shows window `wind` modally, blocking the caller until the window is closed.

Example:

```
int  result;

result = gPerformModal(myWind);
```

See also: `Perform`

`PopMenu::Window`

[`PopMenu`]

```
r = gPopMenu(wind);
```

```
object  wind;  /* a window object */
object  r;      /* menu object      */
```

This method is used to remove and destroy the current menu associated with window `wind` and restore the previous menu associated with the window. A last-in-first-out list of menus associated with a window may be established via the `LoadMenu`, `LoadMenuStr` or `Use` methods.

All function associations and modes previously associated with the new menu will be restored.

The object returned is the new menu object.

Example:

```
object  myWind;

gPopMenu(myWind);
```

See also: LoadMenu, Use

PreviousControl::Window

[PreviousControl]

```

r = gPreviousControl(wind, ctl);

object  wind;    /* a window object      */
object  ctl;     /* current control      */
object  r;       /* previous control or NULL */

```

This method returns the previous focusable control in window `wind` before control `ctl`. If `ctl` is `NULL`, the last focusable control in the window is returned.

Example:

```

object  prev;

prev = gPreviousControl(myWind, currentCtl);

```

See also: NextControl

Printf::Window

[Printf]

```

r = vPrintf(wind, fmt, ...);

object  wind;    /* a window object      */
char    *fmt;    /* format string        */
int     r;       /* length of output     */

```

This method is used to display a string of text (`str`) in a sequential fashion on window `wind`. It is analogous to the standard C library function `fprintf`. All of the standard features of your C library `fprintf` function are supported and that documentation should be consulted for full documentation on the arguments.

This method is used to support the standard streams interface, is actually defined by the `Stream` class, and is documented here for convenience.

Note that this method begins with “v” since it takes variable arguments. The length of the resulting output will be returned.

Example:

```

object  myWind;
int     age = 32;

vPrintf(myWind, "My age == %d\n", age);

```


See also: `TextOut`, `Puts`, `Write`

`PrintScreen::Window`

[`PrintScreen`]

```
r = gPrintScreen(wind, printerObj);
```

```
object  wind;          /* a window object      */
object  printerObj;    /* printer object or NULL */
object  r;             /* wind                  */
```

This method prints the contents of window `wind` to the printer specified by `printerObj`. If `printerObj` is `NULL`, the default printer is used.

The window object passed is returned.

Example:

```
gPrintScreen(myWind, NULL); /* print to default printer */
```

`Puts::Window`

[`Puts`]

```
r = gPuts(wind, str);
```

```
object  wind; /* a window object */
char    *str; /* string to be output */
int      r;   /* length of str */
```

This method is used to display a string of text (`str`) in a sequential fashion on window `wind`. This method is used to support the standard streams interface, is actually defined by the `Stream` class, and is documented here for convenience.

`str` is the text to be displayed. Text `str` will be displayed on window `wind` and its length will be returned.

Example:

```
object  myWind;

gPuts(myWind, "Hello World\n");
```

See also: `TextOut`, `Printf`, `Write`

Read::Window

[Read]

```

r = gRead(wind, buf, len);

object  wind; /* a window object */
char    *buf; /* input buffer      */
unsigned len; /* length of buffer  */
int      r;   /* bytes read         */

```

This method is used to read (accept) **len** key strokes from the user and place them in **buf**.

Since the **Window** class is a subclass of **Stream**, this method is mainly provided to support the standard interface dictated by the **Stream** class.

This method returns the number of characters actually accepted. It will not be more than **len**, but may be less if non-blocking io is selected (via **SetBlock**) and there aren't enough characters available. **SetRaw** may also be used to control whether backspace processing will be performed.

Example:

```

object myWind;
char    buf[80];

gRead(myWind, buf, sizeof(buf)-1);

```

See also: **SetBlock**, **SetRaw**, **Gets**, **Getch**

RedrawMenu::Window

[RedrawMenu]

```

r = gRedrawMenu(wind);

object wind; /* a window object */
object r;    /* wind           */

```

This method redraws the menu bar of window **wind**. This is useful after programmatically modifying menu items.

The window object passed is returned.

Example:

```

gRedrawMenu(myWind);

```

See also: **RedrawWindow**, **LoadMenu**

RedrawWindow::Window

[RedrawWindow]

```
r = gRedrawWindow(wind);

object wind; /* a window object */
object r;    /* wind           */
```

This method invalidates the entire client area of window `wind`, causing Windows to send a repaint message.

The window object passed is returned.

Example:

```
gRedrawWindow(myWind);
```

See also: `RedrawMenu`

ScrollHorz::Window

[ScrollHorz]

```
r = gScrollHorz(wind, cols);

object wind; /* a window object */
int cols;    /* columns to scroll */
object r;    /* the window object */
```

This method is used to perform a horizontal scrolling of the text in window `wind`. This has the same effect as if the user caused horizontal scrolling via the horizontal scroll bar at the bottom of the window. No text is lost, a different portion of the text is displayed.

`wind` is the window which is to be affected, and `cols` is the number of columns to scroll. If `cols` is positive the scroll moves the text to the left, and negative moves the text to the right.

The scaling factor associated with `cols` is set by `SetScalingMode::Application`.

Example:

```
object myWind;

gScrollHorz(myWind, 2);
```

See also: `ScrollVert`, `SetScalingMode::Application`

ScrollVert::Window

[ScrollVert]

```

r = gScrollVert(wind, rows);

object  wind;    /* a window object    */
int     rows;    /* rows to scroll      */
object  r;       /* the window object  */

```

This method is used to perform a vertical scrolling of the text in window **wind**. This has the same effect as if the user caused vertical scrolling via the vertical scroll bar at the right side of the window. No text is lost, a different portion of the text is displayed.

wind is the window which is to be affected, and **rows** is the number of rows to scroll. If **rows** is positive the scroll moves the text up, and negative moves the text down.

The scaling factor associated with **rows** is set by **SetScalingMode::Application**.

Example:

```

object  myWind;

gScrollVert(myWind, 2);

```

See also: **ScrollHorz**, **VertShift**, **SetScalingMode::Application**

SetBlock::Window

[SetBlock]

```

r = gSetBlock(wind, flag);

object  wind;    /* a window object    */
int     flag;    /* enable/disable flag */
int     r;       /* previous flag       */

```

This method is used to set the blocking mode associated with keyboard IO. It only has effect on **Read**, **Gets**, and **Getch**. If flag is 1, blocking is enabled, and 0 disables blocking. When a new window is created it defaults to blocking enabled.

If blocking is turned on and a keyboard entry is requested (via **Read**, **Gets** or **Getch**), the keyboard entry function will not return until the request can be satisfied. If, however, blocking is disabled, a keyboard request is made, and insufficient characters are available, then the input function will return immediately with a return value indicating the result was short.

The value returned by this method is the previous blocking mode.

Example:

```
object myWind;  
  
gSetBlock(myWind, 0);
```

See also: `Getch`, `SetRaw`, `Gets`

`SetCursor::Window`

[`SetCursor`]

```
r = gSetCursor(wind, cursor);  
  
object wind;      /* a window object      */  
object cursor;    /* cursor object or NULL */  
object r;          /* wind                */
```

This method sets a custom cursor for window `wind`. Pass `NULL` for `cursor` to restore the default cursor.

The window object passed is returned.

Example:

```
gSetCursor(myWind, myCursor);  
gSetCursor(myWind, NULL); /* restore default */
```

See also: `WaitCursor`, `LoadCursor`

`SetFocus::Window`

[`SetFocus`]

```
r = gSetFocus(wind);  
  
object wind;      /* a window object */  
object r;          /* wind            */
```

This method sets the keyboard input focus to window `wind`.

The window object passed is returned.

Example:

```
gSetFocus(myWind);
```

SetMaxLines::Window**[SetMaxLines]**

```

r = gSetMaxLines(wind, rows);

object  wind;    /* a window object    */
int     rows;    /* max rows          */
int     r;       /* previous max rows */

```

This method is used to set or obtain the maximum number of lines of text which may be associated to a window. This includes all lines associated with a window, including lines not being displayed because they are scrolled off the screen. Whenever **rows** number of lines are exceeded, WDS automatically and permanently removes the lines at the logical top of the internal buffer in order to make room for new lines.

WDS keeps a buffer which holds a programmer definable number of lines of text. The user is then able to scroll through this text. If the application attempts to display more lines than this maximum (via **vPrintf** for example) the system will automatically call **gVertShift** in order to eliminate the top line and make room for the new line being appended.

wind is the window which is to be affected, and **rows** is the maximum number of rows to retain. If **rows** is zero or negative, the value associated with the window will not be changed. This is used to obtain the current value without changing it.

The value returned is the previous value associated with the window.

Example:

```

object  myWind;

gSetMaxLines(myWind, 60);

```

See also: **VertShift**

SetParent::Window**[SetParent]**

```

r = gSetParent(wind, prnt);

object  wind;    /* child window object */
object  prnt;    /* parent window object */
object  r;       /* wind                */

```

This method is used to create a child / parent window relationship. This relationship is automatically established when a child window is created. However, this method is provided for increased flexibility.

Whenever the parent window is disposed, WDS will automatically dispose of all its children windows. This relationship should normally be established prior to the child window being `Shown`.

The value returned is the child window passed.

Example:

```
object myWind, parentWind;

gSetParent(myWind, parentWind);
```

See also: `GetParent`

`SetPosition::Window`

[`SetPosition`]

```
r = gSetPosition(wind, vert, horz);

object wind; /* a window object */
int vert; /* vertical position */
int horz; /* horizontal position */
object r; /* wind arg passed */
```

This method is used to set the initial position of a window. `vert` and `horz` are in increments dictated by the mode selected by `SetScalingMode::Application`. The window object passed is returned.

If this function is not called, Windows will automatically set it to a reasonable default.

Example:

```
object myWind;

myWind = vNew(MainWindow, "App Name");
gSetPosition(myWind, 3, 10);
```

See also: `SetScalingMode::Application`, `SetSize`, `GetPosition`

`SetRaw::Window`

[`SetRaw`]

```
r = gSetRaw(wind, flag);

object wind; /* a window object */
int flag; /* enable/disable flag */
int r; /* previous flag */
```

This method is used to set the raw mode associated with keyboard IO. It only has effect on `Read`, `Gets`, and `Getch`. If flag is 1, raw mode is enabled, and 0 disables raw mode. The default is raw mode disabled.

Normally, with raw mode disabled, when a user enters keyboard data, they are able to correct mistakes by using the backspace and reentering the correct data. The resulting data the program receives is the final, corrected input.

When raw mode is enabled, every key the user hits gets returned. This includes backspaces. Therefore, with raw mode enabled, if the user types “ABD” followed by backspace and then “C”, the program will receive all five characters hit. However, with raw mode disabled, the program would only receive the resulting string, “ABC”.

The value returned by this method is the previous raw mode.

Example:

```
object myWind;

gSetRaw(myWind, 1);
```

See also: `Getch`, `SetBlock`, `Gets`

`SetSize::Window`

[`SetSize`]

```
r = gSetSize(wind, vert, horz);

object wind; /* a window object */
int     vert; /* vertical size    */
int     horz; /* horizontal size  */
object r;    /* wind arg passed */
```

This method is used to set the initial size of a window. `vert` and `horz` are in increments dictated by the mode selected by `SetScalingMode::Application`. The window object passed is returned.

If this function is not called, Windows will automatically set it to a reasonable default.

Example:

```
object myWind;

myWind = vNew(MainWindow, "App Name");
gSetSize(myWind, 10, 40);
```

See also: `SetScalingMode::Application`, `SetPosition`, `GetSize`

SetStyle::Window

[SetStyle]

```

r = gSetStyle(wind, sty);

object  wind;    /* a window object          */
DWORD   sty;     /* the window style to use                    */
object  r;       /* returns wind                               */

```

This method is used to set the window style associated with window **wind** to style **sty**. The **DWORD** data type and valid styles are defined by Windows and fully documented by the Windows documentation. See the Windows documentation for the function called **CreateWindow**. The style types normally begin with **WS_** and would be or'd together to form the selected style. Note that WDS automatically assigns reasonable defaults to a window style when it is created.

Example:

```

object  myWind;

myWind = vNew(MainWindow, "App Name");
gSetStyle(myWind, WS_OVERLAPPEDWINDOW | WS_VSCROLL | WS_HSCROLL);

```

SetTag::Window

[SetTag]

```

r = gSetTag(wind, tag);

object  wind;    /* a window object          */
object  tag;     /* tag                      */
object  r;       /* previous tag             */

```

This method is used to associate an arbitrary Dynace object with a window object. This may later be retrieved via the **GetTag** method. Since WDS passes around the window object to all **Window** methods this mechanism may be used to pass additional information with the window. And since Dynace treats all objects in a uniform manner, this information attached to the window may be arbitrarily complex.

WDS does not dispose of the tag when the window object is disposed. This method returns any previous object associated with the window or **NULL**.

Example:

```

object  myWind;

gSetTag(myWind, gNewWithInt(ShortInteger, 17));

```

See also: **GetTag**, **SetTag::Dialog**

SetTask::Window

[SetTask]

```

r = gSetTask(wind, task);

object wind; /* a window object */
object task; /* task object */
object r; /* wind */

```

This method associates a Task object `task` with window `wind`.

The window object passed is returned.

Example:

```
gSetTask(myWind, myTask);
```

See also: `GetTask`

SetTitle::Window

[SetTitle]

```

r = gSetTitle(wind, title);

object wind; /* a window object */
char *title; /* the new title */
object r; /* wind arg passed */

```

This method is used to set the title displayed at the top of window `wind`, if it has a title bar. `title` may also be a Dynace string object typecast to a `(char *)`. The value returned is the window (`wind`) object passed.

Example:

```

object myWind;

myWind = vNew(MainWindow, "Old Title");
gSetTitle(myWind, "New Title");

```

See also: `New::MainWindow`

SetTopic::Window

[SetTopic]

```

pt = gSetTopic(wind, tpc);

object wind; /* child window object */
char *tpc; /* help topic */
char *pt; /* previous help topic */

```

This method is used to associate help text with window `wind`. The help text is defined using the Windows help system and labeled with the topic indicated by `tpc`. Then, if the user hits the F1 key while in the window, WDS will automatically bring up the Windows help system and find the indicated topic.

WDS also supports dialog and control specific topics. See the appropriate sections.

This method returns any previous topic associated with the window.

Example:

```
object myWind;

gSetTopic(myWind, "myWindHelp");
```

See also: The `HelpSystem` class.

`SetZOrder::Window`

[SetZOrder]

```
r = gSetZOrder(wind, m);

object wind;    /* a window object    */
HWND    m;      /* Z-order position    */
object r;       /* wind                */
```

This method sets the Z-order position of window `wind`. `m` specifies the position and can be `HWND_TOP`, `HWND_TOPMOST`, `HWND_BOTTOM`, or `HWND_NOTOPMOST` as defined by the Windows API.

The window object passed is returned.

Example:

```
gSetZOrder(myWind, HWND_TOPMOST);
```

See also: `MoveToTop`

`Show::Window`

[Show]

```
r = gShow(wind);

object wind;    /* a window object    */
int    r;       /* always 0            */
```

Once a window object is created (via `vNew`) and its various attributes set, `gShow` is called in order to actually create the Windows window, with the selected attributes, and display (show) it.

Example:

```
object myWind;

myWind = vNew(PopupWindow, "Name", 10, 40);
gShow(myWind);
```

See also: `AutoShow`, `ProcessMessages::MainWindow`

`TextBrush::Window`

[`TextBrush`]

```
r = gTextBrush(wind, brsh);

object wind; /* a window object */
object brsh; /* brush object */
object r; /* wind */
```

This method is used to determine what brush object is used for foreground text which is displayed. Any previously associated brush object will be disposed. This brush object will also be automatically disposed when the window is disposed.

The window passed is returned.

Example:

```
object myWind;

gTextBrush(myWind, vNew(SolidBrush, 255, 0, 0));
```

See also: `BackBrush`, `Use`, `SetBackBrush::Application` and the `Brush` classes

`TextOut::Window`

[`TextOut`]

```
r = gTextOut(wind, row, col, txt);

object wind; /* a window object */
int row; /* row number of output */
int col; /* column number of output */
char *txt; /* string to be output */
object r; /* wind */
```

This method is used to display a string of text (`txt`) at row `row` and column `col`. `row` and `col` have their origin in the upper left hand corner of the window and are scaled as dictated by the `SetScalingMode::Application` method. Their index origin is 0.

This method returns the window argument passed.

Example:

```
object myWind;

gTextOut(myWind, 10, 30, "Hello World");
```

See also: `Write`, `Puts`, `Printf`

`Update::Window`

[Update]

```
r = gUpdate(wind);

object wind;    /* a window object    */
object r;       /* wind                      */
```

This method is used to explicitly update the display with changes the program may have made to window `wind`. WDS normally handles this need, however, this method is available in case the programmer performs special processing and wishes to update the entire window at one time.

This method returns the window argument passed. `Update::MainWindow`.

Example:

```
object myWind;

gUpdate(myWind);
```

`Use::Window`

[Use]

```
r = gUse(wind, obj);

object wind;    /* a window object    */
object obj;     /* arbitrary object   */
object r;       /* the object passed   */
```

This method is used as a general purpose mechanism to associate a number of object types with a window. `obj` may be a `Font`, `Icon`, `Cursor`, `Menu`, or the background `Brush` object. Those objects would have normally been created via their associated classes and then may be associated with a window via this method.

Note that the same object should not be associated with more than one window. The problem is that if one window is deleted, WDS would delete all the objects associated with that window and then the other window would reference objects which have been deleted. The way around this is to use the `Copy` method in order to make a copy of an object prior to associating with a new window. This way there would be two independent objects such that if one is deleted the other would still exist.

Note also that the `Application` class may be used to set application wide defaults for these types of objects.

The value returned is the object passed.

Example:

```
object myWind, myOtherWind, someFont;

someFont = vNew(ExternalFont, "Times New Roman", 12);
if (someFont) {
    gUse(myWind, someFont);
    gUse(myOtherWind, gCopy(someFont));
}
```

See also: `LoadFont`, `LoadIcon`, `LoadCursor`, `LoadMenu`, `TextBrush`, `BackBrush`

`VertShift::Window`

[VertShift]

```
r = gVertShift(wind, rows);

object wind;    /* a window object    */
int      rows;  /* rows to shift      */
object r;       /* the window object  */
```

This method is used to perform a vertical shift of the text in the memory buffer which is being displayed in the window. WDS keeps a buffer which holds a programmer definable number of lines of text. The user is then able to scroll through this text. If the application attempts to display more lines than this maximum (via `vPrintf` for example) the system will automatically call `gVertShift` in order to eliminate the top line and make room for the new line being appended. This method is mainly used internally.

`wind` is the window which is to be affected, and `rows` is the number of rows to scroll. If `rows` is positive the scroll moves the text up, and negative moves the text down. Scrolling up permanently destroys lines at the beginning of the buffer and scrolling down permanently destroys lines at the end of the buffer.

The scaling factor associated with `rows` is set by `SetScalingMode::Application` and the maximum lines associated with a window may be set with `SetMaxLines`.

Example:

```
object myWind;

gVertShift(myWind, 2);
```

See also: `ScrollVert`, `SetMaxLines`

`WaitCursor::Window`

[`WaitCursor`]

```
r = gWaitCursor(wind, wait);

object  wind;    /* a window object */
int     wait;    /* show/hide flag  */
object  r;       /* wind           */
```

This method shows or hides the hourglass (`wait`) cursor for window `wind` using reference counting. Pass a non-zero value for `wait` to show the wait cursor. Pass 0 to hide it. The reference counting ensures that nested calls work correctly — the cursor is restored only when the count reaches zero.

The window object passed is returned.

Example:

```
gWaitCursor(myWind, 1); /* show hourglass */
/* ... long operation ... */
gWaitCursor(myWind, 0); /* restore cursor */
```

See also: `SetCursor`

`Write::Window`

[`Write`]

```
r = gWrite(wind, txt, len);

object  wind;    /* a window object      */
char    *txt;    /* string to be output  */
unsigned len;    /* length of string     */
int     r;       /* bytes written        */
```

This method is used to display a string of text (`txt`) in a sequential fashion on window `wind`. Since the `Window` class is a subclass of `Stream`, this method is mainly provided to support the standard interface dictated by the `Stream` class. By providing this method, the `Window` class automatically inherits the `Puts` and `Printf` capability.

`txt` is the text to be displayed and `len` is the length of that string. Text `txt` will be displayed on window `wind` and `len` will be returned.

Example:

```
object  myWind;

gWrite(myWind, "Hello World\n", 12);
```

See also: `TextOut`, `Puts`, `Printf`

4.4.1 Main Window

This class, named `MainWindow`, is used to create and manipulate an application's main window. There is normally one main window associated with each application and this is the first window created.

This class is a subclass of the `Window` class and therefore inherits all of the `Window` class's functionality. The methods documented in this subsection are only those which are particular to the `MainWindow` class.

`New::MainWindow`

[New]

```
r = vNew(MainWindow, ttl);

char    *ttl;    /* window title */
object  r;       /* new window    */
```

This class method is used to create the main application window. Since this is a class method the first argument must be literally `MainWindow`. The window title (`ttl`) will appear at the top of the window.

The value returned is the new window created.

Example:

```
object  myWind;

myWind = vNew(MainWindow, "My Application");
```

See also: `New::ChildWindow`, `New::PopupWindow`, `Show`, `Dispose::Window`

`ProcessMessages::MainWindow`

[ProcessMessages]

```
r = gProcessMessages(wind);

object  wind;    /* a window object    */
int     r;       /* final message result */
```

Once the main application window is created (via `vNew`) and its various attributes set, `gProcessMessages` is called in order to actually create the Windows window, with the selected attributes, display (show) it, and process the application's messages. Processing the application's messages is what allows the user to interact with the application.

The value returned is the return value specified when the application is terminated. This can be specified via `QuitApplication::Application`.

Example:

```
object myWind;

myWind = vNew(MainWindow, "Application Name");
gProcessMessages(myWind);
```

See also: `New`, `Show::Window`, `ProcessMessages::MessageDispatcher`

4.4.2 Child Windows

The Child Window class, called `ChildWindow`, is used in the creation of windows which are children of other windows. As such, they can not be positioned outside of their parent window, and they get iconized along with their parent window.

This class is a subclass of the `Window` class and therefore inherits all of the `Window` class's functionality. The methods documented in this subsection are only those which are particular to the `ChildWindow` class.

`New::ChildWindow`

[New]

```
r = vNew(ChildWindow, prnt, rows, cols);

object prnt; /* parent window object */
int rows; /* length of window */
int cols; /* width of window */
object r; /* new window */
```

This class method is used to create a child window. Since this is a class method the first argument must be literally `ChildWindow`. `prnt` represents the parent window object of which the new window will be a child. `rows` and `cols` determine the initial size of the window are specified in increments dictated by `SetScalingMode::Application`.

The default style associated with the child window is `WS_CHILD | WS_VISIBLE` and may be changed with `SetStyle::Window`. The position may be set with `SetPosition::Window`.

The value returned is the new window created.

Example:

```
object myWind, mainWind;

myWind = vNew(ChildWindow, mainWind, 10, 45);
```

See also: `New::MainWindow`, `New::PopupWindow`, `Show`, `Dispose::Window`

4.4.3 Popup Windows

The `PopupWindow` class is used to create arbitrary windows which function independently of other windows. That is, they may overlap or be moved outside of other windows and iconized independently of other windows. If, however, a popup window is associated with a parent window (via `SetParent::Window`) then it may move outside the parent but will be iconized with it.

This class is a subclass of the `Window` class and therefore inherits all of the `Window` class's functionality. The methods documented in this subsection are only those which are particular to the `PopupWindow` class.

`New::PopupWindow`

[New]

```

r = vNew(PopupWindow, name, rows, cols);

char    *name; /* window title    */
int     rows; /* length of window */
int     cols; /* width of window  */
object  r;    /* new window      */

```

This class method is used to create a popup window. Since this is a class method the first argument must be literally `PopupWindow`. `name` represents the window title and will appear in the window's top border. `rows` and `cols` determine the initial size of the window are specified in increments dictated by `SetScalingMode::Application`.

The default style associated with the popup window is `WS_POPUP | WS_VISIBLE | WS_CAPTION | WS_THICKFRAME | WS_MINIMIZEBOX | WS_MAXIMIZEBOX | WS_SYSMENU` and may be changed with `SetStyle::Window`. The position may be set with `SetPosition::Window`.

The value returned is the new window created.

Example:

```

object  myWind, mainWind;

myWind = vNew(PopupWindow, "Window Title", 10, 45);

```

See also: `New::MainWindow`, `New::ChildWindow`, `Show`, `Dispose::Window`

4.5 Printing

The `Printer` class is used for all aspects of printing. It is a subclass of the Dynace `Stream` class and as such inherits all of its functionality.

All methods in the class use an argument referred to as `pnttr`. This will always be the printer object returned by `QueryPrinter`, `New` or `NewWithHDC` and used to identify the printer which is to be affected.

The value returned by all methods which cause text or graphics output is very significant. During normal operation, the printer object passed will be returned. However, if an error occurs or the user aborted the report a `NULL` will be returned. In this case further output should be avoided (although it won't hurt - it'll just be ignored) and the printer object should be disposed.

All positioning parameters are in increments dictated by `SetScale`. Positions begin in the upper left hand corner and have an index origin of 0.

`Arc::Printer`

[Arc]

```
r = gArc(pnttr, yBeg, xBeg, yEnd, xEnd, yaBeg, xaBeg, yaEnd, xaEnd);
```

```
object pnttr; /* printer object */
int yBeg; /* starting row */
int xBeg; /* starting column */
int yEnd; /* ending row */
int xEnd; /* ending column */
int yaBeg; /* starting arc row */
int xaBeg; /* starting arc column */
int yaEnd; /* ending arc row */
int xaEnd; /* ending arc column */
object r; /* printer object */
```

This method is used to output an elliptical arc to the printer. The currently selected pen object will indicate the thickness and pattern of the outline of the shape, and the currently selected brush object will be used to determine what pattern the shape will be filled with. The parameters indicate location of the beginning and ending of the shape as well as the coordinates of the arc and are in increments dictated by `SetScale`.

See the note at the beginning of this section regarding the return value.

Example:

```
object pnttr;

if (!gArc(pnttr, 10, 10, 180, 140, 12, 12, 128, 135))
    abort report;
```

See also: `NewPage`, `SetScale`, `Use`, `Line`, `Rectangle`, `Ellipse`, `RoundRect`, `Chord`, `Pie`

Chord::Printer

[Chord]

```

r = gChord(pntr, yBeg, xBeg, yEnd, xEnd,
           ylBeg, xlBeg, ylEnd, xlEnd);

object  pntr;    /* printer object      */
int     yBeg;    /* starting row        */
int     xBeg;    /* starting column     */
int     yEnd;    /* ending row          */
int     xEnd;    /* ending column       */
int     ylBeg;   /* starting line row   */
int     xlBeg;   /* starting line column */
int     ylEnd;   /* ending line row     */
int     xlEnd;   /* ending line column  */
object  r;       /* printer object      */

```

This method is used to output a chord shape to the printer. The currently selected pen object will indicate the thickness and pattern of the outline of the shape, and the currently selected brush object will be used to determine what pattern the shape will be filled with. The parameters indicate location of the beginning and ending of the shape as well as the coordinates of the intersecting line and are in increments dictated by `SetScale`.

See the note at the beginning of this section regarding the return value.

Example:

```

object  pntr;

if (!gChord(pntr, 10, 10, 180, 140, 12, 12, 128, 135))
    abort report;

```

See also: `NewPage`, `SetScale`, `Use`, `Line`, `Rectangle`, `Ellipse`, `RoundRect`, `Pie`, `Arc`

Copies::Printer

[Copies]

```

n = gCopies(prt);

object  prt;    /* printer object      */
int     n;      /* number of copies    */

```

This instance method returns the number of copies set for this print job.

Example:

```
object prt;
int nc;

nc = gCopies(prt);
```

DeepDispose::Printer

[DeepDispose]

This method performs the same function as **Dispose**. See that method for details.

Dispose::Printer

[Dispose]

```
r = gDispose(pntr);

object pntr; /* printer object */
object r;    /* NULL          */
```

This method is used to flush the final output page, close the printer and dispose of the printer object. It must be called when a report is complete and the printer is no longer needed.

The value returned is always **NULL** and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object pntr;

pntr = gDispose(pntr);
```

Ellipse::Printer

[Ellipse]

```
r = gEllipse(pntr, yBeg, xBeg, yEnd, xEnd);

object pntr; /* printer object */
int yBeg;    /* starting row   */
int xBeg;    /* starting column */
int yEnd;    /* ending row      */
int xEnd;    /* ending column   */
object r;    /* printer object */
```

This method is used to output an ellipse to the printer. The currently selected pen object will indicate the thickness and pattern of the outline of the shape, and the currently selected brush object will be used to determine what pattern the shape will

be filled with. The parameters indicate location of the beginning and ending of the shape and are in increments dictated by **SetScale**.

See the note at the beginning of this section regarding the return value.

Example:

```
object  pntr;

if (!gEllipse(pntr, 10, 20, 30, 40))
    abort report;
```

See also: **NewPage**, **SetScale**, **Use**, **Line**, **Rectangle**, **RoundRect**, **Chord**, **Pie**, **Arc**

Handle::Printer

[Handle]

```
r = gHandle(pntr);

object  pntr;    /* printer object      */
HANDLE  hdc;     /* handle device context */
```

This method is used to obtain the device context handle associated with an opened printer represented by **pntr**. It is used internally by Windows and should not normally be needed.

Example:

```
HDC      hdc;

hdc = (HDC) gHandle(pntr);
```

Line::Printer

[Line]

```
r = gLine(pntr, yBeg, xBeg, yEnd, xEnd);

object  pntr;    /* printer object      */
int      yBeg;   /* starting row        */
int      xBeg;   /* starting column     */
int      yEnd;   /* ending row          */
int      xEnd;   /* ending column       */
object  r;       /* printer object      */
```

This method is used to output a line to the printer. The currently selected pen object will indicate the thickness and pattern of the line. The parameters indicate location of the beginning and ending of the line and are in increments dictated by **SetScale**.

See the note at the beginning of this section regarding the return value.

Example:

```
object  pntr;

if (!gLine(pntr, 10, 20, 30, 40))
    abort report;
```

See also: `NewPage`, `SetScale`, `Use`, `Arc`, `Rectangle`, `Ellipse`, `RoundRect`, `Chord`, `Pie`

`LoadFont::Printer`

[`LoadFont`]

```
r = gLoadFont(pntr, fname, sz);

object  pntr; /* printer object */
char    *fname; /* font name */
int      sz; /* point size */
object  r; /* font object */
```

This method is used to load an arbitrary font by name at any point size and associate it as the default font for future text output to printer `pntr`. `fname` is the full name of the font as it appears when you list the available fonts via the control-panel / fonts Windows utility, minus the font type in parentheses. `sz` indicates the desired point size.

Any font object previously associated with the printer will be disposed. When the printer object is disposed, the font object will also be disposed.

The value returned is an object representing the font loaded, or `NULL` if the font was not found.

Note that `fname` may also be a Dynace object cast as a `(char *)`.

Example:

```
object  pntr;

gLoadFont(pntr, "Times New Roman", 12);
```

See also: `LoadSystemFont`, `Indirect::ExternalFont`, `Use`

LoadSystemFont::Printer

[LoadSystemFont]

```

r = gLoadSystemFont(pntr, fnt);

object   pntr; /* a printer object */
unsigned fnt;  /* font identifier */
object   r;    /* font object      */

```

This method is used to load a Windows predefined font and associate it with printer **pntr**. The last font associated with a printer is the one which will be used when any text is output to the printer.

fnt is a Windows defined macro which identifies the font. The available options are defined in the Windows documentation under the function named **GetStockObject** and normally end with **_FONT**. The font object will be automatically destroyed whenever the printer object is disposed.

The value returned is an object representing the font, or **NULL** if the font was not found.

Example:

```

object   pntr;

gLoadSystemFont(pntr, SYSTEM_FONT);

```

See also: **LoadFont**, **Load::SystemFont**, **Use**

New::Printer

[New]

```

pntr = vNew(Printer, pwind, rname);

object   pwind; /* parent window      */
char     *rname; /* report name        */
object   pntr;  /* new printer object */

```

This class method is used to create a new **Printer** object which will be used by the **Printer** instance methods to control the printer, fonts and content of output. This method opens up the default printer.

pwind is the window which will act as the parent to any messages which may be displayed when a report is being printed. **rname** determines what the report is referred to as in any messages.

The value returned represents the printer to be used. If the default printer couldn't be opened, **NULL** will be returned. If an object is returned, it must be disposed (via **Dispose**) when it is no longer needed.

Example:

```
object  pnttr, pwind;

pnttr = vNew(Printer, pwind, "My Report");
```

See also: `QueryPrinter`, `NewWithHDC`

`NewPage::Printer`

[`NewPage`]

```
r = gNewPage(pnttr);

object  pnttr;    /* printer object */
object  r;        /* printer object */
```

This method is used to flush and eject the current output page (if anything had been output to it) and prepare for a possible new page of output.

See the note at the beginning of this section regarding the return value.

Example:

```
object  pnttr;

if (!gNewPage(pnttr))
    abort report;
```

`NewWithHDC::Printer`

[`NewWithHDC`]

```
pnttr = gNewWithHDC(Printer, pwind, rname, hdc);

object  pwind;    /* parent window      */
char    *rname;   /* report name      */
HDC     hdc;      /* device context   */
object  pnttr;    /* new printer object */
```

This class method is used to create a new `Printer` object which will be used by the `Printer` instance methods to control the printer, fonts and content of output.

This method opens up the printer identified by `hdc`. This is a Windows internal identifier and may be obtained via the `PrintDialog` class.

`pwind` is the window which will act as the parent to any messages which may be displayed when a report is being printed. `rname` determines what the report is referred to as in any messages.

The value returned represents the printer to be used. If the printer couldn't be opened, `NULL` will be returned.

This method is seldom needed due to `QueryPrinter` and `New`. Use them. If an object is returned, it must be disposed (via `Dispose`) when it is no longer needed.

Example:

```
object  pntr, pwind;
HDC     hdc;

pntr = gNewWithHDC(Printer, pwind, "My Report", hdc);
```

See also: `QueryPrinter`, `New`

`OpenDefault::Printer`

[OpenDefault]

```
prt = gOpenDefault(Printer, wind, name);

object  wind; /* parent window          */
char    *name; /* report name or NULL    */
object  prt;   /* new printer object or NULL */
```

This class method is used to open a printer using the system default printer without showing a print dialog. `wind` is the parent window for any messages that may be displayed. `name` is the report name and may be `NULL`.

The value returned is a new `Printer` instance, or `NULL` if the default printer could not be opened.

Example:

```
object  prt, wind;

prt = gOpenDefault(Printer, wind, "My Report");
```

See also: `New`, `QueryPrinter`

Pie::Printer

[Pie]

```
r = gPie(pntr, yBeg, xBeg, yEnd, xEnd, yaBeg, xaBeg, yaEnd, xaEnd);
```

```
object pntr;    /* printer object      */
int     yBeg;    /* starting row        */
int     xBeg;    /* starting column     */
int     yEnd;    /* ending row          */
int     xEnd;    /* ending column       */
int     yaBeg;   /* starting arc row    */
int     xaBeg;   /* starting arc column */
int     yaEnd;   /* ending arc row      */
int     xaEnd;   /* ending arc column   */
object r;        /* printer object      */
```

This method is used to output a pie shaped wedge to the printer. The currently selected pen object will indicate the thickness and pattern of the outline of the shape, and the currently selected brush object will be used to determine what pattern the shape will be filled with. The parameters indicate location of the beginning and ending of the shape as well as the coordinates of the intersecting line and are in increments dictated by **SetScale**.

See the note at the beginning of this section regarding the return value.

Example:

```
object pntr;

if (!gPie(pntr, 10, 10, 180, 140, 12, 12, 128, 135))
    abort report;
```

See also: **NewPage**, **SetScale**, **Use**, **Line**, **Rectangle**, **Ellipse**, **RoundRect**, **Chord**, **Arc**

PrintBitmap::Printer

[PrintBitmap]

```
r = gPrintBitmap(prt, file, yPos, xPos, height, width);
```

```
object prt;      /* printer object      */
char     *file;   /* bitmap file path    */
int     yPos;    /* vertical position    */
int     xPos;    /* horizontal position  */
int     height;   /* height of output image */
int     width;    /* width of output image */
object r;        /* printer object      */
```

This instance method is used to print a bitmap file at the specified position and size on the current page. The coordinates are scaled to printer units.

Example:

```
object prt;

gPrintBitmap(prt, "logo.bmp", 10, 20, 100, 200);
```

Printf::Printer

[Printf]

```
r = vPrintf(pntr, fmt, ...);

object pntr; /* printer object */
char *fmt; /* format string */
int r; /* length of output */
```

This method is used to output a string of text (**str**) in a sequential fashion on printer **pntr**. It is analogous to the standard C library function **fprintf**. All of the standard features of your C library **fprintf** function are supported and that documentation should be consulted for full documentation on the arguments.

This method is used to support the standard streams interface, is actually defined by the **Stream** class, and is documented here for convenience.

Note that this method begins with “v” since it takes variable arguments.

The value returned by this method is very significant. During normal operation, the length of the output string will be returned. However, if an error occurs or the user aborted the report a -1 will be returned. In this case further output should be avoided (although it won’t hurt - it’ll just be ignored) and the printer object should be disposed.

Example:

```
object pntr;
int age = 32;

if (-1 == vPrintf(pntr, "My age == %d\n", age))
    goto abort report;
```

See also: **TextOut**, **Puts**

Puts::Printer

[Puts]

```

r = gPuts(pntr, str);

object  pntr; /* printer object      */
char    *str; /* string to be output */
int     r;    /* length of str          */

```

This method is used to output a string of text (**str**) in a sequential fashion on printer **pntr**. This method is used to support the standard streams interface, is actually defined by the **Stream** class, and is documented here for convenience. **str** is the text to be output.

The value returned by this method is very significant. During normal operation, the length of the output string will be returned. However, if an error occurs or the user aborted the report a -1 will be returned. In this case further output should be avoided (although it won't hurt - it'll just be ignored) and the printer object should be disposed.

Example:

```

object  pntr;

if (-1 == gPuts(pntr, "Hello World\n"))
    goto abort report;

```

See also: **TextOut**, **Printf**

QueryPrinter::Printer

[QueryPrinter]

```

pntr = gQueryPrinter(Printer, pwind, rname);

object  pwind; /* parent window      */
char    *rname; /* report name        */
object  pntr;   /* new printer object */

```

This class method is used to create a new **Printer** object which will be used by the **Printer** instance methods to control the printer, fonts and content of output.

This method queries the user for printer selection and optional configuration, and uses that information to open the selected printer.

pwind is the window which will act as the parent to any messages which may be displayed when a report is being printed. **rname** determines what the report is referred to as in any messages.

The value returned represents the printer to be used. If the user canceled the printer selection or the printer couldn't be opened, NULL will be returned. If an object is returned, it must be disposed (via `Dispose`) when it is no longer needed.

Example:

```
object  pnter, pwind;

pnter = gQueryPrinter(Printer, pwind, "My Report");
```

See also: `New`, `NewWithHDC`

Rectangle::Printer

[Rectangle]

```
r = gRectangle(pnter, yBeg, xBeg, yEnd, xEnd);

object  pnter;    /* printer object    */
int      yBeg;    /* starting row      */
int      xBeg;    /* starting column   */
int      yEnd;    /* ending row        */
int      xEnd;    /* ending column     */
object  r;        /* printer object    */
```

This method is used to output a rectangle to the printer. The currently selected pen object will indicate the thickness and pattern of the outline of the shape, and the currently selected brush object will be used to determine what pattern the shape will be filled with. The parameters indicate location of the beginning and ending of the shape and are in increments dictated by `SetScale`.

See the note at the beginning of this section regarding the return value.

Example:

```
object  pnter;

if (!gRectangle(pnter, 10, 20, 30, 40))
    abort report;
```

See also: `NewPage`, `SetScale`, `Use`, `Line`, `Ellipse`, `RoundRect`, `Chord`, `Pie`, `Arc`

RoundRect::Printer

[RoundRect]

```

r = gRoundRect(pntr, yBeg, xBeg, yEnd, xEnd, eHt, eWth);

object  pntr;    /* printer object          */
int     yBeg;    /* starting row                */
int     xBeg;    /* starting column             */
int     yEnd;    /* ending row                  */
int     xEnd;    /* ending column               */
int     eHt;     /* corner ellipse height      */
int     eWth;    /* corner ellipse width       */
object  r;       /* printer object             */

```

This method is used to output a rectangle with rounded corners to the printer. The currently selected pen object will indicate the thickness and pattern of the outline of the shape, and the currently selected brush object will be used to determine what pattern the shape will be filled with. The parameters indicate location of the beginning and ending of the shape and are in increments dictated by **SetScale**.

See the note at the beginning of this section regarding the return value.

Example:

```

object  pntr;

if (!gRoundRect(pntr, 10, 20, 30, 40, 1, 1))
    abort report;

```

See also: **NewPage**, **SetScale**, **Use**, **Line**, **Rectangle**, **Ellipse**, **Chord**, **Pie**, **Arc**

Scale::Printer

[Scale]

```

r = gScale(prt, row, col);

object  prt;    /* printer object          */
int     *row;   /* pointer to row coordinate */
int     *col;   /* pointer to column coordinate */
object  r;      /* printer object          */

```

This instance method scales logical coordinates to physical printer coordinates in place, accounting for printer size and offsets.

Example:

```
object prt;
int      row = 10, col = 20;

gScale(prt, &row, &col);
```

SetScale::Printer

[SetScale]

```
r = gSetScale(pntr, ht, wth);

object pntr;    /* printer object */
int     ht;     /* logical height */
int     wth;    /* logical width  */
object r;       /* printer object */
```

This method is used to set the logical scaling factor associated with an output device. Each output page is divided up into **ht** evenly spaced row and **wth** evenly spaced columns. This scaling factor will be used by all text and graphics output when determining output size and location on the page.

Coordinates begin at the upper left hand of the page and are zero origin. The defaults are set to 80 columns and 66 lines.

Example:

```
object pntr;

gSetScale(pntr, 132, 160);
```

See also: TextOut

TextOut::Printer

[TextOut]

```
r = gTextOut(pntr, row, col, txt);

object pntr;    /* printer object */
int     row;    /* output row      */
int     col;    /* output column  */
char    *txt;   /* text to output */
object r;       /* printer object */
```

This method is used to output a line of text (**txt**) to the printer. **row** and **col** indicate the position of the text and are in increments dictated by **SetScale**. Positions begin in the upper left hand corner and have an index origin of 0.

The text will be printed in the currently selected font. Note that the actual printing will not occur until the report is complete and the print object disposed.

See the note at the beginning of this section regarding the return value.

Example:

```
object  pntr;

if (!gTextOut(pntr, 10, 20, "output text"))
    abort report;
```

See also: `NewPage`, `Printf`, `SetScale`, `LoadFont`

Use::Printer

[Use]

```
r = gUse(pntr, obj);

object  pntr;    /* printer object      */
object  obj;     /* arbitrary object    */
object  r;       /* the object passed   */
```

This method is used as a general purpose mechanism to associate a number of object types with a printer. `obj` may be a `Font`, `Brush` or `Pen` object. Those objects would have normally been created via their associated classes and then may be associated with a printer via this method.

Note that the same object should not be associated with more than one printer object. The problem is that if one printer object is disposed, WDS would dispose of all the objects associated with that printer and then the other printer would reference objects which have been deleted. The way around this is to use the `Copy` method in order to make a copy of an object prior to associating it with a new printer. This way there would be two independent objects such that if one is deleted the other would still exist.

The value returned is the object passed.

Example:

```
object  myPntr, myOtherPntr, someFont;

someFont = vNew(ExternalFont, "Times New Roman", 12);
if (someFont) {
    gUse(myPntr, someFont);
    gUse(myOtherPntr, gCopy(someFont));
}
```

See also: `LoadFont` and the `Brush` and `Pen` classes.

4.6 Menus

The `Menu` class, although not used directly by an application, is used to house the common functionality associated with the `ExternalMenu` and `InternalMenu` classes. Most of the functionality of those classes is implemented and documented in this section.

External menus (those defined in resources) would be created and used via the `ExternalMenu` class. Internal menus (those defined at runtime by the application code) would be created and used via the `InternalMenu` and `PopupMenu` classes. Since both of these classes are subclasses of the `Menu` class, they inherit most of their functionality from it.

`Associate::Menu`

[Associate]

```
r = mAssociate(menu, id, fun);

object menu; /* a menu object */
int id; /* menu item id */
long (*fun)(object); /* function to execute */
object r; /* the menu object */
```

This method is used to associate a function with a menu item such that if the user selects the menu item, `fun` gets executed.

In the case of external menus, `id` is normally a macro created by the resource editor while the programmer defines the menu and identifies a particular menu option.

`fun` is the application specific function which automatically gets executed whenever the user selects the indicated option. `fun` has the following structure:

```
static long menu_option(object wind)
{
    .
    .
    .
    return 0L;
}
```

Where `wind` is the window object which the menu is attached to. The value returned is what is returned by the window procedure associated with the window. This value is normally 0 and is fully documented by the Windows documentation under the `WM_COMMAND` message.

The value returned is the menu object passed.

Example:

```
object myMenu;

mAssociate(myMenu, ID_FILE_OPEN, menu_option);
```

See also: `AddMenuOption::InternalMenu`, `AddMenuOption::PopupMenu`

`DeepDispose::Menu`

[`DeepDispose`]

```
r = gDeepDispose(menu);

object menu;    /* a menu object    */
object r;       /* NULL                          */
```

This method is used to dispose of a menu object and all menu objects which were pushed (via `Push`) into the same menu stack. It is not often needed because menus associated with a window are automatically disposed of (via this method) when the window is disposed.

If `menu` is an internal menu, all associated popup menus will also be disposed.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object myMenu;

myMenu = gDeepDispose(myMenu);
```

See also: `Dispose`, `Push`

`Dispose::Menu`

[`Dispose`]

```
r = gDispose(menu);

object menu;    /* a menu object    */
object r;       /* NULL                          */
```

This method is used to dispose of a menu object when it is no longer needed. It is not often needed because menus associated with a window are automatically disposed of (via `DeepDispose`) when the window is disposed.

If `menu` is an internal menu, all associated popup menus will also be disposed.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object myMenu;

myMenu = gDispose(myMenu);
```

See also: DeepDispose

EnableMenuItem::Menu

[EnableMenuItem]

```
prev = gEnableMenuItem(menu, id, flag);

object menu; /* a menu object */
unsigned id; /* menu item identifier */
unsigned flag; /* MF_ENABLED, MF_DISABLED, or MF_GRAYED */
unsigned prev; /* previous state */
```

This method enables, disables, or grays a menu item identified by id. flag should be one of MF_ENABLED, MF_DISABLED, or MF_GRAYED.

The value returned is the previous state of the menu item.

Example:

```
object myMenu;

gEnableMenuItem(myMenu, ID_FILE_SAVE, MF_GRAYED);
```

See also: SetMode

Handle::Menu

[Handle]

```
h = gHandle(menu);

object menu; /* menu object */
HANDLE h; /* Windows handle */
```

This method is used to obtain the Windows internal handle associated with a menu object.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```
object myMenu;
HANDLE h;

h = gHandle(myMenu);
```

MenuFunction::Menu

[MenuFunction]

```
fun = mMenuFunction(menu, id);

object menu; /* a menu object */
int id; /* menu item id */
long (*fun)(object); /* function to execute */
```

This method is used to obtain the function which was associated with a menu item.

See also: **Associate**

Pop::Menu

[Pop]

```
prev = gPop(top);

object top; /* top menu */
object prev; /* previous menu */
```

This method is used to dispose of menu **top** and gain access to the next menu in menu **top**'s last in, first out list. It is mainly used by the **Window** class in order to support the ability to change a menu and later return to a previous menu. The value returned is the next menu in the stack.

Example:

```
object myMenu, subMenu;
HANDLE h;

subMenu = gPop(myMenu);
```

See also: **Push**, **Use::Window**, **PopupMenu::Window**

Push::Menu

[Push]

```

r = gPush(top, psh);

object top;    /* top menu    */
object psh;    /* pushed menu */
object r;      /* top menu    */

```

This method is used to push menu (**psh**) into a last in, first out stack accessible through menu **top**. It is mainly used by the **Window** class in order to support the ability to change a menu and later return to a previous menu. The value returned is the top menu passed.

Example:

```

object myMenu, subMenu;
HANDLE h;

h = gPush(myMenu, subMenu);

```

See also: **Pop**, **Use::Window**, **PopupMenu::Window**

SetCheckMark::Menu

[SetCheckMark]

```

prev = gSetCheckMark(menu, id, val);

object menu;    /* a menu object    */
unsigned id;    /* menu item identifier */
int val;        /* non-zero to check, zero to uncheck */
int prev;       /* previous state    */

```

This method checks or unchecks a menu item identified by **id**. If **val** is non-zero, the menu item is checked; if zero, it is unchecked.

The value returned is the previous check state.

Example:

```

object myMenu;

gSetCheckMark(myMenu, ID_VIEW_TOOLBAR, 1);

```

SetMode::Menu

[SetMode]

```

r = mSetMode(menu, id, mode);

object menu; /* menu */
unsigned id; /* menu item */
unsigned mode; /* item mode */
object r; /* menu */

```

This method is used to set the mode associated with a menu item. This mode specifies whether the menu is enabled, disabled or grayed.

In the case of external menus, `id` is normally a macro created by the resource editor while the programmer defines the menu and identifies a particular menu option. In the case of internal menus, `id` is the number returned by `AddMenuOption::InternalMenu` or `AddMenuOption::PopupMenu`.

`mode` is a Windows defined macro and may be one of the following:

```

MF_ENABLED      to enable the menu item
MF_DISABLED     to disable the menu item
MF_GRAYED       to gray the menu option

```

The value returned is the menu passed.

Example:

```

object myMenu;

mSetMode(myMenu, ID_FILE_OPEN, MF_DISABLED);

```

See also: `AddMenuOption::InternalMenu`, `AddMenuOption::PopupMenu`

4.6.1 External Menus

The `ExternalMenu` class is used to access menus which were defined using the resource editor. Since this class is a subclass of `Menu`, all of `Menu`'s functionality is accessible through instance of this class. Therefore, see the `Menu` class for additional functionality.

Load::ExternalMenu

[Load]

```

menu = mLoad(ExternalMenu, id);

unsigned id; /* menu id */
object menu; /* menu */

```

This method is used to create a new menu object representing a menu defined with the resource editor.

`id` is normally a macro created by the resource editor which identifies a particular menu.

The value returned is a new object representing the menu or `NULL` if the menu identified is not found.

Example:

```
object myMenu;

myMenu = mLoad(ExternalMenu, MY_MENU);
```

See also: `LoadStr`, `LoadMenu::Window`, `LoadMenuStr::Window`

`LoadStr::ExternalMenu`

[`LoadStr`]

```
menu = gLoadStr(ExternalMenu, id);

char    *id;    /* menu id */
object menu;    /* menu    */
```

This method is used to create a new menu object representing a menu defined with the resource editor.

`id` is a string which names the desired menu. This name is defined by the resource editor and identifies a particular menu.

The value returned is a new object representing the menu or `NULL` if the menu identified is not found.

Example:

```
object myMenu;

myMenu = gLoadStr(ExternalMenu, "mymenu");
```

See also: `Load`, `LoadMenu::Window`, `LoadMenuStr::Window`

4.6.2 Internal Menus

The `InternalMenu` class is used to enable an application to create menus on the fly – without the need to pre-specify the menu's structure with the resource editor. Since this class is a subclass of `Menu`, all of `Menu`'s functionality is accessible through instance of this class. Therefore, see the `Menu` class for additional functionality.

AddMenuOption::InternalMenu

[AddMenuOption]

```
id = gAddMenuOption(mnu, ttl, fun)
```

```
object menu; /* menu */
char *ttl; /* title */
long (*fun)(); /* function */
int id; /* item id */
```

This method is used to append a new option to internal menu object `mnu` and associate it to an application specific function (`fun`). Once this is done, if the user selects the new menu option the function `fun` will be executed.

`ttl` represents the character string which will be displayed in the menu. `ttl` may also contain an embedded ampersand (&) character. This causes the character following the ampersand to be underlined. It also causes the following character to be the Alt key selection the user can use to quickly select a menu option.

`fun` is the function which will be executed when the user selects the menu option and has the following form:

```
long fun(object wind)
{
    .
    .
    .
    return 0L;
}
```

The function executed (`fun`) is passed the window object and returns a long. The return value is documented in the Windows documentation under the message named `WM_COMMAND`. It should normally be `0L`.

This method returns a unique WDS generated id which identifies this particular menu option and may be used to control the status of the option.

Example:

```
static long file_message(object wind)
{
    gMessage(wind, "File_Message");
    return 0L;
}

.
.
mnu = vNew(InternalMenu);
gAddMenuOption(mnu, "&File", file_message);
```

See also: `AddPopupMenu`

`AddPopupMenu::InternalMenu`

[`AddPopupMenu`]

```
id = gAddPopupMenu(mnu, ttl, pm)

object mnu;    /* menu      */
char   *ttl;   /* title   */
object pm;     /* Popup menu */
object r;      /* menu     */
```

This method is used to append a new option to menu object `mnu` and associate it to a popup menu. Once this is done, if the user selects the new menu option the popup menu will be displayed.

`ttl` represents the character string which will be displayed in the menu. `ttl` may also contain an embedded ampersand (&) character. This causes the character following the ampersand to be underlined. It also causes the following character to be the Alt key selection the user can use to quickly select a menu option.

`pm` is a popup menu object created with the `PopupMenu` class.

This method returns `mnu`.

Example:

```
object mnu, pm;

mnu = vNew(InternalMenu);
pm  = vNew(PopupMenu, mnu);
gAddPopupMenu(mnu, "&File", pm);
```

See also: `AddMenuOption`, `New::PopupMenu`

`New::InternalMenu`

[`New`]

```
menu = vNew(InternalMenu);

object menu;    /* menu      */
```

This method is used to create a new internal menu. An internal menu is one which is not pre-specified with the resource editor. It may therefore be structured at runtime.

The object returned is a new internal menu object with no items associated with it.

Example:

```
object myMenu;

myMenu = vNew(InternalMenu);
```

See also: `AddMenuOption`, `AddMenu`, `Use::Window`, `LoadMenu::Window`

4.7 Popup Menus

The `PopupMenu` class is used in conjunction with the `InternalMenu` class in order to provide a nested menu structure. Nesting of popup menus is supported to arbitrary levels.

`AddMenuOption::PopupMenu`

[`AddMenuOption`]

```
id = gAddMenuOption(mnu, ttl, fun)

object menu; /* menu */
char *ttl; /* title */
long (*fun)(); /* function */
int id; /* item id */
```

This method works exactly like `AddMenuOption::InternalMenu`. See that description for full documentation.

See also: `AddPopupMenu`, `AddSeparator`

`AddPopupMenu::PopupMenu`

[`AddPopupMenu`]

```
id = gAddPopupMenu(mnu, ttl, pm)

object mnu; /* menu */
char *ttl; /* title */
object pm; /* Popup menu */
object r; /* menu */
```

`mnu` is the popup menu which is to act as the parent of `pm` and may be arbitrarily nested.

This method is the same as `AddPopupMenu::InternalMenu`. See that method for complete documentation.

See also: `AddMenuOption`, `AddSeparator`

AddSeparator::PopupMenu

[AddSeparator]

```

r = gAddSeparator(mnu)

object mnu;    /* menu    */
object r;      /* menu    */

```

This method is used to append a horizontal bar to the end of a popup menu. Any menu items added subsequently will appear after the horizontal separator.

The menu object passed is returned.

Example:

```
gAddSeparator(pm);
```

See also: **AddMenuOption**

Dispose::PopupMenu

[Dispose]

```

r = gDispose(menu);

object menu;    /* a menu object */
object r;       /* NULL        */

```

This method is used to dispose of a menu object when it is no longer needed. It is not often needed because popup menus associated with other menus are automatically disposed of (via **DeepDispose**) when the top level menu is disposed.

This class also provides a **DeepDispose** which performs the same function.

The value returned is always **NULL** and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```

object myMenu;

myMenu = gDispose(myMenu);

```

See also: **DeepDispose::Menu**

MenuFunction::PopupMenu

[MenuFunction]

```

    fun = mMenuFunction(menu, id);

    object menu;    /* a menu object    */
    int id;         /* menu item id    */
    long (*fun)(object); /* function to execute */

```

This method is used to obtain the function which was associated with a menu item.

See also: `AddMenuOption`

New::PopupMenu

[New]

```

    pm = vNew(PopupMenu, tm);

    object tm;      /* top menu    */
    object pm;      /* popup menu */

```

This method is used to create a new popup menu. A popup menu is one which pops up or appears when a user selects an associated menu option. Popup menus are used in conjunction with internal menus in order to create arbitrarily complex menu structures.

`tm` is the top menu object. It must be an `InternalMenu`, regardless of where the new popup menu will be nested.

The object returned represents the new popup menu created and may be used to add items to that menu.

Example:

```

    object myMenu, pm;

    myMenu = vNew(InternalMenu);
    pm = vNew(PopupMenu, myMenu);
    gAddPopupMenu(myMenu, "&File", pm);

```

See also: `AddMenuOption`, `AddPopupMenu`, `AddSeparator`,
`AddPopupMenu::InternalMenu`

4.8 Dialogs

The `Dialog` class implements all the functionality which is common to the `ModalDialog` and `ModelessDialog` classes, and although this class is not used directly, most of their functionality is documented in this section.

4.8.1 Standard Dialog Method Arguments

Since all dialog instance methods have the dialog object as the first argument (referred to as `dlg`), this argument will not be described each time. It always refers to the dialog object which you wish to perform the desired operation on.

Many of the methods associated with this class take an argument identified as `id`. This is a macro defined by the programmer via the resource editor when the dialog is being defined and is used to uniquely identify a particular control within the dialog. Due to the fact that this argument has the same meaning for every method which uses it, it will not be defined each time.

The variable `ctl` will always refer to a control object. Each control object represents a unique control within a dialog. Each control object will be an instance of one of the subclasses of the `Control` class (such as `TextControl` or `NumericControl`).

4.8.2 Dialog Methods

`AddActivateFunctionAfter::Dialog`

[`AddActivateFunctionAfter`]

```
r = gAddActivateFunctionAfter(dlg, fun);

object  dlg;          /* a dialog object */
int      (*fun)();     /* function pointer */
object  r;             /* the dialog obj  */
```

This method is used to add a function which will be called when the dialog is activated (receives focus). The new function is added after any existing activation handlers.

The value returned is the dialog object passed.

Example:

```
static int  my_activate(object dlg)
{
    /* handle activation */
    return 0;
}

gAddActivateFunctionAfter(dlg, my_activate);
```

See also: `AddActivateFunctionBefore`

AddActivateFunctionBefore::Dialog

[AddActivateFunctionBefore]

```
r = gAddActivateFunctionBefore(dlg, fun);

object  dlg;          /* a dialog object */
int     (*fun)();      /* function pointer */
object  r;             /* the dialog obj  */
```

This method is used to add a function which will be called when the dialog is activated (receives focus). The new function is added before any existing activation handlers.

The value returned is the dialog object passed.

Example:

```
static int  my_activate(object dlg)
{
    /* handle activation */
    return 0;
}

gAddActivateFunctionBefore(dlg, my_activate);
```

See also: **AddActivateFunctionAfter**

AddCompletionFunctionAfter::Dialog

[AddCompletionFunctionAfter]

```
r = gAddCompletionFunctionAfter(dlg, fun);

object  dlg;          /* a dialog object */
int     (*fun)();      /* function pointer */
object  r;             /* the dialog obj  */
```

This method is used to add a function which will be called when the dialog completes (when the user accepts or cancels the dialog). The new function is added after any existing completion handlers.

This is similar to **CompletionFunction** but allows multiple handlers and controls the execution order.

The value returned is the dialog object passed.

Example:

```
static int  my_completion(object dlg)
{
    /* process completion */
    return 0;
}

gAddCompletionFunctionAfter(dlg, my_completion);
```

See also: `AddCompletionFunctionBefore`, `CompletionFunction`

`AddCompletionFunctionBefore::Dialog`

[`AddCompletionFunctionBefore`]

```
r = gAddCompletionFunctionBefore(dlg, fun);

object  dlg;          /* a dialog object */
int     (*fun)();      /* function pointer */
object  r;             /* the dialog obj  */
```

This method is used to add a function which will be called when the dialog completes (when the user accepts or cancels the dialog). The new function is added before any existing completion handlers.

This is similar to `CompletionFunction` but allows multiple handlers and controls the execution order.

The value returned is the dialog object passed.

Example:

```
static int  my_completion(object dlg)
{
    /* process completion */
    return 0;
}

gAddCompletionFunctionBefore(dlg, my_completion);
```

See also: `AddCompletionFunctionAfter`, `CompletionFunction`

AddControl::Dialog

[AddControl]

```

    ctl = mAddControl(dlg, ctlClass, id);

    object  dlg;          /* a dialog object */
    object  ctlClass;     /* class of control */
    unsigned id;          /* control id */
    object  ctl;          /* control object */

```

This method is used to create a new control object and associate it to a control defined in the dialog. `ctlClass` must be literally one of the subclasses of the `Control` class (such as `TextControl`, `CheckBox`, `RadioButton`, etc). See the class hierarchy for a complete list.

`id` identifies which control within dialog `dlg` to associate the new control object with.

The value returned (`ctl`) is the new control object created and will be an instance of the class indicated by the `ctlClass` argument. This object can be configured and queried via the protocol defined by its class. See that section for available options. Setting various options associated with this object will control default values associated with the control and how this control functions within the dialog.

Example:

```

    object  dlg, ctl;

    ctl = mAddControl(dlg, TextControl, PERSONS_NAME);

```

See also: `GetControl`

AddDlgHandlerAfter::Dialog

[AddDlgHandlerAfter]

```

    r = gAddDlgHandlerAfter(dlg, msg, func);

    object  dlg;          /* a dialog object */
    unsigned msg;          /* message */
    BOOL     (*func)();    /* function pointer */
    object  r;             /* the dialog obj */

```

This method is used to associate function `func` with Windows dialog message `msg` for dialog `dlg`. Whenever dialog `dlg` receives message `msg`, `func` will be called.

`dlg` is the dialog object who's messages you wish to process. `msg` is the particular message you wish to trap. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with `WM_`.

`func` is the function which gets called whenever the specified message gets received and takes the following form:

```

    BOOL    func(object    dlg,
                  HWND     hdlg,
                  UINT      mMsg,
                  WPARAM    wParam,
                  LPARAM     lParam)
{
    .
    .
    .
    return FALSE; /* or whatever is appropriate */
}

```

Where `dlg` is the dialog being sent the message. The remaining arguments and return value is fully documented in the Windows documentation under the `DialogProc` function and the Windows Messages documentation.

WDS keeps a list of functions associated with each message associated with each dialog. When a particular message is received the appropriate list of handler functions gets executed sequentially. `AddDlgHandlerAfter` appends the new function to the end of this list, and `AddDlgHandlerBefore` adds the new function to the beginning of the list.

Windows will only see the return value of the last message handler executed.

Example:

```

    int      hSize, vSize;

    static  BOOL    process_wm_size(object    dlg,
                                      HWND     hwnd,
                                      UINT      mMsg,
                                      WPARAM    wParam,
                                      LPARAM     lParam)
    {
        hSize = LOWORD(lParam);
        vSize = HIWORD(lParam);
        return 0L;
    }

    .
    .
    gAddDlgHandlerAfter(dlg, (unsigned) WM_SIZE,
                        process_wm_size);
    .
    .

```

See also: `AddDlgHandlerBefore`

AddDlgHandlerBefore::Dialog

[AddDlgHandlerBefore]

```

r = gAddDlgHandlerBefore(dlg, msg, func);

object  dlg;      /* a dialog object */
unsigned msg;     /* message          */
BOOL    (*func)(); /* function pointer */
object  r;        /* the dialog obj  */

```

This function is fully documented under `AddDlgHandlerAfter`.

See also: `AddDlgHandlerAfter`

AddInitFunctionAfter::Dialog

[AddInitFunctionAfter]

```

r = gAddInitFunctionAfter(dlg, fun);

object  dlg;      /* a dialog object */
int     (*fun)(); /* function pointer */
object  r;        /* the dialog obj  */

```

This method is used to add a function which will be called after the dialog has been initialized. The new function is added after any existing initialization handlers.

The value returned is the dialog object passed.

Example:

```

static int  my_init(object dlg)
{
    /* perform initialization */
    return 0;
}

gAddInitFunctionAfter(dlg, my_init);

```

See also: `AddInitFunctionBefore`

AddInitFunctionBefore::Dialog

[AddInitFunctionBefore]

```

r = gAddInitFunctionBefore(dlg, fun);

object  dlg;      /* a dialog object */
int     (*fun)(); /* function pointer */
object  r;        /* the dialog obj  */

```

This method is used to add a function which will be called before the dialog has been initialized. The new function is added before any existing initialization handlers.

The value returned is the dialog object passed.

Example:

```
static int  my_init(object dlg)
{
    /* perform initialization */
    return 0;
}

gAddInitFunctionBefore(dlg, my_init);
```

See also: `AddInitFunctionAfter`

`AutoDispose::Dialog`

[AutoDispose]

```
pflg = gAutoDispose(dlg, flg);

object  dlg;    /* a dialog object    */
int     flg;    /* desired mode      */
int     pflg;   /* previous mode set */
```

This method is used to control the auto disposal facility associated with a given dialog. The default is disabled for modal dialogs and enabled for modeless dialogs.

If enabled, the auto dispose feature will cause the dialog object (`dlg`) to be automatically disposed of whenever the user accepts or aborts the dialog. If disabled, the application may continue to use the object (for querying control values for example) after the dialog has been terminated. If the auto dispose feature is disabled the application must explicitly dispose of the object when it is no longer needed.

Note that if the auto dispose feature is used, the `gCompletionFunction` method may be used to access the control values immediately prior to the object's automatic disposal.

Set `flg` to 1 to enable the feature and 0 to disable it. The previous state will be returned.

Example:

```
object  dlg;

gAutoDispose(dlg, 1);
```

See also: `CompletionFunction`, `Perform`, `SetResult`

BackBrush::Dialog

[BackBrush]

```
r = gBackBrush(dlg, brsh);

object dlg;    /* a dialog object */
object brsh;   /* brush object    */
object r;      /* dlg                    */
```

This method is used to set the brush object which is used for the background of the dialog. Any previously associated brush object will be disposed. This brush object will also be automatically disposed when the dialog is disposed.

The dialog passed is returned.

Example:

```
object dlg;

gBackBrush(dlg, vNew(SolidBrush, 0, 255, 0));
```

See also: **TextBrush**, **SetBackBrush::Application** and the **Brush** classes

Center::Dialog

[Center]

```
r = gCenter(dlg);

object dlg;    /* a dialog object */
object r;      /* the dialog obj  */
```

This method is used to center the dialog on its parent window. If the dialog is currently active, it is centered immediately. If the dialog is not yet visible, it will be centered when it is shown.

The value returned is the dialog object passed.

Example:

```
object dlg;

gCenter(dlg);
```

CheckValue::Dialog

[CheckValue]

```
r = gCheckValue(dlg);

object dlg;    /* a dialog object */
int    r;      /* validation result */
```

This method is used to validate all controls in the dialog. Each control's check function (if any) is called to verify its current value.

The value returned is 0 if all controls pass validation, or 1 if any control has a validation error.

Example:

```
object dlg;

if (gCheckValue(dlg))
    /* handle validation error */
```

CompletionFunction::Dialog

[CompletionFunction]

```
r = gCompletionFunction(dlg, fun);

object dlg;      /* dialog object */
int    (*fun)(); /* completion function */
object r;        /* dialog object */
```

This method is used to associate a C function with a dialog such that when the user accepts or aborts the dialog, function **fun** will get executed by WDS. The function will get executed prior to any automatic disposal of the dialog object.

The completion function facility is best used in conjunction with modeless dialogs and the auto dispose facility in order to process control values when the user accepts the dialog and prior to the automatic disposal of the dialog object.

The format of **fun** is as follows:

```
r = fun(dlg, res);

object dlg; /* the dialog object */
int    res; /* result status of the dialog */
int    r;   /* result for gPerform */
```

Where **res** will be **TRUE** if the user accepted the dialog or **FALSE** if the user canceled the dialog. **r** is the value which will become the result of the dialog which is returned by **gPerform** (if it was a modal dialog). **r** will normally be **res**.

Example:

```
static int fun(object dlg, int res)
{
    .
    .
    return res;
}

gCompletionFunction(dlg, fun);
```

See also: `AutoDispose`, `Perform`, `SetTag`, `SetResult`

`CtlDoubleValue::Dialog`

[`CtlDoubleValue`]

```
val = mCtlDoubleValue(dlg, id);

object dlg; /* a dialog object */
unsigned id; /* control id */
double val; /* control value */
```

This method is used to gain access to the value associated with a particular control as a C double. For example, if the control was a numeric control and the user entered “3.141”, then this method would return a double “3.141”.

Example:

```
object dlg;
double val;

val = mCtlDoubleValue(dlg, PI_VALUE);
```

See also: `CtlStringValue`, `CtlShortValue`, ... `CtlValue`

`CtlLongValue::Dialog`

[`CtlLongValue`]

```
val = mCtlLongValue(dlg, id);

object dlg; /* a dialog object */
unsigned id; /* control id */
long val; /* control value */
```

This method is used to gain access to the value associated with a particular control as a C long. For example, if the control was a numeric control and the user entered “6”, then this method would return a long “6”.

In the case of date controls, the value returned will be in the form YYYYMMDD. For example November 24, 1956 would be 19561124.

Example:

```
object  dlg;
long    val;

val = mCtlLongValue(dlg, PERSONS_AGE);
```

See also: CtlStringValue, CtlShortValue, ... CtlValue

CtlShortValue::Dialog

[CtlShortValue]

```
val = mCtlShortValue(dlg, id);

object  dlg;    /* a dialog object */
unsigned id;    /* control id      */
short   val;    /* control value  */
```

This method is used to gain access to the value associated with a particular control as a C short. For example, if the control was a numeric control and the user entered “6”, then this method would return a short “6”.

In the case of a list box or combo box the value returned will be in terms of an ordinal value. This value returned is a zero based index from top to bottom indicating the selection made by the user. If no selection was made negative value will be returned.

In the case of check boxes and radio buttons this method will return 0 if the button is not selected, 1 if the button is selected, and 2 if the button is grayed.

In the case of scroll bars, this method will return a short value between the minimum and maximum set for the control which indicates where the control was set to.

mCtlLongValue should be used for date controls.

Example:

```
object  dlg;
short   val;

val = mCtlShortValue(dlg, PERSONS_AGE);
```

See also: CtlStringValue, CtlLongValue, ... CtlValue

CtlStringValue::Dialog

[CtlStringValue]

```

    val = mCtlStringValue(dlg, id);

    object  dlg;    /* a dialog object */
    unsigned id;    /* control id      */
    char    *val;   /* control value  */

```

This method is used to gain access to the value associated with a particular control as a C character string. For example, if the control was a text control and the user entered “Miami”, then this method would return a pointer to the C string “Miami”.

If the control being accessed is a list box or combo box, the value returned will be a string representation of the text associated with the choice made by the user. See **CtlShortValue** or **IndexValue** to get an ordinal value for this control type.

The character pointer returned will not be valid once the dialog or control has been disposed. Therefore, the value should be kept by some other means if it is desired past the life of the dialog.

Example:

```

    object  dlg;
    char    *val;

    val = mCtlStringValue(dlg, PERSONS_NAME);

```

See also: **CtlShortValue**, **CtlLongValue**, ... **CtlValue**

CtlUnsignedShortValue::Dialog

[CtlUnsignedShortValue]

```

    val = mCtlUnsignedShortValue(dlg, id);

    object  dlg;    /* a dialog object */
    unsigned id;    /* control id      */
    unsigned short val; /* control value  */

```

This method is used to gain access to the value associated with a particular control as a C unsigned short. For example, if the control was a numeric control and the user entered “6”, then this method would return a unsigned short “6”.

mCtlLongValue should be used for date controls.

Example:

```
object dlg;
unsigned short val;

val = mCtlUnsignedShortValue(dlg, PERSONS_AGE);
```

See also: `CtlStringValue`, `CtlLongValue`, ... `CtlValue`

`CtlValue::Dialog`

[`CtlValue`]

```
val = mCtlValue(dlg, id);

object dlg;    /* a dialog object */
unsigned id;   /* control id      */
object val;    /* control value   */
```

This method is used to gain access to the value associated with a particular control as a Dynace object. For example, if the control was a text control and user entered “Miami”, then this method would return a Dynace string object (not a normal C string) which represents the value typed in. This returned value may be used and accessed like any other Dynace object using the appropriate interface mechanism.

If the control being accessed is a list box or combo box, the value returned will be a representation of the text associated with the choice made by the user. See `IndexValue` or `CtlShortValue` to get a numeric representation for this control type.

The object returned will be automatically disposed when the dialog is disposed, therefore, a copy (via `gCopy`) should be made of it if its existence is required subsequent to the dialog’s disposal.

WDS also provides several methods to obtain normal C data types directly.

Example:

```
object dlg, val;

val = mCtlValue(dlg, PERSONS_NAME);
```

See also: `CtlStringValue`, `CtlShortValue`, `CtlLongValue`, ...

`DeepDispose::Dialog`

[`DeepDispose`]

This method performs the same function as `Dispose`. See that method for details.

Disable::Dialog

[Disable]

```
r = gDisable(dlg);

object dlg; /* a dialog object */
object r;   /* the dialog obj  */
```

This method is used to disable the dialog window, preventing user input. A disabled dialog will not respond to mouse or keyboard events until it is re-enabled with **gEnable**.

The value returned is the dialog object passed.

Example:

```
object dlg;

gDisable(dlg);
```

See also: **Enable**

DisableAll::Dialog

[DisableAll]

```
r = gDisableAll(dlg);

object dlg; /* a dialog object */
object r;   /* the dialog obj  */
```

This method is used to disable all controls contained within the dialog, preventing user input to any of them. Individual controls or all controls can be re-enabled with **gEnableAll**.

The value returned is the dialog object passed.

Example:

```
object dlg;

gDisableAll(dlg);
```

See also: **EnableAll**

Dispose::Dialog

[Dispose]

```
r = gDispose(dlg);

object dlg; /* a dialog object */
object r;   /* NULL           */
```

This method is used to remove and dispose of a dialog object when it is no longer needed. This method should be called on all dialogs when they are no longer needed. In addition to disposing of the dialog, this method will also dispose of all the control objects associated with the dialog.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object dlg;

dlg = gDispose(dlg);
```

See also: `AutoDispose`

Enable::Dialog

[Enable]

```
r = gEnable(dlg);

object dlg; /* a dialog object */
object r;   /* the dialog obj  */
```

This method is used to enable the dialog window for user input. A dialog that has been previously disabled with `gDisable` can be re-enabled with this method.

The value returned is the dialog object passed.

Example:

```
object dlg;

gEnable(dlg);
```

See also: `Disable`

EnableAll::Dialog

[EnableAll]

```
r = gEnableAll(dlg);

object dlg; /* a dialog object */
object r;   /* the dialog obj  */
```

This method is used to enable all controls contained within the dialog. This is useful for re-enabling all controls after a previous call to `gDisableAll`.

The value returned is the dialog object passed.

Example:

```
object dlg;

gEnableAll(dlg);
```

See also: `DisableAll`

GetBackBrush::Dialog

[GetBackBrush]

```
brsh = gGetBackBrush(dlg);

object dlg; /* dialog object */
object brsh; /* brush object */
```

This method is used to obtain the background brush object which has been associated with the dialog. If no specific background brush was associated with the dialog this method will return the application default background brush, which is what the dialog uses when no specific brush is specified.

Example:

```
object dlg, brsh;

brsh = gGetBackBrush(dlg);
```

See also: `BackBrush`, `GetTextBrush`, `GetBackBrush::Application`

GetControl::Dialog

[GetControl]

```

    ctl = mGetControl(dlg, id);

    object  dlg;    /* a dialog object */
    unsigned id;    /* control id      */
    object  ctl;    /* control object */

```

This method is used to gain access to a control object which has been previously associated with a particular control via its associated control id. The control object is returned.

Example:

```

    object  dlg, ctl;

    ctl = mGetControl(dlg, PERSONS_NAME);

```

See also: AddControl

GetParent::Dialog

[GetParent]

```

    prnt = gGetParent(dlg);

    object  dlg;    /* dialog object      */
    object  prnt;    /* parent window object */

```

This method is used to obtain the parent window object associated with dialog `dlg`. This parent window would have established when the dialog object was created.

Example:

```

    object  dlg, parentWind;

    parentWind = gGetParent(dlg);

```

See also: NewDialog::ModalDialog, NewDialog::ModelessDialog

GetPosition::Dialog

[GetPosition]

```

    r = gGetPosition(dlg, y, x);

    object  dlg;    /* a dialog object      */
    int     *y;     /* vertical position    */
    int     *x;     /* horizontal position  */
    object  r;      /* the dialog obj       */

```

This method is used to obtain the current screen position of the dialog. The position is returned in the current scaling mode through the `y` and `x` pointer arguments.

The value returned is the dialog object passed.

Example:

```
object  dlg;
int     yPos, xPos;

gGetPosition(dlg, &yPos, &xPos);
```

See also: `GetSize`

`GetResourceID::Dialog`

[`GetResourceID`]

```
r = gGetResourceID(dlg);

object  dlg;  /* a dialog object */
unsigned r;   /* resource ID      */
```

This method is used to obtain the resource identifier associated with the dialog. The resource ID is the value used when the dialog was created.

The value returned is the dialog's resource identifier.

Example:

```
object  dlg;
unsigned id;

id = gGetResourceID(dlg);
```

`GetSize::Dialog`

[`GetSize`]

```
r = gGetSize(dlg, y, x);

object  dlg;  /* a dialog object */
int     *y;   /* vertical size */
int     *x;   /* horizontal size */
object  r;    /* the dialog obj */
```

This method is used to obtain the current size of the dialog. The size is returned in the current scaling mode through the `y` and `x` pointer arguments.

The value returned is the dialog object passed.

Example:

```
object  dlg;
int     height, width;

gGetSize(dlg, &height, &width);
```

See also: `GetPosition`

`GetTag::Dialog`

[`GetTag`]

```
r = gGetTag(dlg);

object  dlg;  /* dialog object */
object  r;    /* tag           */
```

This method is used to obtain a Dynace object which has been associated with a dialog via `SetTag`. The value return is the object which has been associated with the dialog object `dlg`. If there is no object associated with the dialog, `NULL` will be returned.

Example:

```
object  dlg, someObj;

someObj = gGetTag(dlg);
```

See also: `SetTag`, `SetTag::Window`

`GetTask::Dialog`

[`GetTask`]

```
r = gGetTask(dlg);

object  dlg;  /* a dialog object */
object  r;    /* Task object    */
```

This method is used to obtain the Task object associated with the dialog. If no Task has been associated, `NULL` is returned.

The value returned is the associated Task object or `NULL`.

Example:

```
object  dlg, task;

task = gGetTask(dlg);
```


See also: `SetTask`

`GetTextBrush::Dialog`

[`GetTextBrush`]

```
brsh = gGetTextBrush(dlg);

object dlg;    /* dialog object */
object brsh;   /* brush object  */
```

This method is used to obtain the text brush object which has been associated with the dialog. If no specific text brush was associated with the dialog this method will return the application default text brush, which is what the dialog uses when no specific brush is specified.

Example:

```
object dlg, brsh;

brsh = gGetTextBrush(dlg);
```

See also: `TextBrush`, `GetBackBrush`, `GetTextBrush::Application`

`GetTopic::Dialog`

[`GetTopic`]

```
r = gGetTopic(dlg);

object dlg;    /* a dialog object */
char *r;       /* help topic string */
```

This method is used to obtain the help topic string associated with the dialog. If no topic has been set, `NULL` is returned.

The value returned is a pointer to the help topic string or `NULL`.

Example:

```
object dlg;
char *topic;

topic = gGetTopic(dlg);
```

See also: `SetTopic`

Handle::Dialog

[Handle]

```

h = gHandle(dlg);

object  dlg;    /* dialog object */
HANDLE  h;      /* Windows handle */

```

This method is used to obtain the Windows internal handle associated with a dialog object. It will only return a valid handle while the dialog is being performed via **gPerform**. **NULL** will be returned otherwise.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```

object  dlg;
HANDLE  h;

h = gHandle(dlg);

```

IndexValue::Dialog

[IndexValue]

```

val = mIndexValue(dlg, id);

object  dlg;    /* a dialog object */
unsigned id;    /* control id */
object  val;    /* control value */

```

This method is used to gain access to a Dynace object (as opposed to a normal C integer) representing the value associated with a list box or combo box in terms of an ordinal value. This value returned is a zero based index from top to bottom indicating the selection made by the user. If no selection was made the object will represent a negative value. This returned value may be used and accessed like any other Dynace object using the appropriate interface mechanisms.

The object returned will be automatically disposed when the dialog is disposed, therefore, a copy (via **gCopy**) should be made of it if its existence is required subsequent to the dialog's disposal.

WDS also provides several methods to obtain normal C data types directly.

Example:

```

object  dlg, val;

val = mIndexValue(dlg, SOME_LISTBOX);

```

See also: `CtlShortValue`, `CtlValue`

`InDialog::Dialog`

[InDialog]

```
flg = gInDialog(dlg);

object  dlg;    /* a dialog object */
int     flg;    /* in dialog flag   */
```

This method is used to determine whether a given dialog is currently being “performed” via `gPerform`. Prior and subsequent to performing a dialog this method will return 0. A 1 will be returned if the dialog is currently being performed.

Example:

```
object  dlg;
int     flg;

flg = gInDialog(dlg);
```

See also: `Perform`

`Message::Dialog`

[Message]

```
r = gMessage(dlg, msg);

object  dlg;    /* dialog object */
char    *msg;    /* message      */
object  r;       /* dialog object */
```

This method is used to open up a temporary informational window. The window will contain the message given by `msg` and the user must acknowledge the window prior to continuing by hitting an OK button.

This method may only be used either while the dialog is being performed or at any time if it has an associated parent window.

The value returned is the dialog passed.

Example:

```
object  dlg;

gMessage(dlg, "Press OK to continue.");
```

See also: `MessageWithTopic`

MessageWithTopic::Dialog

[MessageWithTopic]

```

    r = gMessageWithTopic(dlg, msg, tpc);

    object  dlg;    /* dialog object */
    char    *msg;   /* message      */
    char    *tpc;   /* help topic   */
    object  r;      /* dialog object */

```

This method is used to open up a temporary informational dialog. The dialog will contain the message given by `msg` and the user must acknowledge the dialog prior to continuing by hitting an OK button.

If the user hits the F1 key while presented with the message, the help topic identified by `tpc` will get displayed via the Windows help system.

This method may only be used either while the dialog is being performed or at any time if it has an associated parent window.

The value returned is the dialog passed.

Example:

```

    object  dlg;

    gMessageWithTopic(dlg, "Press OK to continue.", "mytopic");

```

See also: `Message` and the `HelpSystem` class.

MoveToTop::Dialog

[MoveToTop]

```

    r = gMoveToTop(dlg);

    object  dlg;    /* a dialog object */
    object  r;      /* the dialog obj  */

```

This method is used to bring the dialog to the top of the Z-order, making it the foremost window. This is a convenience method equivalent to calling `gSetZOrder` with `HWND_TOP`.

The value returned is the dialog object passed.

Example:

```

    object  dlg;

    gMoveToTop(dlg);

```

See also: `SetZOrder`

`Perform::Dialog`

[Perform]

```
r = gPerform(dlg);

object dlg;    /* a dialog object */
int     r;     /* result          */
```

Once a dialog is created and fully specified, this method is used to actually display the dialog and allow the user to interact with it. The dialog will remain active until the user pushes the push buttons with the label `IDOK` or `IDCANCEL`.

What occurs after calling `gPerform` depends on whether the dialog was a modal or modeless dialog.

Control initial values should be set prior to calling `gPerform`.

MODAL DIALOGS

If the dialog being performed is a modal, then once `gPerform` is evoked the user will be able to interact with the dialog and `gPerform` will not return until the user either accepts or aborts the entire dialog. This, in effect, will prevent the user from switching to any other window or dialog within the application until the dialog is completed.

Finally, the value returned by `gPerform` will be the Windows constant `FALSE` if the user canceled the dialog, the Windows constant `TRUE` if the user accepted the dialog, or the value returned by any completion function which was attached to the dialog (via `CompletionFunction`).

Once `gPerform` returns, the dialog object may be queried in order to obtain the final values associated with each control.

Unless the auto dispose feature is manually set for a modal dialog, the dialog object is not automatically disposed and must be when no longer needed.

MODELESS DIALOGS

Modeless dialogs operate different from modal dialogs. When `gPerform` is evoked on a modeless dialog, `gPerform` returns immediately with a 0 value. At that point the user is presented with the dialog and allowed to edit it. During that time your program would typically return to the menu and wait for further user selections. The user may continue with the current dialog, abort it, or switch to another window within the application with the ability to return at any point. All the user interaction is automatically handled by Windows and WDS.

Since the application code has gone on about its business after a call to `gPerform` two things are left to be completed whenever the user finally accepts or aborts the dialog. First, the application will typically want to do something with the data the user has entered on the dialog. And second, the dialog object will need to be disposed when it's no longer needed.

When using modeless dialogs the programmer normally attaches a completion function to the dialog via `gCompletionFunction`. What this does is cause the completion function to be executed whenever the user accepts or aborts the dialog. This application specific function can be used to perform the final processing of the dialog's data. See `gCompletionFunction` for complete details.

By default, the auto dispose flag associated with modeless dialogs is normally enabled. This causes WDS to automatically dispose of a dialog object and all associated controls immediately subsequent to executing the completion function. This way everything is cleaned up automatically. This feature may be disabled via `gAutoDispose`, in which case the application must be sure to dispose of the unneeded object.

Example:

```
object  dlg;
int     r;

r = gPerform(dlg);
```

See also: `CompletionFunction`, `AutoDispose`

`PressButton::Dialog`

[`PressButton`]

```
r = gPressButton(dlg, id);

object  dlg;  /* a dialog object */
unsigned id;  /* button control id */
object  r;    /* the dialog obj  */
```

This method is used to programmatically simulate clicking a button control within the dialog. The `id` argument identifies the button by its resource id. If no button with the given `id` is found, `NULL` is returned.

The value returned is the dialog object passed, or `NULL` if the button was not found.

Example:

```
object  dlg;

gPressButton(dlg, IDOK);
```

SetCursor::Dialog

[SetCursor]

```
r = gSetCursor(dlg, cursor);

object  dlg;      /* a dialog object */
object  cursor;   /* cursor object   */
object  r;        /* the dialog obj  */
```

This method is used to set the cursor for the dialog and all of its controls. Pass `NULL` for `cursor` to restore the default cursor.

The value returned is the dialog object passed.

Example:

```
object  dlg, cur;

gSetCursor(dlg, cur);
gSetCursor(dlg, NULL); /* restore default */
```

See also: `WaitCursor`

SetFocus::Dialog

[SetFocus]

```
r = gSetFocus(dlg);

object  dlg; /* a dialog object */
object  r;   /* the dialog obj  */
```

This method is used to set the keyboard input focus to the dialog window. This is useful when the dialog needs to regain focus after another window has been activated.

The value returned is the dialog object passed.

Example:

```
object  dlg;

gSetFocus(dlg);
```

SetResult::Dialog

[SetResult]

```
r = gSetResult(dlg, obj);

object  dlg; /* a dialog object */
object  obj; /* result object   */
object  r;   /* dlg             */
```

This method is used to associate a Dynace short integer object with a dialog such that when the dialog is completed or canceled by the user, the associated object will be set to the dialog's result value. This feature is most often needed in conjunction with modeless dialogs and the auto dispose feature. It can be used to find out what happened to a dialog subsequent to the dialog object being disposed.

The object associated with the dialog will never be disposed by WDS and must be manually disposed when it is no longer needed.

Example:

```
object dlg, obj;

gSetResult(dlg, obj = gNewWithInt(ShortInteger, -1));
```

See also: `AutoDispose`, `Perform`, `SetTag`

`SetState::Dialog`

[`SetState`]

```
r = gSetState(dlg, state);

object dlg;    /* a dialog object */
int      state; /* show state      */
object r;      /* the dialog obj  */
```

This method is used to set the display state of the dialog window. The `state` argument uses the standard Windows show state constants such as `SW_SHOW`, `SW_HIDE`, `SW_MINIMIZE`, `SW_MAXIMIZE`, and `SW_RESTORE`.

The value returned is the dialog object passed.

Example:

```
object dlg;

gSetState(dlg, SW_HIDE);
```

`SetTag::Dialog`

[`SetTag`]

```
r = gSetTag(dlg, tag);

object dlg; /* a dialog object */
object tag; /* tag                */
object r;   /* previous tag       */
```

This method is used to associate an arbitrary Dynace object with a dialog object. This may later be retrieved via the `GetTag` method. Since WDS passes around the

dialog object to all `Dialog` methods this mechanism may be used to pass additional information with the dialog. And since Dynace treats all objects in a uniform manner, this information attached to the dialog may be arbitrarily complex.

WDS does not dispose of the tag when the dialog object is disposed. This method returns any previous object associated with the dialog or `NULL`.

Example:

```
object dlg;

gSetTag(dlg, gNewWithInt(ShortInteger, 17));
```

See also: `GetTag`, `SetTag::Window`

`SetTask::Dialog`

[SetTask]

```
r = gSetTask(dlg, task);

object dlg;    /* a dialog object */
object task;   /* Task object */
object r;      /* the dialog obj */
```

This method is used to associate a Task object with the dialog. The Task object can subsequently be retrieved with `gGetTask`.

The value returned is the dialog object passed.

Example:

```
object dlg, task;

gSetTask(dlg, task);
```

See also: `GetTask`

`SetTitle::Dialog`

[SetTitle]

```
r = gSetTitle(dlg, title);

object dlg;    /* a dialog object */
char *title;   /* new title string */
object r;      /* the dialog obj */
```

This method is used to set or change the text displayed in the dialog's title bar.

The value returned is the dialog object passed.

Example:

```
object dlg;

gSetTitle(dlg, "Customer Entry");
```

SetTopic::Dialog

[SetTopic]

```
pt = gSetTopic(dlg, tpc);

object dlg;    /* dialog object */
char *tpc;     /* help topic */
char *pt;      /* previous help topic */
```

This method is used to associate help text with dialog `dlg`. The help text is defined using the Windows help system and labeled with the topic indicated by `tpc`. Then, if the user hits the F1 key while in the dialog, WDS will automatically bring up the Windows help system and find the indicated topic.

WDS also supports window and control specific topics. See the appropriate sections.

This method returns any previous topic associated with the dialog.

Example:

```
object dlg;

gSetTopic(dlg, "myDialogHelp");
```

See also: The `HelpSystem` class and `SetTopic::Control`

SetZOrder::Dialog

[SetZOrder]

```
r = gSetZOrder(dlg, m);

object dlg;    /* a dialog object */
HWND m;        /* Z-order flag */
object r;      /* the dialog obj */
```

This method is used to set the Z-order position of the dialog window. The `m` argument specifies the position and can be one of the standard Windows constants such as `HWND_TOP`, `HWND_TOPMOST`, `HWND_BOTTOM`, or `HWND_NOTOPMOST`.

The value returned is the dialog object passed.

Example:

```
object dlg;

gSetZOrder(dlg, HWND_TOPMOST);
```

See also: `MoveToTop`

`TextBrush::Dialog`

[`TextBrush`]

```
r = gTextBrush(dlg, brsh);

object dlg;    /* a dialog object */
object brsh;   /* brush object    */
object r;      /* dlg              */
```

This method is used to set the brush object which is used for foreground text which is displayed. Any previously associated brush object will be disposed. This brush object will also be automatically disposed when the dialog is disposed.

The dialog passed is returned.

Example:

```
object dlg;

gTextBrush(dlg, vNew(SolidBrush, 255, 0, 0));
```

See also: `BackBrush`, `SetTextBrush::Application` and the `Brush` classes

`Update::Dialog`

[`Update`]

```
r = gUpdate(dlg);

object dlg;    /* a dialog object */
object r;      /* the dialog obj  */
```

This method causes all controls in the dialog to push their current values to their associated data objects. This is useful when you need to transfer control values to the underlying data without closing the dialog.

The value returned is the dialog object passed.

Example:

```
object dlg;

gUpdate(dlg);
```

UseDefault::Dialog

[UseDefault]

```
r = gUseDefault(dlg);

object dlg; /* a dialog object */
object r;   /* the dialog obj  */
```

This method is used to reset all controls in the dialog to their default values.

The value returned is the dialog object passed.

Example:

```
object dlg;

gUseDefault(dlg);
```

WaitCursor::Dialog

[WaitCursor]

```
r = gWaitCursor(dlg, wait);

object dlg; /* a dialog object */
int    wait; /* 1=show, 0=hide */
object r;   /* the dialog obj  */
```

This method is used to show or hide the hourglass (wait) cursor for the dialog. A reference counting mechanism is used so that nested calls work correctly — each call with `wait` set to 1 must be balanced by a corresponding call with `wait` set to 0.

The value returned is the dialog object passed.

Example:

```
object dlg;

gWaitCursor(dlg, 1);
/* long operation */
gWaitCursor(dlg, 0);
```

See also: `SetCursor`

4.8.3 Modal Dialogs

Modal dialogs are created with the methods described in this section. However, since the `ModalDialog` class is a subclass of `Dialog`, and the `Dialog` class implements all the functionality common to both the `ModalDialog` and `ModelessDialog` classes, the majority of the functionality is inherited from and documented in the `Dialog` class. Therefore, see the `Dialog` class for documentation on additional functionality available to this class.

`NewDialog::ModalDialog`

[`NewDialog`]

```
dlg = mNewDialog(ModalDialog, id, wnd);
```

```
unsigned id; /* dialog id */
object wnd; /* parent window */
object dlg; /* dialog object */
```

`mNewDialog` is a macro (defined in `dynwin.h`) that expands to a call to `gNewDialog` on the `Dialog` base class.

This method is used to create a new modal dialog. The dialog must have been previously laid out using the resource editor. The `id` is a macro generated by the resource editor while the programmer defines the dialog. This `id` uniquely identifies a particular dialog.

`wnd` allows the specification of the parent window object associated with the new dialog. This is an optional parameter and may be `NULL` if it not desired. If you do specify a parent window, the dialog will iconize when the window is iconized and will be disposed if the window is disposed.

The object returned represents the new dialog created and may be used to further control the dialog.

Example:

```
object wind, dlg;

dlg = mNewDialog(ModalDialog, MY_DIALOG, wind);
```

See also: `NewDialogStr`, `NewDialogFromFile`, `Perform::Dialog`,
`NewDialog::ModelessDialog`

`NewDialogStr::ModalDialog`

[`NewDialogStr`]

```
dlg = gNewDialogStr(ModalDialog, id, wnd);
```

```
char *id; /* dialog id */
object wnd; /* parent window */
object dlg; /* dialog object */
```

This method is used to create a new modal dialog. The dialog must have been previously laid out using the resource editor. The `id` is the string name associated with the dialog. This `id` uniquely identifies a particular dialog.

`wnd` allows the specification of the parent window object associated with the new dialog. This is an optional parameter and may be `NULL` if it not desired. If you do specify a parent window, the dialog will iconize when the window is iconized and will be disposed if the window is disposed.

The object returned represents the new dialog created and may be used to further control the dialog.

Example:

```
object wind, dlg;

dlg = gNewDialogStr(ModalDialog, "mydialog", wind);
```

See also: `NewDialog`, `NewDialogFromFile`, `Perform::Dialog`,
`NewDialogStr::ModelessDialog`

`NewDialogFromFile::ModalDialog`

[`NewDialogFromFile`]

```
dlg = gNewDialogFromFile(ModalDialog, file, res, wnd);

char      *file; /* CLD file name */
unsigned  res;   /* resource id   */
object    wnd;   /* parent window */
object    dlg;   /* dialog object  */
```

This method is used to create a new modal dialog from a CLD resource file rather than from a compiled Windows resource. `file` is the path to the CLD file and `res` is the resource identifier within that file.

`wnd` allows the specification of the parent window object associated with the new dialog. This is an optional parameter and may be `NULL` if it not desired.

The object returned represents the new dialog created and may be used to further control the dialog.

Example:

```
object wind, dlg;

dlg = gNewDialogFromFile(ModalDialog, "dialogs.cld", 100, wind);
```

See also: `NewDialog`, `NewDialogStr`, `Perform::Dialog`

4.8.4 Modeless Dialogs

Modeless dialogs are created with the methods described in this section. However, since the `ModelessDialog` class is a subclass of `Dialog`, and the `Dialog` class implements all the functionality common to both the `ModalDialog` and `ModelessDialog` classes, the majority of the functionality is inherited from and documented in the `Dialog` class. Therefore, see the `Dialog` class for documentation on additional functionality available to this class.

`NewDialog::ModelessDialog`

[`NewDialog`]

```
dlg = mNewDialog(ModelessDialog, id, wnd);
```

```
unsigned id;    /* dialog id      */
object  wnd;    /* parent window */
object  dlg;    /* dialog object  */
```

`mNewDialog` is a macro (defined in `dynwin.h`) that expands to a call to `gNewDialog` on the `Dialog` base class.

This method is used to create a new modeless dialog. The dialog must have been previously laid out using the resource editor. The `id` is a macro generated by the resource editor while the programmer defines the dialog. This `id` uniquely identifies a particular dialog.

`wnd` allows the specification of the parent window object associated with the new dialog. This is an optional parameter and may be `NULL` if it not desired. If you do specify a parent window, the dialog will iconize when the window is iconized and will be disposed if the window is disposed.

When a new modeless dialog is created, its auto dispose mode is enabled. This means that, unless disabled, the object representing the dialog will be automatically disposed when the user closes the window. This is done due to the independent nature of modeless dialogs and the need to be sure that objects no longer needed are disposed. Note that the programmer may specify a function which gets executed prior to the disposal of a modeless dialog in order to capture any data.

The object returned represents the new dialog created and may be used to further control the dialog.

Example:

```
object wind, dlg;
```

```
dlg = mNewDialog(ModelessDialog, MY_DIALOG, wind);
```

See also: `NewDialogStr`, `NewDialogFromFile`, `Perform::Dialog`,
`NewDialog::ModalDialog`, `CompletionFunction::Dialog`,
`AutoDispose::Dialog`

NewDialogStr::ModelessDialog

[NewDialogStr]

```
dlg = gNewDialogStr(ModelessDialog, id, wnd);
```

```
char      *id;  /* dialog id      */
object    wnd;  /* parent window */
object    dlg;  /* dialog object  */
```

This method is used to create a new modeless dialog. The dialog must have been previously laid out using the resource editor. The *id* is the string name associated with the dialog. This *id* uniquely identifies a particular dialog.

wnd allows the specification of the parent window object associated with the new dialog. This is an optional parameter and may be `NULL` if it not desired. If you do specify a parent window, the dialog will iconize when the window is iconized and will be disposed if the window is disposed.

When a new modeless dialog is created, its auto dispose mode is enabled. This means that, unless disabled, the object representing the dialog will be automatically disposed when the user closes the window. This is done due to the independent nature of modeless dialogs and the need to be sure that objects no longer needed are disposed. Note that the programmer may specify a function which gets executed prior to the disposal of a modeless dialog in order to capture any data.

The object returned represents the new dialog created and may be used to further control the dialog.

Example:

```
object  wind, dlg;

dlg = gNewDialogStr(ModelessDialog, "mydialog", wind);
```

See also: `NewDialog`, `NewDialogFromFile`, `Perform::Dialog`,
`NewDialogStr::ModalDialog`, `CompletionFunction::Dialog`,
`AutoDispose::Dialog`

NewDialogFromFile::ModelessDialog

[NewDialogFromFile]

```
dlg = gNewDialogFromFile(ModelessDialog, file, res, wnd);
```

```
char      *file;  /* CLD file name */
unsigned  res;    /* resource id    */
object    wnd;    /* parent window  */
object    dlg;    /* dialog object   */
```


This method is used to create a new modeless dialog from a CLD resource file rather than from a compiled Windows resource. **file** is the path to the CLD file and **res** is the resource identifier within that file.

wnd allows the specification of the parent window object associated with the new dialog. This is an optional parameter and may be **NULL** if it not desired.

When a new modeless dialog is created, its auto dispose mode is enabled. This means that, unless disabled, the object representing the dialog will be automatically disposed when the user closes the window.

The object returned represents the new dialog created and may be used to further control the dialog.

Example:

```
object wind, dlg;

dlg = gNewDialogFromFile(ModelessDialog, "dialogs.cld", 100, wind);
```

See also: `NewDialog`, `NewDialogStr`, `Perform::Dialog`,
`CompletionFunction::Dialog`, `AutoDispose::Dialog`

4.9 Controls

The `Control` class is never used directly. It is used to group functionality common to all the control types which are all subclasses of this class. Therefore, this section documents all the methods which are accessible to all subclasses of this class.

Control instances are normally created via `AddControl::Dialog` and may be subsequently accessed via `GetControl::Dialog`.

4.9.1 Standard Control Method Arguments

Since all control instance methods have the control object as their first argument (referred to as `ctl`), this argument will not be described each time. It always refers to the control object which you wish to perform the desired operation on. Each control object will be an instance of one of the subclasses of the `Control` class (such as `TextControl` or `NumericControl`).

Many of the methods associated with this class take an argument identified as `id`. This is a macro defined by the programmer via the resource editor when the dialog is being defined and is used to uniquely identify a particular control within the dialog. Due to the fact that this argument has the same meaning for every method which uses it, it will not be defined each time.

4.9.2 Control Methods

AddHandlerAfter::Control

[AddHandlerAfter]

```

r = gAddHandlerAfter(ctl, msg, func);

object   ctl;      /* a control object */
unsigned msg;      /* message          */
long     (*func)(); /* function pointer */
object   r;        /* the control obj  */

```

This method is inherited from the `Window` class.

This method is used to associate function `func` with Windows control message `msg` for control `ctl`. Whenever control `ctl` receives message `msg`, `func` will be called.

`ctl` is the control object who's messages you wish to process. `msg` is the particular message you wish to trap. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with `WM_`.

`func` is the function which gets called whenever the specified message gets received and takes the following form:

```

long     func(object   ctl,
                  HWND   hwnd,
                  UINT   mMsg,
                  WPARAM wParam,
                  LPARAM lParam)
{
    .
    .
    .
    return 0L; /* or whatever is appropriate */
}

```

Where `ctl` is the control being sent the message. The remaining arguments and return value is fully documented in the Windows documentation under the `WindowProc` function and the Windows Messages documentation.

WDS keeps a list of functions associated with each message associated with each control. When a particular message is received the appropriate list of handler functions gets executed sequentially. **AddHandlerAfter** appends the new function to the end of this list, and **AddHandlerBefore** adds the new function to the beginning of the list.

WDS may also, and optionally, execute the Windows default procedure associated with a given message either before or after the user added list of functions. This behavior may be controlled via `DefaultProcessingMode`.

Windows will only see the return value of the last message handler executed including, if applicable, the default.

Example:

```
int      hSize, vSize;

static long  process_wm_size(object ctl,
                                HWND   hwnd,
                                UINT    mMsg,
                                WPARAM  wParam,
                                LPARAM  lParam)
{
    hSize = LOWORD(lParam);
    vSize = HIWORD(lParam);
    return 0L;
}

.
.
gAddHandlerAfter(ctl, (unsigned) WM_SIZE, process_wm_size);
.
.
```

See also: `DefaultProcessingMode`, `AddHandlerBefore`, `CallDefaultProc`

`AddHandlerBefore::Control`

[`AddHandlerBefore`]

```
r = gAddHandlerBefore(ctl, msg, func);

object  ctl;      /* a control object */
unsigned msg;     /* message          */
long    (*func)(); /* function pointer */
object  r;        /* the control obj  */
```

This method is inherited from the `Window` class. It is fully documented under `AddHandlerAfter`.

See also: `AddHandlerAfter`

`AutoAttach::Control`

[`AutoAttach`]

```
prev = gAutoAttach(ctl, mode);

object  ctl;      /* control object */
int     mode;     /* auto-attach mode (0 or 1) */
int     prev;     /* previous mode    */
```

This method sets whether the control automatically attaches to associated database fields. A non-zero `mode` enables auto-attach; zero disables it.

The value returned is the previous auto-attach mode.

`CallDefaultProc::Control`

[`CallDefaultProc`]

```
r = gCallDefaultProc(ctl, msg, wp, lp)

object  ctl;    /* a control object */
unsigned msg;   /* message           */
WPARAM  wp;     /* wParam value      */
LPARAM  lp;     /* lParam value      */
long     r;     /* result of call    */
```

This method is inherited from the `Window` class.

This method is used to explicitly call the default Windows message handler associated with message `msg`. This method is normally called from within a programmer defined message handler (see `AddHandlerAfter`) which is provided with the `wp` and `lp` parameters. These parameters are fully documented in the Windows Messages documentation and relate directly to the particular message.

`msg` is the particular message you wish to affect. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with `WM_`.

Example:

```
gCallDefaultProc(ctl, msg, wParam, lParam);
```

See also: `DefaultProcessingMode`, `AddHandlerAfter`

`CheckFunction::Control`

[`CheckFunction`]

```
r = gCheckFunction(ctl, fun);

object  ctl;    /* control object */
int      (*fun)(); /* check function */
object  r;      /* ctl object      */
```

This method is implemented by all control subclasses (not in the `Control` base class itself).

This method is used to associate an auxiliary checking function to a control. When a dialog is accepted, WDS goes through each control to assure the validity of the data associated with each control as defined by the control object. The ability to associate an additional function for validating the data associated with a control gives

the programmer the ability to perform any additional application specific checking against a control's data.

The auxiliary checking function takes the following form:

```
int      fun(object ctl, object val, char *buf)
{
    ....
}
```

Where `ctl` is the control object, and `val` is a Dynace object which represents the value the control has associated with it. `buf` is a pointer to a buffer area which `fun` must set to an appropriate error message if an error occurs. `fun` returns a 1 if an error occurs and 0 otherwise.

All controls support this feature except the `PushButton` class, because it is an immediate action control with no associated value.

Example:

```
object  ctl;

gCheckFunction(ctl, fun);
```

See also: `GetControl::Dialog`

`CheckValue::Control`

[`CheckValue`]

```
r = gCheckValue(ctl)

object  ctl;  /* a control object */
int      r;    /* result of call   */
```

This method is used to explicitly cause all error checking functions and parameters associated with control `ctl` to be checked. If an error is encountered an appropriate error message will be displayed and a 1 will be returned. If no error is encountered a 0 is returned.

This method is implemented by all subclasses of `Control` and mainly used internally when the dialog is accepted.

Example:

```
gCheckValue(ctl);
```

See also: `CheckFunction::Control`

DeepDispose::Control

[DeepDispose]

This method performs the same function as **Dispose**. See that method for details.

DefaultProcessingMode::Control

[DefaultProcessingMode]

```

r = gDefaultProcessingMode(ctl, msg, mode);

object   ctl;    /* a control object          */
unsigned msg;    /* message                      */
int      mode;   /* default processing mode      */
object   r;      /* the control obj              */

```

This method is inherited from the **Window** class.

This method is used to determine when or if the Windows default message procedure is processed for a given message (**msg**) associated with a particular control (**ctl**).

WDS allows a programmer to specify an arbitrary number of functions to be executed whenever a control receives a specific message (via **AddHandlerAfter** and **AddHandlerBefore**). Windows has default procedures associated with many control messages. At times it is necessary to replace or augment this default functionality. **DefaultProcessingMode** gives the programmer control over when and if this default Windows functionality. **mode** is used to specify the desired mode. The following table indicates the valid modes:

- | | |
|---|--|
| 0 | Do not execute the Windows default processing |
| 1 | Execute default processing <i>after</i> programmer defined handlers |
| 2 | Execute default processing <i>before</i> programmer defined handlers |

Note that the default mode is always 1, and must be explicitly changed, if desired, for each message associated with each control.

msg is the particular message you wish to affect. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with **WM_**.

Example:

```
gDefaultProcessingMode(ctl, (unsigned) WM_SIZE, 0);
```

See also: **CallDefaultProc**, **AddHandlerAfter**

Disable::Control

[Disable]

```
r = gDisable(ctl);

object  ctl;  /* control object */
object  r;    /* ctl           */
```

This method disables the control, graying it out so the user cannot interact with it.

The value returned is the control object passed.

Display::Control

[Display]

```
r = gDisplay(ctl);

object  ctl;  /* control object */
object  r;    /* ctl           */
```

This method shows a previously hidden control, making it visible again.

The value returned is the control object passed.

See also: Hide

Dispose::Control

[Dispose]

```
r = gDispose(ctl);

object  ctl;  /* a control object */
object  r;    /* NULL           */
```

This method is used to remove and dispose of a control object when it is no longer needed. This method is rarely needed due to the fact that when a dialog is disposed it automatically calls this method on each of its associated controls.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object  ctl;

ctl = gDispose(ctl);
```

See also: DeepDispose

Enable::Control

[Enable]

```
r = gEnable(ctl);

object  ctl;  /* control object */
object  r;    /* ctl           */
```

This method enables the control, making it active and available for user interaction. The control may remain disabled if security restrictions are in effect.

The value returned is the control object passed.

GetFont::Control

[GetFont]

```
font = gGetFont(ctl);

object  ctl;  /* control object */
object  font; /* Font object or NULL */
```

This method returns the **Font** object associated with the control, or **NULL** if no font has been set.

See also: **SetFont**

GetResourceID::Control

[GetResourceID]

```
id = gGetResourceID(ctl);

object  ctl;  /* control object */
unsigned id;  /* resource identifier */
```

This method returns the resource identifier associated with the control.

GetTabOrder::Control

[GetTabOrder]

```
t = gGetTabOrder(ctl);

object  ctl;  /* control object */
int     t;    /* tab order index */
```

This method returns the current tab order index for the control.

See also: **SetTabOrder**

Handle::Control

[Handle]

```
h = gHandle(ctl);

object  ctl;    /* control object */
HANDLE  h;      /* Windows handle */
```

This method is inherited from the `Window` class.

This method is used to obtain the Windows internal handle associated with a control object. It will only return a valid handle while the dialog is being performed via `gPerform`. `NULL` will be returned otherwise.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```
object  ctl;
HANDLE  h;

h = gHandle(ctl);
```

See also: `GetControl::Dialog`

Hide::Control

[Hide]

```
r = gHide(ctl);

object  ctl;    /* control object */
object  r;      /* ctl          */
```

This method hides the control so that it is not visible on the dialog.

The value returned is the control object passed.

See also: `Display`

SetFocus::Control

[SetFocus]

```
r = gSetFocus(ctl);

object  ctl;    /* control object */
object  r;      /* ctl          */
```

This method sets the keyboard focus to the specified control.

The value returned is the control object passed.

SetFont::Control

[SetFont]

```
r = gSetFont(ctl, font);
```

```
object  ctl;    /* control object */
object  font;   /* Font object    */
object  r;      /* ctl                */
```

This method sets the display font used by the control.

The value returned is the control object passed.

See also: **GetFont**

SetName::Control

[SetName]

```
r = gSetName(ctl, name);
```

```
object  ctl;    /* control object */
char    *name;  /* control name   */
object  r;      /* ctl            */
```

This method sets the name of the control. The name is used for programmatic lookup of controls within a dialog.

The value returned is the control object passed.

SetTabOrder::Control

[SetTabOrder]

```
prev = gSetTabOrder(ctl, t);
```

```
object  ctl;    /* control object */
int      t;      /* tab order index */
int      prev;   /* previous index   */
```

This method sets the tab order index for the control. The tab order determines the sequence in which controls receive focus when the user presses the Tab key.

The value returned is the previous tab order index.

See also: **GetTabOrder**

SetTopic::Control

[SetTopic]

```

    pt = gSetTopic(ctl, tpc);

    object  ctl;    /* control object      */
    char    *tpc;   /* help topic        */
    char    *pt;    /* previous help topic */

```

This method is inherited from the `Window` class.

This method is used to associate help text with specific control `ctl`. The help text is defined using the Windows help system and labeled with the topic indicated by `tpc`. Then, if the user hits the F1 key while in the control, WDS will automatically bring up the Windows help system and find the indicated topic. If no control specific help is specified, WDS will use any help associated with the dialog as a whole.

WDS also supports dialog and control specific topics. See the appropriate sections.

This method returns any previous topic associated with the control.

Example:

```

    object  ctl;

    gSetTopic(ctl, "myControlHelp");

```

See also: The `HelpSystem` class and `SetTopic::Dialog`

Update::Control

[Update]

```

    r = gUpdate(ctl);

    object  ctl; /* control object */
    object  r;   /* ctl           */

```

This method pushes the control's current value to its associated data object.

The value returned is the control object passed.

UseDefault::Control

[UseDefault]

```

    r = gUseDefault(ctl);

    object  ctl; /* control object */
    object  r;   /* ctl           */

```

This method resets the control to its default value.

The value returned is the control object passed.

4.9.3 Text Control

The `TextControl` class is a control which enables the user to enter arbitrary alphanumeric data on a single line. This control has numerous facilities to control the length and type of input the user is allowed to enter.

The `TextControl` class is a subclass of `Control` and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled “Standard Control Method Arguments”.

`Attach::TextControl`

[Attach]

```
r = gAttach(ctl, val);

object  ctl;  /* control object */
object  val;  /* ctl value      */
object  r;    /* control object */
```

This method is used to associate an independent Dynace object with the value associated with a control object. `val` should be an instance of the `String` class and will be automatically updated to reflect the value associated with the control.

This object (`val`) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control’s value after the life of the control. It is the programmer’s responsibility to dispose of the object when it is no longer needed.

Example:

```
object  ctl, val;

val = gNew(String);
gAttach(ctl, val);
```

See also: `Value`, `StringValue`, `SetValue`

`Capitalize::TextControl`

[Capitalize]

```
r = gCapitalize(ctl);

object  ctl;  /* control object */
object  r;    /* control object */
```

This method is used to enable the auto-capitalize feature of the text control. If enabled, all alpha entry made by the user will be converted to upper case both on the display and internally to the control.

Example:

```
object   ctl;

gCapitalize(ctl);
```

See also: `TextRange`

`GetMinLength::TextControl`

[`GetMinLength`]

```
len = gGetMinLength(ctl);

object   ctl; /* control object */
int      len; /* minimum input length */
```

This method returns the minimum required input length for the control.

See also: `MinLength`

`HideData::TextControl`

[`HideData`]

```
prev = gHideData(ctl, flag);

object   ctl; /* control object */
int      flag; /* hide data flag */
int      prev; /* previous flag */
```

This method sets whether the data displayed in the control is hidden. A non-zero `flag` hides the data; zero shows it.

The value returned is the previous hide data flag.

`MaxLength::TextControl`

[`MaxLength`]

```
r = gMaxLength(ctl, len);

object   ctl; /* control object */
int      len; /* maximum length */
object   r;   /* control object */
```

This method is used to set the maximum number of characters the user may enter into a text control. If the user attempts to enter more than `len` characters, including

spaces, the system will just beep. If the number of characters exceeds the field display width, the display will scroll.

Example:

```
object   ctl;

gMaxLength(ctl, 25);
```

See also: `MinLength`, `TextRange`, `Capitalize`, `CheckFunction::Control`

`MinLength::TextControl`

[`MinLength`]

```
r = gMinLength(ctl, len);

object   ctl;   /* control object */
int      len;   /* minimum length */
object   r;     /* control object */
```

This method is used to set the minimum number of characters the user must enter into a text control. If the user attempts to accept the dialog without entering `len` characters, including spaces, WDS will issue an error message and return the user to the incomplete field.

Example:

```
object   ctl;

gMinLength(ctl, 5);
```

See also: `MaxLength`, `TextRange`, `Capitalize`, `CheckFunction::Control`

`NewCtl::TextControl`

[`NewCtl`]

```
ctl = mNewCtl(TextControl, id);

unsigned id;   /* control id      */
object   ctl;  /* control object */
```

`mNewCtl` is a macro (defined in `dynwin.h`) that expands to a call to `vNew`.

This method is used to create a new control object to be identified as `id` (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use `AddControl::Dialog` to create controls and associate them to a dialog.

Example:

```
object   ctl;

ctl = mNewCtl(TextControl, PERSON_NAME);
```

See also: `AddControl::Dialog`, `GetControl::Dialog`

`PasswordFlag::TextControl`

[PasswordFlag]

```
flag = gPasswordFlag(ctl);

object   ctl;    /* control object */
int      flag;   /* current password flag */
```

This method returns the current password flag for the control.

See also: `SetPasswordFlag`

`Select::TextControl`

[Select]

```
r = gSelect(ctl);

object   ctl;    /* control object */
object   r;      /* ctl */
```

This method selects (highlights) all text in the control.

The value returned is the control object passed.

`SetMask::TextControl`

[SetMask]

```
r = gSetMask(ctl, mask);

object   ctl;    /* control object */
char     *mask;  /* input mask pattern or NULL */
object   r;      /* ctl */
```

This method sets an input mask pattern for the control. The mask defines the format of allowable input. For example, "(###) ###-####" would be used for a phone number field, where # represents a digit. Passing NULL clears the mask.

The value returned is the control object passed.

SetPasswordFlag::TextControl**[SetPasswordFlag]**

```

prev = gSetPasswordFlag(ctl, flag);

object  ctl;    /* control object */
int     flag;   /* password mode flag */
int     prev;   /* previous flag */

```

This method sets password entry mode for the control. When enabled (non-zero **flag**), characters typed by the user are displayed as asterisks.

The value returned is the previous password flag.

See also: PasswordFlag

SetStringValue::TextControl**[SetStringValue]**

```

r = gSetStringValue(ctl, val);

object  ctl;    /* control object */
char    *val;   /* ctl value */
object  r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. **val** should be a pointer to a character string which represents the desired value for the control.

Any previously associated value object will be disposed when the new value is set.

Example:

```

object  ctl;

gSetStringValue(ctl, "Some value");

```

See also: SetValue, StringValue

SetValue::TextControl**[SetValue]**

```

r = gSetValue(ctl, val);

object  ctl;    /* control object */
object  val;    /* ctl value */
object  r;      /* control object */

```


This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be a Dynace object which is an instance of the `String` class and initialized to the value desired for the control.

Any previously associated object will be disposed when the new value is set. Also, `val` will automatically be disposed when the control or associated dialog is disposed.

Example:

```
object ctl;

gSetValue(ctl, gNewWithStr(String, "Some value"));
```

See also: `SetStringValue`, `Value`, `Attach`

`StringValue::TextControl`

[`StringValue`]

```
val = gStringValue(ctl);

object ctl; /* control object */
char *val; /* ctl value */
```

This method is used to obtain a C character pointer which represents the value associated with the control. This pointer will not be valid after the control or associated dialog are disposed.

Example:

```
object ctl;
char *val;

val = gStringValue(ctl);
```

See also: `Value`, `Attach`, `SetStringValue`, `CtlStringValue::Dialog`

`TextRange::TextControl`

[`TextRange`]

```
r = gTextRange(ctl, min, max);

object ctl; /* control object */
int min; /* minimum length */
int max; /* maximum length */
object r; /* control object */
```

This method is used to set the minimum number of characters the user must enter into a text control as well as the maximum number of characters allowed.

If the user attempts to enter more than **max** characters, including spaces, the system will just beep. If the number of characters exceeds the field display width, the display will scroll.

If the user attempts to accept the dialog without entering **min** characters, including spaces, WDS will issue an error message and return the user to the incomplete field.

Example:

```
object   ctl;

gTextRange(ctl, 5, 25);
```

See also: `MaxLength`, `MinLength`, `Capitalize`, `CheckFunction::Control`

Value::TextControl

[Value]

```
val = gValue(ctl);

object   ctl;   /* control object */
object   val;   /* ctl value      */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the **String** class. This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object   ctl, val;

val = gValue(ctl);
```

See also: `StringValue`, `Attach`, `SetValue`

4.9.4 Numeric Control

The **NumericControl** class is a control which enables the user to enter arbitrary numeric data. This control has numerous facilities to control the range and type of input the user is allowed to enter.

The **NumericControl** class is a subclass of **Control** and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled “Standard Control Method Arguments”.

Attach::NumericControl

[Attach]

```

r = gAttach(ctl, val);

object  ctl;  /* control object */
object  val;  /* ctl value      */
object  r;    /* control object */

```

This method is used to associate an independent Dynace object with the value associated with a control object. **val** should be an instance of one of the Dynace numeric classes which are subclasses of the **Number** class, such as **ShortInteger** or **DoubleFloat**. This numeric object will be automatically updated to reflect the value associated with the control.

This object (**val**) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control's value after the life of the control. It is the programmer's responsibility to dispose of the object when it is no longer needed.

Example:

```

object  ctl, val;

val = gNewWithDouble(DoubleFloat, 0.0);
gAttach(ctl, val);

```

See also: **Value**, **DoubleValue**, **ShortValue**, **SetValue**

DoubleValue::NumericControl

[DoubleValue]

```

val = gDoubleValue(ctl);

object  ctl;  /* control object */
double  val;  /* ctl value      */

```

This method is used to obtain a C double which represents the value associated with the control.

Example:

```

object  ctl;
double  val;

val = gDoubleValue(ctl);

```

See also: Value, Attach, SetDoubleValue, CtlDoubleValue::Dialog
 UnsignedShortValue, ShortValue, LongValue

LongValue::NumericControl

[LongValue]

```
val = gLongValue(ctl);

object  ctl;  /* control object */
long    val;  /* ctl value      */
```

This method is used to obtain a C long integer which represents the value associated with the control.

Example:

```
object  ctl;
long    val;

val = gLongValue(ctl);
```

See also: Value, Attach, SetLongValue, CtlLongValue::Dialog
 UnsignedShortValue, ShortValue, DoubleValue

NewCtl::NumericControl

[NewCtl]

```
ctl = mNewCtl(NumericControl, id);

unsigned id;  /* control id      */
object   ctl; /* control object */
```

mNewCtl is a macro (defined in dynwin.h) that expands to a call to vNew.

This method is used to create a new control object to be identified as id (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use AddControl::Dialog to create controls and associate them to a dialog.

Example:

```
object  ctl;

ctl = mNewCtl(NumericControl, PERSON_AGE);
```

See also: AddControl::Dialog, GetControl::Dialog

NumericRange::NumericControl**[NumericRange]**

```

r = gNumericRange(ctl, min, max, dp);

object  ctl;    /* control object */
double  min;    /* minimum value  */
double  max;    /* maximum value  */
int     dp;     /* decimal places */
object  r;      /* control object */

```

This method is used to set the minimum and maximum allowable values the control will accept from the user. It also sets the number of digits to the right of the decimal point the control will accept.

If the user enters a number outside the specified range, WDS will issue an error message and prompt the user for an acceptable value.

Example:

```

object  ctl;

gNumericRange(ctl, 5.0, 25.0, 1);

```

See also: **CheckFunction::Control**

Select::NumericControl**[Select]**

```

r = gSelect(ctl);

object  ctl;    /* control object */
object  r;      /* ctl          */

```

This method selects (highlights) all text in the numeric control.

The value returned is the control object passed.

SetDefaultDouble::NumericControl**[SetDefaultDouble]**

```

r = gSetDefaultDouble(ctl, val);

object  ctl;    /* control object */
double  val;    /* default value  */
object  r;      /* ctl          */

```

This method sets the default double value for the numeric control. This value is used when the control is reset via **UseDefault**.

The value returned is the control object passed.

See also: `UseDefault`, `SetDefaultLong`

`SetDefaultLong::NumericControl`

[`SetDefaultLong`]

```

r = gSetDefaultLong(ctl, val);

object  ctl;    /* control object */
long    val;    /* default value  */
object  r;      /* ctl          */

```

This method sets the default long integer value for the numeric control. This value is used when the control is reset via `UseDefault`.

The value returned is the control object passed.

See also: `UseDefault`, `SetDefaultDouble`

`SetDoubleValue::NumericControl`

[`SetDoubleValue`]

```

r = gSetDoubleValue(ctl, val);

object  ctl;    /* control object */
double  val;    /* ctl value      */
object  r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be the value which represents the desired value for the control.

Any previously associated value object (associated via `SetValue`) will be disposed when the new value is set.

Example:

```

object  ctl;

gSetDoubleValue(ctl, 3.14159265358979);

```

See also: `SetValue`, `DoubleValue`, `CtlDoubleValue::Dialog`, `SetUShortValue`, `SetShortValue`, `SetLongValue`

SetFormat::NumericControl**[SetFormat]**

```

r = gSetFormat(ctl, fmt, wth);

object  ctl;    /* control object    */
char    *fmt;   /* printf-style format  */
int     wth;    /* display width        */
object  r;      /* ctl                   */

```

This method sets the display format and width for the numeric control. `fmt` is a `printf`-style format string (e.g., "%.2f") and `wth` specifies the display width.

The value returned is the control object passed.

SetLongValue::NumericControl**[SetLongValue]**

```

r = gSetLongValue(ctl, val);

object  ctl;    /* control object */
long    val;    /* ctl value      */
object  r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be the value which represents the desired value for the control.

Any previously associated value object (associated via `SetValue`) will be disposed when the new value is set.

Example:

```

object  ctl;

gSetLongValue(ctl, 66L);

```

See also: `SetValue`, `LongValue`, `CtlLongValue::Dialog`, `SetUShortValue`, `SetShortValue`, `SetDoubleValue`

SetShortValue::NumericControl**[SetShortValue]**

```

r = gSetShortValue(ctl, val);

object  ctl;    /* control object */
int     val;    /* ctl value      */
object  r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be the value which represents the desired value for the control.

Any previously associated value object (associated via `SetValue`) will be disposed when the new value is set.

Example:

```
object ctl;

gSetShortValue(ctl, 66);
```

See also: `SetValue`, `ShortValue`, `CtlShortValue::Dialog`, `SetUShortValue`, `SetLongValue`, `SetDoubleValue`

`SetUShortValue::NumericControl`

[`SetUShortValue`]

```
r = gSetUShortValue(ctl, val);

object ctl; /* control object */
unsigned val; /* ctl value */
object r; /* control object */
```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be the value which represents the desired value for the control.

Any previously associated value object (associated via `SetValue`) will be disposed when the new value is set.

Example:

```
object ctl;

gSetUShortValue(ctl, 66);
```

See also: `SetValue`, `UnsignedShortValue`, `CtlUnsignedShortValue::Dialog`, `SetShortValue`, `SetLongValue`, `SetDoubleValue`

`SetValue::NumericControl`

[`SetValue`]

```
r = gSetValue(ctl, val);

object ctl; /* control object */
object val; /* ctl value */
object r; /* control object */
```


This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be a Dynace object which is an instance of one of the subclasses of the `Number` class and initialized to the value desired for the control.

Any previously associated object will be disposed when the new value is set. Also, `val` will automatically be disposed when the control or associated dialog is disposed.

Example:

```
object ctl;

gSetValue(ctl, gNewWithDouble(DoubleFloat, 3.141));
```

See also: `Value`, `SetShortValue`, `SetUShortValue`, `SetLongValue`, `SetDoubleValue`

`ShortValue::NumericControl`

[`ShortValue`]

```
val = gShortValue(ctl);

object ctl; /* control object */
short val; /* ctl value */
```

This method is used to obtain a C short integer which represents the value associated with the control.

Example:

```
object ctl;
short val;

val = gShortValue(ctl);
```

See also: `Value`, `Attach`, `SetShortValue`, `CtlShortValue::Dialog`, `UnsignedShortValue`, `LongValue`, `DoubleValue`

`UnsignedShortValue::NumericControl`

[`UnsignedShortValue`]

```
val = gUnsignedShortValue(ctl);

object ctl; /* control object */
unsigned short val; /* ctl value */
```

This method is used to obtain a C unsigned short integer which represents the value associated with the control.

Example:

```
object ctl;
unsigned short val;

val = gUnsignedShortValue(ctl);
```

See also: `Value`, `Attach`, `SetUShortValue`, `CtlUnsignedShortValue::DialogShortValue`, `LongValue`, `DoubleValue`

`Value::NumericControl`

[Value]

```
val = gValue(ctl);

object ctl; /* control object */
object val; /* ctl value      */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of one of the subclasses of the `Number` class. This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object ctl, val;

val = gValue(ctl);
```

See also: `ShortValue`, `DoubleValue`, `Attach`, `SetValue`

4.9.5 Date Control

The `DateControl` class is a control which enables the user to enter date information. The user enters dates in the form mm/dd/yy or mm/dd/yyyy, and when the user leaves the field it changes to the form MMM DD, YYYY. For example, the user would enter 6/8/59 and when the field is accepted it will be changed to display Jun 8, 1959.

Dates are stored internally as C longs in the form YYYYMMDD so that 6/8/59 would be represented as the long 19590608. This control has numerous facilities to control the range and type of input the user is allowed to enter.

The `DateControl` class is a subclass of `Control` and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled “Standard Control Method Arguments”.

Attach::DateControl

[Attach]

```

r = gAttach(ctl, val);

object  ctl;  /* control object */
object  val;  /* ctl value      */
object  r;    /* control object */

```

This method is used to associate an independent Dynace object with the value associated with a control object. `val` should be an instance of the `Date` class. This date object will be automatically updated to reflect the value associated with the control.

This object (`val`) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control's value after the life of the control. It is the programmer's responsibility to dispose of the object when it is no longer needed.

Example:

```

object  ctl, val;

val = vNew(Date, 0L);
gAttach(ctl, val);

```

See also: `Value`, `LongValue`, `SetValue`, `SetLongValue`

DateRange::DateControl

[DateRange]

```

r = gDateRange(ctl, min, max, an);

object  ctl;  /* control object */
long    min;  /* minimum value */
long    max;  /* maximum value */
int     an;   /* allow none   */
object  r;    /* control object */

```

This method is used to set the minimum and maximum allowable values the control will accept from the user. It also controls whether or not the control will accept no date.

`min` and `max` are of the form `YYYYMMDD`. For example `6/8/59` would be represented as `19590608`. If `an` is 0 the user must enter a valid date between `min` and `max`. If, however, `an` is 1, the user must either enter a valid date between the given ranges or may also leave the field blank. If the user does not enter a date the field value will be `0L`.

If the user enters an invalid date or one outside the specified range, WDS will issue an error message and prompt the user for an acceptable value.

Example:

```
object   ctl;

gDateRange(ctl, 19990101L, 19991231L, 1);
```

See also: `CheckFunction::Control`

`LongValue::DateControl`

[LongValue]

```
val = gLongValue(ctl);

object   ctl;   /* control object */
long     val;   /* ctl value      */
```

This method is used to obtain a C long integer which represents the value associated with the control. It will be in the form YYYYMMDD. For example 6/8/59 would be represented as 19590608.

Example:

```
object   ctl;
long     val;

val = gLongValue(ctl);
```

See also: `Value`, `Attach`, `SetLongValue`, `CtlLongValue::Dialog`

`NewCtl::DateControl`

[NewCtl]

```
ctl = mNewCtl(DateControl, id);

unsigned id;   /* control id      */
object   ctl;  /* control object */
```

`mNewCtl` is a macro (defined in `dynwin.h`) that expands to a call to `vNew`.

This method is used to create a new control object to be identified as `id` (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use `AddControl::Dialog` to create controls and associate them to a dialog.

Example:

```
object ctl;

ctl = mNewCtl(DateControl, PERSON_BD);
```

See also: `AddControl::Dialog`, `GetControl::Dialog`

`SetLongValue::DateControl`

[`SetLongValue`]

```
r = gSetLongValue(ctl, val);

object ctl;    /* control object */
long    val;    /* ctl value      */
object r;      /* control object */
```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be the value which represents the desired value for the control of the form YYYYMMDD. For example 6/8/59 would be 19590608.

Any previously associated value object (associated via `SetValue`) will be disposed when the new value is set.

Example:

```
object ctl;

gSetLongValue(ctl, 19990101L);
```

See also: `SetValue`, `LongValue`, `CtlLongValue::Dialog`

`SetValue::DateControl`

[`SetValue`]

```
r = gSetValue(ctl, val);

object ctl;    /* control object */
object val;    /* ctl value      */
object r;      /* control object */
```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be a Dynace object which is an instance of the `Date` class and initialized to the value desired for the control.

Any previously associated object will be disposed when the new value is set. Also, `val` will automatically be disposed when the control or associated dialog is disposed.

Example:

```
object ctl;

gSetValue(ctl, vNew(Date, 19940101L));
```

See also: `SetLongValue`, `Value`

`Value::DateControl`

[Value]

```
val = gValue(ctl);

object ctl; /* control object */
object val; /* ctl value      */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the `Date` class. This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object ctl, val;

val = gValue(ctl);
```

See also: `LongValue`, `Attach`, `SetValue`

4.9.6 Push Buttons

The `PushButton` class represents a control which allows the user to perform an immediate action. That means that there is no particular data associated with the control. The user pushes the button and an associated action gets performed at that point. The `PushButton` class allows the programmer to associate a C function to the control such that whenever the user clicks on the button the specified function will be evoked.

The `PushButton` class is a subclass of `Control` and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled “Standard Control Method Arguments”.

Click::PushButton

[Click]

```

    r = gClick(ctl);

    object  ctl;    /* push button object */
    object  r;      /* ctl                */

```

This method programmatically simulates a button click, causing the button's associated function to be executed as if the user had clicked it.

The value returned is the control object passed.

GetExitType::PushButton

[GetExitType]

```

    type = gGetExitType(ctl);

    object  ctl;    /* push button object */
    int     type;    /* exit type          */

```

This method returns the button's current exit type.

See also: **SetExitType**

NewCtl::PushButton

[NewCtl]

```

    ctl = mNewCtl(PushButton, id);

    unsigned id;    /* control id        */
    object  ctl;    /* control object    */

```

mNewCtl is a macro (defined in **dynwin.h**) that expands to a call to **vNew**.

This method is used to create a new control object to be identified as **id** (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use **AddControl::Dialog** to create controls and associate them to a dialog.

Example:

```

    object  ctl;

    ctl = mNewCtl(PushButton, MY_BUTTON);

```

See also: **AddControl::Dialog**, **GetControl::Dialog**

Perform::PushButton

[Perform]

```

r = gPerform(ctl);

object  ctl;      /* control object */
int     r;        /* result          */

```

This method is used to manually evoke the function a programmer associated with a push button. The value returned is the result of the function attached to the button.

This method is seldom needed because WDS automatically evokes the function when the user clicks the button.

Example:

```

object  ctl;

gPerform(ctl);

```

See also: **SetFunction**

SetExitType::PushButton

[SetExitType]

```

r = gSetExitType(ctl, type);

object  ctl;      /* push button object */
int     type;     /* exit type          */
object  r;        /* ctl                */

```

This method sets the exit type for the button, which determines the dialog close behavior when the button is pressed.

The value returned is the control object passed.

See also: **GetExitType**

SetFunction::PushButton

[SetFunction]

```

r = gSetFunction(ctl, fun);

object  ctl;      /* control object          */
int     (*fun)(); /* function pointer       */
ofun    r;        /* previous function      */

```

This method is inherited from the **Control** class.

This method is used to associate a C function to a push button such that if the user clicks the button the C function will immediately get evoked. The value returned is the previous function, if any, associated with the control.

The C function takes the following form:

```
int      fun(object ctl, object dlg)
{
    ....
}
```

Where `ctl` is the control object, and `dlg` is the object representing the dialog the control is associated with. The value returned by `fun` only has meaning if the button was either `IDOK` or `IDCANCEL` (the ones normally used to exit the dialog). If the return value is 1 then the dialog will exit like normal. If the return value is 0 then the dialog will not exit.

Example:

```
object  ctl;

gSetFunction(ctl, fun);
```

See also: `Perform`

`SetStringValue::PushButton`

[`SetStringValue`]

```
r = gSetStringValue(ctl, val);

object  ctl;    /* push button object */
char    *val;    /* display text      */
object  r;       /* ctl                  */
```

This method sets the display text shown on the button.

The value returned is the control object passed.

See also: `StringValue`

`StringValue::PushButton`

[`StringValue`]

```
val = gStringValue(ctl);

object  ctl;    /* push button object */
char    *val;    /* current display text */
```

This method returns the button's current display text.

See also: `SetStringValue`

4.9.7 Check Boxes

The `CheckBox` class represents a control which allows the user to select or de-select a particular option. Unlike radio buttons, check boxes are not mutually exclusive.

The `CheckBox` class is a subclass of `Control` and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled “Standard Control Method Arguments”.

`Attach::CheckBox`

[Attach]

```

r = gAttach(ctl, val);

object  ctl;  /* control object */
object  val;  /* ctl value      */
object  r;    /* control object */

```

This method is used to associate an independent Dynace object with the state associated with a control object. `val` should be an instance of the `ShortInteger` class. This object will be automatically updated to reflect the state associated with the control.

The object will represent 0 if the box is not checked, 1 if it is checked, or 2 if the box is grayed.

This object (`val`) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control's value after the life of the control. It is the programmer's responsibility to dispose of the object when it is no longer needed.

Example:

```

object  ctl, val;

val = gNewWithInt(ShortInteger, 0);
gAttach(ctl, val);

```

See also: `Value`, `ShortValue`, `SetValue`, `SetShortValue`

NewCtl::CheckBox

[NewCtl]

```

    ctl = mNewCtl(CheckBox, id);

    unsigned id;    /* control id      */
    object   ctl;   /* control object */

```

mNewCtl is a macro (defined in `dynwin.h`) that expands to a call to **vNew**.

This method is used to create a new control object to be identified as `id` (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use **AddControl::Dialog** to create controls and associate them to a dialog.

Example:

```

    object   ctl;

    ctl = mNewCtl(CheckBox, MY_CHECKBOX);

```

See also: **AddControl::Dialog**, **GetControl::Dialog**

SetShortValue::CheckBox

[SetShortValue]

```

    r = gSetShortValue(ctl, val);

    object   ctl;    /* control object */
    int      val;    /* ctl value      */
    object   r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be the value which represents the desired state associated with the check box.

`val` should be set to 0 to uncheck the box, 1 to check it, or 2 to gray the box (only work on 3-state boxes).

Any previously associated value object (associated via **SetValue**) will be disposed when the new value is set.

Example:

```

    object   ctl;

    gSetShortValue(ctl, 1);

```

See also: **SetValue**, **ShortValue**, **CtlShortValue::Dialog**

SetValue::CheckBox

[SetValue]

```

    r = gSetValue(ctl, val);

    object ctl;    /* control object */
    object val;    /* ctl value      */
    object r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. **val** should be a Dynace object which is an instance of the **ShortInteger** class and initialized to the value desired for the control.

val should represent 0 to uncheck the box, 1 to check it, or 2 to gray the box (only work on 3-state boxes).

Any previously associated object will be disposed when the new value is set. Also, **val** will automatically be disposed when the control or associated dialog is disposed.

Example:

```

    object ctl;

    gSetValue(ctl, gNewWithInt(ShortInteger, 1));

```

See also: **SetShortValue**, **Value**

ShortValue::CheckBox

[ShortValue]

```

    val = gShortValue(ctl);

    object ctl;    /* control object */
    short  val;    /* ctl value      */

```

This method is used to obtain a C short integer which represents the state associated with the control. The returned integer will be 0 if the box is not checked, 1 if it is checked, or 2 if the box is grayed.

Example:

```

    object ctl;
    short  val;

    val = gShortValue(ctl);

```

See also: **Value**, **Attach**, **SetShortValue**, **CtlShortValue::Dialog**

Value::CheckBox

[Value]

```

    val = gValue(ctl);

    object  ctl;  /* control object */
    object  val;  /* ctl value      */

```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the **ShortInteger** class. The returned object will represent 0 if the box is not checked, 1 if it is checked, or 2 if the box is grayed. This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```

    object  ctl, val;

    val = gValue(ctl);

```

See also: **ShortValue**, **Attach**, **SetValue**

4.9.8 Radio Buttons

The **RadioButton** class represents a control which allows the user to select or de-select a particular option. Unlike check boxes, however, radio buttons are mutually exclusive within a group - similar to the buttons on old fashioned radios, when one button gets selected all the other ones in the group get de-selected.

When using radio buttons, be sure to use the **Group** function in order to tell WDS which radio buttons should be grouped together.

The **RadioButton** class is a subclass of **Control** and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled “Standard Control Method Arguments”.

Attach::RadioButton

[Attach]

```

    r = gAttach(ctl, val);

    object  ctl;  /* control object */
    object  val;  /* ctl value      */
    object  r;    /* control object */

```

This method is used to associate an independent Dynace object with the state associated with a control object. **val** should be an instance of the **ShortInteger** class.

This object will be automatically updated to reflect the state associated with the control.

The object will represent 0 if the button is not selected, 1 if it is selected, or 2 if the button is grayed.

This object (`val`) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control's value after the life of the control. It is the programmer's responsibility to dispose of the object when it is no longer needed.

Example:

```
object ctl, val;

val = gNewWithInt(ShortInteger, 0);
gAttach(ctl, val);
```

See also: `Value`, `ShortValue`, `SetValue`, `SetShortValue`

`Group::RadioButton`

[Group]

```
r = mGroup(ctl, id1, id2);

object ctl;    /* control object */
unsigned id1;  /* starting ctl id */
unsigned id2;  /* ending ctl id */
object r;      /* control object */
```

This method is used to tell WDS which radio buttons are to be considered part of the same mutually exclusive group. `id1` and `id2` are the resource editor defined id's associated with the beginning and end of the group. WDS uses this information to automatically de-select all radio buttons which are part of a group when one of the buttons is selected.

Example:

```
object ctl;

mGroup(ctl, FIRST_RB, LAST_RB);
```

`GroupShortValue::RadioButton`

[GroupShortValue]

```
idx = gGroupShortValue(ctl);

object ctl; /* radio button object */
int idx;    /* 0-based index or -1 */
```

This method returns the zero-based index of the currently selected radio button within the group. Returns -1 if no button is selected.

See also: `GroupStringValue`, `SetGroupShortValue`

`GroupStringValue::RadioButton`

[`GroupStringValue`]

```
name = gGroupStringValue(ctl);

object  ctl;    /* radio button object */
char    *name;  /* name of selected button */
```

This method returns the control name of the currently selected radio button within the group.

See also: `GroupShortValue`, `SetGroupStringValue`

`NewCtl::RadioButton`

[`NewCtl`]

```
ctl = mNewCtl(RadioButton, id);

unsigned id;    /* control id      */
object  ctl;    /* control object */
```

`mNewCtl` is a macro (defined in `dynwin.h`) that expands to a call to `vNew`.

This method is used to create a new control object to be identified as `id` (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use `AddControl::Dialog` to create controls and associate them to a dialog.

Example:

```
object  ctl;

ctl = mNewCtl(RadioButton, MY_RADIOBUTTON);
```

See also: `AddControl::Dialog`, `GetControl::Dialog`, `Group`

SetGroupShortValue::RadioButton

[SetGroupShortValue]

```

r = gSetGroupShortValue(ctl, index);

object  ctl;    /* radio button object */
int     index;  /* 0-based index       */
object  r;      /* ctl                             */

```

This method selects the radio button at the given zero-based index within the group.

The value returned is the control object passed.

See also: `GroupShortValue`, `SetGroupStringValue`

SetGroupStringValue::RadioButton

[SetGroupStringValue]

```

r = gSetGroupStringValue(ctl, name);

object  ctl;    /* radio button object */
char    *name;  /* control name         */
object  r;      /* ctl                             */

```

This method selects the radio button within the group that has the specified control name.

The value returned is the control object passed.

See also: `GroupStringValue`, `SetGroupShortValue`

SetShortValue::RadioButton

[SetShortValue]

```

r = gSetShortValue(ctl, val);

object  ctl;    /* control object */
int     val;    /* ctl value       */
object  r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be the value which represents the desired state associated with the radio button.

`val` should be set to 0 to de-select the button, 1 to select it, or 2 to gray the button (only work on 3-state buttons).

Any previously associated value object (associated via `SetValue`) will be disposed when the new value is set.

Example:

```
object ctl;

gSetShortValue(ctl, 1);
```

See also: `SetValue`, `ShortValue`, `CtlShortValue::Dialog`, `Group`

`SetValue::RadioButton`

[`SetValue`]

```
r = gSetValue(ctl, val);

object ctl;    /* control object */
object val;    /* ctl value      */
object r;      /* control object */
```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. `val` should be a Dynace object which is an instance of the `ShortInteger` class and initialized to the value desired for the control.

`val` should represent 0 to de-select the button, 1 to select it, or 2 to gray the button (only work on 3-state buttons).

Any previously associated object will be disposed when the new value is set. Also, `val` will automatically be disposed when the control or associated dialog is disposed.

Example:

```
object ctl;

gSetValue(ctl, gNewWithInt(ShortInteger, 1));
```

See also: `SetShortValue`, `Value`, `Group`

`ShortValue::RadioButton`

[`ShortValue`]

```
val = gShortValue(ctl);

object ctl;    /* control object */
short  val;    /* ctl value      */
```

This method is used to obtain a C short integer which represents the state associated with the control. The returned integer will be 0 if the button is not selected, 1 if it is selected, or 2 if the button is grayed.

Example:

```
object   ctl;
short    val;

val = gShortValue(ctl);
```

See also: `Value`, `Attach`, `SetShortValue`, `CtlShortValue::Dialog`

Value::RadioButton

[Value]

```
val = gValue(ctl);

object   ctl; /* control object */
object   val; /* ctl value      */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the **ShortInteger** class. The returned object will represent 0 if the button is not selected, 1 if it is selected, or 2 if the button is grayed. This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object   ctl, val;

val = gValue(ctl);
```

See also: `ShortValue`, `Attach`, `SetValue`

4.9.9 List Boxes

The **ListBox** class represents a control which allows the user to select from a list of choices. These choices are presented in a vertical, possibly drop down, list of text choices. This control supports access to the user's choice via the text option selected or an ordinal value.

The application specifies, at runtime, the choices located in the list box.

The main difference between list boxes and combo boxes is that with list boxes the user can only select from the available choices, however, in addition, combo boxes allow the user to enter a choice independent of the available options.

The **ListBox** class is a subclass of **Control** and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled "Standard Control Method Arguments".

AddOption::ListBox

[AddOption]

```

r = gAddOption(ctl, op);

object  ctl;    /* control object */
char    *op;    /* new option      */
object  r;      /* control object */

```

This method is used to append a new option to the list of options associated with a list box. This method may be used prior to or during the execution (via **gPerform**) of a dialog.

op may also be a Dynace object, an instance of the **String** class, representing the new choice. If a Dynace object is used, it must be typecast to a string and it will be disposed when the control or associated dialog are disposed.

Example:

```

object  ctl;

gAddOption(ctl, "The first choice");
gAddOption(ctl, "The second choice");

```

See also: **Alphabetize::ListBox**, **AddOptionAt::ListBox**

AddOptionAt::ListBox

[AddOptionAt]

```

r = gAddOptionAt(ctl, pos, ops);

object  ctl;    /* list box object */
int      pos;    /* insertion position (0-based) */
char    *ops;    /* option text      */
object  r;      /* ctl              */

```

This method inserts an option at position **pos** in the list box.

The value returned is the control object passed.

See also: **AddOption**, **RemoveAll**

Alphabetize::ListBox

[Alphabetize]

```

r = gAlphabetize(ctl);

object  ctl;    /* control object */
object  r;      /* control object */

```

This method is used to cause the automatic alphabetization of all options added via the `AddOption` method. In order to function properly, `Alphabetize` must be called prior to any calls to `AddOption`. This method simply returns the object passed.

See also: `AddOption::ListBox`

`Attach::ListBox`

[Attach]

```
r = gAttach(ctl, val);

object  ctl;    /* control object */
object  val;    /* ctl value      */
object  r;      /* control object */
```

This method is used to associate an independent Dynace object with the state associated with a control object. `val` should be an instance of the `ShortInteger` class or the `String` class. This object will be automatically updated to reflect the state associated with the control.

If `val` is an instance of the `ShortInteger` class it will be used to represent the ordinal value of the selected item. This value is a 0 based index from the top of the list to the bottom. -1 is used to represent no valid selection.

If `val` is an instance of the `String` class it will be used to represent the string represented by the user's choice. If no choice is made it will represent "".

This object (`val`) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control's value after the life of the control. It is the programmer's responsibility to dispose of the object when it is no longer needed.

Example:

```
object  ctl, val;

val = gNewWithInt(ShortInteger, 0);
gAttach(ctl, val);
```

See also: `Value`, `ShortValue`, `StringValue`

`DeselectLine::ListBox`

[DeselectLine]

```
r = gDeselectLine(ctl, line);

object  ctl;    /* list box object */
int     line;    /* 0-based line index */
object  r;      /* ctl                */
```

This method deselects the specified line in a multi-selection list box. `line` is a zero-based index.

The value returned is the control object passed.

See also: `SelectLine`, `GetSelections`

`GetSelections::ListBox`

[`GetSelections`]

```
ary = gGetSelections(ctl);

object ctl; /* control object */
object ary; /* array of selections */
```

This method is used to obtain an array representing the items selected by the user. It is most useful with list boxes which have multi-selection enabled. The array returned is an instance of the `IntegerArray` class and *must* be explicitly disposed when no longer needed. Each element of the array represents a zero based index of one of the user's selections, and the size of the array represents the number of items selected.

This method may only be used while a dialog is active and will return `NULL` otherwise.

See also: `ValueAt`, `NumbSelected`, `Value`, `ListIndex`

`ListIndex::ListBox`

[`ListIndex`]

```
val = gListIndex(ctl);

object ctl; /* control object */
object val; /* ctl value */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the `ShortInteger` class. The returned object will represent the ordinal value of the choice made by the user. This ordinal value is a zero based index from top to bottom. -1 indicates that no choice was made.

This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object ctl, val;

val = gListIndex(ctl);
```

See also: `ShortValue`, `Value`, `StringValue`, `GetSelections`, `SetValue`

`NewCtl::ListBox`

[`NewCtl`]

```
ctl = mNewCtl(ListBox, id);

unsigned id;    /* control id    */
object   ctl;   /* control object */
```

`mNewCtl` is a macro (defined in `dynwin.h`) that expands to a call to `vNew`.

This method is used to create a new control object to be identified as `id` (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use `AddControl::Dialog` to create controls and associate them to a dialog.

Example:

```
object   ctl;

ctl = mNewCtl(ListBox, MY_LISTBOX);
```

See also: `AddControl::Dialog`, `GetControl::Dialog`, `AddOption`

`NumbSelected::ListBox`

[`NumbSelected`]

```
n = gNumbSelected(ctl);

object   ctl;    /* control object */
int      n;       /* number selected */
```

This method is used to obtain the number of list box items the user has selected. It is mainly used with multi-selection list boxes. This method should only be used while the dialog is active and will return -1 otherwise.

See also: `GetSelections`

`RemoveAll::ListBox`

[`RemoveAll`]

```
r = gRemoveAll(ctl);

object   ctl;    /* control object */
object   r;       /* control object */
```

This method is used to remove all items from a list box. It may be used prior to or during the execution of a dialog. The control object passed is returned.

See also: `RemoveStr`, `RemoveInt`

`RemoveInt::ListBox`

[`RemoveInt`]

```
r = gRemoveInt(ctl, idx);

object  ctl;    /* control object */
int     idx;    /* index          */
object  r;      /* control object */
```

This method is used to remove an item from a list box while the dialog is active. `idx` is a zero based index of the item to be removed. If the operation succeeded `ctl` is returned, otherwise `NULL` is returned.

This method may only be used while a dialog is active. It should not be used prior to performing (via `gPerform`) a dialog or after the user has accepted or canceled the dialog.

Example:

```
object  ctl;

gRemoveInt(ctl, 1);
```

See also: `RemoveStr`, `RemoveAll`

`RemoveStr::ListBox`

[`RemoveStr`]

```
r = gRemoveStr(ctl, itm);

object  ctl;    /* control object */
char    *itm;    /* item           */
object  r;      /* control object */
```

This method is used to remove an item from a list box while the dialog is active. `itm` is the string to be removed. If the operation succeeded `ctl` is returned, otherwise `NULL` is returned.

This method may only be used while a dialog is active. It should not be used prior to performing (`gPerform`) a dialog or after the user has accepted or canceled the dialog.

Example:

```
object  ctl;

gRemoveStr(ctl, "Some Option");
```

See also: `RemoveInt`, `FindMode`

`Required::ListBox`

[Required]

```
r = gRequired(ctl, mode);

object  ctl;    /* control object */
int      mode;  /* required mode */
object  r;      /* control object */
```

This method is used to determine whether or not the user is required to make a valid selection prior to WDS allowing the acceptance of the dialog. If it is required and the user does not make a valid selection, WDS will issue an error message and return them to the control.

`mode` is 1 to make it required and 0 otherwise.

Example:

```
object  ctl;

gRequired(ctl, 1);
```

See also: `CheckFunction::Control`, `CheckValue::Control`

`SelectLine::ListBox`

[SelectLine]

```
r = gSelectLine(ctl, line);

object  ctl;    /* list box object */
int      line;  /* 0-based line index */
object  r;      /* ctl */
```

This method selects the specified line in a multi-selection list box. `line` is a zero-based index.

The value returned is the control object passed.

See also: `DeselectLine`, `GetSelections`

SetFunction::ListBox

[SetFunction]

```

    r = gSetFunction(ctl, fun);

    object  ctl;      /* control object      */
    int     (*fun)(); /* function pointer   */
    ofun    r;        /* previous function   */

```

This method is inherited from the **Control** class.

This method is used to associate a C function to a list box such that if the user double clicks an item in the list box the C function will immediately get evoked. The value returned by this method is the function, if any, which was previously associated with the control.

The C function takes the following form:

```

    int     fun(object ctl, object dlg)
    {
        ....
    }

```

Where **ctl** is the control object, and **dlg** is the object representing the dialog the control is associated with. The value returned by **fun** is ignored.

Example:

```

    object  ctl;

    gSetFunction(ctl, fun);

```

See also: **Perform**, **SetChgFunction**

SetShortValue::ListBox

[SetShortValue]

```

    r = gSetShortValue(ctl, val);

    object  ctl; /* control object */
    int     val; /* ctl value     */
    object  r;   /* control object */

```

This method is used to set the default selection associated with the control. It is often used to set the initial value prior to performing a dialog.

val will be used as the ordinal value of the selected item. This value is a 0 based index from the top of the list to the bottom.

Any previously associated object (via **Value**) will be disposed when the new value is set.

Example:

```
object ctl;

gSetShortValue(ctl, 1);
```

See also: `SetStringValue`, `SetValue`

`SetStringValue::ListBox`

[`SetStringValue`]

```
r = gSetStringValue(ctl, val);

object ctl;    /* control object */
char    *val;   /* ctl value      */
object r;      /* control object */
```

This method is used to set the default selection associated with the control. It is often used to set the initial value prior to performing a dialog.

`val` will be used to select the option which matches the string.

Any previously associated object (via `val`) will be disposed when the new value is set.

Example:

```
object ctl;

gSetStringValue(ctl, "The choice");
```

See also: `SetShortValue`, `SetValue`

`SetValue::ListBox`

[`SetValue`]

```
r = gSetValue(ctl, val);

object ctl;    /* control object */
object val;    /* ctl value      */
object r;      /* control object */
```

This method is used to set the default selection associated with the control. It is often used to set the initial value prior to performing a dialog. `val` should be a Dynace object which is an instance of either the `String` class or the `ShortInteger` class and initialized to the value desired for the control.

If `val` is an instance of the `ShortInteger` class it will be used as the ordinal value of the selected item. This value is a 0 based index from the top of the list to the bottom.

If `val` is an instance of the `String` class it will be used to select the option which matches the string represented by `val`.

Any previously associated object will be disposed when the new value is set. Also, `val` will automatically be disposed when the control or associated dialog is disposed.

Example:

```
object ctl;

gSetValue(ctl, gNewWithInt(ShortInteger, 1));
      or
gSetValue(ctl, gNewWithStr(String, "The choice"));
```

See also: `SetShortValue`, `SetStringValue`

`ShortValue::ListBox`

[ShortValue]

```
val = gShortValue(ctl);

object ctl; /* control object */
short val; /* ctl value      */
```

This method is used to obtain a C short which represents the value associated with the control. The returned value will represent the ordinal value of the choice made by the user. This ordinal value is a zero based index from top to bottom. -1 indicates that no choice was made.

Example:

```
object ctl;
short val;

val = gShortValue(ctl);
```

See also: `ListIndex`, `Value`, `GetSelections`, `StringValue`, `SetValue`

`Size::ListBox`

[Size]

```
n = gSize(ctl);

object ctl; /* list box object */
int n; /* number of items */
```

This method returns the number of items in the list box.

StringValue::ListBox

[StringValue]

```

    val = gStringValue(ctl);

    object  ctl;  /* control object */
    char    *val; /* ctl value      */

```

This method is used to obtain a character string pointer which represents the value associated with the control. The returned pointer will represent the text associated with the user selected choices. It will point to "" if the user had not made a valid selection.

The returned pointer will not be valid once the control object or associated dialog is disposed.

Example:

```

    object  ctl;
    char    *val;

    val = gStringValue(ctl);

```

See also: ShortValue, Value, ListIndex, GetSelections, SetValue

Value::ListBox

[Value]

```

    val = gValue(ctl);

    object  ctl;  /* control object */
    object  val;  /* ctl value      */

```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the **String** class. The returned object will represent the text associated with the user selected choices. If no selection was made the object will represent "".

This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```

    object  ctl, val;

    val = gValue(ctl);

```

See also: ShortValue, StringValue, ValueAt, ListIndex, GetSelections, SetValue

ValueAt::ListBox

[ValueAt]

```

    val = gValueAt(ctl, idx);

    object  ctl;    /* control object */
    int     idx;    /* index          */
    object  val;    /* value at idx   */

```

This method is used to obtain a Dynace object which represents the text associated with the line indexed by the zero based index `idx`. The object returned will be an instance of the **String** class. If the index is out of range this method will return **NULL**.

This method may only be called when the dialog is active. The object returned *must* be explicitly disposed when no longer needed.

See also: **ShortValue**, **Value**, **ListIndex**, **GetSelections**, **SetValue**

4.9.10 Combo Boxes

The **ComboBox** class represents a control which allows the user to select from a list of choices or enter an alternate text string. These choices are presented in a vertical, possibly drop down, list of text choices. This control supports access to the user's choice via the text option selected or an ordinal value.

The application specifies, at runtime, the choices located in the list box.

The main difference between list boxes and combo boxes is that with list boxes the user can only select from the available choices, however, in addition, combo boxes allow the user to enter a choice independent of the available options.

The **ComboBox** class is a subclass of **Control** and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled "Standard Control Method Arguments".

AddEdtHandlerAfter::ComboBox

[AddEdtHandlerAfter]

```

    r = gAddEdtHandlerAfter(ctl, msg, func);

    object  ctl;      /* a control object */
    unsigned msg;     /* message          */
    long    (*func)(); /* function pointer */
    object  r;        /* the control obj  */

```

This method is used to associate function `func` with the text entry window portion of the combo box, message `msg` for control `ctl`. Whenever the text entry window of control `ctl` receives message `msg`, `func` will be called.

ctl is the control object who's text window messages you wish to process. **msg** is the particular message you wish to trap. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with **WM_**.

func is the function which gets called whenever the specified message gets received and takes the following form:

```

long    func(object    ctl,
                  HWND   hwnd,
                  UINT   mMsg,
                  WPARAM wParam,
                  LPARAM lParam)
{
    .
    .
    .
    return 0L; /* or whatever is appropriate */
}

```

Where **ctl** is the control being sent the message. The remaining arguments and return value is fully documented in the Windows documentation under the **WindowProc** function and the Windows Messages documentation.

WDS keeps a list of functions associated with each message associated with each control. When a particular message is received the appropriate list of handler functions gets executed sequentially. **AddEdtHandlerAfter** appends the new function to the end of this list, and **AddEdtHandlerBefore** adds the new function to the beginning of the list.

WDS may also, and optionally, execute the Windows default procedure associated with a given message either before or after the user added list of functions. This behavior may be controlled via **DefaultEdtProcessingMode**.

Windows will only see the return value of the last message handler executed including, if applicable, the default.

Example:

```
int      hSize, vSize;

static long  process_wm_size(object ctl,
                               HWND   hwnd,
                               UINT    mMsg,
                               WPARAM  wParam,
                               LPARAM  lParam)
{
    hSize = LOWORD(lParam);
    vSize = HIWORD(lParam);
    return OL;
}

.
.
gAddEdtHandlerAfter(ctl, (unsigned) WM_SIZE,
                    process_wm_size);
.
.
```

See also: `DefaultProcessingMode`, `AddEdtHandlerBefore`,
`AddHandlerAfter::Control`

`AddEdtHandlerBefore::ComboBox`

[`AddEdtHandlerBefore`]

```
r = gAddEdtHandlerBefore(ctl, msg, func);

object  ctl;      /* a control object */
unsigned msg;     /* message          */
long    (*func)(); /* function pointer */
object  r;        /* the control obj  */
```

This function is fully documented under `AddEdtHandlerAfter`.

See also: `AddEdtHandlerAfter`, `AddHandlerAfter::Control`

`AddOption::ComboBox`

[`AddOption`]

```
r = gAddOption(ctl, op);

object  ctl;      /* control object */
char    *op;      /* new option      */
object  r;        /* control object */
```

This method is used to append a new option to the list of options associated with a combo box. This method may be used prior to or during the execution (via `gPerform`) of a dialog.

`op` may also be a Dynace object, an instance of the `String` class, representing the new choice. If a Dynace object is used, it must be typecast to a string and it will be disposed when the control or associated dialog are disposed.

Example:

```
object ctl;

gAddOption(ctl, "The first choice");
gAddOption(ctl, "The second choice");
```

See also: `Alphabetize::ComboBox`, `AddOptionAt::ComboBox`

`AddOptionAt::ComboBox`

[`AddOptionAt`]

```
r = gAddOptionAt(ctl, pos, ops);

object ctl;    /* combo box object */
int     pos;   /* insertion position (0-based) */
char    *ops;  /* option text */
object  r;     /* ctl */
```

This method inserts an option at position `pos` in the combo box.

The value returned is the control object passed.

See also: `AddOption`, `RemoveAll`

`Alphabetize::ComboBox`

[`Alphabetize`]

```
r = gAlphabetize(ctl);

object ctl;    /* control object */
object r;      /* control object */
```

This method is used to cause the automatic alphabetization of all options added via the `AddOption` method. In order to function properly, `Alphabetize` must be called prior to any calls to `AddOption`. This method simply returns the object passed.

See also: `AddOption::ComboBox`

Attach::ComboBox

[Attach]

```

r = gAttach(ctl, val);

object  ctl;  /* control object */
object  val;  /* ctl value      */
object  r;    /* control object */

```

This method is used to associate an independent Dynace object with the state associated with a control object. **val** should be an instance of the **ShortInteger** class or the **String** class. This object will be automatically updated to reflect the state associated with the control.

If **val** is an instance of the **ShortInteger** class it will be used to represent the ordinal value of the selected item. This value is a 0 based index from the top of the list to the bottom. -1 is used to represent no valid selection.

If **val** is an instance of the **String** class it will be used to represent the string represented by the user's choice. If no choice is made it will represent "".

This object (**val**) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control's value after the life of the control. It is the programmer's responsibility to dispose of the object when it is no longer needed.

Example:

```

object  ctl, val;

val = gNewWithInt(ShortInteger, 0);
gAttach(ctl, val);

```

See also: **Value**, **ShortValue**, **StringValue**

DefaultEdtProcessingMode::ComboBox

[DefaultEdtProcessingMode]

```

r = gDefaultEdtProcessingMode(ctl, msg, mode);

object  ctl;  /* a control object      */
unsigned msg; /* message                  */
int      mode; /* default processing mode */
object  r;    /* the control obj         */

```

This method is used to determine when or if the Windows default message procedure is processed for a given message (**msg**) associated with the text entry window portion of control (**ctl**).

WDS allows a programmer to specify an arbitrary number of functions to be executed whenever the text entry portion of a combo box control receives a specific message (via `AddEdtHandlerAfter` and `AddEdtHandlerBefore`). Windows has default procedures associated with many control messages. At times it is necessary to replace or augment this default functionality. `DefaultEdtProcessingMode` gives the programmer control over when and if this default Windows functionality. `mode` is used to specify the desired mode. The following table indicates the valid modes:

0	Do not execute the Windows default processing
1	Execute default processing <i>after</i> programmer defined handlers
2	Execute default processing <i>before</i> programmer defined handlers

Note that the default mode is always 1, and must be explicitly changed, if desired, for each message associated with each control.

`msg` is the particular message you wish to affect. These messages are fully documented in the Windows documentation in the Messages section. They normally begin with `WM_`.

Example:

```
gDefaultEdtProcessingMode(ctl, (unsigned) WM_SIZE, 0);
```

See also: `AddEdtHandlerAfter`

`FindIndex::ComboBox`

[FindIndex]

```
idx = gFindIndex(ctl, choice);

object  ctl;      /* combo box object */
char    *choice;  /* text to find      */
int     idx;      /* 0-based index or -1 */
```

This method returns the zero-based index of `choice` in the combo box's option list, or -1 if the choice is not found.

`ListIndex::ComboBox`

[ListIndex]

```
val = gListIndex(ctl);

object  ctl;  /* control object */
object  val;  /* ctl value      */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the `ShortInteger` class. The returned object will represent the ordinal value of the choice made by the user.

This ordinal value is a zero based index from top to bottom. -1 indicates that no choice was made.

This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object ctl, val;

val = gListIndex(ctl);
```

See also: `ShortValue`, `Value`, `StringValue`, `Attach`, `SetValue`

`NewCtl::ComboBox`

[`NewCtl`]

```
ctl = mNewCtl(ComboBox, id);

unsigned id; /* control id */
object ctl; /* control object */
```

`mNewCtl` is a macro (defined in `dynwin.h`) that expands to a call to `vNew`.

This method is used to create a new control object to be identified as `id` (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use `AddControl::Dialog` to create controls and associate them to a dialog.

Example:

```
object ctl;

ctl = mNewCtl(ComboBox, MY_COMBOBOX);
```

See also: `AddControl::Dialog`, `GetControl::Dialog`, `AddOption`

`NumbSelected::ComboBox`

[`NumbSelected`]

```
n = gNumbSelected(ctl);

object ctl; /* combo box object */
int n; /* 1 if selected, 0 otherwise */
```

This method returns 1 if an item is currently selected in the combo box, or 0 if no item is selected.

RemoveAll::ComboBox

[RemoveAll]

```

r = gRemoveAll(ctl);

object  ctl;    /* control object */
object  r;      /* control object */

```

This method is used to remove all items from a combo box. It may be used prior to or during the execution of a dialog. The control object passed is returned.

See also: `RemoveStr`, `RemoveInt`

RemoveInt::ComboBox

[RemoveInt]

```

r = gRemoveInt(ctl, idx);

object  ctl;    /* control object */
int      idx;    /* index          */
object  r;      /* control object */

```

This method is used to remove an item from a combo box while the dialog is active. `idx` is a zero based index of the item to be removed. If the operation succeeded `ctl` is returned, otherwise `NULL` is returned.

This method may only be used while a dialog is active. It should not be used prior to performing (`gPerform`) a dialog or after the user has accepted or canceled the dialog.

Example:

```

object  ctl;

gRemoveInt(ctl, 1);

```

See also: `RemoveStr`, `RemoveAll`

RemoveStr::ComboBox

[RemoveStr]

```

r = gRemoveStr(ctl, itm);

object  ctl;    /* control object */
char    *itm;    /* item          */
object  r;      /* control object */

```

This method is used to remove an item from a combo box while the dialog is active. `itm` is the string to be removed. If the operation succeeded `ctl` is returned, otherwise `NULL` is returned.

This method may only be used while a dialog is active. It should not be used prior to performing (`gPerform`) a dialog or after the user has accepted or canceled the dialog.

Example:

```
object ctl;

gRemoveStr(ctl, "Some Option");
```

See also: `RemoveInt::ComboBox`, `FindMode::ComboBox`

`Required::ComboBox`

[Required]

```
r = gRequired(ctl, mode);

object ctl;    /* control object */
int     mode;   /* required mode  */
object r;      /* control object */
```

This method is used to determine whether or not the user is required to make a valid selection prior to WDS allowing the acceptance of the dialog. If it is required and the user does not make a valid selection, WDS will issue an error message and return them to the control.

`mode` is 1 to make it required and 0 otherwise.

Example:

```
object ctl;

gRequired(ctl, 1);
```

See also: `CheckFunction::Control`, `CheckValue::Control`

`SetChgFunction::ComboBox`

[SetChgFunction]

```
ofun = gSetChgFunction(ctl, fun);

object ctl;          /* combo box object */
int     (*fun)();     /* change callback  */
int     (*ofun)();    /* previous callback */
```

This method sets the function to be called when the user changes the selection in the combo box.

The value returned is the previous change function.

See also: `SetFunction`

`SetFunction::ComboBox`

[`SetFunction`]

```

r = gSetFunction(ctl, fun);

object  ctl;      /* control object      */
int     (*fun)(); /* function pointer   */
ofun    r;        /* previous function  */

```

This method is inherited from the `Control` class.

This method is used to associate a C function to a combo box such that if the user double clicks an item in the combo box the C function will immediately get evoked. The value returned by this method is the function, if any, which was previously associated with the control.

The C function takes the following form:

```

int     fun(object ctl, object dlg)
{
    ....
}

```

Where `ctl` is the control object, and `dlg` is the object representing the dialog the control is associated with. The value returned by `fun` is ignored.

Example:

```

object  ctl;

gSetFunction(ctl, fun);

```

See also: `Perform`, `SetChgFunction`

`SetShortValue::ComboBox`

[`SetShortValue`]

```

r = gSetShortValue(ctl, val);

object  ctl; /* control object */
int     val; /* ctl value      */
object  r;   /* control object */

```

This method is used to set the default selection associated with the control. It is often used to set the initial value prior to performing a dialog.

`val` will be used as the ordinal value of the selected item. This value is a 0 based index from the top of the list to the bottom.

Any previously associated object (via `Value`) will be disposed when the new value is set.

Example:

```
object ctl;

gSetShortValue(ctl, 1);
```

See also: `SetStringValue`, `SetValue`

`SetStringValue::ComboBox`

[`SetStringValue`]

```
r = gSetStringValue(ctl, val);

object ctl;    /* control object */
char    *val;   /* ctl value      */
object  r;      /* control object */
```

This method is used to set the default selection associated with the control. It is often used to set the initial value prior to performing a dialog.

`val` will be used to select the option which matches the string.

Any previously associated object (via `val`) will be disposed when the new value is set.

Example:

```
object ctl;

gSetStringValue(ctl, "The choice");
```

See also: `SetShortValue`, `SetValue`

`SetValue::ComboBox`

[`SetValue`]

```
r = gSetValue(ctl, val);

object ctl;    /* control object */
object val;     /* ctl value      */
object  r;      /* control object */
```

This method is used to set the default selection associated with the control. It is often used to set the initial value prior to performing a dialog. `val` should be a Dynace object which is an instance of either the `String` class or the `ShortInteger` class and initialized to the value desired for the control.

If **val** is an instance of the **ShortInteger** class it will be used as the ordinal value of the selected item. This value is a 0 based index from the top of the list to the bottom.

If **val** is an instance of the **String** class it will be used to select the option which matches the string represented by **val**.

Any previously associated object will be disposed when the new value is set. Also, **val** will automatically be disposed when the control or associated dialog is disposed.

Example:

```
object ctl;

gSetValue(ctl, gNewWithInt(ShortInteger, 1));
      or
gSetValue(ctl, gNewWithStr(String, "The choice"));
```

See also: **SetShortValue**, **SetStringValue**

ShortValue::ComboBox

[ShortValue]

```
val = gShortValue(ctl);

object ctl; /* control object */
short val; /* ctl value      */
```

This method is used to obtain a C short which represents the value associated with the control. The returned value will represent the ordinal value of the choice made by the user. This ordinal value is a zero based index from top to bottom. -1 indicates that no choice was made.

Example:

```
object ctl;
short val;

val = gShortValue(ctl);
```

See also: **ListIndex**, **Value**, **StringValue**, **Attach**, **SetValue**

Size::ComboBox

[Size]

```
n = gSize(ctl);

object ctl; /* combo box object */
int n; /* number of items */
```


This method returns the number of items in the combo box.

StringValue::ComboBox

[StringValue]

```
val = gStringValue(ctl);

object  ctl;  /* control object */
char    *val; /* ctl value      */
```

This method is used to obtain a character string pointer which represents the value associated with the control. The returned pointer will represent the text associated with the user selected choices. It will point to "" if the user had not made a valid selection.

The returned pointer will not be valid once the control object or associated dialog is disposed.

Example:

```
object  ctl;
char    *val;

val = gStringValue(ctl);
```

See also: [ShortValue](#), [Value](#), [ListIndex](#), [Attach](#), [SetValue](#)

Value::ComboBox

[Value]

```
val = gValue(ctl);

object  ctl;  /* control object */
object  val;  /* ctl value      */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the **String** class. The returned object will represent the text associated with the user selected choices. If no selection was made the object will represent "".

This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object  ctl, val;

val = gValue(ctl);
```

See also: `ShortValue`, `StringValue`, `ValueAt`, `ListIndex`, `Attach`, `SetValue`

`ValueAt::ComboBox`

[`ValueAt`]

```
val = gValueAt(ctl, idx);

object  ctl;  /* control object */
int     idx;  /* index          */
object  val;  /* value at idx   */
```

This method is used to obtain a Dynace object which represents the text associated with the line indexed by the zero based index `idx`. The object returned will be an instance of the `String` class. If the index is out of range this method will return `NULL`.

This method may only be called when the dialog is active. The object returned *must* be explicitly disposed when no longer needed.

See also: `ShortValue`, `Value`, `ListIndex`, `SetValue`

4.9.11 Scroll Bars

The `ScrollBar` class represents a control which allows the user to select a number between two ranges via a linear, visually intuitive control. The range defaults to 0 to 100 and may be controlled via `ScrollBarRange`.

The `ScrollBar` class is a subclass of `Control` and as such inherits all the functionality associated with that class. This section only documents functionality particular to this class.

Standard control arguments are documented in the section entitled “Standard Control Method Arguments”.

`Attach::ScrollBar`

[`Attach`]

```
r = gAttach(ctl, val);

object  ctl;  /* control object */
object  val;  /* ctl value      */
object  r;    /* control object */
```

This method is used to associate an independent Dynace object with the state associated with a control object. `val` should be an instance of the `ShortInteger` class. This object will be automatically updated to reflect the position of the scroll bar.

This object (`val`) will never be disposed by WDS, even after the control or associated dialog are disposed. Therefore, this is one way of gaining access to a control’s value after the life of the control. It is the programmer’s responsibility to dispose of the object when it is no longer needed.

Example:

```
object   ctl, val;

val = gNewWithInt(ShortInteger, 0);
gAttach(ctl, val);
```

See also: `Value`, `ShortValue`, `SetValue`, `SetShortValue`, `ScrollBarRange`

`Increment::ScrollBar`

[Increment]

```
r = gIncrement(ctl, val);

object   ctl; /* control object */
int      val; /* increment value */
object   r;   /* control object */
```

This method is used to increment the position of the scroll bar `val` points from its current position. `val` may be negative or positive, which will determine the direction of movement.

Example:

```
object   ctl;

gIncrement(ctl, 10);
```

See also: `SetShortValue`, `SetValue`, `ScrollBarRange`

`NewCtl::ScrollBar`

[NewCtl]

```
ctl = mNewCtl(ScrollBar, id);

unsigned id; /* control id */
object   ctl; /* control object */
```

`mNewCtl` is a macro (defined in `dynwin.h`) that expands to a call to `vNew`.

This method is used to create a new control object to be identified as `id` (see section “Standard Control Method Arguments”). This method is mainly used internally. A programmer would more often use `AddControl::Dialog` to create controls and associate them to a dialog.

Example:

```
object   ctl;

ctl = mNewCtl(ScrollBar, MY_SCROLLBAR);
```

See also: `AddControl::Dialog`, `GetControl::Dialog`

`ScrollBarRange::ScrollBar`

[ScrollBarRange]

```
r = gScrollBarRange(ctl, min, max, pginc, lineinc)

object   ctl;    /* control object */
int      min;    /* minimum range */
int      max;    /* maximum range */
int      pginc;  /* page increment */
int      lineinc; /* line increment */
object   r;      /* control object */
```

This method is used to control the range and scrolling characteristics associated with a given scroll bar control.

`min` and `max` are used to determine the range of the control. These are the values which are returned when the control is at either end of its extremes. The default values are 0 and 100 respectively.

`pginc` is used to control exactly how much the position of the scroll bar will change when the user clicks the control in such a way as to cause a page jump in the position. This is normally done by clicking in the area on either side of position indicating element of the control. The default value for the variable is 10. It must be less than the difference between `max` and `min`, and is normally larger than `lineinc`.

`lineinc` is used to control exactly how much the position of the scroll bar will change when the user clicks the line increment arrows located on the extreme ends of the control. The default value of this control is 2.

Example:

```
object   ctl;

gScrollBarRange(ctl, 0, 100, 10, 2);
```

SetShortValue::ScrollBar

[SetShortValue]

```

r = gSetShortValue(ctl, val);

object  ctl;    /* control object */
int     val;    /* ctl value      */
object  r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. **val** should be the value which represents the desired position of the scroll bar. It must be between the minimum and maximum range associated with the control.

Any previously associated value object (associated via **SetValue**) will be disposed when the new value is set.

Example:

```

object  ctl;

gSetShortValue(ctl, 50);

```

See also: **SetValue**, **Increment**, **CtlShortValue::Dialog**, **ScrollBarRange**

SetValue::ScrollBar

[SetValue]

```

r = gSetValue(ctl, val);

object  ctl;    /* control object */
object  val;    /* ctl value      */
object  r;      /* control object */

```

This method is used to set the value associated with a control. It is often used to set the initial value prior to performing a dialog. **val** should be a Dynace object which is an instance of the **ShortInteger** class and initialized to the value desired for the control.

val must represent a number between the minimum and maximum range associated with the scroll bar.

Any previously associated object will be disposed when the new value is set. Also, **val** will automatically be disposed when the control or associated dialog is disposed.

Example:

```

object  ctl;

gSetValue(ctl, gNewWithInt(ShortInteger, 50));

```

See also: `SetShortValue`, `Increment`, `Value`, `ScrollBarRange`

`ShortValue::ScrollBar`

[ShortValue]

```
val = gShortValue(ctl);

object  ctl;  /* control object */
short   val;  /* ctl value      */
```

This method is used to obtain a C short integer which represents the position of the scroll bar. The returned value will represent the position of the scroll bar control. This number will be between the minimum and maximum range associated with the control via `ScrollBarRange`.

Example:

```
object  ctl;
short   val;

val = gShortValue(ctl);
```

See also: `Value`, `Attach`, `SetShortValue`, `CtlShortValue::Dialog`

`Value::ScrollBar`

[Value]

```
val = gValue(ctl);

object  ctl;  /* control object */
object  val;  /* ctl value      */
```

This method is used to obtain a Dynace object which represents the value associated with the control. The object returned will be an instance of the `ShortInteger` class. The returned object will represent the position of the scroll bar control. This number will be between the minimum and maximum range associated with the control via `ScrollBarRange`.

This object will be disposed by WDS when the control object or associated dialog is disposed.

Example:

```
object  ctl, val;

val = gValue(ctl);
```

See also: `ShortValue`, `Attach`, `SetValue`

4.9.12 Custom Controls

4.10 Cursors

The `Cursor` class (as well as its subclasses) are used to represent cursor objects. This class is never used by an application. It is used to house the functionality common to its subclasses. Therefore, this class documents functionality which is common to all of its subclasses.

Note that a more convenient mechanism for using cursors is provided by `LoadCursor::Window` and `LoadSystemCursor::Window`

`Copy::Cursor`

[Copy]

```
c = gCopy(csr);

object csr;    /* cursor object      */
object c;      /* copy of cursor object */
```

This method is implemented by all subclasses of `Cursor` (`SystemCursor`, `ExternalCursor`).

This method is used to create a new cursor object which is a copy of a given cursor object. The value of this is to be able to associate a cursor with multiple objects which will automatically dispose of the cursor when they are disposed. If copies weren't used the second object referencing the cursor would reference a disposed cursor object.

Each cursor object must be disposed (either automatically or manually) when it is no longer needed.

Example:

```
object c1, c2;

c2 = gCopy(c1);
```

See also: `DeepCopy`

`DeepCopy::Cursor`

[DeepCopy]

This method performs the same function as `Copy`. See that method for details.

`DeepDispose::Cursor`

[DeepDispose]

This method performs the same function as `Dispose`. See that method for details.

Dispose::Cursor

[Dispose]

```

r = gDispose(csr);

object  csr;    /* a cursor object    */
object  r;      /* NULL                               */

```

This method is used to dispose of a cursor object when it is no longer needed. This method is rarely needed due to the fact that when a window is disposed it automatically calls this method to dispose of its associated cursor object.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```

object  csr;

csr = gDispose(csr);

```

See also: **DeepDispose**

Handle::Cursor

[Handle]

```

h = gHandle(csr);

object  csr;    /* cursor object    */
HANDLE  h;      /* Windows handle   */

```

This method is used to obtain the Windows internal handle associated with a cursor object.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```

object  csr;
HCURSOR h;

h = gHandle(csr);

```

4.10.1 System Cursors

The **SystemCursor** class represents Windows predefined cursors. This class is a subclass of **Cursor** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Cursor** class for additional functionality.

LoadSys::SystemCursor

[LoadSys]

```

    csr = gLoadSys(SystemCursor, id);

    char    *id;    /* cursor id        */
    object   csr;    /* cursor object   */

```

This method is used to create a new object which represents one of the Windows predefined cursors. `id` should be one of the Windows defined macros specifying the desired cursor. It is defined in the Windows documentation under the function `LoadCursor` and starts with `IDC_`.

Example:

```

    object   csr;

    csr = gLoadSys(SystemCursor, IDC_IBEAM);

```

See also: `LoadSystemCursor::Window`, `SetCursor::Application`

4.10.2 External Cursors

The `ExternalCursor` class represents arbitrary application defined cursors. This class is a subclass of `Cursor` and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the `Cursor` class for additional functionality.

Load::ExternalCursor

[Load]

```

    csr = mLoad(ExternalCursor, id);

    unsigned id;    /* cursor id        */
    object   csr;    /* cursor object     */

```

This method is used to load a programmer defined application specific cursor.

`id` is a programmer defined unsigned integer which identifies the cursor. This identifier is normally a macro and defined through the resource editor.

The value returned is an object representing the cursor loaded, or `NULL` if the cursor was not found.

Example:

```

    object   csr;

    csr = mLoad(ExternalCursor, MY_CURSOR);

```

See also: `LoadCursor::Window`, `SetCursor::Application`

`LoadStr::ExternalCursor`

[`LoadStr`]

```
csr = mLoadStr(ExternalCursor, id);

char    *id;    /* cursor id        */
object   csr;   /* cursor object   */
```

This method is used to load a programmer defined application specific cursor by name.

`id` is a programmer defined name which identifies the cursor. This identifier is normally defined through the resource editor.

The value returned is an object representing the cursor loaded, or `NULL` if the cursor was not found.

Example:

```
object   csr;

csr = mLoadStr(ExternalCursor, "mycursor");
```

See also: `LoadCursor::Window`, `SetCursor::Application`, `Use::Window`

4.11 Icons

The `Icon` class (as well as its subclasses) are used to represent icon objects. This class is never used by an application. It is used to house the functionality common to its subclasses. Therefore, this class documents functionality which is common to all of its subclasses.

Note that a more convenient mechanism for using icons is provided by `LoadIcon::Window` and `LoadSystemIcon::Window`

`Copy::Icon`

[`Copy`]

```
c = gCopy(icn);

object   icn;    /* icon object        */
object   c;      /* copy of icon object */
```

This method is implemented by all subclasses of `Icon` (`SystemIcon`, `ExternalIcon`).

This method is used to create a new icon object which is a copy of a given icon object. The value of this is to be able to associate a icon with multiple objects which will automatically dispose of the icon when they are disposed. If copies weren't used the second object referencing the icon would reference a disposed icon object.

Each icon object must be disposed (either automatically or manually) when it is no longer needed.

Example:

```
object i1, i2;

i2 = gCopy(i1);
```

See also: `DeepCopy`

`DeepCopy::Icon`

[`DeepCopy`]

This method performs the same function as `Copy`. See that method for details.

`DeepDispose::Icon`

[`DeepDispose`]

This method performs the same function as `Dispose`. See that method for details.

`Dispose::Icon`

[`Dispose`]

```
r = gDispose(icn);

object icn; /* an icon object */
object r;   /* NULL           */
```

This method is used to dispose of an icon object when it is no longer needed. This method is rarely needed due to the fact that when a window is disposed it automatically calls this method to dispose of its associated icon object.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object icn;

icn = gDispose(icn);
```

See also: `DeepDispose`

Handle::Icon

[Handle]

```

h = gHandle(icn);

object  icn;    /* icon object    */
HANDLE  h;      /* Windows handle */

```

This method is used to obtain the Windows internal handle associated with an icon object.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```

object  icn;
HICON   h;

h = gHandle(icn);

```

4.11.1 System Icons

The **SystemIcon** class represents Windows predefined icons. This class is a subclass of **Icon** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Icon** class for additional functionality.

LoadSys::SystemIcon

[LoadSys]

```

icn = gLoadSys(SystemIcon, id);

char    *id;    /* icon id      */
object  icn;    /* icon object  */

```

This method is used to create a new object which represents one of the Windows predefined icons. **id** should be one of the Windows defined macros specifying the desired icon. It is defined in the Windows documentation under the function **LoadIcon** and starts with **IDI_**.

Example:

```

object  icn;

icn = gLoadSys(SystemIcon, IDI_HAND);

```

See also: **LoadSystemIcon::Window**, **SetIcon::Application**

4.11.2 External Icons

The `ExternalIcon` class represents arbitrary application defined icons. This class is a subclass of `Icon` and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the `Icon` class for additional functionality.

`Load::ExternalIcon`

[Load]

```
icn = mLoad(ExternalIcon, id);

unsigned id;    /* icon id      */
object  icn;    /* icon object */
```

This method is used to load a programmer defined application specific icon.

`id` is a programmer defined unsigned integer which identifies the icon. This identifier is normally a macro and defined through the resource editor.

The value returned is an object representing the icon loaded, or `NULL` if the icon was not found.

Example:

```
object  icn;

icn = mLoad(ExternalIcon, MY_ICON);
```

See also: `LoadIcon::Window`, `SetIcon::Application`

`LoadStr::ExternalIcon`

[LoadStr]

```
icn = mLoadStr(ExternalIcon, id);

char    *id;    /* icon id      */
object  icn;    /* icon object */
```

This method is used to load a programmer defined application specific icon by name.

`id` is a programmer defined name which identifies the icon. This identifier is normally defined through the resource editor.

The value returned is an object representing the icon loaded, or `NULL` if the icon was not found.

Example:

```
object  icn;

icn = mLoadStr(ExternalIcon, "myicon");
```

See also: `LoadIcon::Window`, `SetIcon::Application`, `Use::Window`

4.12 Fonts

The `Font` class (as well as its subclasses) are used to represent font objects. This class is never used by an application. It is used to house the functionality common to its subclasses. Therefore, this class documents functionality which is common to all of its subclasses.

Note that a more convenient mechanism for using fonts is provided by `LoadFont::Window`, `LoadSystemFont::Window`, `LoadFont::Printer`, and `LoadSystemFont::Printer`.

`AveCharWidth::Font`

[`AveCharWidth`]

```
r = gAveCharWidth(fnt);

object fnt; /* a font object */
int    r;   /* ave char width */
```

This method is used to gain access to the average character width associated with a particular font.

Example:

```
object fnt;
int    cw;

cw = gAveCharWidth(fnt);
```

See also: `LineHeight`, `GetTM`

`Copy::Font`

[`Copy`]

```
c = gCopy(fnt);

object fnt; /* font object */
object c;   /* copy of font object */
```

This method is implemented by all subclasses of `Font` (`SystemFont`, `ExternalFont`).

This method is used to create a new font object which is a copy of a given font object. The value of this is to be able to associate a font with multiple objects which will automatically dispose of the font when they are disposed. If copies weren't used the second object referencing the font would reference a disposed font object.

Each font object must be disposed (either automatically or manually) when it is no longer needed.

Example:

```
object f1, f2;

f2 = gCopy(f1);
```

See also: `DeepCopy`

`DeepCopy::Font`

[`DeepCopy`]

This method performs the same function as `Copy`. See that method for details.

`DeepDispose::Font`

[`DeepDispose`]

This method performs the same function as `Dispose`. See that method for details.

`Dispose::Font`

[`Dispose`]

```
r = gDispose(fnt);

object fnt; /* a font object */
object r;   /* NULL          */
```

This method is used to dispose of a font object when it is no longer needed. This method is rarely needed due to the fact that when a window or printer object is disposed it automatically calls this method to dispose of its associated font object.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object fnt;

fnt = gDispose(fnt);
```

See also: `DeepDispose`

GetTM::Font

[GetTM]

```

r = gGetTM(fnt, tm);

object    fnt; /* a font object */
TEXTMETRIC *tm; /* font metrics */
object    r;   /* fnt          */

```

This method is used to gain access to the font metrics associated with a particular font.

Example:

```

object fnt;
TEXTMETRIC tm;

gGetTM(fnt, &tm);

```

See also: LineHeight, AveCharWidth

Handle::Font

[Handle]

```

h = gHandle(fnt);

object fnt; /* font object */
HANDLE h;   /* Windows handle */

```

This method is used to obtain the Windows internal handle associated with a font object.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```

object fnt;
HGDIOBJ h;

h = gHandle(fnt);

```

LineHeight::Font

[LineHeight]

```

r = gLineHeight(fnt);

object fnt; /* a font object */
int    r;   /* line height */

```


This method is used to gain access to the line height associated with a particular font. This number is equal to the height of the largest character in the font plus a reasonable amount of space to separate lines containing the font.

Example:

```
object fnt;
int    lh;

lh = gLineHeight(fnt);
```

See also: AveCharWidth, GetTM

Name::Font

[Name]

```
s = gName(fnt);

object fnt; /* a font object */
char   *s;  /* font face name */
```

This instance method returns the font's face name including style suffixes (e.g., "Arial Bold Italic").

Example:

```
object fnt;
char   *name;

name = gName(fnt);
```

PixelHeight::Font

[PixelHeight]

```
n = gPixelHeight(Font);

int n; /* vertical DPI (pixels per logical inch) */
```

This class method returns the screen's vertical DPI (pixels per logical inch). It is called on the Font class itself, not on an instance.

Example:

```
int dpi;

dpi = gPixelHeight(Font);
```

PointSize::Font

[PointSize]

```

n = gPointSize(fnt);

object fnt; /* a font object */
int    n;   /* point size   */

```

This instance method returns the font's point size.

Example:

```

object fnt;
int     ps;

ps = gPointSize(fnt);

```

4.12.1 System Fonts

The **SystemFont** class represents Windows predefined fonts. This class is a subclass of **Font** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Font** class for additional functionality.

Load::SystemFont

[Load]

```

fnt = mLoad(SystemFont, id);

unsigned id; /* icon id */
object fnt; /* icon object */

```

This method is used to create a new object which represents one of the Windows predefined fonts. *id* should be one of the Windows defined macros specifying the desired font. It is defined in the Windows documentation under the function **GetStockObject** and ends with **_FONT**.

Example:

```

object fnt;

fnt = mLoad(SystemFont, ANSI_FIXED_FONT);

```

See also: **LoadSystemFont::Window**, **LoadSystemFont::Printer**,
SetFont::Application, **Use::Window**, **Use::Printer**

4.12.2 External Fonts

The **ExternalFont** class represents arbitrary external fonts. This class is a subclass of **Font** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Font** class for additional functionality.

Indirect::ExternalFont

[Indirect]

```
fnt = gIndirect(ExternalFont, lf);

LOGFONT *lf;    /* logical font */
object fnt;     /* font object */
```

This method is used to find and load a font which most closely matches the parameters indicated by `lf`. The structure of `lf` is fully described in the Windows documentation under the structure `LOGFONT`.

The value returned is an object representing the font loaded, or `NULL` if the font was not found.

Example:

```
LOGFONT lf;
object fnt;

/* initialize lf */
fnt = gIndirect(ExternalFont, &lf);
```

See also: `LoadFont::Window`, `LoadFont::Printer`, `SetFont::Application`,
`Use::Window`, `Use::Printer`

New::ExternalFont

[New]

```
fnt = vNew(ExternalFont, nm, ps);

char *nm;    /* font name */
int ps;      /* point size */
object fnt;  /* font object */
```

This method is used to load an arbitrary font by name at any point size. `nm` is the full name of the font as it appears when you list the available fonts via the control-panel / fonts Windows utility, minus the font type in parentheses. `ps` indicates the desired point size.

The value returned is an object representing the font loaded, or `NULL` if the font was not found.

Note that `nm` may also be a Dynace object cast as a `(char *)`.

Example:

```
object fnt;

fnt = vNew(ExternalFont, "Times New Roman", 12);
```

See also: `LoadFont::Window`, `LoadFont::Printer`, `SetFont::Application`,
`Use::Window`, `Use::Printer`

4.13 Brushes

The `Brush` class (as well as its subclasses) are used to represent brush objects. This class is never used by an application. It is used to house the functionality common to its subclasses. Therefore, this class documents functionality which is common to all of its subclasses.

`Color::Brush` [Color]

```
c = gColor(bsh);

object    bsh; /* brush object */
COLORREF  c;   /* brush color  */
```

This method is used to obtain the color associated with a brush.

Example:

```
object    bsh;
COLORREF  c;

c = gColor(bsh);
```

`Copy::Brush` [Copy]

```
c = gCopy(bsh);

object    bsh; /* brush object */
object    c;   /* copy of brush object */
```

This method is implemented by all subclasses of `Brush` (`SystemBrush`, `StockBrush`, `SolidBrush`, `HatchBrush`).

This method is used to create a new brush object which is a copy of a given brush object. The value of this is to be able to associate a brush with multiple objects which will automatically dispose of the brush when they are disposed. If copies weren't used the second object referencing the brush would reference a disposed brush object.

Each brush object must be disposed (either automatically or manually) when it is no longer needed.

Example:

```
object    b1, b2;

b2 = gCopy(b1);
```

See also: `DeepCopy`

`DeepCopy::Brush`

[`DeepCopy`]

This method performs the same function as `Copy`. See that method for details.

`DeepDispose::Brush`

[`DeepDispose`]

This method performs the same function as `Dispose`. See that method for details.

`Dispose::Brush`

[`Dispose`]

```
r = gDispose(bsh);

object bsh; /* a brush object */
object r;   /* NULL           */
```

This method is used to dispose of a brush object when it is no longer needed. This method is rarely needed due to the fact that when a window or printer object is disposed it automatically calls this method to dispose of its associated brush object.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object bsh;

bsh = gDispose(bsh);
```

See also: `DeepDispose`

`Handle::Brush`

[`Handle`]

```
h = gHandle(bsh);

object bsh; /* brush object */
HANDLE h;   /* Windows handle */
```

This method is used to obtain the Windows internal handle associated with a brush object.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```
object  bsh;
HBRUSH  h;

h = gHandle(bsh);
```

4.13.1 Stock Brushes

The **StockBrush** class represents common Windows defined brushes. This class is a subclass of **Brush** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Brush** class for additional functionality.

New::StockBrush

[New]

```
bsh = vNew(StockBrush, id);

unsigned id;    /* brush id      */
object  bsh;    /* brush object */
```

This method is used to load one of the Windows pre-defined brushes. The available options are macros documented in the Windows documentation under the function **GetStockObject** and end with **_BRUSH**.

The value returned is an object representing the brush loaded, or **NULL** if the brush was not found.

Example:

```
object  bsh;

bsh = vNew(StockBrush, GRAY_BRUSH);
```

See also: **TextBrush::Window**, **BackBrush::Window**, **Use::Window**, **Use::Printer**

4.13.2 Solid Brushes

The **SolidBrush** class represents arbitrary application defined brushes. This class is a subclass of **Brush** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Brush** class for additional functionality.

New::SolidBrush

[New]

```

    bsh = vNew(SolidBrush, red, green, blue);

    int    red;
    int    green;
    int    blue;
    object bsh;    /* brush object */

```

This method is used to create a solid colored brush with specific colors. Each color argument specifies a number between 0 and 255 and indicates the intensity of the related color. If all three are 0 you get black, and all three at 255 is white.

The value returned is an object representing the brush created, or NULL if the brush was not created.

Example:

```

    object bsh;

    bsh = vNew(SolidBrush, 255, 0, 0);

```

See also: **TextBrush::Window**, **BackBrush::Window**, **Use::Window**, **Use::Printer**

4.13.3 System Brushes

The **SystemBrush** class represents brushes which are those colors which were selected by the user as global to their Windows environment. The programmer may select, for example, the color the user chose for background windows.

This class is a subclass of **Brush** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Brush** class for additional functionality.

New::SystemBrush

[New]

```

    bsh = vNew(SystemBrush, id);

    unsigned id;    /* brush id */
    object bsh;    /* brush object */

```

This method is used to load one of the Windows user defined brushes. The available options are macros documented in the Windows documentation under the function **GetSysColor**.

The value returned is an object representing the brush loaded, or NULL if the brush was not found.

Example:

```
object bsh;

bsh = vNew(SystemBrush, COLOR_ACTIVEBORDER);
```

See also: `TextBrush::Window`, `BackBrush::Window`, `Use::Window`, `Use::Printer`

4.13.4 Hatch Brushes

The `HatchBrush` class represents arbitrary application defined brushes with a specified pattern. This class is a subclass of `Brush` and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the `Brush` class for additional functionality.

`New::HatchBrush`

[New]

```
bsh = vNew(HatchBrush, red, green, blue, style);

int    red;
int    green;
int    blue;
int    style; /* brush pattern */
object bsh;   /* brush object  */
```

This method is used to create a colored brush with specific colors and pattern. Each color argument specifies a number between 0 and 255 and indicates the intensity of the related color. If all three are 0 you get black, and all three at 255 is white.

The `style` parameter indicates the specific pattern for the brush. This parameter is a macro documented in the Windows documentation under the function `CreateHatchBrush` and begin with `HS_`.

The value returned is an object representing the brush created, or `NULL` if the brush was not created.

Example:

```
object bsh;

bsh = vNew(HatchBrush, 255, 10, 10, HS_VERTICAL);
```

See also: `TextBrush::Window`, `BackBrush::Window`, `Use::Window`, `Use::Printer`

4.14 Pens

The **Pen** class (as well as its subclasses) are used to represent pen objects. This class is never used by an application. It is used to house the functionality common to its subclasses. Therefore, this class documents functionality which is common to all of its subclasses.

Color::Pen

[Color]

```
c = gColor(pn);

object    pn;    /* pen object    */
COLORREF  c;     /* pen color   */
```

This method is used to obtain the color associated with a pen.

Example:

```
object    pn;
COLORREF  c;

c = gColor(pn);
```

Copy::Pen

[Copy]

```
c = gCopy(pn);

object    pn;      /* pen object      */
object    c;       /* copy of pen object */
```

This method is implemented by all subclasses of **Pen** (**StockPen**, **CustomPen**).

This method is used to create a new pen object which is a copy of a given pen object. The value of this is to be able to associate a pen with multiple objects which will automatically dispose of the pen when they are disposed. If copies weren't used the second object referencing the pen would reference a disposed pen object.

Each pen object must be disposed (either automatically or manually) when it is no longer needed.

Example:

```
object    p1, p2;

p2 = gCopy(p1);
```

See also: **DeepCopy**

DeepCopy::Pen

[DeepCopy]

This method performs the same function as **Copy**. See that method for details.

DeepDispose::Pen

[DeepDispose]

This method performs the same function as **Dispose**. See that method for details.

Dispose::Pen

[Dispose]

```

r = gDispose(pn);

object pn;    /* a pen object */
object r;     /* NULL          */

```

This method is used to dispose of a pen object when it is no longer needed. This method is rarely needed due to the fact that when a window or printer object is disposed it automatically calls this method to dispose of its associated pen object.

The value returned is always **NULL** and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```

object pn;

pn = gDispose(pn);

```

See also: **DeepDispose**

Handle::Pen

[Handle]

```

h = gHandle(pn);

object pn;    /* pen object */
HANDLE h;     /* Windows handle */

```

This method is used to obtain the Windows internal handle associated with a pen object.

Note that this method may be used with most WDS objects in order to obtain the internal handle that Windows normally associates with each type of object. See the appropriate documentation.

Example:

```
object   pn;  
HPEN     h;  
  
h = gHandle(pn);
```

4.14.1 Stock Pens

The **StockPen** class represents common Windows defined pens. This class is a subclass of **Pen** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Pen** class for additional functionality.

New::StockPen

[New]

```
pn = vNew(StockPen, id);  
  
unsigned id;    /* pen id      */  
object   pn;    /* pen object */
```

This method is used to load one of the Windows pre-defined pens. The available options are macros documented in the Windows documentation under the function **GetStockObject** and end with **_PEN**.

The value returned is an object representing the pen loaded, or **NULL** if the pen was not found.

Example:

```
object   pn;  
  
pn = vNew(StockPen, BLACK_PEN);
```

See also: **Use::Printer**

4.14.2 Custom Pens

The **CustomPen** class represents arbitrary application defined pens with a specified pattern and width. This class is a subclass of **Pen** and as such inherits most of its functionality from it. This section documents the methods particular to this class. See the **Pen** class for additional functionality.

New::CustomPen

[New]

```

pn = vNew(CustomPen, red, green, blue, style, width);

int      red;
int      green;
int      blue;
int      style; /* pen pattern */
int      width; /* pen line width */
object   pn;    /* pen object */

```

This method is used to create a colored pen with specific colors, pattern and line width. Each color argument specifies a number between 0 and 255 and indicates the intensity of the related color. If all three are 0 you get black, and all three at 255 is white.

The **style** parameter indicates the specific pattern for the pen. This parameter is a macro documented in the Windows documentation under the function **CreatePen** and begin with **PS_**. The **width** parameter specifies the width of the line in logical units.

The value returned is an object representing the pen created, or NULL if the pen was not created.

Example:

```

object   pn;

pn = vNew(CustomPen, 255, 10, 10, PS_DASH, 5);

```

See also: **Use::Printer**

4.15 Help System

The **HelpSystem** class is used to support the standard Windows help system. In addition to being able to support arbitrary evocation of help messages, this class is used by other WDS classes in order to provide complete support for context sensitive help to any level. Each class provides mechanisms in order to associate context sensitive help text to windows, dialogs, menus or controls.

Most classes which provide context sensitive help support have a method called **SetTopic** which is used to associate a particular topic within a given context.

All the methods in this class are class methods. This means that the first argument to all the methods will be **HelpSystem** and there is never an instance object to keep track of.

See the appropriate examples for detailed information on how to create the actual help file.

HelpContents::HelpSystem

[HelpContents]

```
r = gHelpContents(HelpSystem);

object r;      /* HelpSystem */
```

This method is used to display the contents screen of the help file. **HelpSystem** will be returned if the request is successful and **NULL** otherwise.

Example:

```
gHelpContents(HelpSystem);
```

See also: **HelpFile**, **HelpTopic**, **HelpInContext**

HelpFile::HelpSystem

[HelpFile]

```
r = gHelpFile(HelpSystem, hf);

char *hf;      /* help file */
object r;      /* HelpSystem */
```

This method is used to determine the external file to be used for all help references. This must be done prior to any of the other help facilities use. The help file will not be opened until one of the help display methods is evoked. The application must also have a main window prior to the evocation of the help system. The help system will automatically terminate when the user terminates the application.

Example:

```
gHelpFile(HelpSystem, "helpfile.hlp");
```

See also: **HelpContents**

HelpInContext::HelpSystem

[HelpInContext]

```
r = gHelpInContext(HelpSystem);

object r;      /* HelpSystem */
```

This method is used to display the help screen associated with the current context (set with **SetTopic**). If no context is set the help contents will be displayed. **HelpSystem** will be returned if the request is successful and **NULL** otherwise.

Note that **SetTopic** and **HelpInContext**, although available to an application program, are mainly used internally by WDS in order to support the context sensitive

help facility provided by the `Window`, `Dialog`, `Menu`, and `Control` classes. See the `SetTopic` method associated with those classes.

Example:

```
gHelpInContext(HelpSystem);
```

See also: `HelpFile`, `SetTopic`, `HelpContents`, `HelpTopic`

`HelpTopic::HelpSystem`

[`HelpTopic`]

```
r = gHelpTopic(HelpSystem, tpc);

char    *tpc;    /* help topic */
object  r;       /* HelpSystem */
```

This method is used to display the help screen associated with a given topic. `HelpSystem` will be returned if the request is successful and `NULL` otherwise.

Example:

```
gHelpTopic(HelpSystem, "fileOpen");
```

See also: `HelpFile`, `HelpContents`, `HelpInContext`

`SetTopic::HelpSystem`

[`SetTopic`]

```
r = gSetTopic(HelpSystem, tpc);

char    *tpc;    /* help topic */
char    *r;      /* previous topic */
```

This method is used to set the current help topic context. It is used by `HelpInContext` to display the help text associated with the current context. The previous help topic will be returned.

Note that `SetTopic` and `HelpInContext`, although available to an application program, are mainly used internally by WDS in order to support the context sensitive help facility provided by the `Window`, `Dialog`, `Menu`, and `Control` classes. See the `SetTopic` method associated with those classes.

Example:

```
gSetTopic(HelpSystem, "someTopic");
```

See also: `HelpFile`, `HelpInContext`, `HelpContents`, `HelpTopic`

4.16 Common Dialogs

The `CommonDialog` class is only used to group the common dialogs which are all subclasses of this class. There is no specific functionality associated with this class. See the particular subclasses for documentation.

4.16.1 File Selection Dialog

The `FileDialog` class provides a standard and convenient method of querying the user for a file name. The user is able to browse the disk or enter a new file name.

The `fd` parameter used by all methods in this class refer to the file dialog object returned by the `New` method.

`AppendFilter::FileDialog` [AppendFilter]

```
r = gAppendFilter(fd, ttl, fltr);

object fd;      /* file dialog */
char   *ttl;    /* title      */
char   *fltr;   /* file filter */
object r;       /* file dialog */
```

This method is used to group files according to some file naming criteria for user selection. There may be any number of groups. The user selects the group they are interested in and are presented with a list of files which meet the criteria.

`ttl` is the name of the group which the user is presented with. `fltr` is the file filter and may consist of several filters, each separated with a semicolon.

This method may be called any number of times to create several groups.

Example:

```
object fd;

gAppendFilter(fd, "Document Files", "*.txt;*.doc");
gAppendFilter(fd, "Source Files", "*.c;*.h");
```

See also: `SetFile`, `InitialDir`, `DefExt`

`DefExt::FileDialog` [DefExt]

```
r = gDefExt(fd, ext);

object fd;      /* file dialog */
char   *ext;    /* file extension */
object r;       /* file dialog */
```

This method is used to set the default file extension which will be displayed for the user. It should not contain a period.

Example:

```
object fd;

gDefExt(fd, "txt");
```

See also: `SetFile`, `AppendFilter`

`Dispose::FileDialog`

[Dispose]

```
r = gDispose(fd);

object fd; /* file dialog */
object r; /* NULL */
```

This method is used to dispose of a file dialog object. This method must be called to dispose of the dialog when it is no longer needed.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object fd;

fd = gDispose(fd);
```

`GetFile::FileDialog`

[GetFile]

```
fname = gGetFile(fd);

object fd; /* file dialog */
char *fname; /* file name */
```

This method is used to obtain the file name the user selected once the file dialog has been completed. This value will include the full path, file name and extension. If multiple selections are allowed, the path will be returned, then a space delimited list of selected file names.

Example:

```
object fd;
char *files;

files = gGetFile(fd);
```


See also: `GetOpenFile`, `GetSaveFile`, `SetFile`, `SetFlags`

`InitialDir::FileDialog`

[InitialDir]

```
r = gInitialDir(fd, pth);

object fd;      /* file dialog */
char *pth;      /* initial path */
object r;       /* file dialog */
```

This method is used to set the initial path associated with the file dialog. If no initial path is set, the system will use the current directory of the application.

Example:

```
object fd;

gInitialDir(fd, "c:\\mypath");
```

See also: `SetFile`, `AppendFilter`, `DefExt`

`New::FileDialog`

[New]

```
fd = vNew(FileDialog, pwind);

object pwind; /* parent window */
object fd;    /* file dialog */
```

This method is used to create a new file dialog object. It will not be displayed until the appropriate method is called. The object returned must be disposed when it is no longer needed.

The `pwind` parameter refers to either the application's main window or any child window object.

Example:

```
object fd, pwind;

fd = vNew(FileDialog, pwind);
```

See also: `Dispose`, `GetOpenFile`, `GetSaveFile`

GetOpenFile::FileDialog

[GetOpenFile]

```
r = gGetOpenFile(fd);

object fd;    /* file dialog */
int    r;     /* return status */
```

This method is used to actually display the dialog and obtain user input. The type of file dialog presented will be one in which the user must select a pre-existing file, presumably to open.

The return value is non-zero if the user makes a valid selection and zero if the user did not make a selection or if an error occurred.

Example:

```
object fd;
int    r;

r = gGetOpenFile(fd);
```

See also: **GetSaveFile**

GetSaveFile::FileDialog

[GetSaveFile]

```
r = gGetSaveFile(fd);

object fd;    /* file dialog */
int    r;     /* return status */
```

This method is used to actually display the dialog and obtain user input. The type of file dialog presented will be one in which the user may select a pre-existing file or type in a new name, presumably to save some data to.

The return value is non-zero if the user makes a valid selection and zero if the user did not make a selection or if an error occurred.

Example:

```
object fd;
int    r;

r = gGetSaveFile(fd);
```

See also: **GetOpenFile**

SetFile::FileDialog

[SetFile]

```
r = gSetFile(fd, fname);

object fd;      /* file dialog */
char   *fname; /* file name   */
object r;      /* file dialog */
```

This method is used to set the default file name displayed when the file dialog is displayed.

Example:

```
object fd;

gSetFile(fd, "somefile.txt");
```

See also: `InitialDir`, `GetFile`, `SetFlags`, `DefExt`

SetFlags::FileDialog

[SetFlags]

```
r = gSetFlags(fd, flgs);

object fd;      /* file dialog */
DWORD flgs;     /* flags       */
object r;      /* file dialog */
```

This method is used to set the option flags associated with a file dialog. The available flags are fully documented in the Windows documentation under the `OPENFILENAME` structure and all begin with `OFN_`.

Example:

```
object fd;

gSetFlags(fd, OFN_ALLOWMULTISELECT);
```

See also: `SetFile`, `DefExt`

SetTitle::FileDialog

[SetTitle]

```
r = gSetTitle(fd, ttl);

object fd;      /* file dialog */
char   *ttl;    /* dialog title */
object r;      /* file dialog */
```

This method is used to set the text which appears at the top of the file dialog. If no value is set the system will use appropriate defaults.

Example:

```
object fd;

gSetTitle(fd, "Select File");
```

See also: `SetFile`, `AppendFilter`, `DefExt`

4.16.2 Printer Selection and Configuration Dialog

The `PrintDialog` class is used to present the user with a standard and convenient dialog for printer selection and configuration.

This class is seldom needed because the `Printer` class has the `QueryPrinter::Printer` method which automatically calls this class for printer information. However, this class may be used independently in order to have better control of user options.

The `pd` parameter used by all methods in this class refer to the print dialog object returned by the `New` method.

`Copies::PrintDialog` [Copies]

```
cp = gCopies(fd);

object fd;    /* file dialog */
int     cp;    /* copies      */
```

This method is used to obtain the number of copies selected by the user subsequent to calling `Perform`.

Example:

```
object fd;
int     cp;

cp = gCopies(fd);
```

See also: `Perform`, `SetFlags`, `GetPageRange`

`Dispose::PrintDialog` [Dispose]

```
r = gDispose(pd);

object pd;    /* print dialog */
object r;     /* NULL        */
```

This method is used to dispose of a print dialog object. This must be done when it is no longer needed.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object  pd;

pd = gDispose(pd);
```

See also: `New`, `Perform`

`GetPageRange::PrintDialog`

[`GetPageRange`]

```
r = gGetPageRange(fd, start, end);

object  fd;      /* file dialog          */
int     *start;  /* starting page number */
int     *end;    /* ending page number   */
object  r;       /* file dialog          */
```

This method is used to obtain the page range selected by the user subsequent to calling `Perform`.

Example:

```
object  fd;
int     start, end;

gGetPageRange(fd, &start, &end);
```

See also: `Perform`, `SetFlags`, `Copies`

`Handle::PrintDialog`

[`Handle`]

```
hdc = gHandle(pd);

object  pd;      /* print dialog */
HANDLE  hdc;     /* handle to dc  */
```

This method is used to obtain the device context handle associated with the print dialog. It will only be valid after performing the dialog (via `Perform`). If the handle is obtained via this method, the `Dispose` method will not release the handle as it would normally do. This is done so the device context can be used for the printer to

be opened. If the handle is obtained it is the application's responsibility to release the handle when it is no longer needed. This may be done via the `DeleteDC` Windows function.

This method is mainly used internally to WDS and is only made available for convenience.

Example:

```
object  pd;
HDC     hdc;

hdc = gHandle(pd);
```

See also: `Perform`

`New::PrintDialog`

[New]

```
pd = vNew(PrintDialog, pwind);

object pwind; /* parent window */
object pd;    /* print dialog   */
```

This method is used to create a new print dialog object. It will not be displayed until the appropriate method is called. The object returned must be disposed when it is no longer needed.

The `pwind` parameter refers to either the application's main window or any child window object.

Example:

```
object pd, pwind;

pd = vNew(PrintDialog, pwind);
```

See also: `Perform`, `Dispose`

`Perform::PrintDialog`

[Perform]

```
r = gPerform(pd);

object pd; /* print dialog */
int     r; /* return status */
```

This method is used to actually present the user with the print dialog. The return value is non-zero if the user appropriately selects a printer. Zero will be returned if the user cancels the dialog or an error occurs.

Example:

```
object pd;
int r;

r = gPerform(pd);
```

See also: `New`, `Dispose`

`SetFlags::PrintDialog`

[SetFlags]

```
r = gSetFlags(pd, flgs);

object pd;      /* print dialog */
DWORD flgs;     /* flags          */
object r;       /* print dialog */
```

This method is used to set the option flags associated with a print dialog. The available flags are fully documented in the Windows documentation under the `PRINTDLG` structure and all begin with `PD_`.

Example:

```
object pd;

gSetFlags(pd, PD_ALLPAGES);
```

4.16.3 Color Selection Dialog

The `ColorDialog` class is used to present the user with a standard and convenient dialog for color selection and configuration.

The `cd` parameter used by all methods in this class refer to the color dialog object returned by the `New` method.

`Dispose::ColorDialog`

[Dispose]

```
r = gDispose(cd);

object cd;      /* color dialog */
object r;       /* NULL         */
```

This method is used to dispose of a color dialog object. This must be done when it is no longer needed.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object  cd;

cd = gDispose(cd);
```

See also: `New`, `Perform`

`GetColor::ColorDialog`

[`GetColor`]

```
clr = gGetColor(cd);

object  cd;    /* color dialog    */
COLORREF clr; /* selected color */
```

This method is used to obtain the users color selection subsequent to executing `Perform`.

Example:

```
object  cd;
COLORREF clr;

clr = gGetColor(cd);
```

See also: `Perform`, `SetColor`, `GetCustomColorPtr`

`GetCustomColorPtr::ColorDialog`

[`GetCustomColorPtr`]

```
cv = gGetCustomColorPtr(cd);

object  cd;    /* color dialog    */
COLORREF *cv; /* color vector    */
```

This method is used to obtain a pointer to 16 `COLORREF`s selected as custom colors by the user. This vector should be inspected subsequent to calling `Perform` and prior to calling `Dispose`. One `Dispose` is called, the returned pointer will no longer be valid.

Example:

```
object  cd;
COLORREF *cv;

cv = gGetCustomColorPtr(cd);
```


See also: `Perform`, `GetColor`

`New::ColorDialog`

[New]

```
cd = vNew(ColorDialog, pwind);

object pwind; /* parent window */
object cd;    /* color dialog  */
```

This method is used to create a new color dialog object. It will not be displayed until the appropriate method is called. The object returned must be disposed when it no longer needed.

The `pwind` parameter refers to either the application's main window or any child window object.

Example:

```
object cd, pwind;

cd = vNew(ColorDialog, pwind);
```

See also: `Perform`, `Dispose`

`Perform::ColorDialog`

[Perform]

```
r = gPerform(cd);

object cd;    /* color dialog */
int      r;    /* return status */
```

This method is used to actually present the user with the color selection dialog. The return value is non-zero if the user appropriately selects a color. Zero will be returned if the user canceled the dialog or an error occurred.

Example:

```
object cd;
int      r;

r = gPerform(cd);
```

See also: `New`, `Dispose`

SetColor::ColorDialog

[SetColor]

```

r = gSetColor(cd, clr);

object  cd;    /* color dialog */
COLORREF clr; /* selected color */
object  r;     /* color dialog */

```

This method is used to set the initial color associated with the color selection dialog. The Windows RGB macro may be used to obtain a valid COLORREF.

Example:

```

object  cd;
COLORREF clr;

gSetColor(cd, RGB(255, 0 ,0));

```

See also: Perform, GetColor

SetFlags::ColorDialog

[SetFlags]

```

r = gSetFlags(cd, flgs);

object  cd;    /* color dialog */
DWORD   flgs;  /* flags */
object  r;     /* color dialog */

```

This method is used to set the option flags associated with a color dialog. The available flags are fully documented in the Windows documentation under the CHOOSECOLOR structure and all begin with CC_.

Example:

```

object  cd;

gSetFlags(cd, CC_FULLOPEN);

```

4.16.4 Font Selection Dialog

The **FontDialog** class is used to present the user with a standard and convenient dialog for font selection.

The **fd** parameter used by all methods in this class refer to the font dialog object returned by the **New** method.

Dispose::FontDialog

[Dispose]

```
r = gDispose(fd);

object fd;    /* font dialog */
object r;     /* NULL      */
```

This method is used to dispose of a font dialog object. This must be done when it is no longer needed.

The value returned is always **NULL** and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object fd;

fd = gDispose(fd);
```

See also: **New**, **Perform**

Font::FontDialog

[Font]

```
fnt = gFont(fd);

object fd;    /* font dialog */
object fnt;   /* font object */
```

This method is used to create a font object representing the font the user selected. This font object will be an instance of the **ExternalFont** class and must be disposed (either directly or indirectly) when it is no longer needed. This method should only be called subsequent to **Perform**. **NULL** will be returned if no font was selected or the font object could not be created.

Example:

```
object fd, fnt;

fnt = gFont(fd);
```

See also: **Perform**

GetColor::FontDialog

[GetColor]

```
clr = gGetColor(fd);

object  fd;    /* font dialog */
COLORREF clr; /* color        */
```

This method is used to get the user selected color once **Perform** has been called. This will only work if the **CF_EFFECTS** option is set.

Example:

```
object  fd;
COLORREF clr;

clr = gGetColor(fd);
```

See also: **SetFlags**, **SetColor**, **Perform**

New::FontDialog

[New]

```
fd = vNew(FontDialog, pwind);

object  pwind; /* parent window */
object  fd;    /* font dialog   */
```

This method is used to create a new font dialog object. It will not be displayed until the appropriate method is called. The object returned must be disposed when it no longer needed.

The **pwind** parameter refers to either the application's main window or any child window object.

Example:

```
object  fd, pwind;

fd = vNew(FontDialog, pwind);
```

See also: **Perform**, **Dispose**

Perform::FontDialog

[Perform]

```

r = gPerform(fd);

object  fd;    /* font dialog */
int     r;     /* return status */

```

This method is used to actually present the user with the font selection dialog. The return value is non-zero if the user appropriately selects a font. Zero will be returned if the user canceled the dialog or an error occurred.

Example:

```

object  fd;
int     r;

r = gPerform(fd);

```

See also: **New**, **Dispose**

SetColor::FontDialog

[SetColor]

```

clr = gSetColor(fd);

object  fd;    /* font dialog */
COLORREF clr;  /* color */

```

This method is used to set the initial color of the user color selection portion of the font dialog. This will only work if the **CF_EFFECTS** option is set. The Windows supplied **RGB** macro may be used to create the **COLORREF**.

Example:

```

object  fd;

gSetColor(fd, RGB(255, 0, 0));

```

See also: **SetFlags**, **GetColor**, **Perform**

SetFlags::FontDialog

[SetFlags]

```

r = gSetFlags(fd, flgs);

object  fd;    /* font dialog */
DWORD   flgs;  /* flags */
object  r;     /* font dialog */

```

This method is used to set the option flags associated with a font dialog. The available flags are fully documented in the Windows documentation under the `CHOOSEFONT` structure and all begin with `CF_`.

Example:

```
object fd;

gSetFlags(fd, CF_ANSIONLY);
```

4.17 Dynamic Link Libraries

The `DynamicLibrary` class is used to support the dynamic link library (DLL) facility of Windows. This class provides a convenient mechanism to load, free and use DLLs.

Throughout this section `dl` will refer to the object which was returned by the `LoadLibrary` method and represents a DLL.

`DeepDispose::DynamicLibrary` [DeepDispose]

This method performs the same function as `Dispose`. See that method for details.

`Dispose::DynamicLibrary` [Dispose]

```
r = gDispose(dl);

object dl; /* a DLL object */
object r;  /* NULL          */
```

This method is used to release and dispose of a DLL object when it is no longer needed. All DLL objects are automatically released by WDS when the application terminates.

The value returned is always `NULL` and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object dl;

dl = gDispose(dl);
```

See also: `FreeAll`, `DeepDispose`

FindStr::DynamicLibrary

[FindStr]

```

dl = gFindStr(DynamicLibrary, fname);

char    *fname; /* DLL file name */
object  dl;      /* DLL object    */

```

This class method is used to obtain the DLL object (previously loaded via **LoadLibrary**) via its associated file name. This won't work after the DLL object is disposed.

Example:

```

object  dl;

dl = gFindStr(DynamicLibrary, "mydll.dll");

```

See also: **LoadLibrary**

FreeAll::DynamicLibrary

[FreeAll]

```

gFreeAll(DynamicLibrary);

```

This class method is used to release and dispose of all DLL objects. It is automatically called by WDS when the application terminates.

Example:

```

gFreeAll(DynamicLibrary);

```

See also: **Dispose**, **DeepDispose**

GetProcAddress::DynamicLibrary

[GetProcAddress]

```

fun = gGetProcAddress(dl, fname);

object  dl;      /* DLL object          */
char    *fname; /* function name      */
FARPROC fun;     /* pointer to function */

```

This method is used to obtain a pointer to a function within a DLL. The DLL function may then be evoked with the pointer.

Example:

```
FARPROC fun;
object dl;

fun = gGetProcAddress(dl, "myfunc");
```

See also: FindStr, LoadLibrary

LoadLibrary::DynamicLibrary

[LoadLibrary]

```
dl = gLoadLibrary(DynamicLibrary, file);

char    *file; /* DLL file    */
object dl;     /* DLL object */
```

This method is used to open a DLL file and create a WDS object which represents the loaded library. If the named file does not contain a path, the normal Windows search path will be searched. If the DLL cannot be found or loaded, NULL will be returned.

Example:

```
object dl;

dl = gLoadLibrary(DynamicLibrary, "mydll.dll");
```

See also: GetProcAddress, Dispose, FindStr

4.18 Tree Views

The **TreeView** class (a subclass of **Control**) implements a hierarchical tree control for displaying and selecting items arranged in a parent-child structure. Individual nodes in the tree are represented by instances of the **TreeViewItem** class.

4.18.1 TreeView Methods

gAddTVItem::TreeView

[AddTVItem]

```
tvi = gAddTVItem(tv, parent, txt);

object tv;      /* TreeView object      */
object parent;  /* parent TreeViewItem or NULL */
char    *txt;    /* item display text     */
object tvi;     /* new TreeViewItem object */
```


Creates and adds a new tree item with the given text. If `parent` is `NULL`, the item is added at the root level. Otherwise it is added as a child of `parent`. Returns the newly created `TreeViewItem`.

See also: `AddTVItemWithImage`

`gAddTVItemWithImage::TreeView`

[`AddTVItemWithImage`]

```
tvi = gAddTVItemWithImage(tv, parent, image, txt);

object tv;      /* TreeView object */
object parent; /* parent TreeViewItem or NULL */
int image;      /* image index in image list */
char *txt;      /* item display text */
object tvi;     /* new TreeViewItem object */
```

Creates and adds a new tree item with the given text and a custom image from the associated image list. Similar to `gAddTVItem` but allows specifying an image index.

See also: `AddTVItem`, `SetImageList`, `NewImageList`

`gAlphabetize::TreeView`

[`Alphabetize`]

```
r = gAlphabetize(tv);

object tv; /* TreeView object */
object r;  /* TreeView object */
```

Enables alphabetical sorting of tree items.

See also: `AlphabetizeOff`, `Resort`

`gAlphabetizeOff::TreeView`

[`AlphabetizeOff`]

```
r = gAlphabetizeOff(tv);

object tv; /* TreeView object */
object r;  /* TreeView object */
```

Disables alphabetical sorting. Items will sort by their original insertion order (or by `order/suborder` properties).

See also: `Alphabetize`, `Resort`

`gCheckFunction::TreeView` [CheckFunction]

```

r = gCheckFunction(tv, fun);

object tv;    /* TreeView object          */
int     (*fun)(); /* validation function          */
object r;     /* TreeView object              */

```

Sets a validation function that is called by `gCheckValue` to validate the tree view's state before the dialog completes.

See also: `CheckValue`

`gCheckValue::TreeView` [CheckValue]

```

err = gCheckValue(tv);

object tv;    /* TreeView object          */
int     err;   /* 0=valid, 1=error          */

```

Validates the tree view's current state using the function set by `gCheckFunction`. Returns 0 if valid, 1 if validation fails.

See also: `CheckFunction`

`gDeselect::TreeView` [Deselect]

```

r = gDeselect(tv);

object tv;    /* TreeView object */
object r;     /* TreeView object */

```

Deselects the current selection in the tree view.

`gFirst::TreeView` [First]

```

tvi = gFirst(tv);

object tv;    /* TreeView object */
object tvi;   /* first TreeViewItem or NULL */

```

Returns the root (first) `TreeViewItem` in the tree, or NULL if the tree is empty.

gGetSelection::TreeView [GetSelection]

```

    tvi = gGetSelection(tv);

    object  tv;      /* TreeView object          */
    object  tvi;     /* selected TreeViewItem or NULL */

```

Returns the currently selected `TreeViewItem`, or `NULL` if no item is selected.

gLoadBitmap::TreeView [LoadBitmap]

```

    id = gLoadBitmap(tv, resID);

    object  tv;      /* TreeView object          */
    unsigned resID;   /* bitmap resource ID       */
    int     id;       /* image ID or -1           */

```

Loads a bitmap resource into the tree view's image list. Returns the image ID for use with `gAddTVItemWithImage`, or `-1` if no image list is associated.

See also: `NewImageList`, `SetImageList`

New::TreeView [New]

```

    tv = vNew(TreeView, ctlID, name, dlg);

    object  tv;      /* new TreeView object      */
    UINT     ctlID;   /* control ID                */
    char     *name;    /* name of control          */
    object  dlg;      /* dialog object             */

```

This method creates a new `TreeView` control and associates it with a control defined in the dialog resource identified by `ctlID`.

gNewImageList::TreeView [NewImageList]

```

    r = gNewImageList(tv, cx, cy, flags, numb, grow);

    object  tv;      /* TreeView object          */
    int     cx;       /* image width              */
    int     cy;       /* image height             */
    unsigned flags;    /* image list flags         */
    int     numb;     /* initial image count       */
    int     grow;     /* grow increment           */
    object  r;        /* TreeView object          */

```

Creates a new `ImageList` and associates it with the tree view.

See also: `SetImageList`, `LoadBitmap`

`gRemoveAll::TreeView`

[RemoveAll]

```
r = gRemoveAll(tv);

object tv;    /* TreeView object */
object r;     /* TreeView object */
```

Clears the entire tree, removing and disposing all items.

`gResort::TreeView`

[Resort]

```
r = gResort(tv);

object tv;    /* TreeView object */
object r;     /* TreeView object */
```

Re-sorts the tree items. If alphabetical sorting is enabled (via `gAlphabetize`), items are sorted alphabetically. Otherwise items are sorted by their `order` and `suborder` properties. The current selection is preserved.

See also: `Alphabetize`, `AlphabetizeOff`

`gSetExpFun::TreeView`

[SetExpFun]

```
prev = gSetExpFun(tv, fun);

object tv;    /* TreeView object */
ifun fun;     /* expand/collapse callback function */
ifun prev;    /* previous callback function */
```

Sets a callback function that is called when a tree item is expanded or collapsed. Returns the previous callback function.

`gSetImageList::TreeView`

[SetImageList]

```
r = gSetImageList(tv, imageList);

object tv;    /* TreeView object */
object imageList; /* ImageList object */
object r;     /* TreeView object */
```

Associates an `ImageList` object with the tree view for custom item icons.

See also: `NewImageList`, `LoadBitmap`

`gSetSelFun::TreeView`

[SetSelFun]

```
prev = gSetSelFun(tv, fun);

object tv;      /* TreeView object */
ifun fun;      /* selection changed callback function */
ifun prev;     /* previous callback function */
```

Sets a callback function that is called when the selected tree item changes. Returns the previous callback function. The callback receives the dialog object, the `TreeView` control, and the newly selected `TreeViewItem`.

4.18.2 TreeViewItem Methods

`gAutoDisposeTag::TreeViewItem`

[AutoDisposeTag]

```
r = gAutoDisposeTag(tvi);

object tvi; /* TreeViewItem object */
object r;   /* TreeViewItem object */
```

Enables automatic disposal of the tag object when the tree item is disposed or when a new tag replaces the old one.

See also: `SetTag`, `GetTag`

`gChangeImage::TreeViewItem`

[ChangeImage]

```
r = gChangeImage(tvi, image);

object tvi; /* TreeViewItem object */
int image; /* new image index */
object r;   /* TreeViewItem object */
```

Changes the display image of the tree item. The image index refers to an image in the `ImageList` associated with the parent `TreeView`.

See also: `GetImageID`

gChild::TreeViewItem [Child]

```
c = gChild(tvi);

object tvi; /* TreeViewItem object */
object c;   /* first child item or NULL */
```

Returns the first child `TreeViewItem`, or `NULL` if the item has no children.

gChildren::TreeViewItem [Children]

```
c = gChildren(tvi);

object tvi; /* TreeViewItem object */
object c;   /* children collection or NULL */
```

Returns the collection of child `TreeViewItem` objects, or `NULL` if the item has no children.

gCollapse::TreeViewItem [Collapse]

```
r = gCollapse(tvi);

object tvi; /* TreeViewItem object */
object r;   /* TreeViewItem object */
```

Collapses the tree node to hide its children.

See also: `Expand`

gControl::TreeViewItem [Control]

```
tv = gControl(tvi);

object tvi; /* TreeViewItem object */
object tv;  /* TreeView object */
```

Returns the `TreeView` control object that contains this item.

gDeleteTVItem::TreeViewItem [DeleteTVItem]

```
r = gDeleteTVItem(tvi);

object tvi; /* TreeViewItem object */
object r;   /* NULL */
```

Removes this item from its parent and disposes it. All children are also disposed.

`gDisposeChildren::TreeViewItem` [DisposeChildren]

```
r = gDisposeChildren(tvi);

object tvi; /* TreeViewItem object */
object r;
```

Disposes all child items of this node.

`gExpand::TreeViewItem` [Expand]

```
r = gExpand(tvi);

object tvi; /* TreeViewItem object */
object r;   /* TreeViewItem object */
```

Expands the tree node to show its children.

See also: Collapse

`gGetImageID::TreeViewItem` [GetImageID]

```
id = gGetImageID(tvi);

object tvi; /* TreeViewItem object */
int     id; /* image index          */
```

Returns the current image index for this tree item.

See also: ChangeImage

`gGetParent::TreeViewItem` [GetParent]

```
p = gGetParent(tvi);

object tvi; /* TreeViewItem object */
object p;   /* parent item or NULL    */
```

Returns the parent `TreeViewItem`, or `NULL` if the item is at the root level.

gGetTag::TreeViewItem

[GetTag]

```

tag = gGetTag(tvi);

object tvi; /* TreeViewItem object */
object tag; /* tag object or NULL */

```

Returns the user data object attached to the tree item, or NULL if none is set.

See also: **SetTag**

gIsChildOf::TreeViewItem

[IsChildOf]

```

val = gIsChildOf(tvi, parent);

object tvi; /* TreeViewItem object */
object parent; /* potential ancestor */
int val; /* 1=yes, 0=no */

```

Returns 1 if the item is a descendant of **parent**, 0 otherwise. Walks up the parent chain to determine the relationship.

gNewTVItem::TreeViewItem

[NewTVItem]

```

tvi = gNewTVItem(TreeViewItem, tv, parent, image, alpha, txt);

object tvi; /* new TreeViewItem object */
object tv; /* TreeView control object */
object parent; /* parent item or NULL */
int image; /* image index */
int alpha; /* alphabetize flag */
char *txt; /* item display text */

```

Low-level factory method to create a **TreeViewItem**. Most applications should use **gAddTVItem** or **gAddTVItemWithImage** on the **TreeView** instead.

gNext::TreeViewItem

[Next]

```

nxt = gNext(tvi);

object tvi; /* TreeViewItem object */
object nxt; /* next item or NULL */

```

Returns the next visible **TreeViewItem** in tree traversal order, or NULL if there is no next item.

`gSelect::TreeViewItem` [Select]

```

r = gSelect(tvi);

object tvi; /* TreeViewItem object */
object r;   /* TreeViewItem object */

```

Programmatically selects this item in the tree view.

`gSetStringValue::TreeViewItem` [SetStringValue]

```

r = gSetStringValue(tvi, val);

object tvi; /* TreeViewItem object */
char    *val; /* new display text */
object r;   /* TreeViewItem object */

```

Updates the display text of the tree item.

See also: `StringValue`

`gSetTag::TreeViewItem` [SetTag]

```

prev = gSetTag(tvi, tag);

object tvi; /* TreeViewItem object */
object tag; /* user data object */
object prev; /* previous tag or NULL */

```

Attaches an arbitrary user data object to the tree item. Returns the previous tag. If auto-dispose is enabled and a previous tag exists, it is automatically disposed.

See also: `GetTag`, `AutoDisposeTag`

`gStringValue::TreeViewItem` [StringValue]

```

s = gStringValue(tvi);

object tvi; /* TreeViewItem object */
char    *s; /* display text string */

```

Returns the current display text of the tree item.

See also: `SetStringValue`

4.19 Tool Bar

The `ToolBar` class (a subclass of `ChildWindow`) implements a toolbar control that displays a row of bitmap buttons and optional combo box controls at the top of a window. Each button can have an associated callback function and tooltip.

4.19.1 ToolBar Methods

`gAddToolBitmap::ToolBar` [AddToolBitmap]

```
r = gAddToolBitmap(tb, id1, id2, space, fun, tip);

object    tb;          /* ToolBar object                */
unsigned  id1;         /* resource ID of normal bitmap    */
unsigned  id2;         /* resource ID of pressed bitmap (0=same) */
int       space;       /* extra space to the left (pixels) */
LRESULT   (*fun)();    /* click callback function         */
char      *tip;        /* tooltip text or NULL            */
object    r;           /* ToolBar object                  */
```

Adds a bitmap button to the toolbar. `id1` is the resource ID of the normal (up) state bitmap. `id2` is the pressed (down) state bitmap; pass 0 to use the same bitmap for both states. `space` adds extra horizontal spacing before the button. `fun` is the callback function invoked when the button is clicked. `tip` is the tooltip text displayed on hover.

The callback function receives two arguments: the parent window object and the button resource ID.

See also: `AddToolBitmapFromFile`

`gAddToolBitmapFromFile::ToolBar` [AddToolBitmapFromFile]

```
r = gAddToolBitmapFromFile(tb, file, id1, id2, space, fun, tip);

object    tb;          /* ToolBar object                */
char      *file;       /* bitmap file path              */
unsigned  id1;         /* resource ID of normal bitmap    */
unsigned  id2;         /* resource ID of pressed bitmap    */
int       space;       /* extra space to the left (pixels) */
LRESULT   (*fun)();    /* click callback function         */
char      *tip;        /* tooltip text or NULL            */
object    r;           /* ToolBar object                  */
```

Adds a bitmap button from an external file rather than a resource. Otherwise identical to `gAddToolBitmap`.

See also: `AddToolBitmap`

`gAddToolComboBox::ToolBar`

[`AddToolComboBox`]

```
ctl = gAddToolComboBox(tb, height, width, space, fun, tip, name);
```

```
object  tb;      /* ToolBar object          */
int     height;  /* drop-down height        */
int     width;   /* control width           */
int     space;   /* extra space to the left (pixels) */
int     (*fun)(); /* change callback function */
char     *tip;    /* tooltip text or NULL     */
char     *name;   /* control name             */
object  ctl;     /* ComboBox control object  */
```

Adds a `ComboBox` control to the toolbar. Returns the combo box control object, which can be configured using the `ComboBox` methods.

`gChangeTip::ToolBar`

[`ChangeTip`]

```
r = gChangeTip(tb, id, tip);
```

```
object  tb;      /* ToolBar object          */
unsigned id;     /* button resource ID      */
char     *tip;    /* new tooltip text        */
object  r;       /* ToolBar object          */
```

Changes the tooltip text for a toolbar button.

See also: `GetTip`

`gEnableToolBitmap::ToolBar`

[`EnableToolBitmap`]

```
changed = gEnableToolBitmap(tb, id, val);
```

```
object  tb;      /* ToolBar object          */
unsigned id;     /* button resource ID      */
int     val;     /* 1=enable, 0=disable     */
int     changed; /* 1 if state changed, 0 if not */
```

Enables or disables a toolbar button. Disabled buttons are drawn with a grayed-out appearance and do not respond to clicks.

gGetControlStr::ToolBar

[GetControlStr]

```
ctl = gGetControlStr(tb, name);
```

```
object  tb;      /* ToolBar object          */
char    *name;   /* control name                */
object  ctl;     /* ComboBox control object or NULL */
```

Retrieves a combo box control embedded in the toolbar by its name. Returns NULL if not found.

gGetTip::ToolBar

[GetTip]

```
s = gGetTip(tb, id);
```

```
object  tb;      /* ToolBar object          */
unsigned id;     /* button resource ID      */
char    *s;      /* tooltip text            */
```

Returns the tooltip text for a toolbar button.

See also: [ChangeTip](#)

New::ToolBar

[New]

```
tb = vNew(ToolBar, win);
```

```
object  tb;      /* new ToolBar object      */
object  win;     /* parent window object    */
```

Creates a new ToolBar and attaches it to the top of the specified parent window.

gPixelHeight::ToolBar

[PixelHeight]

```
h = gPixelHeight(tb);
```

```
object  tb;      /* ToolBar object          */
int      h;      /* toolbar pixel height    */
```

Returns the pixel height of the toolbar.

`gSetAccessModeFunction::ToolBar` [SetAccessModeFunction]

```
prev = gSetAccessModeFunction(ToolBar, fun);

ifun fun;    /* access mode function */
ifun prev;   /* previous function    */
```

This is a class method. Sets a function that determines whether each toolbar button should be enabled or disabled based on application-level access control. Returns the previous function.

The function is called for each button during `gUpdateAccessMode` and receives the button resource ID as an argument.

See also: `UpdateAccessMode`

`gSetToolBarMouseFunction::ToolBar` [SetToolBarMouseFunction]

```
prev = gSetToolBarMouseFunction(tb, id, button, fun);

object    tb;          /* ToolBar object                */
unsigned  id;           /* button resource ID          */
unsigned  button;       /* mouse button/modifier combination */
ifun      fun;          /* callback function           */
ofun      prev;         /* previous callback function    */
```

Sets a mouse event callback for a specific toolbar button and mouse button/modifier combination. The `button` parameter encodes both the mouse button (left/right) and modifier keys (Shift, Control).

`gSetToolFunction::ToolBar` [SetToolFunction]

```
prev = gSetToolFunction(tb, id, fun);

object    tb;          /* ToolBar object                */
unsigned  id;           /* button resource ID          */
LRESULT   (*fun)();     /* new click callback           */
ifun      prev;         /* previous callback function    */
```

Changes the click callback function for a toolbar button. Returns the previous function.

gShowToolBitmap::ToolBar

[ShowToolBitmap]

```

    prev = gShowToolBitmap(tb, id, val);

    object    tb;    /* ToolBar object          */
    unsigned  id;    /* button resource ID          */
    int       val;   /* 1=show, 0=hide              */
    int       prev;  /* previous hidden state       */

```

Shows or hides a toolbar button.

gUpdateAccessMode::ToolBar

[UpdateAccessMode]

```

    r = gUpdateAccessMode(tb);

    object  tb;    /* ToolBar object */
    object  r;     /* ToolBar object */

```

Updates the enabled/disabled state of all toolbar buttons by calling the access mode function set via `gSetAccessModeFunction`.

See also: `SetAccessModeFunction`

gUpdateState::ToolBar

[UpdateState]

```

    r = gUpdateState(tb);

    object  tb;    /* ToolBar object */
    object  r;     /* ToolBar object */

```

Updates the toolbar's position and size to match the parent window's current width. Typically called after the parent window is resized.

gUseAlternateColor::ToolBar

[UseAlternateColor]

```

    gUseAlternateColor(tb);

    object  tb;    /* ToolBar object */

```

Enables alternate color mode for toolbar button rendering.

4.20 Status Bar

The `StatusBar` class (a subclass of `ChildWindow`) implements a status bar control that displays one or more text sections at the bottom of a window.

4.20.1 StatusBar Methods

`gAddSection::StatusBar`

[AddSection]

```
r = gAddSection(sb, id, width, mode);

object sb;      /* StatusBar object      */
int id;         /* section identifier      */
int width;      /* section width           */
int mode;       /* alignment mode          */
object r;       /* StatusBar object or NULL */
```

Adds a new section to the status bar. `id` is used to identify the section when setting text. `width` specifies the section width. Returns NULL if the maximum number of sections (20) has been reached.

See also: `SetSectionText`

`New::StatusBar`

[New]

```
sb = vNew(StatusBar, win);

object sb;      /* new StatusBar object */
object win;     /* parent window object */
```

Creates a new `StatusBar` and attaches it to the bottom of the specified parent window.

`gPixelHeight::StatusBar`

[PixelHeight]

```
h = gPixelHeight(sb);

object sb;      /* StatusBar object */
int h;          /* status bar pixel height */
```

Returns the pixel height of the status bar.

`gSetSectionText::StatusBar`

[SetSectionText]

```
r = gSetSectionText(sb, id, text);

object sb;      /* StatusBar object */
int id;         /* section ID        */
char *text;     /* display text      */
object r;       /* StatusBar object */
```

Sets or updates the text displayed in a status bar section.

See also: `AddSection`

`gUpdateState::StatusBar`

[UpdateState]

```

r = gUpdateState(sb);

object sb;    /* StatusBar object */
object r;    /* StatusBar object */

```

Updates the status bar's position and size to align with the parent window's bottom edge. Typically called after the parent window is resized.

4.21 Image Control

The `ImageControl` class (a subclass of `Control`) implements a control for displaying bitmap images in dialogs and windows. Bitmaps can be loaded from resource IDs or from external `.bmp` files.

4.21.1 ImageControl Methods

`gGetExitType::ImageControl`

[GetExitType]

```

type = gGetExitType(ic);

object ic;    /* ImageControl object */
int    type;  /* exit type */

```

Returns the exit type previously set by `gSetExitType`.

See also: `SetExitType`

`New::ImageControl`

[New]

```

ic = vNew(ImageControl, ctlID, name, dlg);

object ic;    /* new ImageControl object */
UINT    ctlID; /* control ID */
char    *name; /* control name */
object  dlg;   /* dialog object */

```

Creates a new `ImageControl` associated with a control defined in the dialog resource.

`gSetBitmapID::ImageControl` [SetBitmapID]

```

r = gSetBitmapID(ic, id);

object ic;    /* ImageControl object      */
int     id;    /* bitmap resource ID                     */
object  r;     /* ImageControl object                     */

```

Sets the displayed bitmap from a resource ID. The bitmap is loaded and displayed when the control is shown.

See also: `SetStringValue`

`gSetButtonBorder::ImageControl` [SetButtonBorder]

```

prev = gSetButtonBorder(ic, val);

object ic;    /* ImageControl object      */
int     val;   /* -1=down, 0=none, 1=up border */
int     prev;  /* previous border value      */

```

Sets the 3D border style around the image control. 1 gives a raised border, -1 gives a sunken border, and 0 removes the border. Returns the previous border setting.

`gSetDCFunction::ImageControl` [SetDCFunction]

```

prev = gSetDCFunction(ic, fun);

object ic;    /* ImageControl object      */
int     (*fun)(); /* double-click callback function */
ofun     prev; /* previous callback function    */

```

Sets a callback function that is invoked when the user double-clicks the image control. Returns the previous callback function.

`gSetExitType::ImageControl` [SetExitType]

```

r = gSetExitType(ic, type);

object ic;    /* ImageControl object      */
int     type;  /* IDOK, IDCANCEL, or 0     */
object  r;     /* ImageControl object      */

```

Configures the image control to act like a button that closes the dialog when clicked. Pass `IDOK` or `IDCANCEL` to enable this behavior, or 0 to disable it.

See also: `GetExitType`

`gSetStringValue::ImageControl`

[`SetStringValue`]

```
r = gSetStringValue(ic, val);

object ic;    /* ImageControl object */
char    *val; /* bitmap file path    */
object r;    /* ImageControl object */
```

Sets the displayed bitmap from an external .bmp file path.

See also: `SetBitmapID`, `StringValue`

`gStringValue::ImageControl`

[`StringValue`]

```
s = gStringValue(ic);

object ic;    /* ImageControl object */
char    *s;    /* bitmap file path    */
```

Returns the bitmap file path currently associated with the control.

See also: `SetStringValue`

4.22 Time Control

The `TimeControl` class (a subclass of `SpinControl`) implements a control for entering and validating time values. It supports configurable time ranges, formatting, and 12-hour wrapping.

4.22.1 TimeControl Methods

`gBlankIfZero::TimeControl`

[`BlankIfZero`]

```
prev = gBlankIfZero(tc, val);

object tc;    /* TimeControl object */
int    val;    /* 1=blank if zero, 0=no */
int    prev;    /* previous setting    */
```

When enabled, the control displays as blank when the time value is zero rather than showing 0:00. Returns the previous setting.

`gFormatTime::TimeControl`

[FormatTime]

```

r = gFormatTime(tc, fmt);

object tc;    /* TimeControl object    */
char    *fmt; /* format string            */
object r;     /* TimeControl object    */

```

Sets the format string used to display the time value.

`gHideData::TimeControl`

[HideData]

```

prev = gHideData(tc, flg);

object tc;    /* TimeControl object    */
int    flg;   /* 1=hide, 0=show        */
int    prev;  /* previous setting      */

```

When enabled, the control displays asterisks instead of the actual time value. Returns the previous setting.

`gIsBlank::TimeControl`

[IsBlank]

```

val = gIsBlank(tc);

object tc;    /* TimeControl object    */
int    val;   /* 1=blank, 0=has value  */

```

Returns 1 if the control is currently blank, 0 otherwise.

`New::TimeControl`

[New]

```

tc = vNew(TimeControl, ctlID, name, dlg);

object tc;    /* new TimeControl object */
UINT    ctlID; /* control ID            */
char    *name; /* control name          */
object dlg;   /* dialog object          */

```

Creates a new `TimeControl` associated with a control defined in the dialog resource.

gSetBeginHour::TimeControl

[SetBeginHour]

```

prev = gSetBeginHour(tc, hour);

object tc;      /* TimeControl object      */
int     hour;   /* beginning hour for wrap  */
int     prev;   /* previous begin hour      */

```

Sets the beginning hour for 12-hour wrap-around behavior. For example, setting this to 8 means hours are interpreted in the range 8:00–7:59. Returns the previous value.

This method may also be called as a class method on **TimeControl** to set the default for all instances.

gSetDefaultLong::TimeControl

[SetDefaultLong]

```

r = gSetDefaultLong(tc, val);

object tc;      /* TimeControl object */
long  val;      /* default time value */
object r;       /* TimeControl object */

```

Sets the default time value used when **gUseDefault** is called.

gSetTimeValue::TimeControl

[SetTimeValue]

```

r = gSetTimeValue(tc, val);

object tc;      /* TimeControl object */
long  val;      /* time as long value */
object r;       /* TimeControl object */

```

Sets the time value from a long integer and updates the display. **gSetLongValue** is a synonym for this method.

See also: **TimeValue**

gTimeRange::TimeControl

[TimeRange]

```

r = gTimeRange(tc, minimum, maximum, allowNone);

object tc;      /* TimeControl object */
long  minimum;  /* minimum time value */
long  maximum;  /* maximum time value */
int    allowNone; /* 1=allow empty, 0=required */
object r;       /* TimeControl object */

```

Sets the valid time range for the control. If `allowNone` is 1, the user may leave the field empty.

`gTimeValue::TimeControl` [TimeValue]

```
val = gTimeValue(tc);

object tc;    /* TimeControl object */
long    val;  /* time as long value  */
```

Returns the current time value as a long integer. `gLongValue` is a synonym for this method.

See also: `SetTimeValue`

4.23 Shortcut Menu

The `ShortcutMenu` class (a subclass of `Menu`) implements context menus (also known as popup or right-click menus) that can be displayed at arbitrary screen positions.

4.23.1 ShortcutMenu Methods

`gAddMenuOption::ShortcutMenu` [AddMenuOption]

```
id = gAddMenuOption(sm, title, fun);

object sm;    /* ShortcutMenu object */
char    *title; /* menu item text      */
void    (*fun)(); /* callback function */
int     id;     /* assigned menu item ID */
```

Dynamically adds a menu item with the given text and callback function. Returns the automatically assigned ID for the menu item.

See also: `AddSubMenu`, `AddSeparator`

`gAddSeparator::ShortcutMenu` [AddSeparator]

```
r = gAddSeparator(sm);

object sm; /* ShortcutMenu object */
object r;  /* ShortcutMenu object */
```

Adds a separator line to the menu.

See also: `AddMenuOption`

`gAddSubMenu::ShortcutMenu``[AddSubMenu]`

```

sub = gAddSubMenu(sm, title);

object sm;      /* ShortcutMenu object */
char *title;    /* submenu title */
object sub;     /* new submenu object */

```

Creates and adds a new submenu with the given title. Returns the new submenu object, which can have items added to it via `gAddMenuOption`.

See also: `AddMenuOption`, `AddSeparator`

`gLoadShortcutMenu::ShortcutMenu``[LoadShortcutMenu]`

```

sm = gLoadShortcutMenu(ShortcutMenu, id, submenu);

object sm;      /* new ShortcutMenu object */
unsigned id;    /* menu resource ID */
int submenu;    /* submenu index */

```

This is a class method. Loads a shortcut menu from a menu resource by numeric ID. `submenu` specifies which submenu to use from the resource.

See also: `LoadShortcutMenuStr`

`gLoadShortcutMenuFromFile::ShortcutMenu``[LoadShortcutMenuFromFile]`

```

sm = gLoadShortcutMenuFromFile(ShortcutMenu, file, id, submenu);

object sm;      /* new ShortcutMenu object */
char *file;     /* resource file path */
unsigned id;    /* menu resource ID */
int submenu;    /* submenu index */

```

This is a class method. Loads a shortcut menu from an external resource file.

`gLoadShortcutMenuStr::ShortcutMenu``[LoadShortcutMenuStr]`

```

sm = gLoadShortcutMenuStr(ShortcutMenu, name, submenu);

object sm;      /* new ShortcutMenu object */
char *name;     /* menu resource name */
int submenu;    /* submenu index */

```

This is a class method. Loads a shortcut menu from a menu resource by string name.

See also: `LoadShortcutMenu`

`New::ShortcutMenu`

[New]

```
sm = vNew(ShortcutMenu);
```

```
object sm; /* new ShortcutMenu object */
```

Creates a new, empty shortcut menu.

See also: `LoadShortcutMenu`, `LoadShortcutMenuStr`

`gPerform::ShortcutMenu`

[Perform]

```
r = gPerform(sm);
```

```
object sm; /* ShortcutMenu object */
```

```
int r; /* result */
```

Displays the shortcut menu at the current cursor position and executes the callback associated with the item selected by the user.

4.24 Static Control

The `StaticControl` class (a subclass of `Control`) implements a basic static text display control. The `StaticTextControl` class (a subclass of `TextControl`) provides additional capabilities including printing, XML serialization, and multi-language support.

4.24.1 StaticControl Methods

`New::StaticControl`

[New]

```
sc = vNew(StaticControl, ctlID, name, dlg);
```

```
object sc; /* new StaticControl object */
```

```
UINT ctlID; /* control ID */
```

```
char *name; /* control name */
```

```
object dlg; /* dialog object */
```

Creates a new `StaticControl` associated with a control defined in the dialog resource.

gSetStringValue::StaticControl**[SetStringValue]**

```

r = gSetStringValue(sc, val);

object  sc;    /* StaticControl object */
char    *val;  /* display text          */
object  r;     /* StaticControl object */

```

Sets the text displayed by the static control. **gSetTitle** is a synonym for this method.

See also: **StringValue**

gStringValue::StaticControl**[StringValue]**

```

s = gStringValue(sc);

object  sc;    /* StaticControl object */
char    *s;    /* display text string  */

```

Returns the current display text.

See also: **SetStringValue**

4.24.2 StaticTextControl Methods

The **StaticTextControl** class inherits from **TextControl** and adds support for URL bindings, multi-language text, and right-alignment.

gResetText::StaticTextControl**[ResetText]**

```

r = gResetText(stc);

object  stc;    /* StaticTextControl object */
object  r;      /* StaticTextControl object */

```

Resets the window text to the current language's text value.

See also: **SetCurrentLanguage**

`gSetCurrentLanguage::StaticTextControl` [SetCurrentLanguage]

```

r = gSetCurrentLanguage(stc, lang);

object stc;    /* StaticTextControl object */
int     lang;   /* language ID                */
object  r;      /* StaticTextControl object */

```

Sets the display language and updates the text accordingly.

See also: `ResetText`

`gSetURL::StaticTextControl` [SetURL]

```

r = gSetURL(stc, url);

object stc;    /* StaticTextControl object */
char   *url;    /* URL binding string        */
object r;      /* StaticTextControl object */

```

Associates a URL with the static text control.

See also: `URL`

`gURL::StaticTextControl` [URL]

```

s = gURL(stc);

object stc;    /* StaticTextControl object */
char   *s;     /* URL string                 */

```

Returns the URL associated with this control, or an empty string if none is set.

See also: `SetURL`

4.25 Bitmap

The `Bitmap` class provides support for displaying bitmap images on windows. Bitmaps can be positioned, centered, tiled, or stretched to fill the window.

4.25.1 Bitmap Methods

`gDrawBitmap::Bitmap`

[DrawBitmap]

```

r = gDrawBitmap(bm);

object  bm;    /* Bitmap object */
object  r;     /* Bitmap object */

```

Draws the bitmap on its parent window using the positioning mode specified at creation time (positioned, centered, or tiled).

`gNewBitmap::Bitmap`

[NewBitmap]

```

bm = gNewBitmap(Bitmap, bmpID, mode, y, x, wind);

object  bm;      /* new Bitmap object      */
UINT    bmpID;   /* bitmap resource ID      */
int     mode;    /* display mode            */
int     y;       /* vertical position       */
int     x;       /* horizontal position     */
object  wind;    /* parent window object    */

```

This is a class method. Creates a new `Bitmap` object from a resource. `mode` controls how the bitmap is displayed: 1 for positioned at (x,y), 2 for centered, 3 for tiled. Position values are scaled to font pixels.

See also: `NewBitmap2`, `DrawBitmap`

`gNewBitmap2::Bitmap`

[NewBitmap2]

```

bm = gNewBitmap2(Bitmap, bmpID, mode, y, x, wind);

object  bm;      /* new Bitmap object      */
UINT    bmpID;   /* bitmap resource ID      */
int     mode;    /* display mode            */
int     y;       /* vertical position       */
int     x;       /* horizontal position     */
object  wind;    /* parent window object    */

```

This is a class method. Identical to `gNewBitmap` except that position values are not scaled to font pixels — they are used as raw pixel coordinates.

See also: `NewBitmap`

4.26 Spin Control

The `SpinControl` class (a subclass of `Control`) provides spin button (up/down arrow) functionality that can be attached to other controls such as `TimeControl` or `NumericControl`.

4.26.1 SpinControl Methods

`gSetSpinFunction::SpinControl` [SetSpinFunction]

```

r = gSetSpinFunction(ctl, spinID, func);

object    ctl;          /* SpinControl object          */
unsigned  spinID;       /* resource ID of spin button      */
int        (*func)(object ctl, object dlg, int val);
                        /* callback function              */
object    r;           /* SpinControl object             */

```

Associates a spin button control with this control and sets the callback function. The callback receives the control object, the dialog object, and a value of +1 (up arrow) or -1 (down arrow).

4.27 Task List

The `TaskList` class provides a workflow management system that presents the user with a list of tasks (steps) displayed in a modeless dialog. Each task in the list is represented by a `Task` object that manages its own dialog or processing step. The user selects tasks from the list, and the system handles transitions, validation, and cleanup between tasks.

4.27.1 TaskList Methods

`gAddCompletionFunctionAfter::TaskList` [AddCompletionFunctionAfter]

```

r = gAddCompletionFunctionAfter(tl, fun);

object  tl;    /* TaskList object      */
int      (*fun)(); /* completion function */
object  r;     /* TaskList object      */

```

Adds a completion function that is called after other completion functions when the task list closes.

See also: `AddCompletionFunctionBefore`, `CompletionFunction`

`gAddCompletionFunctionBefore::TaskList` [AddCompletionFunctionBefore]

```

r = gAddCompletionFunctionBefore(tl, fun);

object tl;    /* TaskList object          */
int      (*fun)(); /* completion function */
object r;     /* TaskList object          */

```

Adds a completion function that is called before other completion functions when the task list closes.

See also: `AddCompletionFunctionAfter`, `CompletionFunction`

`gAddTask::TaskList` [AddTask]

```

r = gAddTask(tl, proc, option);

object tl;    /* TaskList object          */
object proc;  /* task procedure           */
char  *option; /* display text for list box */
object r;     /* link object              */

```

Adds a task to the task list with the given display text. The text appears in the list box presented to the user.

`gCheckValue::TaskList` [CheckValue]

```

err = gCheckValue(tl);

object tl;    /* TaskList object          */
int      err;  /* 0=valid, non-zero=error */

```

Validates the current task's dialog values. Returns 0 if valid, non-zero if validation fails.

`gCompletionFunction::TaskList` [CompletionFunction]

```

r = gCompletionFunction(tl, fun);

object tl;    /* TaskList object          */
int      (*fun)(); /* completion function */
object r;     /* TaskList object          */

```

Sets a completion function to be called when the task list closes. Replaces any previously set completion function.

See also: `AddCompletionFunctionAfter`, `AddCompletionFunctionBefore`

`gCurrentTask::TaskList`

[CurrentTask]

```
task = gCurrentTask(tl);

object tl;    /* TaskList object */
object task;  /* current Task or NULL */
```

Returns the currently active Task object, or NULL if no task is active.

`gDialog::TaskList`

[Dialog]

```
dlg = gDialog(tl);

object tl;    /* TaskList object */
object dlg;   /* ModelessDialog object */
```

Returns the ModelessDialog object that contains the task list UI.

`gDisable::TaskList`

[Disable]

```
r = gDisable(tl);

object tl;    /* TaskList object */
object r;     /* TaskList object */
```

Disables the task list dialog.

See also: `Enable`

`gEnable::TaskList`

[Enable]

```
r = gEnable(tl);

object tl;    /* TaskList object */
object r;     /* TaskList object */
```

Enables the task list dialog and restores focus to the current task if one is active.

See also: `Disable`

gGetPosition::TaskList

[GetPosition]

```

r = gGetPosition(tl, y, x);

object tl;    /* TaskList object          */
int     *y;   /* pointer to vertical position */
int     *x;   /* pointer to horizontal position */
object  r;    /* TaskList object          */

```

Retrieves the current position of the task list dialog.

gGetTag::TaskList

[GetTag]

```

tag = gGetTag(tl);

object tl;    /* TaskList object          */
object tag;   /* tag object or NULL      */

```

Returns the user data object attached to the task list, or NULL if none is set.

See also: SetTag, AutoDisposeTag

gNewTaskList::TaskList

[NewTaskList]

```

tl = gNewTaskList(TaskList, dlg_id, lb_id, pwind, fun);

object tl;    /* new TaskList object          */
unsigned dlg_id; /* dialog resource ID          */
unsigned lb_id; /* list box control ID          */
object pwind; /* parent window                */
int      (*fun)(); /* initialization function or NULL */

```

This is a class method. Creates a new TaskList with a modeless dialog (**dlg_id**) containing a list box (**lb_id**). **pwind** is the parent window. **fun** is an optional initialization function called when the dialog is set up.

gNextTask::TaskList

[NextTask]

```

r = gNextTask(tl, result);

object tl;    /* TaskList object          */
int     result; /* task completion result */
object  r;    /* TaskList object          */

```

Advances to the next task. The `result` parameter indicates how the current task completed (e.g. OK or Cancel), which determines whether the current task's save or cleanup phase is executed.

`gPerform::TaskList`

[Perform]

```
r = gPerform(tl);

object tl;    /* TaskList object */
int     r;    /* 0                */
```

Displays the task list selection dialog non-modally.

See also: `PerformModal`

`gPerformModal::TaskList`

[PerformModal]

```
r = gPerformModal(tl);

object tl;    /* TaskList object */
int     r;    /* 0                */
```

Displays the task list selection dialog modally, disabling the parent window until the task list is closed.

See also: `Perform`

`gSetShortValue::TaskList`

[SetShortValue]

```
r = gSetShortValue(tl, val);

object tl;    /* TaskList object      */
int     val;  /* task index to select  */
object r;    /* TaskList object      */
```

Selects a task by index in the list box.

`gSetTag::TaskList`

[SetTag]

```
prev = gSetTag(tl, tag);

object tl;    /* TaskList object      */
object tag;   /* user data object     */
object prev;  /* previous tag or NULL */
```

Attaches a user data object to the task list. Returns the previous tag. If auto-dispose is enabled and a previous tag exists, it is automatically disposed.

See also: `GetTag`, `AutoDisposeTag`

`gSetZOrder::TaskList`

[`SetZOrder`]

```
r = gSetZOrder(tl, hwnd);

object tl;      /* TaskList object      */
HWND    hwnd;   /* window to position after */
object r;      /* TaskList object      */
```

Sets the z-order (window stacking position) for the task list dialog.

4.27.2 Task Methods

`gAutoDisposeTag::Task`

[`AutoDisposeTag`]

```
r = gAutoDisposeTag(task);

object task; /* Task object */
object r;    /* Task object */
```

Enables automatic disposal of the tag object when the task is disposed or when a new tag replaces the old one.

See also: `SetTag`, `GetTag`

`gCheckValue::Task`

[`CheckValue`]

```
err = gCheckValue(task);

object task; /* Task object */
int    err;  /* 0=valid, non-zero=error */
```

Validates the task's dialog values. Returns 0 if valid, non-zero if validation fails.

`gGetTag::Task`

[`GetTag`]

```
tag = gGetTag(task);

object task; /* Task object */
object tag;  /* tag object or NULL */
```

Returns the user data object attached to the task, or NULL if none is set.

See also: `SetTag`, `AutoDisposeTag`

`gNewTask::Task` [NewTask]

```
task = gNewTask(Task, tl);

object task;    /* new Task object    */
object tl;      /* parent TaskList    */
```

This is a class method. Creates a new `Task` associated with the given `TaskList`.

`gNextTask::Task` [NextTask]

```
r = gNextTask(task, result);

object task;    /* Task object        */
int    result;  /* completion result code */
object r;       /* Task object        */
```

Advances to the next task in the parent `TaskList` with the given result code.

`gSetTag::Task` [SetTag]

```
prev = gSetTag(task, tag);

object task;    /* Task object        */
object tag;     /* user data object    */
object prev;    /* previous tag or NULL */
```

Attaches a user data object to the task. Returns the previous tag.

See also: `GetTag`, `AutoDisposeTag`

`gTaskList::Task` [TaskList]

```
tl = gTaskList(task);

object task;    /* Task object        */
object tl;      /* TaskList object    */
```

Returns the `TaskList` that this task belongs to.

4.28 HTTP Request

The `HttpRequest` class provides an HTTP client for making HTTP and HTTPS requests. It wraps the WinInet API and supports custom headers, authentication, request bodies, and

response handling. The `WebService` class builds on `HttpRequest` to provide a higher-level SOAP web service client.

4.28.1 HttpRequest Methods

`gAddHeader::HttpRequest` [AddHeader]

```
r = gAddHeader(req, name, value);

object req;    /* HttpRequest object */
char    *name; /* header name         */
char    *value; /* header value       */
object r;      /* HttpRequest object */
```

Adds a custom HTTP request header.

`gGetErrorMessage::HttpRequest` [GetErrorMessage]

```
s = gGetErrorMessage(req);

object req; /* HttpRequest object */
char    *s; /* error message or NULL */
```

Returns the error message string if the request failed, or `NULL` if no error occurred.

`gGetResponse::HttpRequest` [GetResponse]

```
s = gGetResponse(req);

object req; /* HttpRequest object */
char    *s; /* response body string */
```

Returns the response body as a string. Only populated if no output file was specified via `gSetOutputFileName`.

See also: `SetOutputFileName`

`gGetResponseHeader::HttpRequest` [GetResponseHeader]

```
s = gGetResponseHeader(req, name);

object req; /* HttpRequest object */
char    *name; /* header name (case-insensitive) */
char    *s;    /* header value or NULL */
```

Returns the value of a single response header by name. The lookup is case-insensitive. Returns NULL if the header is not found.

See also: `GetResponseHeaders`

`gGetResponseHeaders::HttpRequest` [`GetResponseHeaders`]

```
dict = gGetResponseHeaders(req);
```

```
object req;    /* HttpRequest object      */
object dict;   /* StringDictionary of headers */
```

Returns a `StringDictionary` containing all response headers. Header names are lowercased.

See also: `GetResponseHeader`

`gNewHttpRequest::HttpRequest` [`NewHttpRequest`]

```
req = gNewHttpRequest(HttpRequest, url, verb);
```

```
object req;    /* new HttpRequest object */
char *url;     /* request URL             */
char *verb;    /* HTTP method (GET, POST, etc.) */
```

This is a class method. Creates a new `HttpRequest` for the given URL and HTTP method.

`gSendRequest::HttpRequest` [`SendRequest`]

```
code = gSendRequest(req, flags);
```

```
object req;    /* HttpRequest object      */
DWORD flags;   /* connection flags        */
DWORD code;    /* 0=success, or HTTP code */
```

Sends the HTTP request with all configured headers and content. Returns 0 on success (HTTP 2xx), or the HTTP response code on error.

gSetAuth::HttpRequest**[SetAuth]**

```

r = gSetAuth(req, user, pass);

object req;    /* HttpRequest object */
char    *user; /* username           */
char    *pass; /* password            */
object  r;     /* HttpRequest object */

```

Sets HTTP Basic Authentication credentials for the request.

gSetContent::HttpRequest**[SetContent]**

```

r = gSetContent(req, content);

object req;    /* HttpRequest object */
char    *content; /* request body      */
object  r;     /* HttpRequest object */

```

Sets the request body content as a string. Replaces any previous content.

See also: `SetContentFromFile`

gSetContentFromFile::HttpRequest**[SetContentFromFile]**

```

r = gSetContentFromFile(req, filename);

object req;    /* HttpRequest object */
char    *filename; /* file path          */
object  r;     /* HttpRequest object or NULL */

```

Loads the request body content from a file. Returns NULL on file error.

See also: `SetContent`

gSetOutputFileName::HttpRequest**[SetOutputFileName]**

```

r = gSetOutputFileName(req, name);

object req;    /* HttpRequest object */
char    *name; /* file path or NULL  */
object  r;     /* HttpRequest object */

```

Sets an output file path to save the response body to instead of keeping it in memory. Pass NULL to disable file output.

See also: `GetResponse`

`gSetResponseTimeoutSeconds::HttpRequest` [SetResponseTimeoutSeconds]

```
gSetResponseTimeoutSeconds(req, seconds);

object req;      /* HttpRequest object */
int      seconds; /* timeout in seconds */
```

Sets the timeout for waiting on a server response. The default is 60 seconds.

`gSetSecure::HttpRequest` [SetSecure]

```
r = gSetSecure(req, secure);

object req;      /* HttpRequest object */
int      secure; /* non-zero for HTTPS */
object r;        /* HttpRequest object */
```

Enables or disables HTTPS for the request. Pass a non-zero value to use HTTPS (port 443 by default).

4.28.2 WebService Methods

The `WebService` class wraps `HttpRequest` to provide a SOAP web service client. It builds SOAP XML envelopes, sends them via HTTP POST, and parses XML responses.

`gAddArgument::WebService` [AddArgument]

```
r = gAddArgument(ws, param, val);

object ws;      /* WebService object */
char      *param; /* parameter name */
char      *val;   /* parameter value */
object r;        /* WebService object */
```

Adds a SOAP method parameter as a name-value pair. Call multiple times to build the parameter list.

`gGetErrorMessage::WebService` [GetErrorMessage]

```
s = gGetErrorMessage(ws);

object ws; /* WebService object */
char      *s; /* error message or NULL */
```

Returns the error message string if the request failed, or NULL if no error occurred.

`gGetResponse::WebService` [GetResponse]

```
s = gGetResponse(ws);

object ws; /* WebService object */
char *s; /* raw XML response string */
```

Returns the raw XML response body from the SOAP service.

See also: `GetXMLResponse`

`gGetXMLResponse::WebService` [GetXMLResponse]

```
xml = gGetXMLResponse(ws);

object ws; /* WebService object */
object xml; /* XMLNode object */
```

Parses the response as XML and returns an `XMLNode` object for structured access to the response elements.

See also: `GetResponse`

`gNewServiceRequest::WebService` [NewServiceRequest]

```
ws = gNewServiceRequest(WebService, url);

object ws; /* new WebService object */
char *url; /* SOAP service URL */
```

This is a class method. Creates a new `WebService` request targeting the given SOAP endpoint URL.

`gSendRequest::WebService` [SendRequest]

```
code = gSendRequest(ws, flags);

object ws; /* WebService object */
DWORD flags; /* connection flags */
DWORD code; /* 0=success, or HTTP code */
```

Builds the SOAP XML envelope from the configured method and arguments, sends it via HTTP POST, and retrieves the response. Returns 0 on success, or the HTTP response code on error.

gSetMethod::WebService

[SetMethod]

```

r = gSetMethod(ws, method);

object ws;      /* WebService object */
char   *method; /* SOAP method name  */
object r;       /* WebService object */

```

Sets the SOAP method (operation) name to invoke on the remote service.

gSetNamespaceURL::WebService

[SetNamespaceURL]

```

r = gSetNamespaceURL(ws, url);

object ws;      /* WebService object */
char   *url;    /* XML namespace URL   */
object r;       /* WebService object */

```

Sets the XML namespace URL for the SOAP envelope.

4.29 Line Control

The **LineControl** class (a subclass of **Control**) implements a control that draws a line on a dialog or window. The line color and style (solid, dotted, dashed) can be configured.

4.29.1 LineControl Methods

New::LineControl

[New]

```

lc = vNew(LineControl, ctlID, name, dlg);

object lc;      /* new LineControl object */
UINT   ctlID;   /* control ID           */
char   *name;   /* control name         */
object dlg;     /* dialog object        */

```

Creates a new **LineControl** associated with a control defined in the dialog resource. The line defaults to black and solid style.

gSetLineColor::LineControl

[SetLineColor]

```

r = gSetLineColor(lc, color);

object lc;      /* LineControl object */
char   color;   /* color index         */
object r;       /* LineControl object */

```

Sets the line color by color index.

See also: `SetLineStyle`

`gSetLineStyle::LineControl`

[`SetLineStyle`]

```

r = gSetLineStyle(lc, style);

object lc;      /* LineControl object      */
char    style; /* line style (solid, dotted, dashed) */
object r;      /* LineControl object      */

```

Sets the line style (solid, dotted, dashed, etc.).

See also: `SetLineColor`

4.30 Rectangle Control

The `RectControl` class (a subclass of `Control`) implements a control that draws a rectangle on a dialog or window. It supports configurable frame styles, fill patterns, background colors, and text display with formatting.

4.30.1 RectControl Methods

`gAllowEdge::RectControl`

[`AllowEdge`]

```

prev = gAllowEdge(rc, val);

object rc;      /* RectControl object      */
int    val;     /* 1=allow edge, 0=no      */
int    prev;    /* previous setting        */

```

Controls whether text extends to the edge of the rectangle. Returns the previous setting.

`gDraw3D::RectControl`

[`Draw3D`]

```

prev = gDraw3D(rc, val);

object rc;      /* RectControl object      */
int    val;     /* 1=enable 3D, 0=disable  */
int    prev;    /* previous setting        */

```

Enables or disables a 3D effect on the rectangle border. Returns the previous setting.

New::RectControl

[New]

```
rc = vNew(RectControl, ctrlID, name, dlg);

object rc;      /* new RectControl object */
UINT    ctrlID; /* control ID             */
char    *name;   /* control name          */
object  dlg;     /* dialog object         */
```

Creates a new **RectControl** associated with a control defined in the dialog resource. Defaults to a frame on all sides, no fill, and black color.

gSetBackgroundColor::RectControl

[SetBackgroundColor]

```
r = gSetBackgroundColor(rc, color);

object rc;      /* RectControl object */
char    color;  /* color index         */
object  r;      /* RectControl object */
```

Sets a solid background color for the rectangle interior.

See also: **SetBackgroundRGBColor**, **SetFill**

gSetBackgroundColorRef::RectControl

[SetBackgroundColorRef]

```
r = gSetBackgroundColorRef(rc, clr);

object rc;      /* RectControl object */
COLORREF clr;   /* Windows COLORREF   */
object  r;      /* RectControl object */
```

Sets the background color using a Windows **COLORREF** value.

See also: **SetBackgroundColor**, **SetBackgroundRGBColor**

gSetBackgroundRGBColor::RectControl

[SetBackgroundRGBColor]

```
r = gSetBackgroundRGBColor(rc, red, green, blue);

object rc;      /* RectControl object */
int    red;     /* red component       */
int    green;   /* green component     */
int    blue;    /* blue component      */
object r;      /* RectControl object */
```

Sets the background color using RGB values.

See also: `SetBackgroundColor`, `SetBackgroundColorRef`

`gSetDT_Format::RectControl`

[SetDT_Format]

```
r = gSetDT_Format(rc, fmt);

object rc;    /* RectControl object */
short  fmt;   /* Windows DT_* format flags */
object r;     /* RectControl object */
```

Sets text formatting flags using Windows DT_* constants (e.g. DT_LEFT, DT_CENTER, DT_WORDBREAK).

`gSetFill::RectControl`

[SetFill]

```
r = gSetFill(rc, fill);

object rc;    /* RectControl object */
char  fill;   /* 1=fill, 0=no fill */
object r;     /* RectControl object */
```

Enables or disables filling the rectangle interior.

See also: `SetPattern`, `SetBackgroundColor`

`gSetFrameColor::RectControl`

[SetFrameColor]

```
r = gSetFrameColor(rc, color);

object rc;    /* RectControl object */
char  color;  /* color index */
object r;     /* RectControl object */
```

Sets the frame (border) color.

See also: `SetFrameStyle`, `SetFrameThickness`

`gSetFrameStyle::RectControl``[SetFrameStyle]`

```

r = gSetFrameStyle(rc, style);

object rc;          /* RectControl object          */
char   style;       /* frame style (which sides have borders) */
object r;           /* RectControl object          */

```

Sets which sides of the rectangle have borders (left, right, top, bottom, or combinations).

See also: `SetFrameColor`, `SetFrameThickness`

`gSetFrameThickness::RectControl``[SetFrameThickness]`

```

r = gSetFrameThickness(rc, thickness);

object rc;          /* RectControl object          */
short  thickness;   /* frame thickness in pixels */
object r;           /* RectControl object          */

```

Sets the frame border thickness in pixels.

See also: `SetFrameColor`, `SetFrameStyle`

`gSetPattern::RectControl``[SetPattern]`

```

r = gSetPattern(rc, dotSize, stepSize, foreColor, backColor);

object rc;          /* RectControl object          */
short  dotSize;     /* dot size for pattern        */
short  stepSize;    /* spacing between dots        */
char   foreColor;   /* pattern foreground color index */
char   backColor;   /* pattern background color index */
object r;           /* RectControl object          */

```

Sets a dot pattern for filling the rectangle interior. Must also call `gSetFill` to enable filling.

See also: `SetFill`, `SetBackgroundColor`

gSetStringValue::RectControl**[SetStringValue]**

```
r = gSetStringValue(rc, val);

object rc;    /* RectControl object */
char    *val; /* display text        */
object r;     /* RectControl object */
```

Sets the text displayed within the rectangle.

See also: **StringValue**, **SetDT_Format**

gSetTextColors::RectControl**[SetTextColor]**

```
r = gSetTextColors(rc, color);

object rc;    /* RectControl object */
char    color; /* color index        */
object r;     /* RectControl object */
```

Sets the text color by color index.

See also: **SetTextRGBColor**, **SetTextColorsRef**

gSetTextColorsRef::RectControl**[SetTextColorsRef]**

```
r = gSetTextColorsRef(rc, clr);

object rc;    /* RectControl object */
COLORREF clr; /* Windows COLORREF    */
object r;     /* RectControl object */
```

Sets the text color using a Windows **COLORREF** value.

See also: **SetTextColors**, **SetTextRGBColor**

`gSetTextRGBColor::RectControl``[SetTextRGBColor]`

```
r = gSetTextRGBColor(rc, red, green, blue);
```

```
object rc;    /* RectControl object */
int     red;   /* red component      */
int     green; /* green component    */
int     blue;  /* blue component     */
object r;     /* RectControl object */
```

Sets the text color using RGB values.

See also: `SetTextColor`, `SetTextColorRef`

`gStringValue::RectControl``[StringValue]`

```
s = gStringValue(rc);
```

```
object rc;    /* RectControl object */
char    *s;    /* display text string */
```

Returns the current display text.

See also: `SetStringValue`

Method Index

A

AddActivateFunctionAfter::Dialog	118
AddActivateFunctionBefore::Dialog	119
AddCompletionFunctionAfter::Dialog	119
AddCompletionFunctionAfter::Window	42
AddCompletionFunctionBefore::Dialog	120
AddCompletionFunctionBefore::Window	42
AddControl::Dialog	121
AddDlgHandlerAfter::Dialog	121
AddDlgHandlerBefore::Dialog	123
AddEdtHandlerAfter::ComboBox	205
AddEdtHandlerBefore::ComboBox	207
AddGlobal::Application	23
AddHandlerAfter::Control	154
AddHandlerAfter::Window	43
AddHandlerBefore::Control	155
AddHandlerBefore::Window	44
AddInitFunctionAfter::Dialog	123
AddInitFunctionAfter::Window	44
AddInitFunctionBefore::Dialog	123
AddInitFunctionBefore::Window	45
AddMenuOption::InternalMenu	113
AddMenuOption::PopupMenu	115
AddOption::ComboBox	207
AddOption::ListBox	195
AddOptionAt::ComboBox	208
AddOptionAt::ListBox	195
AddPopupMenu::InternalMenu	114
AddPopupMenu::PopupMenu	115
AddSeparator::PopupMenu	116
AddTimer::Window	45
Alphabetize::ComboBox	208
Alphabetize::ListBox	195
AppendFilter::FileDialog	247
Arc::Printer	91
Associate::Menu	106
Associate::Window	46
Attach::CheckBox	186
Attach::ComboBox	209
Attach::DateControl	179
Attach::ListBox	196
Attach::NumericControl	171
Attach::RadioButton	189
Attach::ScrollBar	218
Attach::TextControl	164
AutoAttach::Control	155
AutoDispose::Dialog	124
AutoDispose::Window	47
AutoShow::Window	47
AveCharWidth::Font	230

B

BackBrush::Dialog	125
BackBrush::Window	48

C

CallDefaultProc::Control	156
Capitalize::TextControl	164
Center::Dialog	125
Center::Window	48
ChangeGlobal::Application	23
CheckFunction::Control	156
CheckMessages::Application	24
CheckValue::Control	157
CheckValue::Dialog	125
Chord::Printer	92
Click::PushButton	183
CmdLine::Application	24
Color::Brush	236
Color::Pen	241
CompletionFunction::Dialog	126
CompletionFunction::Window	49
Copies::PrintDialog	252
Copies::Printer	92
Copy::Brush	236
Copy::Cursor	223
Copy::Font	230
Copy::Icon	226
Copy::Pen	241
CtlDoubleValue::Dialog	127
CtlLongValue::Dialog	127
CtlShortValue::Dialog	128
CtlStringValue::Dialog	129
CtlUnsignedShortValue::Dialog	129
CtlValue::Dialog	130

D

DateRange::DateControl	179
DeepCopy::Brush	237
DeepCopy::Cursor	223
DeepCopy::Font	231
DeepCopy::Icon	227
DeepCopy::Pen	242
DeepDispose::Brush	237
DeepDispose::Control	158
DeepDispose::Cursor	223
DeepDispose::Dialog	130
DeepDispose::DynamicLibrary	262
DeepDispose::Font	231
DeepDispose::Icon	227
DeepDispose::Menu	107
DeepDispose::Pen	242

DeepDispose::Printer	93
DefaultEdtProcessingMode::ComboBox	209
DefaultProcessingMode::Control	158
DefaultProcessingMode::Window	49
DefExt::FileDialog	247
DeselectLine::ListBox	196
Disable::Control	159
Disable::Dialog	131
Disable::Window	50
DisableAll::Dialog	131
DisableAll::Window	50
DisallowMultipleInstances::Application	24
Display::Control	159
Dispose::Brush	237
Dispose::ColorDialog	255
Dispose::Control	159
Dispose::Cursor	224
Dispose::Dialog	132
Dispose::DynamicLibrary	262
Dispose::FileDialog	248
Dispose::Font	231
Dispose::FontDialog	259
Dispose::Icon	227
Dispose::Menu	107
Dispose::Pen	242
Dispose::PopupMenu	116
Dispose::PrintDialog	252
Dispose::Printer	93
Dispose::Window	51
DisposeAtExit::Application	25
DisposeGlobal::Application	25
DoubleValue::NumericControl	171
DrawText::Window	51

E

Ellipse::Printer	93
Enable::Control	160
Enable::Dialog	132
Enable::Window	52
EnableAll::Dialog	133
EnableAll::Window	52
EnableMenuItem::Menu	108
Erase::Window	53
EraseAll::Window	53
EraseLines::Window	54
ErrorMessage::Application	25

F

FindIndex::ComboBox	210
FindStr::DynamicLibrary	263
Font::FontDialog	259
FreeAll::DynamicLibrary	263

G

gAddArgument	301
gAddArgument::WebService	301
gAddCompletionFunctionAfter::TaskList	291
gAddCompletionFunctionBefore::TaskList	292
gAddHeader	298
gAddHeader::HttpRequest	298
gAddMenuOption::ShortcutMenu	285
gAddSection	279
gAddSection::StatusBar	279
gAddSeparator::ShortcutMenu	285
gAddSubMenu	286
gAddSubMenu::ShortcutMenu	286
gAddTask	292
gAddTask::TaskList	292
gAddToolBitmap	274
gAddToolBitmap::ToolBar	274
gAddToolBitmapFromFile	274
gAddToolBitmapFromFile::ToolBar	274
gAddToolComboBox	275
gAddToolComboBox::ToolBar	275
gAddTVItem	264
gAddTVItem::TreeView	264
gAddTVItemWithImage	265
gAddTVItemWithImage::TreeView	265
gAllowEdge	304
gAllowEdge::RectControl	304
gAlphabetize::TreeView	265
gAlphabetizeOff::TreeView	265
gAutoDisposeTag::Task	296
gAutoDisposeTag::TreeViewItem	269
gBlankIfZero	282
gBlankIfZero::TimeControl	282
gChangeImage::TreeViewItem	269
gChangeTip	275
gChangeTip::ToolBar	275
gCheckFunction::TreeView	266
gCheckValue::Task	296
gCheckValue::TaskList	292
gCheckValue::TreeView	266
gChild::TreeViewItem	270
gChildren::TreeViewItem	270
gCollapse::TreeViewItem	270
gCompletionFunction::TaskList	292
gControl::TreeViewItem	270
gCurrentTask	293
gCurrentTask::TaskList	293
gDeleteTVItem	270
gDeleteTVItem::TreeViewItem	270
gDeselect::TreeView	266
gDialog::TaskList	293
gDisable::TaskList	293
gDisposeChildren::TreeViewItem	271
gDraw3D	304
gDraw3D::RectControl	304
gDrawBitmap	290
gDrawBitmap::Bitmap	290

<code>gEnable::TaskList</code>	293	<code>gGetParent::TreeViewItem</code>	271
<code>gEnableToolBitmap</code>	275	<code>gGetPosition::TaskList</code>	294
<code>gEnableToolBitmap::ToolBar</code>	275	<code>gGetResponse::HttpRequest</code>	298
<code>GetArg::Application</code>	26	<code>gGetResponse::WebService</code>	302
<code>GetBackBrush::Application</code>	26	<code>gGetResponseHeader::HttpRequest</code>	298
<code>GetBackBrush::Dialog</code>	133	<code>gGetResponseHeaders</code>	299
<code>GetCh::Window</code>	54	<code>gGetResponseHeaders::HttpRequest</code>	299
<code>GetColor::ColorDialog</code>	256	<code>gGetSelection::TreeView</code>	267
<code>GetColor::FontDialog</code>	260	<code>gGetTag::Task</code>	296
<code>GetColorTheme::Application</code>	27	<code>gGetTag::TaskList</code>	294
<code>GetControl::Dialog</code>	134	<code>gGetTag::TreeViewItem</code>	272
<code>GetCursor::Application</code>	27	<code>gGetTip</code>	276
<code>GetCustomColorPtr::ColorDialog</code>	256	<code>gGetTip::ToolBar</code>	276
<code>GetExitType::PushButton</code>	183	<code>gGetXMLResponse</code>	302
<code>GetFile::FileDialog</code>	248	<code>gGetXMLResponse::WebService</code>	302
<code>GetFont::Application</code>	28	<code>gHideData::TimeControl</code>	283
<code>GetFont::Control</code>	160	<code>gIsBlank::TimeControl</code>	283
<code>GetGlobal::Application</code>	28	<code>gIsChildOf::TreeViewItem</code>	272
<code>GetIcon::Application</code>	28	<code>gLoadBitmap::TreeView</code>	267
<code>GetMinLength::TextControl</code>	165	<code>gLoadShortcutMenu</code>	286
<code>GetName::Application</code>	29	<code>gLoadShortcutMenu::ShortcutMenu</code>	286
<code>GetOpenFile::FileDialog</code>	250	<code>gLoadShortcutMenuFromFile</code>	286
<code>GetPageRange::PrintDialog</code>	253	<code>gLoadShortcutMenuFromFile::ShortcutMenu</code>	286
<code>GetParent::Dialog</code>	134	<code>gLoadShortcutMenuStr</code>	286
<code>GetParent::Window</code>	55	<code>gLoadShortcutMenuStr::ShortcutMenu</code>	286
<code>GetPosition::Dialog</code>	134	<code>gNewBitmap</code>	290
<code>GetPosition::Window</code>	55	<code>gNewBitmap::Bitmap</code>	290
<code>GetProcAddress::DynamicLibrary</code>	263	<code>gNewBitmap2</code>	290
<code>GetResourceID::Control</code>	160	<code>gNewBitmap2::Bitmap</code>	290
<code>GetResourceID::Dialog</code>	135	<code>gNewHttpRequest</code>	299
<code>Gets::Window</code>	56	<code>gNewHttpRequest::HttpRequest</code>	299
<code>GetSaveFile::FileDialog</code>	250	<code>gNewImageList::TreeView</code>	267
<code>GetScalingMode::Application</code>	29	<code>gNewServiceRequest</code>	302
<code>GetSelections::ListBox</code>	197	<code>gNewServiceRequest::WebService</code>	302
<code>GetSize::Application</code>	30	<code>gNewTask</code>	297
<code>GetSize::Dialog</code>	135	<code>gNewTask::Task</code>	297
<code>GetSize::Window</code>	56	<code>gNewTaskList</code>	294
<code>GetStyle::Window</code>	57	<code>gNewTaskList::TaskList</code>	294
<code>GetTabOrder::Control</code>	160	<code>gNewTVItem</code>	272
<code>GetTag::Dialog</code>	136	<code>gNewTVItem::TreeViewItem</code>	272
<code>GetTag::Window</code>	57	<code>gNext::TreeViewItem</code>	272
<code>GetTask::Dialog</code>	136	<code>gNextTask::Task</code>	297
<code>GetTask::Window</code>	58	<code>gNextTask::TaskList</code>	294
<code>GetTextBrush::Application</code>	30	<code>gPerform::ShortcutMenu</code>	287
<code>GetTextBrush::Dialog</code>	137	<code>gPerform::TaskList</code>	295
<code>GetTM::Font</code>	232	<code>gPerformModal::TaskList</code>	295
<code>GetTopic::Dialog</code>	137	<code>gPixelHeight::StatusBar</code>	279
<code>GetTopic::Window</code>	58	<code>gPixelHeight::ToolBar</code>	276
<code>gExpand::TreeViewItem</code>	271	<code>gRemoveAll::TreeView</code>	268
<code>gFirst::TreeView</code>	266	<code>gResetText</code>	288
<code>gFormatTime</code>	283	<code>gResetText::StaticTextControl</code>	288
<code>gFormatTime::TimeControl</code>	283	<code>gResort::TreeView</code>	268
<code>gGetControlStr::ToolBar</code>	276	<code>Group::RadioButton</code>	190
<code>gGetErrorMessage::HttpRequest</code>	298	<code>GroupShortValue::RadioButton</code>	190
<code>gGetErrorMessage::WebService</code>	301	<code>GroupStringValue::RadioButton</code>	191
<code>gGetExitType::ImageControl</code>	280	<code>gSelect::TreeViewItem</code>	273
<code>gGetImageID::TreeViewItem</code>	271	<code>gSendRequest::HttpRequest</code>	299

gSendRequest::WebService.....	302	gSetStringValue::ImageControl.....	282
gSetAccessModeFunction::ToolBar.....	277	gSetStringValue::RectControl.....	308
gSetAuth.....	300	gSetStringValue::StaticControl.....	288
gSetAuth::HttpRequest.....	300	gSetStringValue::TreeViewItem.....	273
gSetBackgroundColor.....	305	gSetTag::Task.....	297
gSetBackgroundColor::RectControl.....	305	gSetTag::TaskList.....	295
gSetBackgroundColorRef.....	305	gSetTag::TreeViewItem.....	273
gSetBackgroundColorRef::RectControl.....	305	gSetTextColors::RectControl.....	308
gSetBackgroundRGBColor.....	305	gSetTextColorsRef.....	308
gSetBackgroundRGBColor::RectControl.....	305	gSetTextColorsRef::RectControl.....	308
gSetBeginHour::TimeControl.....	284	gSetTextRGBColor.....	309
gSetBitmapID.....	281	gSetTextRGBColor::RectControl.....	309
gSetBitmapID::ImageControl.....	281	gSetTimeValue.....	284
gSetButtonBorder.....	281	gSetTimeValue::TimeControl.....	284
gSetButtonBorder::ImageControl.....	281	gSetToolBarMouseFunction.....	277
gSetContent.....	300	gSetToolBarMouseFunction::ToolBar.....	277
gSetContent::HttpRequest.....	300	gSetToolFunction.....	277
gSetContentFromFile.....	300	gSetToolFunction::ToolBar.....	277
gSetContentFromFile::HttpRequest.....	300	gSetURL.....	289
gSetCurrentLanguage::StaticTextControl.....	289	gSetURL::StaticTextControl.....	289
gSetDCFunction::ImageControl.....	281	gSetZOrder::TaskList.....	296
gSetDefaultLong::TimeControl.....	284	gShowToolBitmap.....	278
gSetDT_Format.....	306	gShowToolBitmap::ToolBar.....	278
gSetDT_Format::RectControl.....	306	gStringValue::ImageControl.....	282
gSetExitType::ImageControl.....	281	gStringValue::RectControl.....	309
gSetExpFun::TreeView.....	268	gStringValue::StaticControl.....	288
gSetFill.....	306	gStringValue::TreeViewItem.....	273
gSetFill::RectControl.....	306	gTaskList::Task.....	297
gSetFrameColor.....	306	gTimeRange.....	284
gSetFrameColor::RectControl.....	306	gTimeRange::TimeControl.....	284
gSetFrameStyle.....	307	gTimeValue.....	285
gSetFrameStyle::RectControl.....	307	gTimeValue::TimeControl.....	285
gSetFrameThickness.....	307	gUpdateAccessMode.....	278
gSetFrameThickness::RectControl.....	307	gUpdateAccessMode::ToolBar.....	278
gSetImageList::TreeView.....	268	gUpdateState::StatusBar.....	280
gSetLineColor.....	303	gUpdateState::ToolBar.....	278
gSetLineColor::LineControl.....	303	gURL.....	289
gSetLineStyle.....	304	gURL::StaticTextControl.....	289
gSetLineStyle::LineControl.....	304	gUseAlternateColor.....	278
gSetMethod.....	303	gUseAlternateColor::ToolBar.....	278
gSetMethod::WebService.....	303		
gSetNamespaceURL.....	303		
gSetNamespaceURL::WebService.....	303		
gSetOutputFileName.....	300		
gSetOutputFileName::HttpRequest.....	300		
gSetPattern.....	307		
gSetPattern::RectControl.....	307		
gSetResponseTimeoutSeconds.....	301		
gSetResponseTimeoutSeconds::HttpRequest.....	301		
gSetSectionText.....	279		
gSetSectionText::StatusBar.....	279		
gSetSecure.....	301		
gSetSecure::HttpRequest.....	301		
gSetSelFun::TreeView.....	269		
gSetShortValue::TaskList.....	295		
gSetSpinFunction.....	291		
gSetSpinFunction::SpinControl.....	291		

H

Handle::Brush.....	237
Handle::Control.....	161
Handle::Cursor.....	224
Handle::Dialog.....	138
Handle::Font.....	232
Handle::Icon.....	228
Handle::Menu.....	108
Handle::Pen.....	242
Handle::PrintDialog.....	253
Handle::Printer.....	94
Handle::Window.....	58
HelpContents::HelpSystem.....	245
HelpFile::HelpSystem.....	245
HelpInContext::HelpSystem.....	245

HelpTopic::HelpSystem 246
 Hide::Control 161
 HideData::TextControl 165

I

Increment::ScrollBar 219
 IndexValue::Dialog 138
 InDialog::Dialog 139
 Indirect::ExternalFont 235
 InitFunction::Window 59
 InitialDir::FileDialog 249
 Instance::Application 31
 IsExiting::Application 31
 IsIconic::Window 59
 IsMaximized::Window 60
 IsNormal::Window 60

K

Kbhit::Window 61
 KillTimer::Window 61

L

Language::Application 31
 Line::Printer 94
 LineHeight::Font 232
 ListIndex::ComboBox 210
 ListIndex::ListBox 197
 Load::ExternalCursor 225
 Load::ExternalIcon 229
 Load::ExternalMenu 111
 Load::SystemFont 234
 LoadCursor::Window 62
 LoadFont::Printer 95
 LoadFont::Window 62
 LoadIcon::Window 63
 LoadLibrary::DynamicLibrary 264
 LoadMenu::Window 63
 LoadMenuStr::Window 64
 LoadStr::ExternalCursor 226
 LoadStr::ExternalIcon 229
 LoadStr::ExternalMenu 112
 LoadSys::SystemCursor 225
 LoadSys::SystemIcon 228
 LoadSystemCursor::Window 65
 LoadSystemFont::Printer 96
 LoadSystemFont::Window 65
 LoadSystemIcon::Window 66
 LongValue::DateControl 180
 LongValue::NumericControl 172

M

Maximize::Window 66
 MaxLength::TextControl 165
 Menu::Window 67
 MenuFunction::Menu 109
 MenuFunction::PopupMenu 117
 MenuItemMode::Window 67
 Message::Application 32
 Message::Dialog 139
 Message::Window 68
 MessageMode::Application 32
 MessageWithTopic::Dialog 140
 MessageWithTopic::Window 68
 MinLength::TextControl 166
 MoveToTop::Dialog 140
 MoveToTop::Window 69

N

Name::Font 233
 New::ChildWindow 89
 New::ColorDialog 257
 New::CustomPen 244
 New::ExternalFont 235
 New::FileDialog 249
 New::FontDialog 260
 New::HatchBrush 240
 New::ImageControl 280
 New::InternalMenu 114
 New::LineControl 303
 New::MainWindow 88
 New::PopupMenu 117
 New::PopupWindow 90
 New::PrintDialog 254
 New::Printer 96
 New::RectControl 305
 New::ShortcutMenu 287
 New::SolidBrush 239
 New::StaticControl 287
 New::StatusBar 279
 New::StockBrush 238
 New::StockPen 243
 New::SystemBrush 239
 New::TimeControl 283
 New::ToolBar 276
 New::TreeView 267
 New::Window 69
 NewBuiltIn::Window 69
 NewCtl::CheckBox 187
 NewCtl::ComboBox 211
 NewCtl::DateControl 180
 NewCtl::ListBox 198
 NewCtl::NumericControl 172
 NewCtl::PushButton 183
 NewCtl::RadioButton 191
 NewCtl::ScrollBar 219
 NewCtl::TextControl 166

NewDialog::ModalDialog	149
NewDialog::ModelessDialog	151
NewDialogFromFile::ModalDialog	150
NewDialogFromFile::ModelessDialog	152
NewDialogStr::ModalDialog	149
NewDialogStr::ModelessDialog	152
NewPage::Printer	97
NewWithHDC::Printer	97
NextControl::Window	70
NumArgs::Application	32
NumSelected::ComboBox	211
NumSelected::ListBox	198
NumericRange::NumericControl	173

O

OpenDefault::Printer	98
OpenURL::Application	33
OpenURLWait::Application	33

P

PasswordFlag::TextControl	167
Perform::ColorDialog	257
Perform::Dialog	141
Perform::FontDialog	261
Perform::PrintDialog	254
Perform::PushButton	184
Perform::Window	70
PerformModal::Window	71
Pie::Printer	99
PixelHeight::Font	233
PointSize::Font	234
Pop::Menu	109
PopupMenu::Window	71
PressButton::Dialog	142
PrevInstance::Application	33
PreviousControl::Window	72
PrintBitmap::Printer	99
Printf::Printer	100
Printf::Window	72
PrintScreen::Window	73
ProcessMessages::MainWindow	88
Push::Menu	110
Puts::Printer	101
Puts::Window	73

Q

QueryPrinter::Printer	101
QuitApplication::Application	34

R

Read::Window	74
Rectangle::Printer	102
RedrawMenu::Window	74
RedrawWindow::Window	75
RemoveAll::ComboBox	212
RemoveAll::ListBox	198
RemoveAtExit::Application	34
RemoveGlobal::Application	35
RemoveInt::ComboBox	212
RemoveInt::ListBox	199
RemoveStr::ComboBox	212
RemoveStr::ListBox	199
Required::ComboBox	213
Required::ListBox	200
ReturnAsTab::Application	35
RoundRect::Printer	103

S

Scale::Printer	103
ScaleToCurrentMode::Application	35
ScaleToPixels::Application	36
ScrollBarRange::ScrollBar	220
ScrollHorz::Window	75
ScrollVert::Window	76
Select::NumericControl	173
Select::TextControl	167
SelectLine::ListBox	200
SetBackBrush::Application	37
SetBlock::Window	76
SetCheckMark::Menu	110
SetChgFunction::ComboBox	213
SetColor::ColorDialog	258
SetColor::FontDialog	261
SetColorTheme::Application	37
SetCursor::Application	38
SetCursor::Dialog	143
SetCursor::Window	77
SetDefaultDouble::NumericControl	173
SetDefaultLong::NumericControl	174
SetDoubleValue::NumericControl	174
SetExitType::PushButton	184
SetFile::FileDialog	251
SetFlags::ColorDialog	258
SetFlags::FileDialog	251
SetFlags::FontDialog	261
SetFlags::PrintDialog	255
SetFocus::Control	161
SetFocus::Dialog	143
SetFocus::Window	77
SetFont::Application	38
SetFont::Control	162
SetFormat::NumericControl	175
SetFunction::ComboBox	214
SetFunction::ListBox	201
SetFunction::PushButton	184

SetGroupShortValue::RadioButton 192
 SetGroupStringValue::RadioButton 192
 SetIcon::Application 39
 SetLanguage::Application 39
 SetLongValue::DateControl 181
 SetLongValue::NumericControl 175
 SetMask::TextControl 167
 SetMaxLines::Window 78
 SetMode::Menu 111
 SetName::Application 39
 SetName::Control 162
 SetParent::Window 78
 SetPasswordFlag::TextControl 168
 SetPosition::Window 79
 SetRaw::Window 79
 SetResult::Dialog 143
 SetScale::Printer 104
 SetScalingMode::Application 40
 SetShortValue::CheckBox 187
 SetShortValue::ComboBox 214
 SetShortValue::ListBox 201
 SetShortValue::NumericControl 175
 SetShortValue::RadioButton 192
 SetShortValue::ScrollBar 221
 SetSize::Window 80
 SetState::Dialog 144
 SetStringValue::ComboBox 215
 SetStringValue::ListBox 202
 SetStringValue::PushButton 185
 SetStringValue::TextControl 168
 SetStyle::Window 81
 SetTabOrder::Control 162
 SetTag::Dialog 144
 SetTag::Window 81
 SetTask::Dialog 145
 SetTask::Window 82
 SetTextBrush::Application 41
 SetTitle::Dialog 145
 SetTitle::FileDialog 251
 SetTitle::Window 82
 SetTopic::Control 163
 SetTopic::Dialog 146
 SetTopic::HelpSystem 246
 SetTopic::Window 82
 SetUShortValue::NumericControl 176
 SetValue::CheckBox 188
 SetValue::ComboBox 215
 SetValue::DateControl 181
 SetValue::ListBox 202
 SetValue::NumericControl 176
 SetValue::RadioButton 193
 SetValue::ScrollBar 221
 SetValue::TextControl 168
 SetZOrder::Dialog 146
 SetZOrder::Window 83
 ShortValue::CheckBox 188
 ShortValue::ComboBox 216

ShortValue::ListBox 203
 ShortValue::NumericControl 177
 ShortValue::RadioButton 193
 ShortValue::ScrollBar 222
 Show::Application 41
 Show::Window 83
 Size::ComboBox 216
 Size::ListBox 203
 StringValue::ComboBox 217
 StringValue::ListBox 204
 StringValue::PushButton 185
 StringValue::TextControl 169

T

TextBrush::Dialog 147
 TextBrush::Window 84
 TextOut::Printer 104
 TextOut::Window 84
 TextRange::TextControl 169

U

UnsignedShortValue::NumericControl 177
 Update::Control 163
 Update::Dialog 147
 Update::Window 85
 Use::Printer 105
 Use::Window 85
 UseDefault::Control 163
 UseDefault::Dialog 148

V

Value::CheckBox 189
 Value::ComboBox 217
 Value::DateControl 182
 Value::ListBox 204
 Value::NumericControl 178
 Value::RadioButton 194
 Value::ScrollBar 222
 Value::TextControl 170
 ValueAt::ComboBox 218
 ValueAt::ListBox 205
 VertShift::Window 86
 vNew::ImageControl 280
 vNew::LineControl 303
 vNew::RectControl 305
 vNew::ShortcutMenu 287
 vNew::StaticControl 287
 vNew::StatusBar 279
 vNew::TimeControl 283
 vNew::ToolBar 276
 vNew::TreeView 267

W

WaitCursor::Dialog.....	148
WaitCursor::Window.....	87
Write::Window	87