Why classical computers need exponentially more time and memory to simulate quantum computers

Ronald Landheer-Cieslak

3 November 2019

1 Introduction

If you're a bit like me, you get annoyed by the over-simplified explanations of quantum computers that have been going around since Google demonstrated quantum supremacy. One of the things that those explanations always gloss over is how it's so much harder for a classical computer to simulate a quantum computer running what is basically linear algebra, than it is for a quantum computer to just run it. The answer to that is quantum entanglement, and in this {whatever this is} I will try to explain how it works.

I should point out that this means either math or meth will be involved in understanding what I'm about to write. The second option being temporary for understanding and permanent for negative effects, I recommend the first.

In order to explain why classical computers need exponentially more time and memory to simulate quantum computers according to the size of the quantum computer (i.e. 2^QN bits to simulate Q qubits in $2^{2Q}T$ time, so there's a linear and an exponential component), I first need to explain a few things about quantum computers. First, I'll explain what a qubit is, and how we represent them in a familiar notation you'll have learned about in highschool, and in a less familiar notation that you may have seen all over the Internet, called the $Dirac\ braket$ notation. The next step is to represent a pair of qubits in those same notations, and do the necessary math to show how that works. Once we've got that, we'll hop¹ over to quantum entanglement to show why those notations were important, and why a classical computer needs all that extra space and time.

2 Qubits

Qubits are the basic unit of data storage and manipulation in quantum computers, like classical bits, or *cbits* are in classical computing. The fundamental difference between a qubit and a classical bit is the way they behave: a classical bit can have only a value of 0 or 1. To encode the value "3", for example, you

¹Subtle pun with quantum leap intended.

need two bits (both set to 1). To represent the value $1/\sqrt{2}$ you need a whole bunch of bits and IEEE StdTM 754-2019.

Qubits don't represent individual values: they represent a value "somewhere between 0 and 1" with a *probability of collapsing* to either 0 or 1 when they are measured.

This got weird in a hurry. That's because fundamentally, you cannot know what the value of any given qubit is at any time without measuring it, and when you measure it, you're almost never 100% sure of the value you're going to get. What you can know is the probability that you're going to get a 0 or a 1 for any given measurement, but which one you're going to get remains *purely* random.

Mathematically, a qubit may be represented as a vector from the origin to any point on a unit sphere, so while a classical bit has just the one dimension, a qubit is a vector in a two-dimensional complex vector space \mathbb{C}^2 called a *Hilbert space*, and can be represented as a vector in a unit sphere, as shown in Figure 1.




Figure 1: A qubit, represented as a vector in a unit sphere

As you'll remember from your highschool linear algebra classes, a *vector* is a value that has both an direction and a magnitude. In this case, the amplitude is always 1, but the direction can be anything.

2.1 Notation

Any vector in this unit sphere can be represented with the usual notation for vectors. Remember that in math, you don't actually need three numbers to represent a two-dimensional complex vector space, even if there are three axes: if you use complex numbers, which is what we do here, the vector \vec{q} in the image can be represented as:

$$q = \begin{pmatrix} \frac{1}{\sqrt{2}} e^{-i\frac{\pi}{12}} \\ \frac{1}{\sqrt{2}} e^{-i\frac{\pi}{12}} \end{pmatrix}$$

Note that there is nothing special about this particular vector \vec{q} , but I wanted it to point out of the page, so I needed a complex component. As you'll remember from your highschool math² any complex number can be represented as either a real part plus an imaginary part (a+bi), or as an amplitude and an angle, $re^{i\theta}$. I chose the second notation here because it is both more compact and allows me to easily set the amplitude to $\frac{1}{\sqrt{2}}$, this keeping my vector's magnitude at 1. Another way to represent a qubit is the Dirac braket notation. It's basically

a shorthand for qubit-typed variables, so our q would be noted as:

$$|q\rangle = \frac{1}{\sqrt{2}}e^{-i\frac{\pi}{12}}|0\rangle + \frac{1}{\sqrt{2}}e^{-i\frac{\pi}{12}}|1\rangle$$

By convention, classical bits are represented in qubits as $|0\rangle$ and $|1\rangle$, which correspond, respectively, to $\begin{pmatrix} 1 \\ 0 \end{pmatrix}$ and $\begin{pmatrix} 0 \\ 1 \end{pmatrix}$, which gets us to what these numbers actually mean.

In the vector notation $\begin{pmatrix} \alpha_0 \\ \alpha_1 \end{pmatrix}$, α_0 is the *probability amplitude* if the qubit collapsing to 0 when measured, and α_1 is the probability amplitude of the qubit collapsing to 1 when it is measured. To find the actual probability, this number has to be multiplied with its complex conjugate.

As a reminder, the complex conjugate of a complex number p + qi is p - qi, so multiplying a number with its own complex conjugate is

$$(p+qi)(p-qi) = p^2 + pqi - pqi - q^2 = p^2 - q^2$$

So, for a real number, this means just taking the square of the probability amplitude to find the probability.

This makes intuitive sense, if you consider that the probability of a qubit collapsing to 0 must be governed by the projection of the vector of that qubit onto the X axis, and the probability of it collapsing to 1 must be governed by its projection onto the Y axis. However, why it maps so cleanly to the probability is one of the mysteries of nature.

For now, there are two take-aways so far: qubits are fundamentally vectors in a unit sphere, so their magnitude is always one (again: unit spere) but they can point in any direction in a two-dimensional complex space; and classical bits can be represented by qubits pointing in either one of two directions: in the direction of the X axis $(|0\rangle)$, or in the direction of the Y axis $(|1\rangle)$.

2.2Operations on qubits

There is one thing you need to know about operations a quantum computer can perform: every operation is reversible, and is often its own inverse. These operations essentially consist of rotating the vector that represents the qubit about one or more of the axes of the complex space it is in. Compare this with

²Did they teach this in highschool? I don't remember.

operations on classical bits: the basic gate in classical computing, the NAND gate, takes two bits as input and outputs a single bit which is set unless both of the input bits are set. This destroys a truckload of information: look at the truth table for NAND (Table 1): three out of the four states have the same output. It is impossible to reverse this gate, as there is no way to know which of the three inputs we had if we get an output 1. While it is possible to implement a NAND gate with a quantum computer, we need a bit of work to get there.

a	b	r
0	0	1
0	1	1
1	0	1
1	1	0

Table 1: Truth table for a classic NAND gate

First, the fact that out quantum version of the gate has to be reversible means we cannot lose any information. It also means we need to have the same number of inputs as we do outputs. In the case of NAND, this means we cannot implement it with just two inputs and one output: we need three inputs and three outputs (looking at the truth table for NAND tells you this). Now, imagine our three inputs are $|a\rangle$, $|b\rangle$ and $|r\rangle$, and that we can guarantee $|r\rangle$ to be $|1\rangle$ on input. We need a gate that flips $|r\rangle$ if both $|a\rangle$ and $|b\rangle$ are true, but leaves it alone if they aren't. Now, remember, again, that $|a\rangle$ and $|b\rangle$ may both be anywhere between $|0\rangle$ and $|1\rangle$, we actually need the probability of flipping $|r\rangle$ to be the probability that both $|a\rangle$ and $|b\rangle$ are true.

This is where we remind ourselves that these are vectors. The way we operate on vectors, if we remember our highschool linear algebra, is to multiply them with matrices. This allows us to do all kinds of nifty things to them, such as rotating them around an axis. So, if we can represent qubits as vectors, we can represent operations on qubits as matrices that we multiply with those vectors.

Harking back to highschool some more, let's remember how the product of a matrix with a vector works:

$$\begin{pmatrix} a & b & c \\ d & e & f \\ g & h & i \end{pmatrix} \begin{pmatrix} x \\ y \\ z \end{pmatrix} = \begin{pmatrix} ax + by + cz \\ dx + ey + fz \\ hx + hy + iz \end{pmatrix}$$

Now let's look at the two simplest operations we can do with a qubit: *Identity* and *NOT*.

$$I = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} \ NOT = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}$$

Applying these two operators to a single qubit we can see how they work:

$$I|0\rangle = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} \begin{pmatrix} 1 \\ 0 \end{pmatrix} = \begin{pmatrix} 1 \times 1 + 0 \times 0 \\ 0 \times 1 + 1 \times 0 \end{pmatrix} = \begin{pmatrix} 1 \\ 0 \end{pmatrix} = |0\rangle$$

$$I |1\rangle = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} \begin{pmatrix} 0 \\ 1 \end{pmatrix} = \begin{pmatrix} 1 \times 0 + 0 \times 1 \\ 0 \times 0 + 1 \times 1 \end{pmatrix} = \begin{pmatrix} 0 \\ 1 \end{pmatrix} = |1\rangle$$

$$I |\psi\rangle = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} \begin{pmatrix} \alpha_0 \\ \alpha_1 \end{pmatrix} = \begin{pmatrix} 1 \times \alpha_0 + 0 \times \alpha_1 \\ 0 \times \alpha_0 + 1 \times \alpha_1 \end{pmatrix} = \begin{pmatrix} \alpha_0 \\ \alpha_1 \end{pmatrix} = |\psi\rangle$$

$$NOT |0\rangle = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} \begin{pmatrix} 1 \\ 0 \end{pmatrix} = \begin{pmatrix} 0 \times 1 + 1 \times 0 \\ 1 \times 1 + 0 \times 0 \end{pmatrix} = \begin{pmatrix} 0 \\ 1 \end{pmatrix} = |1\rangle$$

$$NOT |1\rangle = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} \begin{pmatrix} 0 \\ 1 \end{pmatrix} = \begin{pmatrix} 0 \times 0 + 1 \times 1 \\ 1 \times 0 + 0 \times 1 \end{pmatrix} = \begin{pmatrix} 1 \\ 0 \end{pmatrix} = |0\rangle$$

$$NOT |\psi\rangle = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} \begin{pmatrix} \alpha_0 \\ \alpha_1 \end{pmatrix} = \begin{pmatrix} 0 \times \alpha_0 + 1 \times \alpha_1 \\ 1 \times \alpha_0 + 0 \times \alpha_1 \end{pmatrix} = \begin{pmatrix} \alpha_1 \\ \alpha_0 \end{pmatrix} = |\psi'\rangle$$

So, applying an operator to a qubit is basically the same as applying a matrix multiplication to a vector. As software engineers know, a classical computer can be programmed to do matrix multiplications in papallel, but as you can see, the matrix is still $n \times n$ for an n-dimensional vector, so there are still n^2 multiplications to be done.

These operators, and quite a few others, allow us to work with a single qubit. The operator we're looking for needs to allow us to work with *three* qubits. How do we do that?

2.3 More dimensions

The Dirac braket notation can be extended to any number of qubits, pretty much the same way as we extend binary notation for classical bits. You'll remember from your computer science classes³, bits can be concatenated from right to left, so $b_0|b_1 \to b_1b_0$. The decimal value of these bits is:

$$2^{n}b_{n} + 2^{n-1}b_{n-1} + \cdots + 2^{2}b_{2} + 2^{1}b_{1} + 2^{0}b_{0}$$

We can do the same thing (kinda) with qubits: two qubits' states can be combined into a single notation. So if $|\psi_{\alpha}\rangle = \alpha_0 |0\rangle + \alpha_1 |1\rangle$ and $|\psi_{\beta}\rangle = \beta_0 |0\rangle + \beta_1 |1\rangle$, the $|\psi_{\alpha}\psi_{\beta}\rangle = \alpha_0\beta_0 |00\rangle + \alpha_0\beta_1 |01\rangle + \alpha_1\beta_0 |10\rangle + \alpha_1\beta_1 |11\rangle$, so the vector becomes

$$\begin{pmatrix} \alpha_0 \beta_0 \\ \alpha_0 \beta_1 \\ \alpha_1 \beta_0 \\ \alpha_1 \beta_1 \end{pmatrix}$$

Note that this is a vector in a four-dimensional complex vector space, \mathbb{C}^4 , still a Hilbert space. Sometimes you'll see these different (basis) states written as the $\alpha_0\beta_0|0\rangle + \alpha_0\beta_1|1\rangle + \alpha_1\beta_0|2\rangle + \alpha_1\beta_1|3\rangle$, which takes us back to the decimal notation we know for classical bits as well.

 $^{^3{\}rm I'm}$ assuming they teach this stuff in computer science. I studied biology and medical biology myself, so I wouldn't know.

Now look at what this does to any operator U_{χ} that we might have: if U_{α} operates on one qubit and U_{β} on another, what does a U look like that operates on both? The answer is fairly easy to derive:

$$U_{\alpha} |\alpha\rangle = \begin{pmatrix} a & c \\ b & d \end{pmatrix} \begin{pmatrix} \alpha_0 \\ \alpha_1 \end{pmatrix} = \begin{pmatrix} a\alpha_0 + c\alpha_1 \\ b\alpha_0 + d\alpha_1 \end{pmatrix} = |\alpha'\rangle \tag{1}$$

$$U_{\beta} |\beta\rangle = \begin{pmatrix} e & g \\ f & h \end{pmatrix} \begin{pmatrix} \beta_0 \\ \beta_1 \end{pmatrix} = \begin{pmatrix} e\beta_0 + g\beta_1 \\ f\beta_0 + h\beta_1 \end{pmatrix} = |\beta'\rangle \tag{2}$$

$$\left|\alpha\beta\right\rangle = \alpha_{0}\beta_{0}\left|0\right\rangle + \alpha_{0}\beta_{1}\left|1\right\rangle + \alpha_{1}\beta_{0}\left|2\right\rangle + \alpha_{1}\beta_{1}\left|3\right\rangle$$

 \Rightarrow

$$|\alpha'\beta'\rangle = (a\alpha_0 + c\alpha_1)(e\beta_0 + g\beta_1)|0\rangle + (a\alpha_0 + c\alpha_1)(f\beta_0 + h\beta_1)|1\rangle + (b\alpha_0 + d\alpha_1)(e\beta_0 + g\beta_1)|2\rangle + (b\alpha_0 + d\alpha_1)(f\beta_0 + h\beta_1)|3\rangle$$
(3)

$$U_{\alpha} \otimes U_{\beta} = \begin{pmatrix} ae & ag & ce & cg \\ ae & ag & ce & cg \\ bf & bh & df & dh \\ bf & bh & df & dh \end{pmatrix} = \begin{pmatrix} a\begin{pmatrix} e & g \\ f & h \end{pmatrix} & c\begin{pmatrix} e & g \\ f & h \end{pmatrix} \\ b\begin{pmatrix} e & g \\ f & h \end{pmatrix} & d\begin{pmatrix} e & g \\ f & h \end{pmatrix} = U$$
 (4)

In step (1), we just get the result of applying an operator U_{α} to a qubit $|\alpha\rangle$. In step (2), we do the same for an operator U_{β} applied to a qubit $|\beta\rangle$. In step (3), we remind ourselves of what $|\alpha\beta\rangle$ looks like, and derive from that what $|\alpha'\beta'\rangle$ should look like. Finally in step (4), we extract the matrix that corresponds to U from what we found in step (3) by applying the matrix in reverse to its outcome. We show how we would have gotten there using a tensor multiplication, which this turns out to be.

Note that we now have a four-by-four matrix as an operator to apply to a four-dimensional complex vector, which implies sixteen parallel multiplications for any operator applied to two qubits.

2.4 Finishing the NAND gate

The quantum circuit we will build needs two input bits and one output bit, which means we need an eight-dimensional complex vector space, \mathbb{C}^8 to represent it. The matrix to reprent it looks like this:

$$\begin{pmatrix} 1 & 0 & 0 & 0 & 0 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 & 0 & 0 & 0 & 0 \\ 0 & 0 & 1 & 0 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 1 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 1 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0 & 1 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0 & 1 & 0 \end{pmatrix}$$

It's called CCNOT and flips the output qubit iff both the control bits are set. As we initialize the output bit to $|1\rangle$, this effectively implements a NAND.

Note that we now have 64 parallel multiplications to do to simulate this eight-dimensional, three-qubit system.

3 Flavors of entanglement

When we combine two qubits, we can make then share a four-dimensional complex state in such a way that it becomes impossible to represent the two individual qubits separately from each other. Consider, for example, the following state for a pair of qubits:

$$|\psi\rangle = \frac{1}{\sqrt{2}} |00\rangle \frac{1}{\sqrt{2}} |11\rangle$$

In this state, there's a 50% chance that both qubits, when measured, collapse to the 0 state and a 50% chance that they both collapse to the 1 state, but no chance that they don't both collapse to the same state! This means that $|\psi\rangle$ can no longer correspond to a state $|\alpha\beta\rangle$ where the two states can be factored out as $\alpha_0\beta_0|0\rangle + \alpha_0\beta_1|1\rangle + \alpha_1\beta_0|2\rangle + \alpha_1\beta_1|3\rangle$ because it is impossible to find a set of values $\{\alpha_0,\alpha_1,\beta_0,\beta_1\}$ such that $\alpha_0\beta_0=\frac{1}{\sqrt{2}}\wedge\alpha_1\beta_1=\frac{1}{\sqrt{2}}\wedge\alpha_0\beta_1=0\wedge\alpha_1\beta_0=0$.

Creating this state is not that difficult: we need to apply a gate called the Hadamard gate to the control bit in a CNOT gate (which is like the CCNOT gate, but with fewer dimensions as it only has one control bit). We can apply this to two unentangled qubits, both initialized to $|0\rangle$, to obtain a maximally entangled pair of qubits:

$$H = \begin{pmatrix} \frac{1}{\sqrt{2}} & \frac{1}{\sqrt{2}} \\ \frac{1}{\sqrt{2}} & -\frac{1}{\sqrt{2}} \end{pmatrix}$$
 (5)

$$CNOT = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 1 & 0 \end{pmatrix} \tag{6}$$

$$H|0\rangle = \begin{pmatrix} \frac{1}{\sqrt{2}} & \frac{1}{\sqrt{2}} \\ \frac{1}{\sqrt{2}} & -\frac{1}{\sqrt{2}} \end{pmatrix} \begin{pmatrix} 1 \\ 0 \end{pmatrix} = \begin{pmatrix} \frac{1}{\sqrt{2}} \\ \frac{1}{\sqrt{2}} \end{pmatrix} = |\psi_0\rangle \tag{7}$$

$$|\psi_1\rangle = |0\rangle \Rightarrow |\psi\rangle = |\psi_0\psi_1\rangle = \frac{1}{\sqrt{2}}|00\rangle + \frac{1}{\sqrt{2}}|10\rangle = \begin{pmatrix} \frac{1}{\sqrt{2}}\\0\\\frac{1}{\sqrt{2}}\\0 \end{pmatrix}$$
(8)

$$CNOT |\psi\rangle = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 1 & 0 \end{pmatrix} \begin{pmatrix} \frac{1}{\sqrt{2}} \\ 0 \\ \frac{1}{\sqrt{2}} \\ 0 \end{pmatrix} = \begin{pmatrix} \frac{1}{\sqrt{2}} \\ 0 \\ 0 \\ \frac{1}{\sqrt{2}} \end{pmatrix} = |\psi'\rangle \tag{9}$$

So, while a classical computer could get around implementing NAND using sixty-four multiplications by assuming the bits are always independent, it can't get around implementing its quantum-equivalent CCNOT gate with sixty-four multiplications, and keeping a state for eight data points, because qubits may be entangled and can therefore not be assumed to be independent.

4 Conclusion

Needing 2^QN bits of memory (where N is a linear factor to allow for representing complex numbers) to represent Q simulated qubits is a conservative lower bound: it does not account for the memory needed to operate on those qubits and to keep the operators in memory. Needing $2^{2Q}T$ units of time for the multiplications needed to perform the operations on the qubits is not quite a lower bound: though it does not account for any overhead needed for efficient scheduling of those operations to allow them to run in parallel, for example, it also does not account for the fact that not all operations run on the entire state of the quantum computer.

A quantum computer uses the laws of physics that underpin the universe to perform its operations, however weird the effects of those laws turn out to be. This means that all those calculations that need to be done by a classical computer to simulate the quantum computer, are done automatically by nature in a real quantum computer. Nobody understands quite why or how it works, but it does seem to work rather nicely.

This is why Google's quantum supremacy experiment was both important, and possible: with 53 qubits, a classical computer needs $2^{53}N$ bits of memory, which is at least (at N=1) 1,125,899,906,842,624 bytes, or about one petabyte of memory just to hold the possible values. Google's quantum computer never did run operations on all the available qubits at once: it could only run them on pairs of qubits, though it could run operations on multiple qubits or pairs of qubits simultaneously. So while the memory requirement would be prohibitive, the execution time requirement ... was still prohibitive.

This does not explain why quantum computers can be useful. A hint for that is provided by Grover's algorithm, which reduces the search time for an item in an unsorted list from O(n) to $O(\sqrt{n})$. Another hint may be found in the quantum computer you already own and carry around with you on a daily basis: your brain. Biology has a lot to gain from quantum computers, including the ability to more accurately model biological processes which are inherently quantum systems. Nature has been using quantum mechanics for things like photosynthesis since life began. Now that we are harnassing those same quantum mechanics for computing, we may be able to exploit it to learn more about nature, medicine, and many other fields.