OSTEP Virtualizing Memory Paging

Questions answered in this lecture:

Review segmentation and fragmentation

What is paging?

Where are page tables stored?

What are advantages and disadvantages of paging?


Problem: Fragmentation

Definition: Free memory that can't be usefully allocated Why?

- Free memory (hole) is too small and scattered
- Rules for allocating memory prohibit using this free space

Types of fragmentation

- External: Visible to allocator (e.g., OS)
- Internal: Visible to requester (e.g., if must allocate at some granularity)




Logical View

Goal: Eliminate requirement that address space is contiguous

- Eliminate external fragmentation
- Grow segments as needed

Idea: Divide address spaces and physical memory into fixed-sized pages

- Size: 2ⁿ, Example: 4KB
- Physical page: page frame



Physical View

Advantages Of Paging

Flexibility: Supporting the abstraction of address space effectively

• Don't need assumption how heap and stack grow and are used.


Simplicity: ease of free-space management

- The page in address space and the page frame are the same size.
- Easy to allocate and keep a free list

Translation of Page Addresses

How to translate logical address to physical address?

- High-order bits of address designate page number
- Low-order bits of address designate offset within page





No addition needed; just append bits correctly...

How does format of address space determine number of pages and size of pages

Example: A Simple Paging

128-byte physical memory with 16 bytes page frames 64-byte address space with 16 bytes pages






64-Byte Address Space Placed In Physical Memory

Example: Address Translation

The virtual address 21 in 64-byte address space



Quiz: Address Format

Given known page size, how many bits are needed in address to specify offset in page?

Page Size	Low Bits (offset)		
16 bytes	4		
1 KB	10		
1 MB	20		
512 bytes	9		
4 KB	12		

Quiz: Address Format

Given number of bits in virtual address and bits for offset, how many bits for virtual page number?

Page Size	Low Bits (offset)	Virt Addr Bits	High Bits (vpn)
16 bytes	4	10	6
1 KB	10	20	10
1 MB	20	32	12
512 bytes	9	16	5 7
4 KB	12	32	20

Correct?


Quiz: Address Format

Given number of bits for vpn, how many virtual pages can there be in an address space?

Page Size	Low Bits (offset)	Virt Addr Bits	High Bits (vpn)	Virt Pages
16 bytes	4	10	6	64
1 KB	10	20	10	1 K
1 MB	20	32	12	4 K
512 bytes	9	16	5	32
4 KB	12	32	20	1 MB

Virtual => Physical Page Mapping

Number of bits in virtual address fo rmat does not ne ed to equal number of bits in physical address f ormat



How should OS translate VPN to PPN?


For segmentation, OS used a formula (e.g., phys addr = virt_offset + base_reg)

For paging, OS needs more general mapping mechanism What data structure is good?


Big array: pagetable

14

The Mapping



Quiz: Fill in Page Table



Where Are Pagetables Stored?

How big is a typical page table?

- assume **32-bit** address space
- assume 4 KB pages
- assume 4 byte entries

Final answer: $2 ^ (32 - \log(4KB)) * 4 = 4 MB$

- Page table size = Num entries * size of each entry
- Num entries = num virtual pages = 2^(bits for vpn)
- Bits for vpn = 32- number of bits for page offset = $32 - \lg(4KB) = 32 - 12 = 20$
- Num entries = $2^2 = 1$ MB
- Page table size = Num entries * 4 bytes = 4 MB


Implication: Store each page table in memory

• Hardware finds page table base with register (e.g., CR3 on x86)

What happens on a context-switch?

- Change contents of page table base register to newly scheduled process
- Save old page table base register in PCB of descheduled process

Example: Page Table in Kernel Physical Memory



What Is In The Page Table?

The page table is just a **data structure** that is used to map the virtual address to physical address.

• Simplest form: a linear page table, an array

The OS **indexes** the array by VPN, and looks up the page-table entry.


Common Flags Of Page Table Entry

- Valid Bit: Indicating whether the particular translation is valid.
- Protection Bit: Indicating whether the page could be read from, written to, or executed from
- Present Bit: Indicating whether this page is in physical memory or on disk(swapped out)
- **Dirty Bit**: Indicating whether the page has been modified since it was brought into memory
- Reference Bit(Accessed Bit): Indicating that a page has been accessed

Pagetable entries are just bits stored in memory

Agreement between hw and OS about interpretation

Example: x86 Page Table Entry



An x86 Page Table Entry(PTE)

• P: present

• R/W: read/write bit

• U/S: supervisor

A: accessed bit

• D: dirty bit

• PFN: the page frame number

Paging: Too Slow

- To find a location of the desired PTE, the **starting location** of the page table is **needed**.
- For every memory reference, paging requires the OS to perform one **extra memory reference**.

Accessing Memory With Paging

```
// Extract the VPN from the virtual address
        VPN = (VirtualAddress & VPN MASK) >> SHIFT
        // Form the address of the page-table entry (PTE)
        PTEAddr = PTBR + (VPN * sizeof(PTE))
        // Fetch the PTE
        PTE = AccessMemory(PTEAddr)
        // Check if process can access the page
10
11
        if (PTE.Valid == False)
12
                 RaiseException (SEGMENTATION FAULT)
13
        else if (CanAccess(PTE.ProtectBits) == False)
14
                 RaiseException (PROTECTION FAULT)
15
        else
16
                 // Access is OK: form physical address and fetch it
17
                 offset = VirtualAddress & OFFSET MASK
                 PhysAddr = (PTE.PFN << PFN SHIFT) | offset
18
19
                 Register = AccessMemory(PhysAddr)
```


A Memory Trace

• Example: A Simple Memory Access

```
prompt> gcc -o array array.c -Wall -o
prompt>./array
```

```
0x1024 movl $0x0,(%edi,%eax,4)
0x1028 incl %eax
0x102c cmpl $0x03e8,%eax
0x1030 jne 0x1024
```

A Virtual(And Physical) Memory Trace




Memory Accesses with Pages

0x0010: movl 0x1100, %edi 0x0013: addl \$0x3, %edi 0x0019: movl %edi, 0x1100

Assume PT is at phys addr 0x5000 Assume PTE's are 4 bytes Assume 4KB pages How many bits for offset? 12

Simplified view of page table



Old: How many mem refs with segmentation? 5 (3 instrs, 2 movl)

Physical Memory Accesses with Paging?

- 1) Fetch instruction at logical addr 0x0010; vpn?
 - Access page table to get ppn for vpn 0
 - Mem ref 1: 0x5000
 - Learn vpn 0 is at ppn 2
 - Fetch instruction at 0x2010 (Mem ref 2)

Exec, load from logical addr 0x1100; vpn?

- Access page table to get ppn for vpn 1
- Mem ref 3: 0x5004
- Learn vpn 1 is at ppn 0
- Movl from 0x0100 into reg (Mem ref 4)

Advantages of Paging

No external fragmentation

Any page can be placed in any frame in physical memory

Fast to allocate and free

- Alloc: No searching for suitable free space
- Free: Doesn't have to coallesce with adjacent free space
- Just use bitmap to show free/allocated page frames

Simple to swap-out portions of memory to disk (later lecture)

- Page size matches disk block size
- Can run process when some pages are on disk
- Add "present" bit to PTE

Disadvantages of Paging

Internal fragmentation: Page size may not match size needed by process


- Wasted memory grows with larger pages
- Tension?

Additional memory reference to page table --> Very inefficient

- Page table must be stored in memory
- MMU stores only base address of page table
- Solution: Add TLBs (future lecture)

Storage for page tables may be substantial

- Simple page table: Requires PTE for all pages in address space
 - Entry needed even if page not allocated
- Problematic with dynamic stack and heap within address space
- Page tables must be allocated contiguously in memory
- Solution: Combine paging and segmentation (future lecture)



Memory Allocators

Free-Space Management

Many systems need to manage/allocate space

- 1. physical space for process segments
- 2. virtual space for malloc calls
- 3. disk blocks for files




Allocation API

```
void *malloc(size_t size);
void free(void *ptr);


void *realloc(void *ptr, size_t size);
```


















Odd Object Sizes


Splitting




Splitting




Splitting















Bookkeeping


Need to know size+location of free spaces


- for malloc()


Need to know size of used spaces

- for free()












Start over




Start over









Free List: free




Free List: free




Free List: free



Free List: coalesce




Free List: coalesce





When coalescing is even trickier


Do we ever have to coalesce multiple areas?

```
free order may be arbitrary:
free(17KB);
" free(15KB);
" free(16KB)
```










Bookkeeping: free list

```
What fields do we need for each node in linked list?
struct node {
    int size;
    void *addr;
    struct node* next;
}
How do we allocate memory for new nodes?
- store them    free space!
- addr = ((void *)node + sizeof(*node)
```

Free List




Free List




Bookkeeping


```
Need to know size+location of free spaces
- for malloc()
Need to know size of used spaces
- for free()
```




Used size









Magic Numbers


Can malloc/free catch bugs for you?

- double frees?
- overflows


Add magic number to each allocated segment, if it is overwritten, there's a bug!

What can you spell with 0 - 1 and A - F? 0xDEADBEEF, 0xFEEDFACE, ...


Magic



Magic



Magic





Allocator Policy


Which free space to consider?


Of those considered, which to use?


No perfect solutions!































Review: Scheduler Vocabulary

Workload: set of job descriptions

Scheduler: logic that decides when jobs run

Metric: measurement of scheduling quality

Scheduler "algebra", given 2 variables, find the 3rd:

$$f(W, S) = M$$

Allocator Vocabulary

Workload: series of malloc()'s and free()'s

Allocator: logic that gives memory to processes

Metric: measurement of allocation quality

Allocator "algebra", given 2 variables, find the 3rd:

$$f(W, A) = M$$

Allocator Basics

Workload:	Allocators:	Metrics:
operations	Best fit	internal fragmentation
addresses	Worst fit	external fragmentation
sizes	First fit	search time
	Next fit	
	Slab	
	Buddy	

Summary

malloc provides a convenient library service to programs, abstracting the raw heap

Allocation is challenging because

- there is no right answer
- we can't use malloc ourselves
- expensive searching for ways to coalesce