OSTEP CPU Virtualization Process

Questions answered in this lecture:

What is a process?

Why is limited direct execution a good approach for virtualizing the CPU?

What execution state must be saved for a process?

What 3 modes could a process in?

What is a Process?

Process: An execution stream in the context of a process state

What is an execution stream?

- Stream of executing instructions
- Running piece of code
- "thread of control"

What is process state?

- Everything that the running code can affect or be affected by
- Registers
 - General purpose, floating point, status, program counter, stack pointer
- Address space
 - Heap, stack, and code
- Open files

Processes vs. Programs


A process is different from a program


- Program: Static code and static data
- Process: Dynamic instance of code and data

Can have multiple process instances of same program


Can have multiple processes of the same program

Example) many users can run "Is" at the same time





Disk



Processes vs. Threads

A process is different from a thread

Thread: "Lightweight process" (LWP)

- An execution stream that shares an address space
- Multiple threads within a single process

Example:

- Two **processes** examining same memory address 0xffe84264 see **different** values (I.e., different contents)
- Two **threads** examining memory address 0xffe84264 see **same** value (I.e., same contents)

Virtualizing the CPU

Goal: Give each process impression it alone is actively using CPU

Resources can be shared in **time** and **space**

```
Assume single uniprocessor

Time-sharing (multi-processors: advanced issue)
```

```
Memory?
Space-sharing (later)
```

Disk?
Space-sharing (later)

How to Provide Good CPU Performance?

Direct execution

- Allow user process to run directly on hardware
- OS creates process and transfers control to starting point (i.e., main())

OS	Program
1. Create entry for process list	
2. Allocate memory for program	
3. Load program into memory	
4. Set up stack with argc / argv	
5. Clear registers	
<pre>6. Execute call main()</pre>	
	7. Run main()
	8. Execute return from main()
9. Free memory of process	
10. Remove from process list	

How to Provide Good CPU Performance? (CONT.)

Problems with direct execution?

- 1. Process could do something restricted

 Could read/write other process data (disk or memory)
- 2. Process could run forever (slow, buggy, or malicious)
 OS needs to be able to switch between processes
- 3. Process could do something slow (like I/O)
 OS wants to use resources efficiently and switch CPU to other process

Without *limits* on running programs, the OS wouldn't be in control of anything and thus would be "just a library"

Solution:

Limited direct execution – OS and hardware maintain some control

Problem 1: Restricted OPs

How can we ensure user process can't harm others? What if a process wishes to perform some kind of restricted operation such as ...

- Issuing an I/O request to a disk
- Gaining access to more system resources such as CPU or memory

Solution: privilege levels supported by hardware (bit of status)

- User processes run in user mode (restricted mode)
- OS runs in kernel mode (not restricted)
 - Instructions for interacting with devices
 - Could have many privilege levels (advanced topic)

How can a process access device?

- System calls (function call implemented by OS)
- Change privilege level through system call (trap)

Allow the kernel to carefully expose certain key pieces of functionality to user programs, such as ...

- Accessing the file system
- Creating and destroying processes
- Communicating with other processes
- Allocating more memory

System Call (Cont.)


Trap instruction (int 0x00)

- Jump into the kernel
- Raise the privilege level to kernel mode

Return-from-trap instruction

- Return into the calling user program
- Reduce the privilege level back to user mode

Process P




P wants to call read()

Process P



P can only see its own memory because of **user mode** (other areas, including kernel, are hidden)

Process P



P wants to call read() but no way to call it directly


Process P




RAM


read():


movl \$3, %eax; int 0x80




movl \$3, %eax; int 0x80 syscall-table index












Kernel mode: we can do anything!






Follow entries to correct system call code



movl \$3, %eax; int 0x80



trap-table index

Kernel can access user memory to fill in user buffer return-from-trap at end to return to Process P

Limited Direct Execution





Limited Direction Execution Protocol

OS @ boot (kernel mode)	Hardware		
initialize trap table	remember address of syscall handler		
OS @ run (kernel mode)	Hardware	Program (user mode)	
Create entry for process list Allocate memory for program Load program into memory Setup user stack with argv Fill kernel stack with reg/PC return-from -trap	restore regs from kernel stack move to user mode jump to main	Run main() Call system trap into OS	23

Limited Direction Execution Protocol (Cont.)

OS @ run (kernel mode)	Hardware	Program (user mode)
	(Cont.)	
Handle trap Do work of syscall return-from-trap	save regs to kernel stack move to kernel mode jump to trap handler	
	restore regs from kernel stack move to user mode jump to PC after trap	
		 return from main trap (via exit())
Free memory of process Remove from process list		• •

What to limit?


User processes are not allowed to perform:

- General memory access
- •Disk I/O
- Special x86 instructions like lidt


load interrupt descriptor table register

What if process tries to do something restricted? Get HW help, put processes in "user mode"


lidt example



lidt example(cont.)



lidt example(cont.)



Problem 2: How to take CPU AWAY?

OS requirements for **multiprogramming** (or multitasking)

- Mechanism
 - To switch between processes
- Policy
 - To decide which process to schedule when

Separation of policy and mechanism

- Reoccurring theme in OS
- Policy: Decision-maker to optimize some workload performance metric

Which process when?

Process **Scheduler**: Future lecture

• Mechanism: Low-level code that implements the decision

How?

Process **Dispatcher**: Today's lecture

Dispatch Mechanism

OS runs dispatch loop

```
while (1) {
    run process A for some time-slice
    stop process A and save its context
    load context of another process B
}
```



Question 1: How does dispatcher gain control?

Question 2: What execution context must be saved and restored?

Q1: How does Dispatcher get CONTROL?

Option 1: Cooperative Multi-tasking


Processes periodically give up the CPU by making system calls such as yield.

- The OS decides to run some other task.
- Application also transfer control to the OS when they do something illegal.
 - Divide by zero
 - Try to access memory that it shouldn't be able to access
- Ex) Early versions of the Macintosh OS, The old Xerox Alto system


A process gets stuck in an infinite loop.

→ Reboot the machine


Switch contexts for syscall interrupt.




Switch contexts for syscall interrupt.




Switch contexts for syscall interrupt.



Switch contexts for syscall interrupt.



Switch contexts for syscall interrupt.



A Non-Cooperative Approach: OS Takes Control

A timer interrupt

- During the boot sequence, the OS start the timer.
- The timer raise an interrupt every so many milliseconds.
- When the interrupt is raised :
 - The currently running process is halted.
 - Save enough of the state of the program
 - A pre-configured interrupt handler in the OS runs.

A timer interrupt gives OS the ability to run again on a CPU.

A Non-Cooperative Approach: OS Takes Control(CONT.)

Switch contexts on timer interrupt.
Set up before running any processes.

HW does not let processes prevent this.

Is it better to be cooperative or non-cooperative?

Saving and Restoring Context

Scheduler makes a decision:

- Whether to continue running the current process, or switch to a different one.
- If the decision is made to switch, the OS executes <u>context</u> switch.

Context Switch

A low-level piece of assembly code

- Save a few register values for the current process onto its kernel stack
 - General purpose registers
 - PC
 - kernel stack pointer
- Restore a few for the soon-to-be-executing process from its kernel stack
- Switch to the kernel stack for the soon-to-be-executing process

Limited Direction Execution Protocol (Timer interrupt)

OS @ boot (kernel mode)	Hardware	
initialize trap table		
	remember address of syscall handler timer handler	
start interrupt timer		
	start timer interrupt CPU in X ms	
OS @ run (kernel mode)	Hardware	Program (user mode)
		Process A
	timer interrupt save regs(A) to k-stack(A) move to kernel mode jump to trap handler	

Limited Direction Execution Protocol (Timer interrupt)

OS @ run (kernel mode)	Hardware	Program (user mode)
	(Cont.)	
Handle the trap Call switch() routine save regs(A) to proc-struct(A) restore regs(B) from proc-struct(B switch to k-stack(B) return-from-trap (into B))	
	restore regs(B) from k-stack(B) move to user mode jump to B's PC	
		Process B

The xv6 Context Switch Code

```
1 # void swtch(struct context **old, struct context *new);
2 #
3 # Save current register context in old
4 # and then load register context from new.
5 .qlobl swtch
6 swtch:
          # Save old registers
          movl 4(%esp), %eax
                                       # put old ptr into eax
                                         # save the old IP
          popl 0(%eax)
          movl %esp, 4(%eax)
10
                                        # and stack
          movl %ebx, 8(%eax)
                                        # and other registers
11
12
          movl %ecx, 12(%eax)
1.3
          movl %edx, 16(%eax)
          movl %esi, 20(%eax)
14
15
          movl %edi, 24(%eax)
          mov1 %ebp, 28(%eax)
16
17
18
          # Load new registers
          movl 4(%esp), %eax
19
                                         # put new ptr into eax
20
          movl 28(%eax), %ebp
                                         # restore other registers
21
          movl 24(%eax), %edi
2.2
          movl 20(%eax), %esi
2.3
          movl 16(%eax), %edx
24
          movl 12(%eax), %ecx
25
          movl 8(%eax), %ebx
26
          movl 4(%eax), %esp
                                         # stack is switched here
2.7
          pushl 0(%eax)
                                         # return addr put in place
2.8
                                         # finally return into new ctxt
          ret
                                                                                   43
```

Worried About Concurrency?

What happens if, during interrupt or trap handling, another interrupt occurs?

OS handles these situations:

- Disable interrupts during interrupt processing
- Use a number of sophisticate **locking** schemes to protect concurrent access to internal data structures.

Q1: How does Dispatcher Run?

Problem with cooperative approach?

Disadvantages: Processes can misbehave

- By avoiding all traps and performing no I/O, can take over entire emachine
- Only solution: Reboot!

Not performed in modern operating systems

Q1: How does Dispatcher run?

Option 2: True Multi-tasking

- Guarantee OS can obtain control periodically
- Enter OS by enabling periodic alarm clock
 - Hardware generates timer interrupt (CPU or separate chip)
 - Example: Every 10ms
- User must not be able to mask timer interrupt
- Dispatcher counts interrupts between context switches
 - Example: Waiting 20 timer ticks gives 200 ms time slice
 - Common time slices range from 10 ms to 200 ms

Q2: What Context must be Saved?

Dispatcher must track context of process when not running Save context in process control block (PCB) (or, process descriptor)

What information is stored in PCB?

- PID
- Process state (I.e., running, ready, or blocked)
- Execution state (all registers, PC, stack ptr)
- Scheduling priority
- Accounting information (parent and child processes)
- Credentials (which resources can be accessed, owner)
- Pointers to other allocated resources (e.g., open files)

Requires special hardware support
Hardware saves process PC and PSR on interrupts

Operating System

Hardware

Program

Process A

••

Operating System

Hardware

Program

Process A

• • •

timer interrupt save regs(A) to k-stack(A) move to kernel mode jump to trap handler Operating System

Hardware

Program

Process A

000

timer interrupt save regs(A) to k-stack(A) move to kernel mode jump to trap handler

Handle the trap
Call switch() routine
save regs(A) to proc-struct(A)
restore regs(B) from proc-struct(B)
switch to k-stack(B)
return-from-trap (into B)

Operating System Hardware Program Process A timer interrupt save regs(A) to k-stack(A) move to kernel mode jump to trap handler Handle the trap Call switch() routine save regs(A) to proc-struct(A) restore regs(B) from proc-struct(B) switch to k-stack(B) return-from-trap (into B) restore regs(B) from k-stack(B) move to user mode

jump to B's IP

Operating System	Hardware	Program Process A
	timer interrupt save regs(A) to k-stack(A) move to kernel mode jump to trap handler	•••
Handle the trap Call switch() routine save regs(A) to proc-struct(A) restore regs(B) from proc-struct(B) switch to k-stack(B) return-from-trap (into B)	restore regs(B) from k-stack(B)	
	move to user mode jump to B's IP	
		Process B
		000

Problem 3: Slow Ops such as I/O?

When running process performs op that does not use CPU, OS switches to process that needs CPU (policy issues)





Transitions?

OS must track mode of each process:



- Running:
 - On the CPU (only one on a uniprocessor)
- Ready:
 - Waiting for the CPU
- Blocked
 - Asleep: Waiting for I/O or synchronization to complete

Problem 3: Slow Ops such as I/O?

OS must track every process in system

Each process identified by unique Process ID (PID)

OS maintains queues of all processes

- Ready queue: Contains all ready processes
- Event queue: One logical queue per event
 - e.g., disk I/O and locks
 - Contains all processes waiting for that event to complete

Next Topic: Policy for determining which ready process to run

Summary

Virtualization:

Context switching gives each process impression it has its own CPU

Direct execution makes processes fast

Limited execution at key points to ensure OS retains control

Hardware provides a lot of OS support

- user vs kernel mode
- timer interrupts
- automatic register saving