# **Project 4**

Due May 31, 2016 at 11:55 PM

You will be working with a partner for this project, you specify your partner in your readme file. This specification is subject to change at anytime for additional clarification. For this project, you and a partner will be implementing a virtual machine threading API in either C or C++. Your virtual machine will be tested on the CSIF machines. You must submit your source files, readme and Makefile in a zip or tar.gz file to smartsite prior to the deadline.

You will be continuing the development of your virtual machine. You will be adding the ability to mount and manipulate a FAT file system image. Except were specified in this description the API will remain as stated in the Project 2 & 3 descriptions. Files that are opened in the virtual machine will now be opened on the FAT image instead of in the host file system. The reading and writing of the files will affect the FAT image with the exception of file descriptor 0-2, which will still affect the standard in, out, and error files. The fatgen103.pdf in the resources is the Microsoft white paper on FAT. You do not need to fully implement all possible FAT file systems. You may make the following assumptions:

- 1. All images have 512 byte sectors
- 2. All images are FAT 16
- 3. Long file name entries will contiguously proceed the corresponding short file name entry

You must implement the ability to create, read and write files that are in the root directory and to open and read the root directory. You must be able to read all of the short file name entries (long file name entries can be skipped) in the root directory.

A working example of the vm and apps can be found in /home/cjnitta/ecs150. The vm syntax is vm [options] appname [appargs]. The possible options for vm are -t, -h, -s and -f; -t specifies the tick time in millisecond, -h specifies the size of the heap this is the size of the VM\_MEMORY\_POOL\_ID\_SYSTEM memory pool, -s specifies the size of the shared memory used between the virtual machine and machine, and -f specifies the FAT image to be mounted. By default the tick time is set to 100ms, for debugging purposes you can increase this value to slow the running of the vm. The size of the heap by default is 16MiB, and the shared memory is 16KiB. The default FAT image is fat.ima. When specifying the application name the ./ should be prepended otherwise vm may fail to load the shared object file. In addition you will find several programs that will help create and manipulate the fat images in the /home/cjnitta/ecs150 directory.

Several functions have been provided for you in the VirtualMachineUtils.c that you might find useful, not all will be necessary: VMDateTime, VMFileSystemValidPathName, VMFileSystemIsRelativePath, VMFileSystemIsAbsolutePath, VMFileSystemGetAbsolutePath, VMFileSystemPathIsOnMount, VMFileSystemDirectoryFromFullPath,

VMFileSystemFileFromFullPath, VMFileSystemConsolidatePath, VMFileSystemSimplifyPath, VMFileSystemRelativePath.

The function specifications for both the virtual machine and machine are provided in the subsequent pages.

You should avoid using existing source code as a primer that is currently available on the Internet. You **must** specify in your readme file any sources of code that you or your partner have viewed to help you complete this project. All class projects will be submitted to MOSS to determine if pairs of students have excessively collaborated with other pairs. Excessive collaboration, or failure to list external code sources will result in the matter being transferred to Student Judicial Affairs.

#### **Extra Credit:**

Add support for subdirectories, this includes creating, deleting, and modifying files and directories anywhere in the directory structure. Implement the VMDirectoryUnlink and VMDirectoryCreate functions. Add support for long file names, the long file names should be both read correctly from directories as well as created when new files are added to the mounted file system.

#### Name

VMStart – Start the virtual machine.

# Synopsys

```
#include "VirtualMachine.h"

TVMStatus VMStart(int tickms, TVMMemorySize heapsize, TVMMemorySize sharedsize, const char *mount,
int argc, char *argv[]);
```

# Description

VMStart() starts the virtual machine by loading the module specified by argv[0]. The argc and argv are passed directly into the VMMain() function that exists in the loaded module. The time in milliseconds of the virtual machine tick is specified by the tickms parameter. The heap size of the virtual machine is specified by heapsize. The heap is accessed by the applications through the VM\_MEMORY\_POOL\_ID\_SYSTEM memory pool. The size of the shared memory space between the virtual machine and the machine is specified by the sharedsize. The name of the FAT file system image is specified by mount.

### Return Value

Upon successful loading and running of the VMMain() function, VMStart() will return VM\_STATUS\_SUCCESS after VMMain() returns. If the module fails to load, or the module does not contain a VMMain() function, or if the *mount* FAT file system image cannot be loaded, VM\_STATUS\_FAILURE is returned.

#### Name

VMFileOpen – Opens and possibly creates a file in the mounted FAT file system.

## Synopsys

```
#include "VirtualMachine.h"

TVMStatus VMFileOpen(const char *filename, int flags, int mode, int *filedescriptor);
```

# Description

VMFileOpen() attempts to open the file specified by *filename*, using the flags specified by *flags* parameter, and mode specified by *mode* parameter. The file descriptor of the newly opened file will be placed in the location specified by *filedescriptor*. The flags and mode values follow the same format as that of open system call. The filedescriptor returned can be used in subsequent calls to VMFileClose(), VMFileRead(), VMFileWrite(), and VMFileSeek(). When a thread calls VMFileOpen() it blocks in the wait state VM\_THREAD\_STATE\_WAITING until the either successful or unsuccessful opening of the file is completed. In order to prevent confusion with standard in, out and error, the file descriptor returned in the location specified by *filedescriptor* will be 3 or larger.

## Return Value

Upon successful opening of the file, VMFileOpen() returns VM\_STATUS\_SUCCESS, upon failure VMFileOpen() returns VM\_STATUS\_FAILURE. If either *filename* or *filedescriptor* are NULL, VMFileOpen() returns VM\_STATUS\_ERROR\_INVALID\_PARAMETER.

## Name

VMFileClose – Closes a file that was previously opened in the mounted FAT file system.

## Synopsys

#include "VirtualMachine.h"

TVMStatus VMFileClose(int filedescriptor);

## Description

VMFileClose() closes a file previously opened with a call to VMFileOpen(). When a thread calls VMFileClose() it blocks in the wait state

VM\_THREAD\_STATE\_WAITING until the either successful or unsuccessful closing of the file is completed.

## Return Value

Upon successful closing of the file VMFileClose() returns VM\_STATUS\_SUCCESS, upon failure VMFileClose() returns VM\_STATUS\_FAILURE.

#### Name

VMFileRead – Reads data from a file.

# Synopsys

#include "VirtualMachine.h"

TVMStatus VMFileRead(int filedescriptor, void \*data, int \*length);

# Description

VMFileRead() attempts to read the number of bytes specified in the integer referenced by *length* into the location specified by *data* from the file specified by *filedescriptor*. The *filedescriptor* should have been obtained by a previous call to VMFileOpen(). The actual number of bytes transferred by the read will be updated in the *length* location. When a thread calls VMFileRead() it blocks in the wait state VM\_THREAD\_STATE\_WAITING until the either successful or unsuccessful reading of the file is completed. If the filedescriptor is less than 3 the reading will be attempted on the main file system, if the value of filedescriptor is 3 or larger the reading will be attempted on the mounted FAT file system file.

### Return Value

Upon successful reading from the file, VMFileRead() returns VM\_STATUS\_SUCCESS, upon failure VMFileRead() returns VM\_STATUS\_FAILURE. If *data* or *length* parameters are NULL, VMFileRead() returns VM\_STATUS\_ERROR\_INVALID\_PARAMETER.

#### Name

VMFileWrite – Writes data to a file.

## Synopsys

#include "VirtualMachine.h"

TVMStatus VMFileWrite(int filedescriptor, void \*data, int \*length);

## Description

VMFileWrite() attempts to write the number of bytes specified in the integer referenced by *length* from the location specified by *data* to the file specified by *filedescriptor*. The *filedescriptor* should have been obtained by a previous call to VMFileOpen(). The actual number of bytes transferred by the write will be updated in the *length* location. When a thread calls VMFileWrite() it blocks in the wait state

VM\_THREAD\_STATE\_WAITING until the either successful or unsuccessful writing of the file is completed. If the *filedescriptor* is less than 3 the writing will be attempted on the main file system, if the value of *filedescriptor* is 3 or larger the writing will be attempted on the mounted FAT file system file.

### Return Value

Upon successful writing from the file, VMFileWrite() returns VM\_STATUS\_SUCCESS, upon failure VMFileWrite() returns VM\_STATUS\_FAILURE. If *data* or *length* parameters are NULL, VMFileWrite() returns VM\_STATUS\_ERROR\_INVALID\_PARAMETER.

#### Name

VMFileSeek – Seeks within a file.

## Synopsys

```
#include "VirtualMachine.h"

TVMStatus VMFileSeek(int filedescriptor, int offset, int whence, int *newoffset);
```

# Description

VMFileSeek() attempts to seek the number of bytes specified by *offset* from the location specified by *whence* in the file specified by *filedescriptor*. The *filedescriptor* should have been obtained by a previous call to VMFileOpen(). The new offset placed in the *newoffset* location if the parameter is not NULL. When a thread calls VMFileSeek() it blocks in the wait state VM\_THREAD\_STATE\_WAITING until the either successful or unsuccessful seeking in the file is completed. If the *filedescriptor* is less than 3 the seeking will be attempted on the main file system, if the value of *filedescriptor* is 3 or larger the seeking will be attempted on the mounted FAT file system file.

### Return Value

Upon successful seeking in the file, VMFileSeek () returns VM\_STATUS\_SUCCESS, upon failure VMFileSeek() returns VM\_STATUS\_FAILURE.

### Name

VMDirectoryOpen – Opens a directory for reading in the mounted FAT file system.

# **Synopsys**

#include "VirtualMachine.h"

TVMStatus VMDirectoryOpen(const char \*dirname, int \*dirdescriptor);

# Description

VMDirectoryOpen() attempts to open the directory specified by *dirname*. The directory descriptor of the newly opened directory will be placed in the location specified by *dirdescriptor*. The directory descriptor returned can be used in subsequent calls to VMDirectoryClose(), VMDirectoryRead(), and VMDirectoryRewind(). When a thread calls VMDirectoryOpen() it must block in the wait state VM\_THREAD\_STATE\_WAITING if the opening of the directory cannot be completed immediately. In order to prevent confusion with standard in, out and error, the file descriptor returned in the location specified by *dirdescriptor* will be 3 or larger.

### Return Value

Upon successful opening of the directory, VMDirectoryOpen() returns VM\_STATUS\_SUCCESS, upon failure VMDirectoryOpen() returns VM\_STATUS\_FAILURE. If either *dirname* or *dirdescriptor* are NULL, VMDirectoryOpen() returns VM\_STATUS\_ERROR\_INVALID\_PARAMETER.

## Name

VMDirectoryClose – Closes a directory that was previously opened in the mounted FAT file system.

# **Synopsys**

#include "VirtualMachine.h"

TVMStatus VMDirectoryClose(int dirdescriptor);

# Description

VMDirectoryClose() closes a directory previously opened with a call to VMDirectoryOpen(). When a thread calls VMDirectoryClose() it blocks in the wait state VM\_THREAD\_STATE\_WAITING if the closing of the directory cannot be completed immediately.

## Return Value

Upon successful closing of the directory VMDirectoryClose() returns VM\_STATUS\_SUCCESS, upon failure VMDirectoryClose() returns VM\_STATUS\_FAILURE.

### Name

VMDirectoryRead – Reads a directory entry from a directory in the mounted FAT file system.

## Synopsys

#include "VirtualMachine.h"

TVMStatus VMDirectoryRead(int dirdescriptor, SVMDirectoryEntryRef dirent);

# **Description**

VMDirectoryRead() attempts to read the next directory entry into the location specified by *dirent* from the file specified by *dirdescriptor*. The *dirdescriptor* should have been obtained by a previous call to VMDirectoryOpen(). When a thread calls VMDirectoryRead() it blocks in the wait state VM\_THREAD\_STATE\_WAITING if the reading of the directory entry cannot be completed immediately.

### Return Value

Upon successful reading from the directory, VMDirectoryRead() returns VM\_STATUS\_SUCCESS, upon failure VMDirectoryRead() returns VM\_STATUS\_FAILURE. If *dirent* parameter is NULL, VMDirectoryRead() returns VM\_STATUS\_ERROR\_INVALID\_PARAMETER.

### Name

VMDirectoryRewind – Rewinds a previously opened directory to the beginning.

## Synopsys

#include "VirtualMachine.h"

TVMStatus VMDirectoryRewind(int dirdescriptor);

# Description

VMDirectoryRewind() attempts to rewind the directory specified by *dirdescriptor* to the beginning. The *dirdescriptor* should have been obtained by a previous call to VMDirectoryOpen(). When a thread calls VMDirectoryRewind() it should block in the wait state VM\_THREAD\_STATE\_WAITING if it is not possible to complete the rewind operation immediately.

## Return Value

Upon successful rewinding of the directory, VMDirectoryRewind() returns VM\_STATUS\_SUCCESS, upon failure VMDirectoryRewind() returns VM\_STATUS\_FAILURE.

## Name

VMDirectoryCurrent – Fill the absolute path with the current working directory in the mounted FAT filesystem.

# Synopsys

```
#include "VirtualMachine.h"

TVMStatus VMDirectoryCurrent(char *abspath);
```

# **Description**

VMDirectoryCurrent() attempts to place the absolute path of the current working directory in the location specified by *abspath*.

## Return Value

Upon successful copying of the directory name into *abspath*, VMDirectoryCurrent() returns VM\_STATUS\_SUCCESS, if *abspath* is NULL then VMDirectoryCurrent() returns VM\_STATUS\_INVALID\_PARAMETER.

## Name

VMDirectoryChange – Changes the current working directory of the mounted FAT file system.

## **Synopsys**

```
#include "VirtualMachine.h"

TVMStatus VMDirectoryChange(const char *path);
```

# **Description**

VMDirectoryChange() attempts to change the current working directory of the mounted FAT file system to the name specified by *path*.

## Return Value

Upon successful changing of the directory to *path*, VMDirectoryChange() returns VM\_STATUS\_SUCCESS, if path specified by *path* does not exist, VMDirectoryChange() returns VM\_STATUS\_FAILURE. If *path* is NULL then VMDirectoryChange() returns VM\_STATUS\_INVALID\_PARAMETER.

### Name

VMDirectoryCreate – Attempts to create a directory in the mounted FAT file system. (EXTRA CREDIT ONLY)

## **Synopsys**

```
#include "VirtualMachine.h"

TVMStatus VMDirectoryCreate(const char *dirname);
```

# **Description**

VMDirectoryCreate() attempts to create a directory in the mounted FAT file system specified by *dirname*.

## Return Value

Upon successful creation of the directory, VMDirectoryCreate() returns VM\_STATUS\_SUCCESS, if *dirname* is NULL then VMDirectoryCreate() returns VM\_STATUS\_INVALID\_PARAMETER. If the directory is unable to be created, VMDirectoryCreate() returns VM\_STATUS\_FAILURE.

### Name

VMDirectoryUnlink – Removes a directory or file from the mounted FAT file system. (EXTRA CREDIT ONLY)

## Synopsys

```
#include "VirtualMachine.h"

TVMStatus VMDirectoryUnlink(const char *path);
```

# **Description**

VMDirectoryUnlink() attempts to remove the file or directory specified by *path* from the mounted FAT file system. VMDirectoryUnlink() will fail if the file or directory is current opened, or if the directory attempting to be unlinked is a parent of an open file or directory.

## Return Value

Upon successful removing of the directory or file, VMDirectoryUnlink() returns VM\_STATUS\_SUCCESS, upon failure VMDirectoryUnlink() returns VM\_STATUS\_FAILURE. If *path* is NULL then VMDirectoryUnlink() returns VM\_STATUS\_INVALID\_PARAMETER.