Reference » mPDF functions

CreateIndex()

(mPDF >= 2.2)

CreateIndex — Generate an Index for the document

Note: This function is removed in mPDF v6.0 and replaced by InsertIndex()

Description

void **CreateIndex** ([int \$numberofcolumns [, float \$fontsize [, float \$linespacing [, float \$offset [, int \$usedivletters [, float \$divlettersfontsize [, float \$columngap [, string \$font [, string \$divletterfont [, boolean \$uselinking]]]]]]))

Inserts an Index for the document based on index entries made using <indexentry> or CreateIndex().

Note: Prior to mPDF 2.2 the function CreateReference() was used. CreateIndex() is now the preferred form.

Note: uselinking was added in mPDF 3.0

Parameters

numberofcolumns

Set the number of (vertical) columns to use for the Index **BLANK** or omitted or 0 or 1 uses the whole page is used as one column. **DEFAULT**: 1

fontsize

Sets the font size for the Index in *points* (pt) **BLANK** or omitted or 0 uses the default font-size for the document.

linespacing

Sets the line-height used for index entries. Usual values between 1.0 and 1.4. **BLANK** or omitted or 0 uses the default value. **DEFAULT**: 1.2 (changed from 1.0 in mPDF < 3.0)

offset

Sets the text indent (in mm) for subsequent lines, if an index entry flows onto two or more lines. **BLANK** or omitted uses a default value of 3mm.

usedivletters

Defines whether to divide index entries starting with the same letter, using a (large) letter as a heading.

DEFAULT: 1

Values

- 1: show dividing letters in the Index
- 0: do not show dividing letters in the Index
- BLANK or omitted uses a default value of 1

divlettersfontsize

2015-08-05

Sets the font size for the dividing letters in *points* (pt)

BLANK or omitted or 0 uses the 1.8 times the default font-size for the document.

columngap

```
Sets the gap between columns (if set) in millimeters.

BLANK or omitted uses the default value.

DEFAULT: 5 (mm)
```

font

```
Set the font-family for the Index.

BLANK or omitted uses default font-family for the document.
```

divletterfont

```
Set the font-family for the dividing letters in the Index.

BLANK or omitted uses default font-family for the document.
```

uselinking

```
Specify whether to add hyperlinks (internal links) to the entries in the document Index.

TRUE or 1: add links to Index

BLANK or omitted, 0 or FALSE: do not add links to the Index

DEFAULT: FALSE
```

Changelog

| Version | Description |
|---------|--|
| 2.2 | Function was added as a synonym for CreateReference(). |
| 3.0 | uselinking parameter was added |
| 3.0 | Default value for linespacing changed to 1.2 |

Examples

Example #1

```
<?php
$mpdf=new mPDF();

$mpdf->WriteHTML('Beginning bit of document...');

$mpdf->IndexEntry("Buffalo");

$mpdf->WriteHTML('Your text which refers to a buffalo, which you would like to see in the Index');

$mpdf->AddPage();

$mpdf->AddPage();

$mpdf->WriteHTML('<h2>Index</h2>',2);

$mpdf->CreateIndex(2, '', '', 3, 1, '', 5, 'serif','sans-serif');

$mpdf=Output();

?>
```

Note: There is no HTML equivalent of CreateIndex()

See Also

- IndexEntry() Add an Index entry in the document
- <indexentry> Mark an Index entry in the document

Printed on Wed 05 Aug 2015 12:14:03 GMT +0100 (DST)

2015-08-05