Reference » HTML control tags

barcode

(mPDF >= 4.0)

barcode - Add a Barcode to the document

Description

```
<barcode code [ type ] [ text ] [ size ] [ height ] [ pr ] />
```

Add a Barcode to the document.

Note: See barcodes and the example file for further information.

Attributes

code

Specifies the code to translate to a barcode.

code for EAN13 / ISBN / ISSN / UPCA / UPCE can contain hyphens '-' but no other characters are allowed. Check-digits can be optionally included for EAN13 / ISBN / ISSN / UPCA / UPCE

REQUIRED

type

type specifies the type of barcode required.

DEFAULT: EAN13

Values

EAN13, ISBN, ISSN, UPCA, UPCE, EAN8

EAN13P2, ISBNP2, ISSNP2, UPCAP2, UPCEP2, EAN8P2 (with EAN-2 supplement code i.e. 01-99)

EAN13P5, ISBNP5, ISSNP5, UPCAP5, UPCEP5, EAN8P5 (with EAN-5 supplement code e.g. 90000)

(UPCE needs the UPCA code entered)

IMB, RM4SCC, KIX, POSTNET, PLANET

C128A, C128B, C128C

EAN128A, EAN128B, EAN128C

C39, C39+, C39E, C39E+

S25, S25+, I25, I25+, I25B, I25B+

C93

MSI, MSI+

CODABAR

CODE11

Note: Type with a + at the end includes check-digits.

text

EAN13 only

Specifies whether to show the the code at the top of an EAN13 barcode.

Note that ISBN and ISSN always show the text, prefixed with ISBN or ISSN.

Values: 1 or 0 **DEFAULT**: 0

size

2015-08-05

Specifies the size of the barcode.

size (float) will scale the nominal size of the barcode as a factor of 1

size="1.5" will generate a barcode one and half times the height and width of the nominal size set in mPDF

NB Sizes between 0.8 and 2.0 are recommended for EAN13 and similar barcodes.

DEFAULT: 1

height

Specifies the height of the barcode.

height (float) will determine the relative height of the barcode as a factor of 1

The height factor is applied after the size

size="2" height="0.5" will generate a barcode of twice the nominal width, but with the nominal height.

NB Ignored for Postcode barcodes

DEFAULT: 1

pr

Specifies the print ratio i.e. narrow:wide bar width for some types of barcode.

Valid for: C39 (Code 39), Standard and Interleaved 2 of 5 (S25, I25 etc.), CODABAR and CODE11

DEFAULT: Varies between 2.5 and 3.0 dependent on barcode specification (see barcodes)

Changelog

Version	Description
4.0	The function was added.

Examples

Examples

```
<barcode code="978-0-9542246-0" type="ISBN" height="0.66" text="1" />
```

```
<barcode code="978-0-9542246-0-8 07" type="ISSNP2" text="1" />
```

```
<barcode code="01234567094987654321-01234567891" type="IMB" />
```

```
<barcode code="SN34RD1A" type="RM4SCC" />
```

```
<barcode code="54321068" type="I25" />
```

<barcode code="A34698735B" type="CODABAR" />

Notes

Note: The following CSS properties can be set on the <bar>
 element as though it were standard

HIML:

vertical-align (default: middle)

border*

margin*

padding* (default 2mm for EAN13)

color (default black)

background-color (default white)

2015-08-05

NB padding has defaults as 0(mm) if not specified Padding is in addition to any specified quiet zones/light margins.

Example with CSS

```
<style>
.barcode {
    padding: 1.5mm;
    margin: 0;
    vertical-align: top;
    color: #000044;
}
.barcodecell {
    text-align: center;
    vertical-align: middle;
}
</style>
<div class="barcodecell"><barcode code="54321068" type="I25" class="barcode" /></div>
```

Note: mPDF will generate a Checkdigit for most barcodes if required, which is added to the barcode. If you need to know what the checkdigit is for a particular barcode, you could do the following:

Example - Generating a checkdigit

```
// Must not contain any - or spaces
include('../classes/barcode.php');
$bc = new PDFBarcode();
echo $bc->getChecksum('9344543204454', 'C93');
exit;
```

See Also

Barcodes - More information on types of barcode

Printed on Wed 05 Aug 2015 12:18:37 GMT +0100 (DST)

2015-08-05