

# C++ GEMS CHRONO & RATIO

Jeff Garland

C++Now 2012

## ALTERNATIVE TITLES

How `boost.date_time` inspired C++11 to handle time better

Why C++11 is the awesomest language to write **timed** threading code

# PART 1: CHRONO

# MOTIVATION – A HORROR STORY

Once upon a time timing was needed for boost  
thread...and there was `xtime`

And the sacred docs said:

“An object of type `xtime` defines a time...”

“This is a `temporary` solution that will be  
replaced by a more robust time library  
once available in Boost.”

`Temporary` almost became 8

# MOTIVATION – A HORROR STORY

What is xtime...

```
struct xtime {  
    platform-specific-type sec;  
};
```

```
int xtime_get(xtime*, int);
```

# MOTIVATION – A HORROR STORY

## It's not just xtime – it's C & Posix

```
struct timespec ts;
```

```
/* Delay for a bit */
```

```
ts.tv_sec = 2;
```

```
ts.tv_nsec = 1030;
```

```
nanosleep (&ts, NULL);
```



Isn't every bit precious?




How long is this sleep exactly?

Need to do math on these? Good luck it's ugly...

Comparison is inefficient

Not awesome – we can do better!

# "TIME" FOR A LITTLE THEORY



Time Point – a location in the time continuum

Handy for saying 'at exactly this time'

Epoch – the anchor point for the counted representation

Durations – a length of time

Handy for saying '10 seconds from now'

A count (with a resolution)

10 seconds, 20 milliseconds, etc

Clocks

Tell us the current time point

At a certain resolution...

# THREADING INTERFACES WITH TIMES

Timed Locking:

```
bool try_lock_for( const duration& relative_time);  
bool try_lock_until( const time_point& absolute_time);
```

Condition Variable Methods:

```
bool wait_until(unique_lock<mutex>& lock,  
                const time_point& absolute_time,  
                Predicate p)
```

```
cv_status wait_for(unique_lock<mutex>& lock,  
                  const duration& relative_time)
```

# MORE THREADING INTERFACES WITH TIMES

Sleeping:

```
void sleep_for ( const duration& relative_time);  
void sleep_until( const time_point& absolute_time);
```

std::future, std::shared\_future

```
bool wait_for(const duration& relative_time) const  
bool wait_until(const time_point& absolute_time) const
```

Last 2 slides – **many lies....**

In the real world things are a bit more complex

More later...

# "TIME" FOR SOME REST – CERTIFIED C++11

Sleeping:

```
using namespace std::chrono;  
std::this_thread::sleep_for( milliseconds(100) );  
std::this_thread::sleep_for( seconds(2) );
```

//when c++ crushes java...how long is that exactly?

```
java.lang.Thread.currentThread().sleep(10000);
```

C++11 is the awesomest

# DURATIONS ARE COOL

```
using namespace std::chrono;  
  
microseconds d1(1000);  
seconds      d2(1);  
  
d1 += seconds(30);    ← Convert seconds to microseconds  
d1 += milliseconds(1) - microseconds(20);  
d2++; d1--;  
d2*=10;  
  
if (d1 > d2) {...} //the usual comparisons  
  
std::cout << d1.count() << std::endl;
```

# DURATIONS INTERFACE

An arithmetic value type (more later)

Expected Comparison operators

Observers

```
constexpr rep_type count() const
```

Traits

```
static constexpr duration zero();
```

```
static constexpr duration min();
```

```
static constexpr duration max();
```

## DURATIONS – CONSTRUCT/COPY/DESTROY

```
constexpr duration() = default;           //duration 0
```

```
~duration() = default;
```

```
duration(const duration&) = default;
```

```
duration& operator=(const duration&) = default;
```

```
template <class Rep2, class Period2>
```

```
constexpr duration(const duration<Rep2, Period2>& d);
```

# DURATIONS INTERFACE - ARITHMETIC

duration& operator++();

duration operator++(int);

duration& operator--();

duration operator--(int);

duration& operator+=(const duration& d);

duration& operator-=(const duration& d);

duration& operator\*=(const rep& rhs);

duration& operator/=(const rep& rhs);

duration& operator%=(const rep& rhs);

duration& operator%=(const duration& rhs);

# LET'S SLEEP TILL AN ABSOLUTE TIME

```
system_clock::time_point tp = system_clock::now();
```

```
tp += milliseconds(20);
```

```
std::this_thread::sleep_until(tp);
```

# CLOCK INTERFACE

Clock is a bundle consisting of a duration, a time\_point, and a function `now()` to get the current time

Construction

None

static time\_point now()

Declared Types

time\_point

duration

# TIME POINTS AND DURATIONS PLAY NICE

```
system_clock::time_point tp;
```

```
system_clock::time_point tp2 = tp + seconds(2) + milliseconds(20);
```

duration + time point ?    time point    duration + duration ?    duration

```
nanoseconds ms = tp2 - tp;
```

time point - time point ?    duration

```
milliseconds ms = tp2 - tp;    ← Compiler error – not enough resolution
```

C++11 is the awesomest

# TIME POINT INTERFACE

## Construction

default //constructs to clock epoch  
call now() on a clock

## Conversion

time\_t to\_time\_t()  
duration time\_since\_epoch()

## Arithmetic

time\_point& operator+= (const duration& d);  
time\_point& operator-= (const duration& d);

# PROBLEMS AND COMPLICATIONS

Clocks are not all created equal...

Resolution of clock depends on machine

Machines are changing

Typically millisecond resolution

How can the C++ standard specify reasonably?

What we want:

Code that can be portable as possible

Code that can take full advantage of a platform

Code that doesn't have to change as clocks improve

Code that 'just works'

**Answer - templates of course!**

# TRY LOCK INTERFACE – THE REAL DEAL

```
template<typename Rep,typename Period>
bool
try_lock_for(std::chrono::duration<Rep,Period> const& relative_time);
```

```
template<typename Clock,typename Duration>
bool
try_lock_until(std::chrono::time_point<Clock,Duration> const& absolute_time);
```

The generic interfaces allow for custom clocks to be added – same interface

# THREE STANDARD CLOCKS

## system\_clock

Represent wall clock time from the system-wide realtime clock

typically this will be implemented via `gettimeofday()`

clock can be adjusted – possibly backward

user sets time, NTP adjust

## steady\_clock

values of `time_point` never decrease as physical time advances

values of `time_point` advance at a steady rate relative to real time

clock cannot be adjusted

## high\_resolution\_clock

Clock with the shortest tick period.

may be a synonym for `system_clock` or `steady_clock`.

Beware – platforms will be different – your mileage may vary

## PART 2: UNDER THE HOOD -- RATIO

# WHERE THE MAGIC HAPPENS

//chrono header

typedef duration<int64_t, nano>	nanoseconds;
typedef duration<int64_t, micro>	microseconds;
typedef duration<int64_t, milli>	milliseconds;
typedef duration<int64_t>	seconds;
typedef duration<int, ratio< 60>>	minutes;
typedef duration<int, ratio<3600>>	hours;

What is 'nano' and what is ratio<3600> doing?

# RATIO THE BASICS

Compile time rational numbers  
template ratio<N, M>

Math functions that go with  
add, subtract, multiply, divide

The magic behind duration to duration conversion

# RATIO EXAMPLE

Example – duration unit conversions

1 second is fundamental unit of measure

There are 1000 milliseconds in a second

Milliseconds to seconds -- divide by 1000

```
//abbreviated list from g++ ratio header
typedef ratio<1,          1000000000> nano;
typedef ratio<1,          1000000> micro;
typedef ratio<1,          1000> milli;
typedef ratio<1,          100> centi;
typedef ratio<1,          10> deci;
typedef ratio<            10, 1> deca;
typedef ratio<            100, 1> hecto;
typedef ratio<           1000, 1> kilo;
```

...

# CONVERSIONS USING RATIO

```
system_clock::time_point tp;
```

```
system_clock::time_point tp2 = tp + seconds(2) + milliseconds(20);
```

Duration added to time point

Duration added to Duration

```
nanoseconds ms = tp2 - tp;
```

Duration subtracted from time point

```
milliseconds ms = tp2 - tp; ← Compiler error – not enough resolution
```

# CONVERSION FROM SECONDS TO HOURS

1 second is fundamental unit of measure

There are 3600 seconds in a hour

Multiply seconds by 3600

ratio<3600, 1> or shorter version ratio<3600>

# CUSTOM DURATIONS – EASY AS PIE

What if I need to deal in other time lengths?

Say 1/2 of a second is important unit

```
typedef std::ratio<1,2> half;  
typedef std::chrono::duration<int64_t, half> half_seconds;
```

half\_seconds is now useable in all thread/sleep APIS

half\_seconds ‘just works’ with all the other durations

## CUSTOM DURATIONS IN ACTION

```
half_seconds hs = seconds(10);
std::cout << hs.count() << std::endl; //20
```

```
seconds s = half_seconds(3);
```

error: conversion from 'half\_seconds' to non-scalar  
type 'std::chrono::seconds' requested

```
seconds s = duration_cast<seconds>(half_seconds(3));
std::cout << s.count() << std::endl; //1
```

## PART 3: FINAL THOUGHTS

# NOT ALL SWEETNESS AND LIGHT

```
#include <chrono>
#include <iostream>
```

...

```
using namespace std::chrono;
```

```
system_clock::time_point tp = system_clock::now();
```

```
std::cout << tp << std::endl; ← Compiler error – no operator
```

# BOOST TO THE RESCUE

```
#include <boost/date_time.hpp>

using namespace std::chrono;
using namespace boost::posix_time;

system_clock::time_point tp = system_clock::now();

ptime tp2(from_time_t(system_clock::to_time_t(tp)));

std::cout << tp2 << std::endl; // YYYY-MM-DD HH:MM:SS
```

# CHRONO VS BOOST DATE.TIME – WHAT NEXT?

Boost date.time needs to be re-written for c++11

Should adopt the duration types from c++11

Should adopt the time\_point abstractions (almost)

Should adopt the clocks from chrono

From there – it's more complicated

ptime stands alone from clocks

Can't promise when this will happen....

## FINAL THOUGHTS

No more excuses – only elegant time code in C++11!

Study the standard library  
powerful tools under the hood

g++4.6 – all examples compiled there – looks good

Thanks to Howard

C++11 is the awesomest!