

Offboarding - Standard Operating Procedure

March 2020



OFFICIAL

Contents

Document Overview	. 4
Background	. 4
Document Audience	. 4
Purpose	. 4
Prerequisites	. 4
Associated Documentation	. 5
Device Offboarding	. 6
Remove Device from Azure AD	. 6
Remove Device from Intune	. 8
Offboard a Device from Microsoft Defender - Manual	. 9
Offboard a Device from Microsoft Defender - Automated	11
Remove Device from Autopilot	13
Abbreviations and Acronyms	15

Document Overview

Background

Agencies are responsible for ensuring only authorised users and or devices are able to access the system. Agencies are responsible for ensuring users are to be removed from the system on the same day they no longer have a business need to access the system. Devices, in particular those that have been lost or stolen must be removed as a soon as practical.

Document Audience

This Standard Operating Procedure (SOP) is intended to support the ongoing operation of the Digital Transformation Agency (DTA) Blueprint. It includes the required steps that a suitably trained administrator should follow to maintain the operational state of the solution.

Purpose

The purpose of this document is to provide the necessary steps to offboard users and/or their devices. This includes when users leave the Agency and return the device, as well as when devices are lost or stolen.

Prerequisites

Before completing the procedures detailed in this document, the following prerequisites should be met:

- It is recommended that the reader/administrator performing the procedures in the document has certification and/or experience with Office 365 and Microsoft Azure.
- Appropriate administrative privileges within the environment to manage user accounts and devices.
- The ID/asset number of the device in question.

Associated Documentation

Table 1 identifies the documents that should be referenced and understood before administering this solution

Table 1 Associated Documentation

Name	Version	Date
DTA – Solution Overview	March	03/2020
DTA – Platform Design	March	03/2020
DTA – Workstation Design	March	03/2020
DTA – Office 365 Design	March	03/2020
DTA – Office 365 - ABAC	March	03/2020
DTA – Platform – ABAC	March	03/2020
DTA – Intune Security Baselines - ABAC	March	03/2020
DTA – Software Updates - ABAC	March	03/2020
DTA – Intune Applications – ABAC	March	03/2020
DTA – Intune Enrolment – ABAC	March	03/2020
DTA - Conditional Access Policies - ABAC	March	03/2020
DTA – Intune Compliance – ABAC	March	03/2020
DTA – Intune Configuration – ABAC	March	03/2020

Device Offboarding

Asset management and security procedures regarding lost and stolen devices are out of scope of this SOP and are expected to be managed by the Agency.

If a device is lost, stolen, broken or simply is being replaced, there are several tasks that must be completed to correctly offboard it. Offboarding simply means removing the device from the Agency Azure Active Directory (Azure AD) instance and anywhere else it can be identified within the overarching tenant.


This includes the following tasks:

- · Removal from Azure Active directory,
- Removal from Intune,
- Removal from Microsoft Defender Security Center, and
- Removed as a Windows Autopilot device.

Remove Device from Azure AD

Complete the below steps to remove the device from Azure AD. Prior to these steps being completed, the administrator performing them must know the ID/asset number of the device being removed from Azure AD.

Table 2 Delete Device from Azure AD




Steps Instruction **Screenshot** 2. In the left-hand pane, select Devices Overview Getting started X Diagnose and solve problems Manage Users Groups Organizational relationships 🚵 Roles and administrators Enterprise applications Devices Ann registrations 3. Within the **Devices** blade, either by scrolling ✓ Enable 🛇 Disable 📋 Delete 🐯 Manage 💍 Refresh | 📰 Columns through the list, or using the search bar, 1 Learn more about activity timestamp and how to use it to manage stale devices in Azure Active Directory identify your device, check the box, then Date Range press Delete Search by name or device ID Enabled Version os Join Type Tim's iPad Yes ios 12.4.1 Azure AD registered MC-UserDesktop Yes Windows 10.0.18363.535 Azure AD joined MC-Admin Yes Windows 10.0.18363.535 Azure AD joined 4. When prompted to delete, press Yes Confirm Delete Deleting the device(s) selected is No 5. Confirm that the process has completed No screenshot required successfully in the Notifications button in the top right of the screen.

Remove Device from Intune

Complete the below steps to remove a device from Intune.

Table 3 Remove Device from Intune




Offboard a Device from Microsoft Defender - Manual

Follow the below steps to manually offboard a device from Microsoft Defender Advanced Threat Protection (ATP). These steps can only be followed if the device is available to be logged into.

Please also note that an administrator with appropriate permissions is required to perform these steps.

Table 4 Offboard a Device from Microsoft Defender - Manual



Steps Instruction


Screenshot

5. When prompted to download the package, click Download

Are you sure you want to download the machine offboarding package? By clicking download you'll create an offboarding package that expires on 2/8/20. The offboarding package can be used to remove Microsoft Defender ATP settings from machines. Offboarded machines will stop collecting and sending data.

Download

6. When the package has downloaded, open the .zip file and extract the .cmd to the endpoint to be offboarded



Cancel


- 7. From within this explorer window, click File > Open Windows PowerShell > Open Windows PowerShell as administrator. When prompted, enter your relevant administrative credentials
- 📙 | 🛂 📙 🔻 | Temp n <u>n</u>ew window Open Windows PowerShel Open Windows PowerShell Open Windows PowerShell as administrator
- 8. Once the PowerShell window launches, type cmd then press enter (this will launch command prompt within your PowerShell session)
- Administrator: Windows PowerShell is C.(Tempo comulicrosoft Windows [Version 10.0.18362.418] (c) 2019 Microsoft Corporation. All rights reserved.
- 9. Type "\" then press tab, the name of the .cmd script you have downloaded should autofill per the screenshot, then press Enter (Return)
- Administrator: Windows PowerShell Microsoft Windows [Version 10.0.18362.418] (c) 2019 Microsoft Corporation. All rights reserved. :\Temp>.\WindowsDefenderATPOffboardingScript_valid_until_2020-02-08.cmd
- 10. Allow the script to run, once it has completed No screenshot required allow up to 24 hours for the offboarding to be complete and the results reflected in the portal.

Note, the machine being offboarded does not need to be continuously online during this period.

Offboard a Device from Microsoft Defender - Automated

Follow the below steps to offboard a device from Microsoft Defender ATP using the automated 'offboarding' process. These steps do not require that the device is available to be logged into and are recommended in the event a device is reported lost or stolen.

Table 5 Offboard a Device from Microsoft Defender - Automated



Steps Instruction **Screenshot** 7. Navigate back to the Groups - All groups grp-agency-IntuneEnrolled 6c3(blade, then select grpgrp-iOS-Devices 9b0 RemoveFromDefenderATP grp-RemoveFromDefenderATP 3b4 grp-User-Workstations 623 grp-Windows-10-Devices 4d9 Within the grp-RemoveFromDefenderATP 8. $grp\hbox{-}Remove From Defender ATP$ select Members 🗓 Delete | 💟 Got Overview Try out the new Ground X Diagnose and solve problems gr Manage GR Properties Members Owners Membership type Group memberships Source 9. Click Add members + Add members 10. Identify your device from the list, or use the Add members Search bar, then press Select Search ① P Call Recorder Centralized Deployment Connectors Cortana at Work Bing Services CPIM Service DESKTOP-B2P5I8L Selected DESKTOP-M6QJJDD DTA-00848191757 DTA-19804069564 Excluded from CA Selected items DESKTOP-B2P5I8L Remove Select

Steps Instruction

 Allow some time for the process to complete, it can take some time as it relies on the device syncing back up with Azure. No screenshot required


Screenshot

Note: this process could take some time as the endpoint device may be switched off, or not have an internet connection. Additionally, the logs for the device will remain in the Security Center by design.

Remove Device from Autopilot

As a prerequisite to this step, you must first delete the device from Azure Active Directory and Intune. Once these steps have been completed the device will not be able to be rebuilt using Autopilot.

Table 6 Remove Device from Autopilot



Steps Instruction

Screenshot

 Within the Windows enrollment blade, select Devices under the Windows Autopilot Deployment Program section

Windows Autopilot Deployment Program



Deployment Profiles

Customize the Windows Autopilot provisioning experience.






Intune Connector for Active Directory

Configure hybrid Azure AD joined devices

5. Within the **Windows Autopilot devices** screen, identify the device in question from the list or by using the search field.

Once identified, tick the box next to the device, then press **Delete**



Note: if you require further information about the device, you can click on it, a pane should appear on the right with further information about that specific device.

6. When prompted to delete, press **Yes**

Are you sure you want to delete the selected devices? (1 selected)

Note that only devices that are not enrolled will be deleted.

7. Confirm that the process has completed successfully in the **Notifications** button in the top right of the screen.

No screenshot required.

Abbreviations and Acronyms

Table 7 details the abbreviations and acronyms used throughout this document.

Table 7 Abbreviations and Acronyms

Acronym	Meaning
ATP	Advanced Threat Protection
Azure AD	Azure Active Directory
DTA	Digital Transformation Agency
SOP	Standard Operating Procedure