Red Hat Enterprise MRG 2.0 Realtime Tuning Guide

Advanced tuning procedures for the Realtime component of Red Hat Enterprise MRG



Lana Brindley

Alison Young

Red Hat Enterprise MRG 2.0 Realtime Tuning Guide Advanced tuning procedures for the Realtime component of Red Hat Enterprise MRG Edition 1

Author Lana Brindley lbrindle@redhat.com
Author Alison Young alyoung@redhat.com

Copyright © 2011 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution—Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at http://creativecommons.org/licenses/by-sa/3.0/. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, MetaMatrix, Fedora, the Infinity Logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux® is the registered trademark of Linus Torvalds in the United States and other countries.

Java® is a registered trademark of Oracle and/or its affiliates.

XFS® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

All other trademarks are the property of their respective owners.

1801 Varsity Drive Raleigh, NC 27606-2072 USA Phone: +1 919 754 3700

Phone: 888 733 4281 Fax: +1 919 754 3701

This book contains advanced tuning procedures for the MRG Realtime component of the Red Hat Enterprise MRG distributed computing platform. For installation instructions, see the *MRG Realtime Installation Guide*.

Pre	eface	V
	1. Document Conventions	. v
	1.1. Typographic Conventions	. vi
	1.2. Pull-quote Conventions	. vii
	1.3. Notes and Warnings	. vii
	2. Getting Help and Giving Feedback	Viii
	2.1. Do You Need Help?	Viii
	2.2. We Need Feedback!	Viii
1 . I	Before you start tuning your MRG Realtime system	1
2. (General System Tuning	3
	2.1. Using the Tuna Interface	
	2.2. Setting persistent tuning parameters	
	2.3. Setting BIOS parameters	
	2.4. Interrupt and Process Binding	
	2.5. File system determinism tips	
	2.6. gettimeofday speedup	
	2.7. Don't run extra stuff	
	2.8. Swapping and Out Of Memory Tips	
	2.9. Network determinism tips	
	2.10. syslog tuning tips	
	2.11. The PC Card Daemon	
	2.12. Reduce TCP performance spikes	
	2.13. Reducing the TCP delayed ack timeout	16
3. l	Realtime-Specific Tuning	17
	3.1. Setting Scheduler Priorities	
	3.2. MRG Realtime Specific gettimeofday speedup	
	3.3. Using kdump and kexec with the MRG Realtime kernel	
	3.4. TSC timer synchronization on Opteron CPUs	
	3.5. Infiniband	
	3.6. Non-Uniform Memory Access	
	3.7. Mount debugfs	
	3.8. Using the ftrace Utility for Tracing Latencies	
	3.9. Latency Tracing Using trace-cmd	
	3.10. Using sched_nr_migrate to limit SCHED_OTHER task migration	31
4.	Application Tuning and Deployment	33
	4.1. Signal Processing in Realtime Applications	33
	4.2. Using sched_yield and Other Synchronization Mechanisms	34
	4.3. Mutex options	
	4.4. TCP_NODELAY and Small Buffer Writes	36
	4.5. Setting Realtime Scheduler Priorities	37
	4.6. Dynamic Libraries Loading	38
5.	More Information	39
	5.1. Reporting Bugs	
	5.2. Further Reading	40

Preface

Red Hat Enterprise MRG

This book contains basic installation and tuning information for the MRG Realtime component of Red Hat Enterprise MRG. Red Hat Enterprise MRG is a high performance distributed computing platform consisting of three components:

- 1. *Messaging* Cross platform, high performance, reliable messaging using the Advanced Message Queuing Protocol (AMQP) standard.
- 2. Realtime Consistent low-latency and predictable response times for applications that require microsecond latency.
- 3. Grid Distributed High Throughput (HTC) and High Performance Computing (HPC).

All three components of Red Hat Enterprise MRG are designed to be used as part of the platform, but can also be used separately.

MRG Realtime

Many industries and organizations need extremely high performance computing and may require low and predictable latency, especially in the financial and telecommunications industries. Latency, or response time, is defined as the time between an event and system response and is generally measured in microseconds (µs). For most applications running under a Linux environment, basic performance tuning can improve latency sufficiently. For those industries where latency not only needs to be low, but also accountable and predictable, Red Hat have now developed a 'drop-in' kernel replacement that provides this. MRG Realtime is distributed as part of Red Hat Enterprise MRG and provides seamless integration with Red Hat Enterprise Linux 5.6 and Red Hat Enterprise Linux 6.1. MRG Realtime offers clients the opportunity to measure, configure and record latency times within their organization.

About The MRG Realtime Tuning Guide

This book is laid out in three main sections: General system tuning, which can be performed on a Red Hat Enterprise Linux 5.6 or Red Hat Enterprise Linux 6.1 kernel and MRG Realtime specific tuning, which should be performed on a MRG Realtime kernel in addition to the standard Red Hat Enterprise Linux 5.6 or Red Hat Enterprise Linux 6.1 tunes. The third section is for developing and deploying your own MRG Realtime programs.

You will need to have the MRG Realtime kernel installed before you begin the tuning procedures in this book. If you have not yet installed the MRG Realtime kernel, or need help with installation issues, read the MRG Realtime Installation Guide.

1. Document Conventions

This manual uses several conventions to highlight certain words and phrases and draw attention to specific pieces of information.

In PDF and paper editions, this manual uses typefaces drawn from the *Liberation Fonts*¹ set. The Liberation Fonts set is also used in HTML editions if the set is installed on your system. If not,

¹ https://fedorahosted.org/liberation-fonts/

alternative but equivalent typefaces are displayed. Note: Red Hat Enterprise Linux 5 and later includes the Liberation Fonts set by default.

1.1. Typographic Conventions

Four typographic conventions are used to call attention to specific words and phrases. These conventions, and the circumstances they apply to, are as follows.

Mono-spaced Bold

Used to highlight system input, including shell commands, file names and paths. Also used to highlight keycaps and key combinations. For example:

To see the contents of the file my_next_bestselling_novel in your current working directory, enter the cat my_next_bestselling_novel command at the shell prompt and press Enter to execute the command.

The above includes a file name, a shell command and a keycap, all presented in mono-spaced bold and all distinguishable thanks to context.

Key combinations can be distinguished from keycaps by the hyphen connecting each part of a key combination. For example:

Press **Enter** to execute the command.

Press **Ctrl+Alt+F2** to switch to the first virtual terminal. Press **Ctrl+Alt+F1** to return to your X-Windows session.

The first paragraph highlights the particular keycap to press. The second highlights two key combinations (each a set of three keycaps with each set pressed simultaneously).

If source code is discussed, class names, methods, functions, variable names and returned values mentioned within a paragraph will be presented as above, in **mono-spaced bold**. For example:

File-related classes include **filesystem** for file systems, **file** for files, and **dir** for directories. Each class has its own associated set of permissions.

Proportional Bold

This denotes words or phrases encountered on a system, including application names; dialog box text; labeled buttons; check-box and radio button labels; menu titles and sub-menu titles. For example:

Choose System \rightarrow Preferences \rightarrow Mouse from the main menu bar to launch Mouse Preferences. In the Buttons tab, click the Left-handed mouse check box and click Close to switch the primary mouse button from the left to the right (making the mouse suitable for use in the left hand).

To insert a special character into a gedit file, choose $Applications \rightarrow Accessories$

→ Character Map from the main menu bar. Next, choose Search → Find... from the Character Map menu bar, type the name of the character in the Search field and click Next. The character you sought will be highlighted in the Character Table. Double-click this highlighted character to place it in the Text to copy field and then click the

Copy button. Now switch back to your document and choose $\textbf{Edit} \rightarrow \textbf{Paste}$ from the gedit menu bar.

The above text includes application names; system-wide menu names and items; application-specific menu names; and buttons and text found within a GUI interface, all presented in proportional bold and all distinguishable by context.

Mono-spaced Bold Italic or Proportional Bold Italic

Whether mono-spaced bold or proportional bold, the addition of italics indicates replaceable or variable text. Italics denotes text you do not input literally or displayed text that changes depending on circumstance. For example:

To connect to a remote machine using ssh, type **ssh** *username@domain.name* at a shell prompt. If the remote machine is **example.com** and your username on that machine is john, type **ssh john@example.com**.

The **mount** -o **remount file-system** command remounts the named file system. For example, to remount the **/home** file system, the command is **mount** -o **remount /home**.

To see the version of a currently installed package, use the rpm -q package command. It will return a result as follows: package-version-release.

Note the words in bold italics above — username, domain.name, file-system, package, version and release. Each word is a placeholder, either for text you enter when issuing a command or for text displayed by the system.

Aside from standard usage for presenting the title of a work, italics denotes the first use of a new and important term. For example:

Publican is a *DocBook* publishing system.

1.2. Pull-quote Conventions

Terminal output and source code listings are set off visually from the surrounding text.

Output sent to a terminal is set in **mono-spaced roman** and presented thus:

```
books Desktop documentation drafts mss photos stuff svn
books_tests Desktop1 downloads images notes scripts svgs
```

Source-code listings are also set in **mono-spaced roman** but add syntax highlighting as follows:

1.3. Notes and Warnings

Finally, we use three visual styles to draw attention to information that might otherwise be overlooked.



Note

Notes are tips, shortcuts or alternative approaches to the task at hand. Ignoring a note should have no negative consequences, but you might miss out on a trick that makes your life easier.



Important

Important boxes detail things that are easily missed: configuration changes that only apply to the current session, or services that need restarting before an update will apply. Ignoring a box labeled 'Important' will not cause data loss but may cause irritation and frustration.



Warning

Warnings should not be ignored. Ignoring warnings will most likely cause data loss.

2. Getting Help and Giving Feedback

2.1. Do You Need Help?

If you experience difficulty with a procedure described in this documentation, visit the Red Hat Customer Portal at http://access.redhat.com. Through the customer portal, you can:

- search or browse through a knowledgebase of technical support articles about Red Hat products.
- · submit a support case to Red Hat Global Support Services (GSS).
- · access other product documentation.

Red Hat also hosts a large number of electronic mailing lists for discussion of Red Hat software and technology. You can find a list of publicly available mailing lists at https://www.redhat.com/mailman/listinfo. Click on the name of any mailing list to subscribe to that list or to access the list archives.

2.2. We Need Feedback!

If you find a typographical error in this manual, or if you have thought of a way to make this manual better, we would love to hear from you! Please submit a report in Bugzilla: http://bugzilla.redhat.com/ against the product **Red Hat Enterprise MRG.**

When submitting a bug report, be sure to mention the manual's identifier: Realtime_Tuning_Guide

If you have a suggestion for improving the documentation, try to be as specific as possible when describing it. If you have found an error, please include the section number and some of the surrounding text so we can find it easily.

Before you start tuning your MRG Realtime system

MRG Realtime is designed to be used on well-tuned systems for applications with extremely high determinism requirements. Kernel system tuning offers the vast majority of the improvement in determinism. For example, in many workloads thorough system tuning improves consistency of results by around 90%. This is why we typically recommend that customers first perform the *Chapter 2*, *General System Tuning* of standard Red Hat Enterprise Linux before using MRG Realtime.

Things to remember while you are tuning your MRG Realtime kernel

1. Be Patient

Realtime tuning is an iterative process; you will almost never be able to tweak a few variables and know that the change is the best that can be achieved. Be prepared to spend days or weeks narrowing down the set of tunings that work best for your system.

Additionally, always make long test runs. Changing some tuning parameters then doing a five minute test run is not a good validation of a set of tunes. Make the length of your test runs adjustable and run them for longer than a few minutes. Try to narrow down to a few different tuning sets with test runs of a few hours, then run those sets for many hours or days at a time, to try and catch corner-cases of max latencies or resource exhaustion.

2. Be Accurate

Build a measurement mechanism into your application, so that you can accurately gauge how a particular set of tuning changes affect the application's performance. Anecdotal evidence (e.g. "The mouse moves more smoothly") is usually wrong and varies from person to person. Do hard measurements and record them for later analysis.

3. Be Methodical

It is very tempting to make multiple changes to tuning variables between test runs, but doing so means that you do not have a way to narrow down which tune affected your test results. Keep the tuning changes between test runs as small as you can.

4. Be Conservative

It is also tempting to make large changes when tuning, but it is almost always better to make incremental changes. You will find that working your way up from the lowest to highest priority values will yield better results in the long run.

5. Be Smart

Use the tools you have available. The Tuna graphical tuning tool makes it easy to change processor affinities for threads and interrupts, thread priorities and to isolate processors for application use. The **taskset** and **chrt** command line utilities allow you to do most of what Tuna does. If you run into performance problems, the **ftrace** facility in the trace kernel can help locate latency issues.

6. Be Flexible

Rather than hard-coding values into your application, use external tools to change policy, priority and affinity. This allows you to try many different combinations and simplifies your logic. Once you have found some settings that give good results, you can either add them to your application, or set up some startup logic to implement the settings when the application starts.

How Tuning Improves Performance

Most performance tuning is performed by manipulating processors (Central Processing Units or CPUs). Processors are manipulated through:

Interrupts:

In software, an interrupt is an event that calls for a change in execution.

Interrupts are serviced by a set of processors. By adjusting the affinity setting of an interrupt we can determine on which processor the interrupt will run.

Threads:

Threads provide programs with the ability to run two or more tasks simultaneously.

Threads, like interrupts, can be manipulated through the affinity setting, which determines on which processor the thread will run.

It is also possible to set scheduling priority and scheduling policies to further control threads.

By manipulating interrupts and threads off and on to processors, you are able to indirectly manipulate the processors. This gives you greater control over scheduling and priorities and, subsequently, latency and determinism.

MRG Realtime Scheduling Policies

Linux uses three main scheduling policies:

SCHED_OTHER (sometimes called SCHED_NORMAL)

This is the default thread policy and has dynamic priority controlled by the kernel. The priority is changed based on thread activity. Threads with this policy are considered to have a realtime priority of 0 (zero).

SCHED_FIFO (First in, first out)

A realtime policy with a priority range of from 1 - 99, with 1 being the lowest and 99 the highest. **SCHED_FIFO** threads always have a higher priority than **SCHED_OTHER** threads (for example, a **SCHED_FIFO** thread with a priority of 1 will have a higher priority than *any***SCHED_OTHER** thread). Any thread created as a **SCHED_OTHER** thread has a fixed priority and will run until it is blocked or preempted by a higher priority thread.

SCHED_RR (Round-Robin)

SCHED_RR is an optimization of **SCHED_FIFO**. Threads with the same priority have a quantum and are round-robin scheduled amongst all equal priority **SCHED_RR** threads. This policy is rarely used.

General System Tuning

This section contains general tuning that can be performed on a standard Red Hat Enterprise Linux installation. It is important that these are performed first, in order to better see the benefits of the MRG Realtime kernel.

It is recommended that you read these sections first. They contain background information on how to modify tuning parameters and will help you perform the other tasks in this book:

- Section 2.1, "Using the Tuna Interface"
- Section 2.2, "Setting persistent tuning parameters"

When are you ready to begin tuning, perform these steps first, as they will provide the greatest benefit:

- · Section 2.3, "Setting BIOS parameters"
- Section 2.4, "Interrupt and Process Binding"
- Section 2.5, "File system determinism tips"

When you are ready to start some fine-tuning on your system, then try the other sections in this chapter:

- Section 2.6, "gettimeofday speedup"
- Section 2.7, "Don't run extra stuff"
- Section 2.8, "Swapping and Out Of Memory Tips"
- Section 2.9, "Network determinism tips"
- Section 2.10, "syslog tuning tips"
- Section 2.11, "The PC Card Daemon"
- Section 2.12, "Reduce TCP performance spikes"
- Section 2.13, "Reducing the TCP delayed ack timeout"

When you have completed all the tuning suggestions in this chapter, move on to *Chapter 3, Realtime-Specific Tuning*

2.1. Using the Tuna Interface

Throughout this book, instructions are given for tuning the MRG Realtime kernel directly. The Tuna interface is a tool that assists you with making changes. It has a graphical interface, or can be run through the command shell.

Tuna can be used to change attributes of threads (scheduling policy, scheduler priority and processor affinity) and interrupts (processor affinity). The tool is designed to be used on a running system, and changes take place immediately. This allows any application-specific measurement tools to see and analyze system performance immediately after the changes have been made.



Note

For instructions on installing and using Tuna, see the *Tuna User Guide*.

2.2. Setting persistent tuning parameters

This book contains many examples on how to specify kernel tuning parameters. Unless stated otherwise, the instructions will cause the parameters to remain in effect until the system reboots or they are explicitly changed. This approach is effective for establishing the initial tuning configuration.

Once you have decided what tuning configuration works for your system, you will probably want those parameters to be persistent across reboots. Which method you choose depends on the type of parameter you are setting.

Editing the /etc/sysctl.conf file

For any parameter that begins with **/proc/sys/**, including it in the **/etc/sysctl.conf** file will make the parameter persistent.

- 1. Open the /etc/sysctl.conf file in your chosen text editor
- Remove the /proc/sys/ prefix from the command and replace the central / character with a . character.

For example: the command echo 2 > /proc/sys/kernel/vsyscall64 will become kernel.vsyscall64.

Insert the new entry into the /etc/sysctl.conf file with the required parameter

```
# Enable gettimeofday(2)
kernel.vsyscall64 = 2
```

4. Run # sysctl -p to refresh with the new configuration

```
# sysctl -p
...[output truncated]...
kernel.vsyscall64 = 2
```

Editing files in the /etc/sysconfig/ directory

Files in the **/etc/sysconfig/** directory can be added for most other parameters. As files in this directory can differ significantly, instructions for these will be explicitly stated where appropriate.

Alternatively, check the *Red Hat Enterprise Linux Deployment Guide* available from the *Red Hat Documentation website*¹ for information on the /etc/sysconfig/ directory.

Editing the /etc/rc.d/rc.local file

Use this alternative only as a last resort!

- 1. Adjust the command as per the *Editing the /etc/sysct1.conf file* instructions.
- 2. Insert the new entry into the /etc/rc.d/rc.local file with the required parameter

¹ http://redhat.com/docs

2.3. Setting BIOS parameters

Because every system and BIOS vendor uses different terms and navigation methods, this section contains only general information about BIOS settings. If you have trouble locating the setting mentioned, contact the BIOS vendor.

Power Management

Anything that tries to save power by either changing the system clock frequency or by putting the CPU into various sleep states can affect how quickly the system responds to external events.

For best response times, disable power management options in the BIOS.

Error Detection and Correction (EDAC) units

EDAC units are devices used to detect and correct errors signaled from Error Correcting Code (ECC) memory. Usually EDAC options range from no ECC checking to a periodic scan of all memory nodes for errors. The higher the EDAC level, the more time is spent in BIOS, and the more likely that crucial event deadlines will be missed.

Turn EDAC off if possible. Otherwise, switch to the lowest functional level.

System Management Interrupts (SMI)

SMIs are a facility used by hardware vendors ensure the system is operating correctly. The SMI interrupt is usually not serviced by the running operating system, but by code in the BIOS. SMIs are typically used for thermal management, remote console management (IPMI), EDAC checks, and various other housekeeping tasks.

If the BIOS contains SMI options, check with the vendor and any relevant documentation to check to what extent it is safe to disable them.



Warning

While it is possible to completely disable SMIs, it is strongly recommended that you do not do this. Removing the ability for your system to generate and service SMIs can result in catastrophic hardware failure.

2.4. Interrupt and Process Binding

Realtime environments need to minimize or eliminate latency when responding to various events. Ideally, interrupts (IRQs) and user processes can be isolated from one another on different dedicated CPUs.

Interrupts are generally shared evenly between CPUs. This can delay interrupt processing through having to write new data and instruction caches, and often creates conflicts with other processing occurring on the CPU. In order to overcome this problem, time-critical interrupts and processes can be dedicated to a CPU (or a range of CPUs). In this way, the code and data structures needed to process this interrupt will have the highest possible likelihood to be in the processor data and instruction caches. The dedicated process can then run as quickly as possible, while all other non-time-critical processes run on the remainder of the CPUs. This can be particularly important in cases where the speeds involved are in the limits of memory and peripheral bus bandwidth available. Here, any wait for memory to be fetched into processor caches will have a noticeable impact in overall processing time and determinism.

In practice, optimal performance is entirely application specific. For example, in tuning applications for different companies which perform similar functions, the optimal performance tunings were completely different. For one firm, isolating 2 out of 4 CPUs for operating system functions and interrupt handling

and dedicating the remaining 2 CPUs purely for application handling was optimal. For another firm, binding the network related application processes onto a CPU which was handling the network device driver interrupt yielded optimal determinism. Ultimately, tuning is often accomplished by trying a variety of settings to discover what works best for your organization.



Important

Disabling the **irqbalance** daemon

This daemon is enabled by default and periodically forces interrupts to be handled by CPUs in an even, fair manner. However in realtime deployments, applications are typically dedicated and bound to specific CPUs, so the **irqbalance** daemon is not required.

1. Check the status of the irqbalance daemon

```
# service irqbalance status
irqbalance (pid PID) is running...
```

2. If the **irqbalance** daemon is running, stop it using the **service** command.

```
# service irqbalance stop
Stopping irqbalance: [ OK ]
```

3. Use **chkconfig** to ensure that **irqbalance** does not restart on boot.

```
# chkconfig irqbalance off
```

Partially Disabling the **irqbalance** daemon

An alternative approach to is to disable **irqbalance** only on those CPUs that have dedicated functions, and enable it on all other CPUs. This can be done by editing the **/etc/sysconfig/irqbalance** file.

 Open /etc/sysconfig/irqbalance in your preferred text editor and find the section of the file titled FOLLOW ISOLCPUS.

```
...[output truncated]...
# FOLLOW_ISOLCPUS

# Boolean value. When set to yes, any setting of IRQ_AFFINITY_MASK above

# is overridden, and instead computed to be the same mask that is defined

# by the isolcpu kernel command line option.

#
```

```
#FOLLOW_ISOLCPUS=no
```

2. Enable FOLLOW_ISOLCPUS by removing the # character from the beginning of the line and changing the value to *yes*.

```
...[output truncated]...

# FOLLOW_ISOLCPUS

# Boolean value. When set to yes, any setting of IRQ_AFFINITY_MASK above

# is overridden, and instead computed to be the same mask that is defined

# by the isolcpu kernel command line option.

#
FOLLOW_ISOLCPUS=yes
```

3. This will make **irqbalance** operate only on the CPUs not specifically isolated. This has no effect on machines with only two processors, but will run effectively on a dual-core machine.

Manually Assigning CPU Affinity to Individual IRQs

1. Check which IRQ is in use by each device by viewing the /proc/interrupts file:

```
# cat /proc/interrupts
```

This file contains a list of IRQs. Each line shows the IRQ number, the number of interrupts that happened in each CPU, followed by the IRQ type and a description:

```
CPU0 CPU1
0: 26575949 11 IO-APIC-edge timer
1: 14 7 IO-APIC-edge i8042
...[output truncated]...
```

2. To instruct an IRQ to run on only one processor, **echo** the CPU mask (as an hexadecimal number) to /proc/interrupts. In this example, we are instructing the interrupt with IRQ number 142 to run on CPU 0 only:

```
# echo 1 > /proc/irq/142/smp_affinity
```

3. This change will only take effect once an interrupt has occurred. To test the settings, generate some disk activity, then check the /proc/interrupts file for changes. Assuming that you have caused an interrupt to occur, you should see that the number of interrupts on the chosen CPU have risen, while the numbers on the other CPUs have not changed.

Binding Processes to CPUs using the taskset utility

The **taskset** utility uses the process ID (PID) of a task to view or set the affinity, or can be used to launch a command with a chosen CPU affinity. In order to set the affinity, **taskset** requires the CPU mask expressed as a decimal or hexadecimal number.

To set the affinity of a process that is not currently running, use taskset and specify the CPU mask and the process. In this example, my_embedded_process is being instructed to use only CPU 3 (using the decimal version of the CPU mask).

```
# taskset 8 /usr/local/bin/my_embedded_process
```

2. It is also possible to set the CPU affinity for processes that are already running by using the -p (--pid) option with the CPU mask and the PID of the process you wish to change. In this example, the process with a PID of 7013 is being instructed to run only on CPU 0.

```
# taskset -p 1 7013
```



Note

The **taskset** utility will only work if Non-Uniform Memory Access (NUMA) is not enabled on the system. See Section 3.6, "Non-Uniform Memory Access" for more information on this.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- chrt(1)
- taskset(1)
- nice(1)
- renice(1)
- sched_setscheduler(2) for a description of the Linux scheduling scheme.

2.5. File system determinism tips

Journal activity can introduce latency through ordering changes and committing data and metadata. Often, journaling file systems can do things in such a way that they slow the system down.

The most common file system for use on Linux machines is the third extended file system, or ext3, which is a journaling file system. Its predecessor - ext2 - is a non-journaling file system that is almost completely compatible with ext3. Unless your organization specifically requires journaling, consider using ext2. In many of our best benchmark results, we utilize the ext2 file system and consider it one of the top initial tuning recommendations.

If using ext2 is not a suitable solution for your system, consider disabling **atime** under ext3 instead. There are very few real-world situations where **atime** is necessary, however it is enabled by default in Red Hat Enterprise Linux for longstanding legacy reasons. By disabling **atime** journal activity is avoided where it is not necessary. It can also help with reducing power consumption as the disk is not required to do as many needless writes, giving the disk more opportunities to enter a low-power state.

Disabling atime

1. Open the /etc/fstab file using your chosen text editor and locate the entry for the root mount point.

```
LABEL=/ / ext3 defaults 1 1 ...[output truncated]...
```

Edit the options sections to include the terms noatime and nodiratime. noatime prevents access timestamps being updated when a file is read and nodiratime will stop directory inode access times being updated.

```
LABEL=/ / ext3 noatime, nodiratime 1 1
```

3. The tmpwatch file on Red Hat Enterprise Linux is set by default to clean files in /tmp based on their atime. If this is the case on your system, then the instructions above will result in users' / tmp/* files being emptied every day. This can be resolved by starting tmpwatch with the -- mtime option.

```
--- /etc/cron.daily/tmpwatch.orig +++ /etc/cron.daily/tmpwatch @@ -3,6 +3,6 @@ /usr/sbin/tmpwatch 720 /var/tmp for d in /var/{cache/man,catman}/{cat?,X11R6/cat?,local/cat?}; do if [ -d "$d" ]; then - /usr/sbin/tmpwatch -f 720 "$d" + /usr/sbin/tmpwatch --mtime -f 720 "$d" fi
```

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- bdflush(2)
- mkfs.ext2(8)
- mkfs.ext3(8)
- mount(8) for information on atime, nodiratime and noatime
- chattr(1)

2.6. gettimeofday speedup

Many application workloads (especially databases and financial service applications) perform extremely frequent **gettimeofday** or similar time function calls. Optimizing the efficiency of this calls can provide major benefits.

A Virtual Dynamic Shared Object (VDSO), is a shared library that allows application in user space to perform some kernel actions without as much overhead as a system call. The VDSO is often used to provide fast access to the **gettimeofday** system call data.

Enabling the VDSO instructs the kernel to use its definition of the symbols in the VDSO, rather than the ones found in any user-space shared libraries, particularly the **glibc**. The effects of enabling the VDSO are system-wide - either all processes use it or none do.

When enabled, the VDSO overrides the **glibc** definition of **gettimeofday** with it's own. This removes the overhead of a system call, as the call is made direct to the kernel memory, rather than going through the **glibc**.

The VDSO boot parameter has three possible values:

0

Provides the most accurate time intervals at μ s (microsecond) resolution, but also produces the highest call overhead, as it uses a regular system call

1 Slightly less accurate, although still at μs resolution, with a lower call overhead

2

The least accurate, with time intervals at the ms (millisecond) level, but offers the lowest call overhead

Enable gettimeofday with VDSO

There is a Virtual Dynamic Shared Object (VDSO) implemented in the **glibc** runtime library. The VDSO maps some of the kernel code, which is necessary to read **gettimeofday** in the user-space. Standard Red Hat Enterprise Linux 5.6 and Red Hat Enterprise Linux 6.1 allows the **gettimeofday** function to be performed entirely in user-space, removing the system call overhead.

 VDSO behavior is enabled by default. The value used to enable the VDSO affects the behavior of gettimeofday. It can be enabled by assigning the desired value to /proc/sys/kernel/ syscall64.

sysctl kernel.vsyscall64=1



Important

At the shell prompt, using **0**, **1**, **and 2** (without a space character) refers to standard input, standard output and standard error. Using them by mistake could result in severe unintended consequences.

Make this change persistent by opening **/etc/sysctl.conf** in your preferred text editor and adding the following line:

kernel.vsyscall64 = 1

Reload **sysctl.conf** by calling:

sysctl -p

2. In addition to the above, the MRG Realtime kernel includes a further **gettimeofday** performance optimization. See *Section 3.2, "MRG Realtime Specific gettimeofday speedup"*.



Important

Currently the **gettimeofday** speed up is implemented only for 64-bit architectures (AMD64 and Intel 64) and is not available on i686 machines.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

2.7. Don't run extra stuff

This is a common tool for improving performance, yet one that is often overlooked. Some 'extra stuff' to look for:

· Graphical desktop

Do not run graphics where they are not absolutely required, especially on servers. To avoid running the desktop software, open the **/etc/inittab** file with your preferred text editor and locate the following line:

```
id:5:initdefault:
...[output truncated]...
```

This setting changes the runlevel that the machine automatically boots into. By default, the runlevel is **5** - full multi-user mode, using the graphical interface. By changing the number in the string to **3**, the default runlevel will be full multi-user mode, but without the graphical interface.

```
id:3:initdefault:
...[output truncated]...
```

Mail Transfer Agents (MTA, such as Sendmail or Postfix)

Unless you are actively using Sendmail on the system you are tuning, disable it. If it is required, ensure it is well tuned or consider moving it to a dedicated machine.



Important

Sendmail is used to send system-generated messages, which are executed by programs such as cron. This includes reports generated by logging functions like logwatch. You will not be able to receive these messages if sendmail is disabled.

- · Remote Procedure Calls (RPCs)
- · Network File System (NFS)
- · Mouse Services

If you are not using a graphical interface like Gnome or KDE, then you probably won't need a mouse either. Remove the hardware and uninstall **gpm**.

· Automated tasks

Check for automated **cron** or **at** jobs that could impact performance.

Remember to also check your third party applications, and any components added by external hardware vendors.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- rpc(3)
- nfs(5)
- gpm(8)

2.8. Swapping and Out Of Memory Tips

Memory Swapping

Swapping pages out to disk can introduce latency in any environment. To ensure low latency, the best strategy is to have enough memory in your systems so that swapping is not necessary. Always size the physical RAM as appropriate for your application and system. Use **vmstat** to monitor memory usage and watch the **si** (swap in) and **so** (swap out) fields. They should remain on zero as much as possible.

Out of Memory (OOM)

Out of Memory (OOM) refers to a computing state where all available memory, including swap space, has been allocated. Normally this will cause the system to panic and stop functioning as expected. There is a switch that controls OOM behavior in /proc/sys/vm/panic_on_oom. When set to 1 the kernel will panic on OOM. The default setting is 0 which instructs the kernel to call a function named oom_killer on an OOM. Usually, oom_killer can kill rogue processes and the system will survive.

1. The easiest way to change this is to **echo** the new value to **/proc/sys/vm/panic_on_oom**.

```
# cat /proc/sys/vm/panic_on_oom
1
# echo 0 > /proc/sys/vm/panic_on_oom
# cat /proc/sys/vm/panic_on_oom
0
```

2. It is also possible to prioritize which processes get killed by adjusting the oom_killer score. In /proc/PID/ there are two tools labeled oom_adj and oom_score. Valid scores for oom_adj are in the range -16 to +15. This value is used to calculate the 'badness' of the process using an algorithm that also takes into account how long the process has been running, among other factors. To see the current oom_killer score, view the oom_score for the process. oom_killer will kill processes with the highest scores first.

This example adjusts the **oom_score** of a process with a PID of 12465 to make it less likely that **oom_killer** will kill it.

```
# cat /proc/12465/oom_score
79872
# echo -5 > /proc/12465/oom_adj
# cat /proc/12465/oom_score
78
```

3. There is also a special value of -17, which disables **oom_killer** for that process. In the example below, **oom_score** returns a value of *O*, indicating that this process would not be killed.

```
# cat /proc/12465/oom_score
78

# echo -17 > /proc/12465/oom_adj

# cat /proc/12465/oom_score
0
```

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- swapon(2)
- swapon(8)
- vmstat(8)

2.9. Network determinism tips

Transmission Control Protocol (TCP)

TCP can have a large effect on latency. TCP adds latency in order to obtain efficiency, control congestion, and to ensure reliable delivery. When tuning, consider the following points:

- · Do you need ordered delivery?
- · Do you need to guard against packet loss?

Transmitting packets more than once can cause delays.

If you must use TCP, consider disabling the Nagle buffering algorithm by using TCP_NODELAY on
your socket. The Nagle algorithm collects small outgoing packets to send all at once, and can have
a detrimental effect on latency.

Network Tuning

There are numerous tools for tuning the network. Here are some of the more useful:

Interrupt Coalescing

To reduce network traffic, packets can be collected and a single interrupt generated.

Use the **-C** (**--coalesce**) option with the **ethtool** command to enable.

Congestion

Often, I/O switches can be subject to back-pressure, where network data builds up as a result of full buffers.

Use the **-A** (**--pause**) option with the **ethtool** command to change pause parameters and avoid network congestion.

Infiniband (IB)

Infiniband is a type of communications architecture often used to increase bandwidth and provide quality of service and failover. It can also be used to improve latency through Remote Direct Memory Access (RDMA) capabilities.

Network Protocol Statistics

Use the -s (--statistics) option with the netstat command to monitor network traffic.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- ethtool(8)
- netstat(8)

2.10. syslog tuning tips

syslog can forward log messages from any number of programs over a network. The less often this occurs, the larger the pending transaction is likely to be. If the transaction is very large an I/O spike can occur. To prevent this, keep the interval reasonably small.

Using syslogd for system logging.

The system logging daemon, called **syslogd**, is used to collect messages from a number of different programs. It also collects information reported by the kernel from the kernel logging daemon **klogd**. Typically, **syslogd** will log to a local file, but it can also be configured to log over a network to a remote logging server.

 To enable remote logging, you will first need to configure the machine that will receive the logs. syslogd uses configuration settings defined in the /etc/sysconfig/syslog and /etc/ syslog.conf files. To instruct syslogd to receive logs from remote machines, open /etc/ sysconfig/syslog in your preferred text editor and locate the SYSLOGD_OPTIONS= line.

```
# Options to syslogd
# -m 0 disables 'MARK' messages.
# -r enables logging from remote machines
# -x disables DNS lookups on messages received with -r
# See syslogd(8) for more details

SYSLOGD_OPTIONS="-m 0"
...[output truncated]...
```

2. Append the -r parameter to the options line:

```
SYSLOGD_OPTIONS="-m 0 -r"
```

3. Once remote logging support is enabled on the remote logging server, each system that will send logs to it must be configured to send its syslog output to the server, rather than writing those logs to the local file system. To do this, edit the /etc/syslog.conf file on each client system. For each of the various logging rules defined in that file, you can replace the local log file with the address of the remote logging server.

```
# Log all kernel messages to remote logging host.
kern.* @my.remote.logging.server
```

The example above will cause the client system to log all kernel messages to the remote machine at @my.remote.logging.server.

4. It is also possible to configure **syslogd** to log all locally generated system messages, by adding a wildcard line to the **/etc/syslog.conf** file:

```
# Log all messages to a remote logging server:
*.* @my.remote.logging.server
```



Important

Note that **syslogd** does not include built-in rate limiting on its generated network traffic. Therefore, we recommend that remote logging on MRG Realtime systems be confined to only those messages that are required to be remotely logged by your organization. For example, kernel warnings, authentication requests, and the like. Other messages should be locally logged instead.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- syslog(3)
- syslog.conf(5)
- syslogd(8)

2.11. The PC Card Daemon

The **pcscd** daemon is used to manage connections to PC and SC smart card readers. Although **pcscd** is usually a low priority task, it can often use more CPU than any other daemon. This additional background noise can lead to higher pre-emption costs to realtime tasks and other undesirable impacts on determinism.

Disabling the **pcscd** Daemon

1. Check the status of the **pcscd** daemon

```
# service pcscd status
pcscd (pid PID) is running...
```

2. If the **pcscd** daemon is running, stop it using the **service** command.

```
# service pcscd stop
Stopping PC/SC smart card daemon (pcscd): [ OK ]
```

3. Use **chkconfig** to ensure that **pcscd** does not restart on boot.

```
# chkconfig pcscd off
```

2.12. Reduce TCP performance spikes

In order to reduce a performance spike with relation to timestamps generation, change the values of the TCP related entries with the **sysct1** command.

1. Change the value of **net.ipv4.neigh.default.unres_qlen** from 3 to 100, by echoing the new value:

```
# echo 100 > /proc/sys/net/ipv4/neigh/default/unres_qlen
```

2. Make the same change for **net.ipv4.neigh.eth0.unres_qlen**:

```
# echo 100 > /proc/sys/net/ipv4/neigh/eth0/unres_qlen
```

3. To make the changes persistent, edit the /etc/sysctl.conf file.

2.13. Reducing the TCP delayed ack timeout

Some applications that send small network packets can experience latencies due to the TCP delayed acknowledgment timeout. This value defaults to 40ms. To avoid this problem, try reducing the **tcp_delack_min** timeout value. This changes the minimum time to delay before sending an acknowledgment systemwide.

 Write the desired minimum value, in microseconds, to /proc/sys/net/ipv4/ tcp_delack_min:

```
# echo 1 > /proc/sys/net/ipv4/tcp_delack_min
```

Realtime-Specific Tuning

Once you have completed the tunes in *Chapter 2, General System Tuning* you are ready to start MRG Realtime specific tuning. You must have the MRG Realtime kernel installed for these procedures.



Important

Do not attempt to use the tools in this section without first having completed *Chapter 2, General System Tuning*. You will not see a performance improvement.

When are you ready to begin MRG Realtime tuning, perform these steps first, as they will provide the greatest benefit:

Section 3.1, "Setting Scheduler Priorities"

When you are ready to start some fine-tuning on your system, then try the other sections in this chapter:

- Section 3.2, "MRG Realtime Specific gettimeofday speedup"
- Section 3.3, "Using kdump and kexec with the MRG Realtime kernel"
- Section 3.4, "TSC timer synchronization on Opteron CPUs"
- Section 3.5, "Infiniband"
- Section 3.6, "Non-Uniform Memory Access"

This chapter also includes information on performance monitoring tools:

- Section 3.8, "Using the **ftrace** Utility for Tracing Latencies"
- Section 3.9, "Latency Tracing Using trace-cmd"

Section 3.10, "Using **sched_nr_migrate** to limit **SCHED_OTHER** task migration."

When you have completed all the tuning suggestions in this chapter, move on to *Chapter 4, Application Tuning and Deployment*

3.1. Setting Scheduler Priorities

The MRG Realtime kernel allows fine grained control of scheduler priorities. It also allows application level programs to be scheduled at a higher priority than kernel threads. This can be useful but may also carry consequences. It is possible that it will cause the system to hang and other unpredictable behavior if crucial kernel processes are prevented from running as needed. Ultimately the correct settings are workload dependent.

Priorities are defined in groups, with some groups dedicated to certain kernel functions:

Table 3.1. Priority Map

Priority	Threads	Description
1	Low priority kernel threads	Priority 1 is usually reserved for those tasks that need to be just above SCHED_OTHER
2 - 69	Available for use	Range used for typical application priorities

Priority	Threads	Description
70 - 79	Soft IRQs	
80	NFS	RPC, Locking and Authentication threads for NFS
81 - 89	Hard IRQs	Dedicated interrupt processing threads for each IRQ in the system
90 - 98	Available for use	Only for use by very high priority application threads
99	Watchdogs and migration	System threads that must run at the highest priority

Using rtct1 to Set Priorities

Priorities are set using a series of levels, ranging from 0 (lowest priority) to 99 (highest priority).
 The system startup script rtctl initializes the default priorities of the kernel threads. By requesting the status of the rtctl service, you can view the priorities of the various kernel threads.

```
# service rtctl status
2  TS   - [kthreadd]
3  FF    99 [migration/0]
4  FF    99 [posix_cpu_timer]
5  FF    50 [softirq-high/0]
6  FF    50 [softirq-timer/0]
7  FF    90 [softirq-net-tx/]
...[output truncated]...
```

2. The output is in the format:

```
[PID] [scheduler policy] [priority] [process name]
```

In the **scheduler policy** field, a value of **TS** indicates a policy of *normal* and **FF** indicates a policy of *FIFO* (first in, first out).

3. The rtctl system startup script relies on the /etc/rtgroups file.

To change this file, open **/etc/rtgroups** in your preferred text editor.

```
kthreads:*:1:*:\[.*\]$
watchdog:f:99:*:\[watchdog.*\]
migration:f:99:*:\[migration\/.*\]
softirq:f:70:*:\[.*(softirq|sirq).*\]
softirq-net-tx:f:75:*:\[(softirq|sirq)-net-tx.*\]
softirq-net-rx:f:75:*:\[(softirq|sirq)-net-rx.*\]
softirq-sched:f:1:*:\[(softirq|sirq)-sched\/.*\]
rpciod:f:65:*:\[rpciod.*\]
lockd:f:65:*:\[lockd.*\]
nfsd:f:65:*:\[lockd.*\]
hardirq:f:85:*:\[(irq|IRQ)[\-_/].*\]
```

4. Each line represents a process. You can change the priority of the process by adjusting the parameters. The entries in this file are in the format:

```
[group name]:[scheduler policy]:[scheduler priority]:[regular expression]
```

In the **scheduler policy** field, the following values are accepted:

0	Sets a policy of <i>other</i> . If the policy is set to o , the scheduler priority field will be set to 0 and ignored.
b	Sets a policy of batch.
f	Sets a policy of FIFO.
*	If the policy is set to *, no change will be made to to any matched thread policy.

The **regular expression** field matches the thread name to be modified.

5. After editing the file, you will need to restart the **rtctl** service to reload it with the new settings:

```
# service rtctl stop

# service rtctl start
Setting kernel thread priorities: done
```

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- rtctl(1)
- rtgroups(5)

3.2. MRG Realtime Specific gettimeofday speedup

In addition to the **gettimeofday(2)** speedup listed in *Section 2.6*, "**gettimeofday** speedup", the MRG Realtime kernel contains a further **gettimeofday** performance optimization. This method caches the most recently used time value in a global system file. If another **gettimeofday** call is performed within the ms (hz) then it is not necessary to re-read the hardware clock. As a result, applications which do not require microsecond precision benefit.

Enable the MRG Realtime **gettimeofday** speedup

This setting is not enabled by default. When you start it, it needs to be enabled on a global basis.

Append kernel.vsyscall64 = 2 to the /etc/sysctl.conf file. This causes the gettimeofday function to be performed entirely in user-space, removing the system call overhead. To do this open the /etc/sysctl.conf file in your preferred text editor and add the following line:

```
kernel.vsyscall64 = 2
```

Make this change effective immediately, reload the **sysctl.conf** file using:

sysctl -p

2. To make the change effective immediately and persistent between reboots, you will need to edit the /proc/sys/kernel/vsyscall64 file directly.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- sysctl(8)
- gettimeofday(2)

3.3. Using kdump and kexec with the MRG Realtime kernel

If **kdump** is enabled on your system, the standard boot kernel will reserve a small section of system RAM and load the **kdump** kernel into the reserved space. When a kernel panic or other fatal error occurs, **kexec** is used to boot into the **kdump** kernel. **Kexec** is a fastboot mechanism that allows the **kdump** kernel to boot without going through BIOS. The **kdump** kernel boots up using only the reserved RAM and sends an error message to the console. It will then write a dump of the boot kernel's address space to a file for later debugging. Because **kexec** does not go through the BIOS, the memory of the original boot is retained, and the crash dump is much more detailed. Once this is done, the kernel reboots, which resets the machine and brings the boot kernel back up.



Important

In Red Hat Enterprise Linux 5.6 and Red Hat Enterprise Linux 6.1 there is no dedicated **kdump** kernel. It uses the main kernel instead. The MRG Realtime kernel cannot be used as a **kdump** kernel, but it supports the use of a separate **kdump** kernel. It is recommended that you use the MRG Realtime kernel as the boot kernel, and the Red Hat Enterprise Linux 5.6 or Red Hat Enterprise Linux 6.1 kernel as the **kdump** kernel.

There are three methods for enabling **kdump** under Red Hat Enterprise Linux 5.6 and Red Hat Enterprise Linux 6.1. The first method uses a tool called **rt-setup-kdump**. The second adds a command line to the boot kernel, and the third uses the graphical system configuration tool included with Red Hat Enterprise Linux 5.6 and Red Hat Enterprise Linux 6.1.

Creating a basic kdump kernel with rt-setup-kdump

1. The rt-setup-kdump tool is part of the rt-setup package, which can be installed using yum:

yum install rt-setup

2. Run the tool by invoking it at the shell prompt as the root user. This will set the Red Hat Enterprise Linux 5.6 or Red Hat Enterprise Linux 6.1 kernel to be the kdump kernel:

rt-setup-kdump

Enabling kdump with grub.conf

1. Check that you have the **kexec-tools** package installed.

```
# rpm -q kexec-tools
kexec-tools-1.101-194.4.el5
```

2. The system knows which kernel is the **kdump** kernel by checking the **KDUMP_KERNELVER** value in the **/etc/sysconfig/kdump** configuration file.

Add the kernel version string for the kdump kernel to the **KDUMP_KERNELVER** variable:

```
KDUMP_KERNELVER="2.6.18-194"
```

3. Open the /etc/grub.conf file in your preferred text editor and add a crashkernel line to the boot kernel. This line takes the form:

```
crashkernel=[MB of RAM to reserve]M
```

A typical **crashkernel** line would reserve 128 megabytes (128M):

```
crashkernel=128M
```

A typical MRG Realtime /etc/grub.conf file would have the MRG Realtime kernel as the boot kernel, with the crashkernel line added:

4. Once you have saved your changes, restart the system to set up the reserved memory space. You can then turn on the **kdump** init script and start the **kdump** service:

```
# chkconfig kdump on
# service kdump status
```

Chapter 3. Realtime-Specific Tuning

```
# service kdump start
Starting kdump: [ OK ]
```

5. If you want to check that the **kdump** is working correctly, you can simulate a panic using **sysrq**:

```
# echo "c" > /proc/sysrq-trigger
```

This will cause the kernel to panic and the system will boot into the **kdump** kernel. Once your system has been brought back up with the boot kernel, you should be able to check the log file at the location you specified.




Note

Additional information about kdump can be found by installing the **kexec-tools** package and viewing the contents of **/usr/share/doc/kexec-tools-2.0.0/kexec-kdump-howto.txt**.


Enabling kdump with system-config-kdump

1. Select the **Kdump** system tool from the **System|Administration** menu, or use the following command at the shell prompt:

system-config-kdump



2. Select the check box labeled **Enable kdump** and adjust the necessary settings for memory reservation and dump file location. Click **OK** to save your changes.



3. The system knows which kernel is the **kdump** kernel by checking the **KDUMP_KERNELVER** value in the **/etc/sysconfig/kdump** configuration file.

Open the /etc/sysconfig/kdump file in your preferred text editor and locate the KDUMP_KERNELVER variable. Add the kernel version string for the kdump kernel to the KDUMP_KERNELVER variable:

```
KDUMP_KERNELVER="2.6.33.2-rt13.12"
```

Remember to save your settings before closing the file.

4. If you want to check that the **kdump** is working correctly, you can simulate a panic using **sysrq**:

```
# echo "c" > /proc/sysrq-trigger
```

This will cause the kernel to panic and the system will boot into the **kdump** kernel. Once your system has been brought back up with the boot kernel, you should be able to check the log file at the location you specified.



Note

Some hardware needs to be reset during the configuration of the **kdump** kernel. If you have any problems getting the **kdump** kernel to work, edit the **/etc/sysconfig/kdump** file and add **reset_devices=1** to the **KDUMP_COMMANDLINE_APPEND** variable.



Important

On IBM LS21 machines, the following warning message may occur when attempting to boot the kdump kernel:

```
irq 9: nobody cared (try booting with the "irqpoll" option) handlers: [<ffffffff811660a0>] (acpi_irq+0x0/0x1b) turning off IO-APIC fast mode.
```

Some systems will recover from this error and continue booting, while some will freeze after displaying the message. This is a known issue. If you see this error, add the line **acpi=noirq** as a boot parameter to the kdump kernel. Only add this line if this error occurs as it can cause boot problems on machines not affected by this issue.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- kexec(8)
- /etc/kdump.conf

3.4. TSC timer synchronization on Opteron CPUs

The current generation of AMD64 Opteron processors can be susceptible to a large **gettimeofday** skew. This skew occurs when both **cpufreq** and the Time Stamp Counter (TSC) are in use. MRG

Realtime provides a method to prevent this skew by forcing all processors to simultaneously change to the same frequency. As a result, the TSC on a single processor never increments at a different rate than the TSC on another processor.

Enabling TSC timer synchronization

1. Open the /etc/grub.conf file in your preferred text editor and add the parameter clocksource=tsc powernow-k8.tscsync=1 to the MRG Realtime kernel. This forces the use of TSC and enables simultaneous core processor frequency transitions.

```
...[output truncated]...
title Red Hat Enterprise Linux (realtime) (2.6.33.2-rt13.12)
root (hd0,0)
kernel /vmlinuz-2.6.33.2-rt13.12 ro root=/dev/RHEL5/Root clocksource=tsc powernow-k8.tscsync=1
initrd /initrd-2.6.33.2-rt13.12.img
```

2. You will need to restart your system for the changes to take effect.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

gettimeofday(2)

3.5. Infiniband

Infiniband is a type of communications architecture often used to increase bandwidth and provide quality of service and failover. It can also be used to improve latency through Remote Direct Memory Access (RDMA) capabilities.

Support for Infiniband under MRG Realtime does not differ from the support offered under Red Hat Enterprise Linux 5.6 and Red Hat Enterprise Linux 6.1.

3.6. Non-Uniform Memory Access

Non-Uniform Memory Access (NUMA) is a design used to allocate memory resources to a specific CPU. This can improve access time and results in fewer memory locks. Although this appears as though it would be useful for reducing latency, NUMA systems have been known to interact badly with realtime applications, as they can cause unexpected event latencies.

As mentioned in *Binding Processes to CPUs using the taskset utility* the taskset utility will only work if NUMA is not enabled on the system. If you want to perform process binding in conjunction with NUMA, use the **numact1** command instead of **taskset**.

For more information about the NUMA API, see Andi Kleen's whitepaper *An NUMA API for Linux*¹.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

• numactl(8)

¹ http://www.halobates.de/numaapi3.pdf

3.7. Mount debugfs

debugfs is file system specially designed for debugging and making information available to users. Mount **debugfs** for use with MRG Realtime functions **ftrace** and **trace-cmd**.

Mount the kernel to /sys/kernel/debug and instruct it to use the debugfs file system.

```
# mount -t debugfs nodev /sys/kernel/debug
```

2. You can choose to make the **debugfs** directory mount automatically on boot. You can do this by opening the **/etc/fstab** file in your preferred text editor, and adding the following line:

```
nodev /sys/kernel/debug debugfs defaults 0 0
```

3.8. Using the ftrace Utility for Tracing Latencies

One of the diagnostic facilities provided with the MRG Realtime kernel is **ftrace**, which is used by developers to analyze and debug latency and performance issues that occur outside of user-space. The **ftrace** utility has a variety of options that allow you to use the utility in a number of different ways. It can be used to trace context switches, measure the time it takes for a high-priority task to wake up, the length of time interrupts are disabled, or list all the kernel functions executed during a given period.

Some tracers, such as the function tracer, will produce exceedingly large amounts of data, which can turn trace log analysis into a time-consuming task. However, it is possible to instruct the tracer to begin and end only when the application reaches critical code paths.

The **ftrace** utility can be set up once the **trace** variant of the MRG Realtime kernel is installed and in use.

Using the ftrace Utility

In the /sys/kernel/debug/tracing/ directory there is a file named available_tracers.
 This file contains all the available tracers for the installed version of ftrace. To see the list of available tracers, use the cat command to view the contents of the file:

```
# cat /sys/kernel/debug/tracing/available_tracers
events wakeup preemptirqsoff preemptoff irqsoff ftrace sched_switch none
```

events

Traces system events such as timers, system calls, interrupts, context switches, process wake up and others

wakeup

Traces the maximum latency in between the highest priority process waking up and being scheduled. Only RT tasks are considered by this tracer (**SCHED_OTHER** tasks are ignored as of now).

preemptirgsoff

Traces the areas that disable pre-emption and interrupts and records the maximum amount of time for which pre-emption or interrupts were disabled.

preemptoff

Similar to the **preemptirqsoff** tracer but traces only the maximum interval for which preemption was disabled.

irqsoff

Similar to the **preemptirqsoff** tracer but traces only the maximum interval for which interrupts were disabled.

ftrace

Records the kernel functions called during a tracing session. The **ftrace** utility can be run simultaneously with any of the other tracers, except the **sched_switch** tracer.

sched_switch

Traces context switches between tasks.

none

Disables tracing.

 To manually start a tracing session, first select the tracer you wish to use from the list in available_tracers and then use the echo to insert the name of the tracer into /sys/ kernel/debug/tracing/current_tracer:

```
# echo events > /sys/kernel/debug/tracing/current_tracer
```

3. To check if the **ftrace** utility can be enabled, use the **cat** command to view the **/proc/sys/kernel/ftrace_enabled** file. A value of **1** indicates that **ftrace** can be enabled, and **0** indicates that it has been disabled.

```
# cat /proc/sys/kernel/ftrace_enabled
1
```

By default, the tracer is enabled. To turn the tracer on or off, **echo** the appropriate value to the / **proc/sys/kernel/ftrace_enabled** file.

```
# echo 0 > /proc/sys/kernel/ftrace_enabled
# echo 1 > /proc/sys/kernel/ftrace_enabled
```



Important

When using the **echo** command, ensure you place a space character in between the value and the > character. At the shell prompt, using **0>, 1>, and 2>** (without a space character) refers to standard input, standard output and standard error. Using them by mistake could result in unexpected trace output.

4. Adjust details and parameters of the tracers by changing the values for the various files in the / debugfs/tracing/ directory. Some examples are:

The irqsoff, preemptoff, preempirqsoff, and wakeup tracers continuously monitor latencies. When they record a latency greater than the one recorded in **tracing_max_latency** the trace of that latency is recorded, and **tracing_max_latency** is updated to the new maximum time. In this way, **tracing_max_latency** will always shows the highest recorded latency since it was last reset.

To reset the maximum latency, **echo** 0 into the **tracing_max_latency** file. To see only latencies greater than a set amount, **echo** the amount in microseconds:

```
# echo 0 > /sys/kernel/debug/tracing//tracing_max_latency
```

When the tracing threshold is set, it overrides the maximum latency setting. When a latency is recorded that is greater than the threshold, it will be recorded regardless of the maximum latency. When reviewing the trace file, only the last recorded latency is shown.

To set the threshold, **echo** the number of microseconds above which latencies should be recorded:

```
# echo 200 > /sys/kernel/debug/tracing//tracing_thresh
```

5. View the trace logs:

```
# cat /sys/kernel/debug/tracing//trace
# cat /sys/kernel/debug/tracing//latency_trace
```

6. To store the trace logs, copy them to another file:

```
# cat /sys/kernel/debug/tracing//latency_trace > /tmp/lat_trace_log
```

7. The **ftrace** utility can be filtered by altering the settings in the **/sys/kernel/debug/ tracing/set_ftrace_filter** file. If no filters are specified in the file, all processes are traced.
Use the **cat** to view the current filters:

```
# cat /sys/kernel/debug/tracing/set_ftrace_filter
```

8. To change the filters, **echo** the name of the function to be traced. The filter allows the use of a * wildcard at the beginning or end of a search term.

The * wildcard can also be used at both the beginning and end of a word. For example: *irq* will select all functions that contain irq in the name.

Encasing the search term and the wildcard character in double quotation marks ensures that that shell will not attempt to expand the search to the present working directory.

Some examples of filters are:

• Trace only the **schedule** process:

```
# echo schedule > /sys/kernel/debug/tracing/set_ftrace_filter
```

Trace all processes that end with lock:

```
# echo "*lock" > /sys/kernel/debug/tracing/set_ftrace_filter
```

• Trace all processes that start with **spin_**:

```
# echo "spin_*" > /sys/kernel/debug/tracing/set_ftrace_filter
```

• Trace all processes with cpu in the name:

```
# echo "*cpu*" > /sys/kernel/debug/tracing/set_ftrace_filter
```



Note

If you use a single > with the **echo** command, it will override any existing value in the file. If you wish to append the value to the file, use >> instead.

3.9. Latency Tracing Using trace-cmd

trace-cmd is a MRG Realtime function that traces all kernel function calls, and some special events. It records what is happening in the system during a short period of time, providing information that can be used to analyze system behavior.

The **trace-cmd** tool is not enabled in the production version of the MRG Realtime kernel as it creates additional overhead. If you wish to use the **trace-cmd** tool you will need to download and install either the **trace** or **debug** variants of the MRG Realtime kernel.



Note

For instructions on how to install kernel variants, see the MRG Realtime Installation Guide.

1. Once you are using either the **trace** or **debug** variants of the MRG Realtime kernel, you can install the **trace-cmd** tool using **yum**.

```
# yum install trace-cmd
```

2. To start the utility, type **trace-cmd** at the shell prompt, along with the options you require, using the following syntax:

```
# trace-cmd [-f] [command]
```

The use of the *-f* option sets Function Tracing and can be used with any other trace command.

The commands instruct **trace-cmd** to trace in specific ways.

Command	Trace Type	Description
-s	Context switch	Traces the context switches between tasks.
-i	Interrupts off	Records the maximum time that an interrupt is disabled. When a new maximum is recorded, it replaces the previous maximum.
-р	Pre-emption off	Records the maximum time that pre-emption is disabled. When a new maximum is recorded, it replaces the previous maximum.
-b	Pre-emption and interrupts off	Records the maximum time that pre-emption or interrupts are disabled. When a new maximum is recorded, it replaces the previous maximum.
-W	Wakeup	Traces and records the maximum time for the highest priority task to get scheduled after it has been woken up.
-е	Event tracing	
-f	Function tracing	Can be used with any other trace
-1	Prints log in the latency_trace format	Can be used with any other trace

- 3. In this example, the **trace-cmd** utility will:
 - Select the **context switch** tracing method
 - Enable the latency tracer
 - Run the 1s -1a command
 - Turn the latency tracer off again

```
# trace-cmd -s /bin/ls -la > /tmp/latency_log.txt
```

3.10. Using sched_nr_migrate to limit SCHED_OTHER task migration.

If a **SCHED_OTHER** task spawns a large number of other tasks, they will all run on the same CPU. The migration task or **softirq** will try to balance these tasks so they can run on idle CPUs. The **sched_nr_migrate** option can be set to specify the number of tasks that will move at a time. Because realtime tasks have a different way to migrate, they are not directly affected by this, however when **softirq** moves the tasks it locks the run queue spinlock that is needed to disable interrupts. If there are a large number of tasks that need to be moved, it will occur while interrupts are disabled, so no timer events or wakeups will happen simultaneously. This can cause severe latencies for realtime tasks when the **sched_nr_migrate** is set to a large value.

Adjusting the value of the **sched_nr_migrate** variable

- Increasing the sched_nr_migrate variable gives high performance from SCHED_OTHER threads
 that spawn lots of tasks, at the expense of realtime latencies. For low realtime task latency at the
 expense of SCHED_OTHER task performance, then the value should be lowered. The default value
 is 8.
- 2. To adjust the value of the **sched_nr_migrate** variable, you can **echo** the value directly to / **proc/sys/kernel/sched_nr_migrate**:

echo 2 > /proc/sys/kernel/sched_nr_migrate

Application Tuning and Deployment

This chapter contains tips related to enhancing and developing MRG Realtime applications.



Note

In general, try to use *POSIX* (Portable Operating System Interface) defined APIs. The MRG Realtime developers are compliant with POSIX standards and latency reduction in the MRG Realtime kernel is also based on POSIX.

Further Reading

For further reading on developing your own MRG Realtime applications, start by reading the *RTWiki Article*¹.

4.1. Signal Processing in Realtime Applications

Traditional UNIXTM and POSIX signals have their uses, especially for error handling, but they are not suitable for use in realtime applications as an event delivery mechanism. The reason for this is that the current Linux kernel signal handling code is quite complex, due mainly to legacy behavior and the multitude of APIs that need to be supported. This complexity means that the code paths that may be taken when delivering a signal are not always the optimal path and quite long latencies may be experienced by applications.

The original motivation behind UNIXTM signals was to multiplex one thread of control (the process) between different "threads" of execution. Signals behave somewhat like operating system interrupts - when a signal is delivered to an application, the application's context is saved and it starts executing a previously registered signal handler. Once the signal handler has completed, the application returns to executing where it was when the signal was delivered. This can get complicated in practice.

Signals are too non-deterministic to trust them in a realtime application. A better option is to use POSIX Threads (pthreads) to distribute your workload and communicate between various components. You can coordinate groups of threads using the pthreads mechanisms of mutexes, condition variables and barriers and trust that the code paths through these relatively new constructs are much cleaner than the legacy handling code for signals.

Further Reading

For more information, or for further reading, the following links are related to the information given in this section.

RTWiki's Build an RT Application²

Ulrich Drepper's Requirements of the POSIX Signal Model³

¹ http://rt.wiki.kernel.org/index.php/HOWTO:_Build_an_RT-application

 $^{^2\} http://rt.wiki.kernel.org/index.php/HOWTO:_Build_an_RT-application$

³ http://people.redhat.com/drepper/posix-signal-model.xml

4.2. Using sched_yield and Other Synchronization Mechanisms

The **sched_yield** system call is used by a thread allowing other threads a chance to run. Often when **sched_yield** is used, the thread can go to the end of the run queues, taking a long time to be scheduled again, or it can be rescheduled straight away, creating a busy loop on the CPU. The scheduler is better able to determine when and if there are actually other threads wanting to run. Avoid using **sched_yield** on any RT task.

POSIX Threads (Pthreads) have abstractions that will provide more consistent behavior across kernel versions. However, this can also mean that the system has less time to process networking packets, leading to considerable performance loss. This type of loss can be difficult to diagnose as there are no significant changes in the networking components of the system. It can also result in a change in behavior of some applications.

For more information, see Arnaldo Carvalho de Melo's paper on Earthquaky kernel interfaces⁴.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- pthread.h(P)
- · sched_yield(2)
- sched_yield(3p)

4.3. Mutex options

Standard Mutex Creation

Mutual exclusion (mutex) algorithms are used to prevent processes simultaneously using a common resource. A fast user-space mutex (futex) is a tool that allows a user-space thread to claim a mutex without requiring a context switch to kernel space, provided the mutex is not already held by another thread.



Note

In this document, we use the terms *futex* and *mutex* to describe POSIX thread (pthread) mutex constructs.

- 1. When you initialize a **pthread_mutex_t** object with the standard attributes, it will create a private, non-recursive, non-robust and non priority inheritance capable mutex.
- 2. Under pthreads, mutexes can be initialized with the following strings:

pthread_mutex_t my_mutex;

⁴ http://vger.kernel.org/~acme/unbehaved.txt

```
pthread_mutex_init(&my_mutex, NULL);
```

3. In this case, your application may not be benefiting of the advantages provided by the pthreads API and the MRG Realtime kernel. There are a number of mutex options that should be considered when writing or porting an application.

Advanced Mutex Options

In order to define any additional capabilities for the mutex you will need to create a **pthread_mutexattr_t** object. This object will store the defined attributes for the futex.



Important

For the sake of brevity, these examples do not include a check of the return value of the function. This is a basic safety procedure and one that you should always perform.

1. Creating the mutex object:

```
pthread_mutex_t my_mutex;
pthread_mutexattr_t my_mutex_attr;
pthread_mutexattr_init(&my_mutex_attr);
```

2. Shared and Private mutexes:

Shared mutexes can be used between processes, however they can create a lot more overhead.

```
pthread_mutexattr_setpshared(&my_mutex_attr, PTHREAD_PROCESS_SHARED);
```

3. Realtime priority inheritance:

Priority inversion problems can be avoided by using priority inheritance.

```
pthread_mutexattr_setprotocol(&my_mutex_attr, PTHREAD_PRIO_INHERIT);
```

4. Robust mutexes:

Robust mutexes are released when the owner dies, however this can also come at a high overhead cost. _NP in this string indicates that this option is non-POSIX or not portable.

```
pthread_mutexattr_setrobust_np(&my_mutex_attr, PTHREAD_MUTEX_ROBUST_NP);
```

5. Mutex initialization:

Once the attributes are set, initialize a mutex using those properties.

```
pthread_mutex_init(&my_mutex, &my_mutex_attr);
```

6. Cleaning up the attributes object:

After the mutex has been created, you can keep the attribute object in order to initialize more mutexes of the same type, or you can clean it up. The mutex is not affected in either case. To clean up the attribute object, use the **_destroy** command.

```
pthread_mutexattr_destroy(&my_mutex_attr);
```

The mutex will now operate as a regular **pthread_mutex**, and can be locked, unlocked and destroyed as normal.

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- futex(7)
- pthread mutex destroy(P)

For information on pthread_mutex_t and pthread_mutex_init

pthread mutexattr setprotocol(3p)

For information on pthread_mutexattr_setprotocol and pthread_mutexattr_getprotocol

pthread_mutexattr_setprioceiling(3p)

For information on pthread_mutexattr_setprioceiling and pthread_mutexattr_getprioceiling

4.4. TCP NODELAY and Small Buffer Writes

As discussed briefly in *Transmission Control Protocol (TCP)*, by default TCP uses Nagle's algorithm to collect small outgoing packets to send all at once. This can have a detrimental effect on latency.

Using TCP_NODELAY and TCP_CORK to improve network latency

 Applications that require lower latency on every packet sent should be run on sockets with TCP_NODELAY enabled. It can be enabled through the setsockopt command with the sockets API:

```
# int one = 1;
# setsockopt(descriptor, SOL_TCP, TCP_NODELAY, &one, sizeof(one));
```

2. For this to be used effectively, applications must avoid doing small, logically related buffer writes. Because TCP_NODELAY is enabled, these small writes will make TCP send these multiple buffers as individual packets, which can result in poor overall performance.

If applications have several buffers that are logically related and that should be sent as one packet it could be possible to build a contiguous packet in memory and then send the logical packet to TCP, on a socket configured with **TCP_NODELAY**.

Alternatively, create an I/O vector and pass it to the kernel using **writev** on a socket configured with **TCP_NODELAY**.

3. Another option is to use TCP_CORK, which tells TCP to wait for the application to remove the cork before sending any packets. This command will cause the buffers it receives to be appended to the existing buffers. This allows applications to build a packet in kernel space, which may be required when using different libraries that provides abstractions for layers. To enable TCP_CORK, set it to a value of 1 using the setsockopt sockets API (this is known as "corking the socket"):

```
# int one = 1;
# setsockopt(descriptor, SOL_TCP, TCP_CORK, &one, sizeof(one));
```

4. When the logical packet has been built in the kernel by the various components in the application, tell TCP to remove the cork. TCP will send the accumulated logical packet right away, without waiting for any further packets from the application.

```
# int zero = 0;
# setsockopt(descriptor, SOL_TCP, TCP_CORK, &zero, sizeof(zero));
```

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

- tcp(7)
- setsockopt(3p)
- setsockopt(2)

4.5. Setting Realtime Scheduler Priorities

Using **rtct1** to set scheduler priorities is described at *Using rtct1* to *Set Priorities*. In the example given in that chapter, some kernel threads have been given a very high priority. This is to have the default priorities integrate well with the requirements of the Real Time Specification for Java (RTSJ). RTSJ requires a range of priorities from 10-89, so many kernel thread priorities are positioned at 90 and above. This avoids unpredictable behavior if a long-running Java application blocks essential system services from running.

For deployments where RTSJ is not in use, there is a wide range of scheduling priorities below 90 which are at the disposal of applications. It is usually dangerous for user level applications to run at priority 90 and above - despite the fact that the capability exists. Preventing essential system services from running can result in unpredictable behavior, including blocked network traffic, blocked virtual memory paging and data corruption due to blocked filesystem journaling.

Extreme caution should be used if scheduling any application thread above priority 89. If any application threads are scheduled above priority 89 you should ensure that the threads only run a very short code path. Failure to do so would undermine the low latency capabilities of the MRG Realtime kernel.

Setting Real-time Priority for Non-privileged Users

Generally, only root users are able to change priority and scheduling information. If you require non-privileged users to be able to adjust these settings, the best method is to add the user to the **Realtime** group.



Important

You can also change user privileges by editing the /etc/security/limits.conf file. This has a potential for duplication and may render the system unusable for regular users. If you do decide to edit this file, exercise caution and always create a copy before making changes.

Further Reading

For more information, or for further reading, the following links are related to the information given in this section.

 There is a testing utility called signaltest which is useful for demonstrating MRG Realtime system behavior. A whitepaper written by Arnaldo Carvalho de Melo explains this in more detail: signaltest: Using the RT priorities⁵

4.6. Dynamic Libraries Loading

When developing your MRG Realtime program, consider resolving symbols at startup. Although it can slow down program initialization, it is one way to avoid non-deterministic latencies during program execution.

Dynamic Libraries can be instructed to load at system startup by setting the **LD_BIND_NOW** variable with **1d.so**, the dynamic linker/loader.

The following is an example shell script. This script exports the **LD_BIND_NOW** variable with a non-null value of 1, then runs a program with a scheduler policy of FIFO and a priority of 1.

#!/bin/sh

LD_BIND_NOW=1
export LD_BIND_NOW

chrt --fifo 1 /opt/myapp/myapp-server &

Related Manual Pages

For more information, or for further reading, the following man pages are related to the information given in this section.

• Id.so(8)

More Information

5.1. Reporting Bugs



Important

An up-to-date listing of known issues can be found on the *MRG Realtime Wiki: Known Bugs*¹. Always check this list before reporting a new bug.

Diagnosing a Bug

Before you a file a bug report, follow these steps to diagnose where the problem has been introduced. This will greatly assist in rectifying the problem.

- 1. Try reproducing the problem with the standard kernel. Check that you have the latest version of the Red Hat Enterprise Linux 5.6 or Red Hat Enterprise Linux 6.1 kernel, then boot into it from the grub menu. Try reproducing the problem. If the problem still occurs with the standard kernel, report a bug against Red Hat Enterprise Linux 5.6 or Red Hat Enterprise Linux 6.1 *not* MRG Realtime.
- 2. If the problem does not occur when using the standard kernel, then the bug is probably the result of changes introduced in either:
 - a. The upstream kernel on which MRG Realtime is based. For example, Red Hat Enterprise Linux 5.6 is based on kernel version 2.6.18, the Red Hat Enterprise Linux 6.1 kernel is 2.6.32 based, and MRG Realtime is based on version 2.6.33
 - b. MRG Realtime specific enhancements Red Hat has applied on top of the baseline (2.6.33) kernel

To determine the problem, it is helpful to see if you can reproduce the problem on an unmodified upstream 2.6.33 kernel. For this reason, in addition to providing the MRG Realtime kernel, we also provide a **vanilla** kernel variant. The **vanilla** kernel is the unmodified upstream kernel build without the MRG Realtime additions.

Reporting a Bug

If you have determined that the bug is specific to MRG Realtime follow these instructions to enter a bug report:

- 1. You will need a *Bugzilla*² account. You can create one at *Create Bugzilla Account*³.
- 2. Once you have a Bugzilla account, log in and click on *Enter A New Bug Report*⁴.
- 3. You will need to identify the product the bug occurs in. MRG Realtime appears under Red Hat Enterprise MRG in the Red Hat products list. It is important that you choose the correct product that the bug occurs in.
- 4. Continue to enter the bug information by designating the appropriate component and giving a detailed problem description. When entering the problem description be sure to include details of

¹ http://rt.et.redhat.com/page/RHEL-RT_KnownBugs

whether you were able to reproduce the problem on the standard Red Hat Enterprise Linux 5.6, Red Hat Enterprise Linux 6.1 or the supplied **vanilla** kernel.

5.2. Further Reading

- Red Hat Enterprise MRG Product Information
 - http://www.redhat.com/mrg
- MRG Realtime Installation Guide and other Red Hat Enterprise MRG documentation
 - http://docs.redhat.com/docs/en-US/Red_Hat_Enterprise_MRG/
- · Mailing List
 - To post to the list, send mail to rhemrg-users-list@redhat.com
 - Subscribe to the mailing list at: http://post-office.corp.redhat.com/mailman/listinfo/rhemrg-users-list

Appendix A. Revision History

Revision 1-0 Thu Jun 23 2011

Alison Young alyoung@redhat.com

Prepared for publishing

Revision 0.1-5 Thu June 02 2011

Alison Young alyoung@redhat.com

Rebuilt following brand package update

Revision 0.1-4 Mon May 23 2011

Alison Young alyoung@redhat.com

Technical Review updates

Revision 0.1-3 Mon May 16 2011

Alison Young alyoung@redhat.com

BZ#584297 - Reorganise the latency tracing sections

BZ#666962 - Update for RHEL6

Revision 0.1-2 Thu Apr 05 2011

Alison Young alyoung@redhat.com

Minor Update

Revision 0.1-1 Tue Apr 05 2011

Alison Young alyoung@redhat.com

BZ#683586 - Update Further Reading section Minor XML updates

Revision 0.1-0 Wed Feb 23 2011

Alison Young alyoung@redhat.com

Fork from 1.3