

天翼云备份产品 客户端部署手册

中国电信股份有限公司云计算分公司



目录

目录

目录	L <		2		
1	安装 Linux NBU8.0 客户端				
	安装准备				
	安装 NBU 8.0	Client (Linux)	6		
	1. 1. 1	配置/etc/hosts 解析	6		
	1.1.2	设置环境变量	6		
	1.1.3	安装 NBU8.0 Client(Linux)	6		
	1.1.4	检查 Linux 客户端的安装后进程	9		
	1. 1. 5	Linux 客户端配置参数	9		
	1. 1. 6	Linux 客户端配置完成需要重启服务	9		
	1. 1. 7	检查客户端的连通情况	10		
	1. 1. 8	客户端加密功能配置	10		
	1. 1. 9	确认 Linux 客户端是否已加密	11		
	1. 1. 10	Linux 文件加密异机恢复	11		
	1. 1. 11	常见故障及解决方案	12		
2	安装 Window	/s NBU8.0 客户端	13		
	安装准备		13		
	安装 NBU 8.0 Client(Windows)		14		
	2. 1. 1	安装 NBU8.0 Windows Client	14		
	2.1.2	查看客户端进程	23		
	2. 1. 3	检查客户端的连通情况	23		
	2.1.4	客户端加密功能配置	23		
	2. 1. 5	确认 Windows 客户端是否做加密	24		
	2. 1. 6	Windows 文件加密异机恢复	25		



1 安装 Linux NBU8.0 客户端

在 UNIX/LINUX 服务器中, Nebackup Client 的安装步骤基本相同, 以 RHEL6 为例说明 Netbackup Client 的安装过程。

安装准备

- 1. 把主服务器(Master Server)和介质服务器(Media Server) 主机名和 IP 地址的对应关系都加入到客户端的/etc/hosts 文件中,并把客户端的主机名和 IP 地址对应关系都分别加入到主服务器(Master Server)/etc/hosts 文件中。
- 2. 上传 NBU 8.0 客户端所需要的软件包(请在天翼云上下载客户所需的客户端软件包)到客户端指定的路径。如以 RedHat Linux 为例:

[root@SH-Oracle-Server ~]# mkdir -p /nbuclient #新建指定的路径, 把客户端下载到此目录中

[root@SH-Oracle-Server ~]# cd /nbuclient

[root@SH-Oracle-Server nbuclient]#

[root@SH-Oracle-Server nbuclient]# Is

RedHat.Client.tar.gz

[root@SH-Oracle-Server nbuclient]# tar zxvf RedHat.Client.tar.gz #解压安装包

NetBackup_8.0_CLIENTS2/Doc/

 $Net Backup_8.0_CLIENTS2/Doc/Net Backup_Documentation.pdf$

NetBackup_8.0_CLIENTS2/install

NetBackup_8.0_CLIENTS2/LICENSE

NetBackup_8.0_CLIENTS2/NBClients/

NetBackup_8.0_CLIENTS2/NBClients/anb/

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/



NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/nbbsdtar

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/VRTSnbclt.rpm

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/cp_to_client

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/VRTSnbpck.rpm

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/.sizes

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/ftp_to_client

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/VRTSnbjava.rpm

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/nb_init_cfg

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/extract_java

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/VRTSnbjre.rpm

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/install_client

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/ssh_to_client

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/nbj.conf

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/sftp_to_client

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/VRTSpbx.rpm

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/pdinstall

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/version



NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/VRTSnbcfg.rpm

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/VRTSpddea.rpm

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/nbcheck

NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18/client_config

NetBackup_8.0_CLIENTS2/NBClients/catalog/

NetBackup_8.0_CLIENTS2/NBClients/catalog/anb/

NetBackup_8.0_CLIENTS2/NBClients/catalog/anb/client.inst

NetBackup_8.0_CLIENTS2/VSM_README

[root@SH-Oracle-Server nbuclient]# Is

NetBackup_8.0_CLIENTS2 RedHat.Client.tar.gz

[root@SH-Oracle-Server nbuclient]# cd NetBackup_8.0_CLIENTS2/ [root@SH-Oracle-Server NetBackup 8.0 CLIENTS2]# Is #查看解压后

的目录内容

Doc install LICENSE NBClients VSM README

- 3. 确保网络连通并双向开通 TCP 1556、TCP 13724、TCP 13782 端口。
 - 客户端与备份服务器通信验证方法

[root@SH-Oracle-Server ~]# yum install telnet -y

[root@SH-Oracle-Server ~]# telnet NJ-Master01 1556

[root@SH-Oracle-Server ~]# telnet NJ-Master01 13724

[root@SH-Oracle-Server ~]# telnet NJ-Master01 13782

[root@SH-Oracle-Server ~]# telnet NJ-Media01 1556

[root@SH-Oracle-Server ~]# telnet NJ-Media01 13724

[root@SH-Oracle-Server ~]# telnet NJ-Media01 13782

[root@SH-Oracle-Server ~]# telnet NJ-Media02 1556

验证网络端口连接是否正常。

[root@SH-Oracle-Server ~]# telnet NJ-Media02 13724

[root@SH-Oracle-Server ~]# telnet NJ-Media02 13782 #通过 telnet

客户端与备份服务器通信验证通过后,请及时通知天翼云备份管理员在备份服务端进行反向验证,反向验证通过后再进行客户端的安装。



安装 NBU 8.0 Client (Linux)

[root@SH-Oracle-Server ~]# mkdir -p /nbu/openv [root@SH-Oracle-Server ~]# In -s /nbu/openv /usr/openv

- 1.1.1 配置/etc/hosts 解析
- 1. 在客户端/etc/hosts 增加对主服务器(Master Server)、介质服务器(Media Server)及备份客户端公网地址的解析。

[root@SH-Oracle-Server ~]# vi /etc/hosts

36.111.194.141 NJ-Master01

36.111.192.116 NJ-Media01

36.111.192.172 NJ-Media02

180.153.52.52 SH-Oracle-Server #根据客户端的不同,填写不同的公网地址和主机名。

注意:客户端解析要与客户端主机名一致。

请客户给天翼云备份管理员要备份的客户端公网地址和主机名解析的对应信息。如:

180.153.52.52 SH-Oracle-Server#根据客户端的不同,填写不同的公网地址和主机名。

1.1.2 设置环境变量

以客户端 root 用户登录,在/etc/profile 中最后一行添加如下内容:

[root@SH-Oracle-Server ~]# vi /etc/profile

PATH=\$PATH:/usr/openv/netbackup/bin:/usr/openv/netbackup/bin/ad mincmd:/usr/openv/netbackup/bin/goodies:/usr/openv/volmgr/bin:/usr/openv/db/bin

export PATH

[root@SH-Oracle-Server ~]# source /etc/profile #添加的配置文件立即 生效。

1.1.3 安装 NBU8.0 Client(Linux)

以客户端 root 用户

[root@SH-Oracle-Server ~]# cd /nbuclient/NetBackup_8.0_CLIENTS2/



[root@SH-Oracle-Server NetBackup_8.0_CLIENTS2]# Is Doc install LICENSE NBClients VSM README [root@SH-Oracle-Server NetBackup_8.0_CLIENTS2]# ./install

Veritas Installation Script Copyright (c) 2016 Veritas Technologies LLC. All rights reserved.

Installing NetBackup Client Software

Please review the VERITAS SOFTWARE LICENSE AGREEMENT located on

the installation media before proceeding. The agreement includes details on the NetBackup Product Improvement Program.

For NetBackup installation and upgrade information specific to your platform and to find out if your installed EEBs or hot fixes are contained in this release, check out the Veritas Services and **Operations Readiness**

Tools (SORT) Installation and Upgrade Checklist and Hot fix and EEB Release Auditor, respectively, at https://sort.veritas.com/netbackup.

Do you wish to continue? [y,n] (y) y #按 y 继续

Checking for required system conditions...

ok be_nb_same_host: inapplicable on linux: skipping ok unsupported platform: Passed checks for unsupported platforms.

Checking for recommended system conditions...

ok hotfix_auditor: NetBackup is not installed or there is no hotfix or EEB data present. Skipping HF/EEB Auditor check.

Do you want to install the NetBackup client software for this client? [y,n] (y) y #按 y 继续

This package will install Linux/RedHat2.6.18 client.

This package will install NetBackup client 8.0.

Enter the name of the NetBackup master server : NJ-Master01 #填写



主服务器的解析名称

Would you like to use "SH-Oracle-Server" as the configured name of the NetBackup client? [y,n] (y) y #按 y 继续

Client binaries are located in /veritas/openv/NetBackup_8.0_CLIENTS2/NBClients/anb/Clients/usr/openv/netbackup/client/Linux/RedHat2.6.18.

Starting NetBackup Deduplication installer

testing: /tmp/pdde_pkg_dir_4133

NetBackup Deduplication preinstall check passed

Installing VRTSnbpck ...

Installation of VRTSnbpck was successful. Check

/tmp/install_VRTSnbpck.rpm_trace.4119 for details.

Installing VRTSpbx ...

Installation of VRTSpbx was successful. Check

/tmp/install_VRTSpbx.rpm_trace.4119 for details.

Installing VRTSnbclt ...

Installation of VRTSnbclt was successful. Check

/tmp/install_VRTSnbclt.rpm_trace.4119 for details.

Terminating NetBackup and/or Media Manager processes.

Installing NB-Java.

Installing VRTSnbjre ...

Installation of VRTSnbjre was successful.

More details regarding VRTSnbjre can be found in file /tmp/install_VRTSnbjre.rpm_trace.4589 on SH-Oracle-Server. Installing VRTSnbjava ...

Installation of VRTSnbjava was successful.

More details regarding VRTSnbjava can be found in file /tmp/install_VRTSnbjava.rpm_trace.4589 on oracle11g-Server.

+ /bin/cp ./nbj.conf /usr/openv/java

Migrating log files in /usr/openv/logs #查看日志的路径 Migration of log files complete.

Send a SIGHUP to (x)inetd so the (x)inetd.conf file will be reread.

Reloading configuration:

[OK]

Installing VRTSpddea.rpm ...

Installation of VRTSpddea.rpm was successful. Check



/tmp/install_VRTSpddea.rpm_trace.4119 for details. Installing VRTSnbcfg.rpm ...

Installation of VRTSnbcfg.rpm was successful. Check /tmp/install_VRTSnbcfg.rpm_trace.4119 for details.

File /usr/openv/tmp/install_trace.3974 contains a trace of this install. That file can be deleted after you are sure the install was successful. #安装成功

1.1.4 检查 Linux 客户端的安装后进程

[root@SH-Oracle-Server ~]# bpps -x #查看 NBU 客户端的进程 NB Processes								
root	27148	1	0	12:57	?	00:00:00		
/usr/openv/netbackup/bin/vnetd -standalone								
root	27154	1	0	12:57	?	00:00:00		
/usr/openv/netbackup/bin/bpcd -standalone								
root	27205	1		12:57	?	00:00:00		
/usr/openy/r	etbackup/bin/r	bdisc	0					
,								
Shared Veritas Processes								
root	25803	1	0	12:57	?	00:00:00		
/opt/VRTSpb	x/bin/pbx_exch	nange						

1.1.5 Linux 客户端配置参数

编辑 /usr/openv/netbackup/bp.conf 文件。具体配置如下:

[root@SH-Oracle-Server ~]# vi /usr/openv/netbackup/bp.conf
[root@SH-Oracle-Server ~]# cat /usr/openv/netbackup/bp.conf
SERVER = NJ-Master01 #nbu 主服务器名
SERVER = NJ-Media01 #nbu 介质服务器名
SERVER = NJ-Media02 #nbu 介质服务器名
CLIENT_NAME = SH-Oracle-Server #nbu 客户端服务名
CONNECT_OPTIONS = localhost 1 0 2

1.1.6 Linux 客户端配置完成需要重启服务

重启服务方法有两种: 任选其一即可



- 1. 用 bp. kill_all 命令杀死服务,然后再用 bp. start_all 启动服务。
- 2. 用 service netbackup stop 关闭服务, 然后再用 service netbackup start 启动服务。

[root@SH-Oracle-Server ~]# service netbackup stop
stopping the NetBackup Discovery Framework
stopping the NetBackup client daemon
stopping the NetBackup network daemon
[root@SH-Oracle-Server ~]# service netbackup start
NetBackup network daemon started.
NetBackup client daemon started.
NetBackup SAN Client Fibre Transport daemon started.
NetBackup Discovery Framework started.
NetBackup Bare Metal Restore Boot Server daemon started.

1.1.7 检查客户端的连通情况

[root@SH-Oracle-Server ~]# bpcIntcmd -pn expecting response from server NJ-Master01 SH-Oracle-Server SH-Oracle-Server 180.153.52.52 21796 #如果不能连接成功,请检查防火墙是否关闭或相应端口是否开放。

1.1.8 客户端加密功能配置

云备份产品支持客户端加密传输的功能,保证客户的数据安全,加密方式为 AES-128,如有加密需求(可在《客户信息反馈表》中说明),请客户在客户端进行以下操作。

备份客户端需要生成 client 的加密秘钥口令。

[root@SH-Oracle-Server ~]# bpkeyutil Enter new NetBackup pass phrase: ******* Re-enter new NetBackup pass phrase: *******

这个加密口令很重要,要由客户自已保管。一旦口令丢失,将无法恢复数据。

注意: 秘钥信息保存在客户端的 Agent 中, 一旦客户端的 Agent 损



坏或重新安装,都会导致秘钥信息的丢失。客户必须保存好秘钥口 令。可以通过秘钥来恢复加密的数据。

1.1.9 确认 Linux 客户端是否已加密

查看 bp. conf 配置文件,如果有一行 CRYPT_KIND = STANDARD 信息,说明客户端进行了数据密码。

[root@XA-Oracle-Server ~]# cat /usr/openv/netbackup/bp.conf

SERVER = NJ-Master01

SERVER = NJ-Media01

SERVER = NJ-Media02

CLIENT_NAME = XA-Oracle-Server

CONNECT OPTIONS = localhost 1 0 2

CRYPT_KIND = STANDARD

输入加密口令后,会在/usr/openv/var/目录下生成 keyfile.dat 文件。

[root@XA-Oracle-Server ~]# Is /usr/openv/var/keyfile.dat /usr/openv/var/keyfile.dat

注意:为了保证数据正常备份,客户也可以自行备份 keyfile. dat 的密钥文件,做双重保管。

1. 1. 10 Linux 文件加密异机恢复

加密文件异机恢复有两种解决方法

• 方法 1:

找到 NBU 客户端 Agent 的安装路径:

默认路径/usr/openv/var/目录中找到 keyfile. dat 文件。此文件是密钥文件。用户必须对此文件做好备份。

一旦 Agent 有问题或异机恢复,可以把 keyfile. dat 文件恢复到/usr/openv/var/下。



• 方法 2:

[root@XA-Client01 bin]# pwd
/usr/openv/netbackup/bin
[root@XA-Client01 bin]# ./bpkeyutil
Enter new NetBackup pass phrase: *******
Re-enter new NetBackup pass phrase: ********

通过 bpkeyut i l 命令输入密码,客户一定要妥善保管。

一旦 Agent 有问题或异机恢复时,通过保管的密码,重新生成 keyfile. dat 文件。这时就可以正常的文件恢复。

- 1.1.11 常见故障及解决方案
- 1. 在出现提示: Would you like to use "SH-Oracle-Server" as the configured name of theNetBackup client? [y, n] (y) 的时候,确认客户端名称为物理主机名。
- 2. 安装完毕, 检查安装日志, 确认安装成功

[root@SH-Oracle-Server logs]#less /usr/openv/tmp/install_trace.3974 #在安装过程就能找到这个日志路径




2 安装 Windows NBU8.0 客户端

安装准备

1. 把主服务器(Master Server)和介质服务器(Media Server)的 IP 地址和主机名的对应关系都加入到客户端的(包括客户端解析)C:\Windows\System32\drivers\etc\hosts 文件中。

注意: NJ-Master01、NJ-Media01、NJ-Media02 信息添加的要和下 图一致。客户端要按客户的实际信息添加。



2. 上传 NBU 8.0 客户端软件包(请在天翼云上下载客户所需的客户端软件包)到客户端指定的路径。如以
NetBackup 8.0 Win x64 Client 为例:



解压 NetBackup_8. 0_Win_x64_Client 客户端





4. 确保网络连通并双向开通 TCP 1556、TCP 13724、TCP 13782 端口。

D:\>telnet NJ-Master01 1556
D:\>telnet NJ-Media01 1556
D:\>telnet NJ-Media02 1556
D:\>telnet NJ-Master01 13782
D:\>telnet NJ-Media01 13782
D:\>telnet NJ-Media02 13782
D:\>telnet NJ-Master01 13724
D:\>telnet NJ-Media01 13724
D:\>telnet NJ-Media02 13724
#通过 telnet 验证网络端口连接是否正常。

在客户端验证通过后,同时要通知天翼云管理员也要在服务端进行验证、验证通过后再进行客户端的安装。


安装 NBU 8.0 Client (Windows)

- 2.1.1 安装 NBU8.0 Windows Client
- 1. 解压 NetBackup_8.0_Win_x64_Client 的压缩包。双击 Setup 进行安装



2. 点击【是】, 开始安装客户端。






3. 弹出一个菜单,点击【Next】



4. 点击复选框【Agree with the Veritas Software License

Agreement】。然后【Next】






5. 点击复选框【Install to this computer only】,再点击


【Custom installNation】,然后【Next】。





6. 选择定义的目录,如:D:\Veritas





7. 点击【Next】。






8. 点击复选框 【Start NetBackup Client Service Automatically】。继续【Next】


∰Veritas HetBack	up Client
	NetBackup Options Customize your NetBackup client.
	Setup will use the following options for all new Installations of the NetBackup Client.
Welcome	At System Startup:
License Agmt	▼ Start NetBackup Client Service Automatically
Install Type	☐ Start NetBackup Client Job Tracker Automatically
▶ Options	
System Names	
Remote Hosts	Ports:
Install	BPCD Port Number: BPRD Port Number: VNETD Port Number VOPIED Port 13782 13720 13724 13783
Technical Support	
VERITAS	De <u>f</u> aults <u>B</u> ack <u>N</u> ext <u>C</u> ancel

9. 点击复选框【Local System Account】。继续【Next】






10. 写客户端的名,主服务机名及介质服务机名,继续【Next】。






11. 开始安装,点击【Install】。




12. 安装过程





13. 点击【Finish】安装完成。





-s

2.1.2 查看客户端进程

进入安装客户端的目录,如: D:\Veritas\NetBackup\bin\bpps.exe

```
管理员: C:\Tindovs\system32\cmd. exe
                                                                                _ 🗆 ×
D:\>Veritas\MetBackup\bin\bpps.exe -s
× XA-UM-SERUER
                                                            4/08/17 15:31:41.365
COMMAND
                  PID
                            LOAD
                                              TIME
                                                     MEM
dbsrv16
                          0.000%
                                         58:13.423
                                                            3/21/17 14:44:03.789
                                                      76M
                  1176
                  3292
                          0.000%
                                             0.015
                                                            4/08/17 15:27:50.485
vnetd
                                                    7.8M
bpinetd
                  5444
                          0.000%
                                             0.078
                                                     10M
                                                            4/08/17 15:27:50.500
                          0.000%
                                             0.046
                                                            4/08/17 15:27:50.594
bpcd
                  1684
                                                     11M
nbdisco
                  1104
                          0.000%
                                             0.655
                                                     27M
                                                            4/08/17 15:27:50.781
                                                            4/08/17 15:28:03.745
                  5452
                          0.000%
                                             0.031
mtstrmd
                                                    6.3M
                  4944
                                                            4/08/17 15:31:40.289
bpps
                          0.000%
                                             0.062
                                                    7.0M
D: \>_
```

2.1.3 检查客户端的连通情况

进入安装客户端的目录,如:

D:\Veritas\NetBackup\bin\bpcIntcmd.exe -pn

```
EN管理员: C:\Vindovs\system32\cmd.exe

D:\>Ueritas\NetBackup\bin\bpcIntcmd.exe -pn
expecting response from server NJ-MasterØ1
XA-UM-Server XA-UM-Server 113.141.64.151 51148

D:\>_
```

说明:如果不能连接成功,请检查防火墙是否关闭或相应端口是否 开放。

2.1.4 客户端加密功能配置

云备份产品支持客户端加密传输的功能,保证客户的数据安全,加密方式为 AES-128,如有加密需求(可在《客户信息反馈表》中说明),请客户在客户端进行以下操作。





备份客户端需要生成 client 的加密秘钥口令。

这个加密口令很重要,要由客户自已保管。一旦口令丢失,将无法恢复数据。

注意: 秘钥信息保存在客户端的 Agent 中,一旦客户端的 Agent 损坏或重新安装,都会导致秘钥信息的丢失。客户必须保存好秘钥口令。可以通过秘钥来恢复加密的数据。

2.1.5 确认 Windows 客户端是否做加密






- 2. HKEY_LOCAL_MACHINE → SOFTWARE → Veritas → NetBackup
 → CurrentVersion → Config 中查看
- 3. CRYPT_KIND 数据值为 STANDARD,表示已通过了标准的加密数据。CRYPT_OPTION 数据值为 ALLOWED,表示加密选项功能开启。



4. 客户端加密备份后,可以再注册表中看到下面的信息,确认数据已做了加密处理。



2. 1. 6 Windows 文件加密异机恢复

加密文件异机恢复有两种解决方法

• 方法 1:

找到 NBU 客户端 Agent 的安装路径:

本次客户端 Agent 安装在 D: 盘路径: D:\Veritas\NetBackup\var目录下,找到 keyfile.dat 文件。此文件是密钥文件。用户必须对此文件做好备份。

一旦 Agent 有问题或异机恢复,可以把 keyfile. dat 文件恢复到 D:\Veritas\NetBackup\var 下。

注意: 为了保证数据正常备份, 客户也可以自行备份 keyfile. dat 的



密钥文件, 做双重保管。

• 方法 2:

```
© 管理员: C:\Tindows\system32\cmd.exe - Veritas\HetBackup\bin\bpkeyutil.exe

□□ X

□□
```

通过 bpkeyut i l. exe 命令输入的密码,客户一定要妥善保管。

说明:一旦 Agent 有问题或异机恢复时,通过保管的密码,重新生成 keyfile.dat 文件。这时就可以正常的文件恢复。