

Search tutorials, courses and ebooks...



</> Coding Ground

🖺 Jobs

□ Whiteboard

X Tools

A storage class defines the scope (visibility) and life-time of variables and/or functions within a C++ Program. These specifiers precede the type that they modify. There are following storage classes, which can be used in a C++ Program

auto register static

extern

mutable

The auto Storage Class

The **auto** storage class is the default storage class for all local variables.

```
{
  int mount;
  auto int month;
}
```

The example above defines two variables with the same storage class, auto can only be used within functions, i.e., local variables.



The **register** storage class is used to define local variables that should be stored in a register instead of RAM. This means that the variable has a maximum size equal to the register size (usually one word) and can't have the unary '&' operator applied to it (as it does not have a memory location).

```
{
  register int miles;
}
```

The register should only be used for variables that require quick access such as counters. It should also be noted that defining 'register' does not mean that the variable will be stored in a register. It means that it MIGHT be stored in a register depending on hardware and implementation restrictions.

The static Storage Class

The **static** storage class instructs the compiler to keep a local variable in existence during the life-time of the program instead of creating and destroying it each time it comes into and goes out of scope. Therefore, making local variables static allows them to maintain their values between function calls.

The static modifier may also be applied to global variables. When this is done, it causes that variable's scope to be restricted to the file in which it is declared.

In C++, when static is used on a class data member, it causes only one copy of that member to be shared by all objects of its class.

```
#include <iostream>

// Function declaration
void func(void);

static int count = 10; /* Global variable */

main() {
   while(count--) {
     func();
}
```



```
// Function definition
void func( void ) {
    static int i = 5; // local static variable
    i++;
    std::cout << "i is " << i ;
    std::cout << " and count is " << count << std::endl;
}</pre>
```

When the above code is compiled and executed, it produces the following result

```
i is 6 and count is 9
i is 7 and count is 8
i is 8 and count is 7
i is 9 and count is 6
i is 10 and count is 5
i is 11 and count is 4
i is 12 and count is 3
i is 13 and count is 2
i is 14 and count is 1
i is 15 and count is 0
```

The extern Storage Class

The **extern** storage class is used to give a reference of a global variable that is visible to ALL the program files. When you use 'extern' the variable cannot be initialized as all it does is point the variable name at a storage location that has been previously defined.

When you have multiple files and you define a global variable or function, which will be used in other files also, then extern will be used in another file to give reference of defined variable or function. Just for understanding extern is used to declare a global variable or function in another file.



First File: main.cpp

```
#include <iostream>
int count ;
extern void write_extern();

main() {
   count = 5;
   write_extern();
}
```

Second File: support.cpp

```
#include <iostream>
extern int count;

void write_extern(void) {
   std::cout << "Count is " << count << std::endl;
}</pre>
```

Here, extern keyword is being used to declare count in another file. Now compile these two files as follows —

```
$g++ main.cpp support.cpp -o write
```

This will produce **write** executable program, try to execute **write** and check the result as follows –

```
$./write
5
```

The mutable Storage Class



function.

Kickstart Your Career

Get certified by completing the course

Get Started



➡ Print Page

Previous

Next

Advertisements

Tutorials Point is a leading Ed Tech company striving to provide the best learning material on technical and nontechnical subjects.







About us	Terms	Our Products

Company Terms of use Free Library

Our Team Privacy Policy Articles

Careers Refund Policy Coding Ground

Jobs Cookies Policy Certifications

Become a Teacher FAQ's Courses

Affiliates eBooks

Contact Us Corporate Training

Free Web Graphics

Contact Us

Tutorials Point India Private Limited, Incor9 Building, Kavuri Hills, Madhapur, Hyderabad, Telangana - 500081, INDIA

© Copyright 2023. All Rights Reserved.