RocketMQ集群部署

1、官网下载rocket-mq安装包

官网地址:

http://rocketmq.incubator.apache.org

linux命令行下载安装包解压:


wget http://mirror.bit.edu.cn/apache/incubator/rocketmq/4.0.0-incubating/rocketmq-all-4.0.0-incubating-bin-release.zip unzip -q rocketmq-all-4.0.0-incubating-bin-release.zip

具体操作步骤截图

```
|root@localhost rocketmq|s pwd | pw
```

2、rocketmq集群部署示意图

注意:由于机器有限,示意图展示的是双Master/Slave模式集群部署方案示意图,本文档记录的双Master模式



两台NameServer集群清单

NameServer集群

IP	PORT	作用	启动命令
172.16.150.143	9876(默认端口)	name server 1	nohup sh bin/mqnamesrv &(参考)
172.16.150.178	9876(默认端口)	name server 2	nohup sh bin/mqnamesrv &(参考)

两台BrokerServer集群清单

BrokerServer集群

IP	PORT	模式	名称	ID	启动命令
172.16.150.143	10911(默认端口)	Master	broker-a	0	nohup sh bin/mqbroker -c 配置文件 &(参考)
x.x.x.x	10911(默认端口)	Slave	broker-a	1(非零值)	nohup sh bin/mqbroker -c 配置文件 &(参考)
172.16.150.178	10911(默认端口)	Master	broker-b	0	nohup sh bin/mqbroker -c 配置文件 &(参考)
x.x.x.x	10911(默认端口)	Slave	broker-b	1(非零值)	nohup sh bin/mqbroker -c 配置文件 &(参考)

3、开始部署

(1)、分别启动两台机器上nameserver服务

172.16.150.143/172.16.150.178

[root@localhost rocketmq]# pwd

/opt/rocketmo

[root@localhost rocketmq]# Is

apache-rocketmq-all rocketmq-all-4.0.0-incubating-bin-release.zip

[root@localhost rocketmq]# cd apache-rocketmq-all/

[root@localhost apache-rocketmq-all]# Is

benchmark bin conf DISCLAIMER lib LICENSE NOTICE README.md

[root@localhost apache-rocketmq-all]# jps

13231 Jps

28863 jai

31313 Bootstrap

31278 Bootstrap

[root@localhost apache-rocketmq-all]# nohup sh bin/mqnamesrv &

[1] 13245

[root@localhost apache-rocketmq-all]# nohup: 忽略输入并把输出追加到"nohup.out"

^C

[root@localhost apache-rocketmq-all]# jps

28863 jar

31313 Bootstrap

13251 NamesryStartur

13300 Jps

31278 Bootstrap

[root@localhost apache-rocketmq-all]#

(2)、根据nameserver集群地址分别启动两台机器上brokerserver服务

172.16.150.143

编辑配置文件

/opt/rocketmq/apache-rocketmq-all/conf/2m-noslave/broker-a.properties 添加配置项

namesrvAddr=172.16.150.143:9876;172.16.150.178:9876

brokerIP1=172.16.150.143

最终内容如下

brokerClusterName=DefaultCluster brokerName=broker-a brokerId=0
deleteWhen=04
fileReservedTime=48
brokerRole=ASYNCMASTER
flushDiskType=ASYNCFLUSH
namesrvAddr=172.16.150.143:9876;172.16.150.178:9876

启动命令

[root@localhost apache-rocketmq-all]# Is benchmark bin conf DISCLAIMER lib LICENSE nohup.out NOTICE README.md [root@localhost apache-rocketmq-all]# tail -f conf/2m-noslave/broker-a.properties brokerClusterName=DefaultCluster

brokerName=broker-a

brokerld=0

deleteWhen=0

fileReservedTime=48

brokerRole=ASYNCMASTER

flushDiskType=ASYNCFLUSH

namesrvAddr=172.16.150.143:9876;172.16.150.178:9876

brokerIP1=172.16.150.143

^C

[root@localhost apache-rocketmq-all]# nohup sh bin/mqbroker -c /opt/rocketmq/apache-rocketmq-all/conf/2m-noslave/broker-a.properties

>/dev/null 2>&1 &

[1] 9514

[root@localhost apache-rocketmq-all]# jps

9521 BrokerStartup

31684 Bootstrap

9304 NamesrvStartup

9579 Jps

31391 Bootstrap

[root@localhost apache-rocketmq-all]#

172.16.150.178

编辑配置文件

/opt/rocketmq/apache-rocketmq-all/conf/2m-noslave/broker-b.properties

添加配置项

namesrvAddr=172.16.150.143:9876;172.16.150.178:9876

brokerIP1=172.16.150.178

最终内容如下

brokerClusterName=DefaultCluster

brokerName=broker-b

brokerld=0

deleteWhen=04

fileReservedTime=48

brokerRole=ASYNCMASTER

flushDiskType=ASYNCFLUSH

namesrvAddr=172.16.150.143:9876;172.16.150.178:9876

brokerIP1=172.16.150.178


启动命令

4、启动RocketMQ集群管理平台

github地址: https://github.com/leorian/rocketmq-console

项目架构是SpringBoot+Angular,只需修改src/main/resources/application.properties文件

修改配置项rocketmq.config.namesrvAddr=172.16.150.143:9876;172.16.150.178:9876



打包发布服务器

mvn clean package -Dmaven.test.skip=true

nohup sh java -jar target/rocketmq-console-ng-1.0.0.jar &



5、参考文档

CSDN-博客

http://blog.csdn.net/lovesomnus/article/details/51769977