
WikipediA

Barycentric coordinate system

In geometry, a **barycentric coordinate system** is a <u>coordinate system</u> in which the location of a point is specified by reference to a <u>simplex</u> (a <u>triangle</u> for points in a plane, a <u>tetrahedron</u> for points in <u>three-dimensional space</u>, etc.). The **barycentric coordinates** of a point can be interpreted as <u>masses</u> placed at the vertices of the simplex, such that the point is the <u>center of mass</u> (or *barycenter*) of these masses. These masses can be zero or negative; they are all positive if and only if the point is inside the simplex.

Every point has barycentric coordinates, and their sum is not zero. Two tuples of barycentric coordinates specify the same point if and only if they are proportional; that is to say, if one tuple can be obtained by multiplying the elements of the other tuple by the same non-zero number. Therefore, barycentric coordinates are either considered to be defined up to multiplication by a nonzero constant, or normalized for summing to unity.



A 3-simplex, with barycentric subdivisions of 1-faces (edges) 2-faces (triangles) and 3-faces (body).

Barycentric coordinates were introduced by <u>August Ferdinand Möbius</u> in 1827. They are special <u>homogenous coordinates</u>. Barycentric coordinates are strongly related with <u>Cartesian coordinates</u> and, more generally, to affine coordinates (see Affine space § Relationship between barycentric and affine coordinates).

Barycentric coordinates are particularly useful in <u>triangle geometry</u> for studying properties that do not depend on the angles of the triangle, such as <u>Ceva's theorem</u>. In <u>computer-aided design</u>, they are useful for defining some kinds of Bézier surfaces. [4][5]

Contents

Definition

Relationship with Cartesian or affine coordinates

Relationship with projective coordinates

Barycentric coordinates on triangles

Conversion between barycentric and Cartesian coordinates

Edge approach

Vertex approach

Conversion between barycentric and trilinear coordinates

Equations in barycentric coordinates

Distance between points

Applications

Determining location with respect to a triangle

Interpolation on a triangular unstructured grid

Integration over a triangle or tetrahedron

Examples of special points

Barycentric coordinates on tetrahedra

Generalized barycentric coordinates

Abstraction

Applications

See also

References
External links
External links

Definition

Let A_0, \ldots, A_n be n+1 points in a <u>Euclidean space</u>, a <u>flat</u> or an <u>affine space</u> \mathbf{A} of dimension n that are <u>affinely independent</u>; this means that there is no <u>affine subspace</u> of dimension n that contains all the points, or, equivalently that the points define a <u>simplex</u>. Given any point $P \in \mathbf{A}$, there are <u>scalars</u> a_0, \ldots, a_n that are not all zero, such that

$$(a_0 + \cdots + a_n)\overrightarrow{OP} = a_0\overrightarrow{OA_0} + \cdots + a_n\overrightarrow{OA_n},$$

for any point O. (As usual, the notation \overrightarrow{AB} represents the <u>translation vector</u> or <u>free vector</u> that maps the point A to the point B.)

The elements of a (n+1) tuple $(a_0:\ldots:a_n)$ that satisfies this equation are called *barycentric coordinates* of P with respect to A_0,\ldots,A_n . The use of colons in the notation of the tuple means that barycentric coordinates are a sort of <u>homogeneous coordinates</u>, that is, the point is not changed if all coordinates are multiplied by the same nonzero constant. Moreover, the barycentric coordinates are also not changed if the auxiliary point O, the origin, is changed.

The barycentric coordinates of a point are unique \underline{up} to a scaling. That is, two tuples $(a_0:\ldots:a_n)$ and $(b_0:\ldots:b_n)$ are barycentric coordinates of the same point \underline{if} and only \underline{if} there is a nonzero scalar λ such that $b_i = \lambda a_i$ for every i.

In some contexts, it is useful to make unique the barycentric coordinates of a point. This is obtained by imposing the condition

$$\sum a_i = 1,$$

or equivalently by dividing every a_i by the sum of all a_i . These specific barycentric coordinates are called **normalized** or **absolute barycentric coordinates**. Sometimes, they are also called <u>affine coordinates</u>, although this term refers commonly to a slightly different concept.

Sometimes, it is the normalized barycentric coordinates that are called *barycentric coordinates*. In this case the above defined coordinates are called *homogeneous barycentric coordinates*.

With above notation, the homogeneous barycentric coordinates of A_i are all zero, except the one of index i. When working over the <u>real numbers</u> (the above definition is also used for affine spaces over an arbitrary field), the points whose all normalized barycentric coordinates are nonnegative form the <u>convex hull</u> of $\{A_0, \ldots, A_n\}$, which is the <u>simplex</u> that has these points as its vertices.

With above notation, a tuple (a_1, \ldots, a_n) such that

$$\sum_{i=0}^n a_i = 0$$

does not define any point, but the vector

$$a_0 \overrightarrow{OA_0} + \cdots + a_n \overrightarrow{OA_n}$$

is independent from the origin O. As the direction of this vector is not changed if all a_i are multiplied by the same scalar, the homogeneous tuple $(a_0:\ldots:a_n)$ defines a direction of lines, that is a point at infinity. See below for more details.

Relationship with Cartesian or affine coordinates

Barycentric coordinates are strongly related to <u>Cartesian coordinates</u> and, more generally, <u>affine coordinates</u>. For a space of dimension n, these coordinate systems are defined relative to a point O, the <u>origin</u>, whose coordinates are zero, and n points A_1, \ldots, A_n , whose coordinates are zero except that of index i that equals one.

A point has coordinates

$$(x_1,\ldots,x_n)$$

for such a coordinate system if and only if its normalized barycentric coordinates are

$$(1-x_1-\cdots-x_n,x_1,\ldots,x_n)$$

relatively to the points O, A_1, \ldots, A_n .

The main advantage of barycentric coordinate systems is to be symmetric with respect to the n+1 defining points. They are therefore often useful for studying properties that are symmetric with respect to n+1 points. On the other hand, distances and angles are difficult to express in general barycentric coordinate systems, and when they are involved, it is generally simpler to use a Cartesian coordinate system.

Relationship with projective coordinates

Homogeneous barycentric coordinates are also strongly related with some <u>projective coordinates</u>. However this relationship is more subtle than in the case of affine coordinates, and, for being clearly understood, requires a coordinate-free definition of the projective completion of an affine space, and a definition of a projective frame.

The *projective completion* of an affine space of dimension n is a <u>projective space</u> of the same dimension that contains the affine space as the <u>complement</u> of a <u>hyperplane</u>. The projective completion is unique <u>up</u> to an <u>isomorphism</u>. The hyperplane is called the <u>hyperplane</u> at infinity, and its points are the <u>points</u> at infinity of the affine space. [7]

Given a projective space of dimension n, a projective frame is an ordered set of n+2 points that are not contained in the same hyperplane. A projective frame defines a projective coordinate system such that the coordinates of the (n+2)th point of the frame are all equal, and, otherwise, all coordinates of the ith point are zero, except the ith one. [7]

When constructing the projective completion from an affine coordinate system, one defines commonly it with respect to a projective frame consisting of the intersections with the hyperplane at infinity of the coordinate axes, the origin of the affine space, and the point that has all its affine coordinates equal to one. This implies that the points at infinity have their last coordinate equal to zero, and that the projective coordinates of a point of the affine space are obtained by completing its affine coordinates by one as (n + 1)th coordinate.

When one has n+1 points in an affine space that define a barycentric coordinate system, this is another projective frame of the projective completion that is convenient to choose. This frame consists of these points and their <u>centroid</u>, that is the point that has all its barycentric coordinates equal. In this case, the homogeneous barycentric coordinates of a point in the affine space are the same as the projective coordinates of this point. A point is at infinity if and only if the sum of its coordinates is zero. This point is in the direction of the vector defined at the end of \S Definition.

Barycentric coordinates on triangles


In the context of a <u>triangle</u>, barycentric coordinates are also known as **area coordinates** or **areal coordinates**, because the coordinates of *P* with respect to triangle *ABC* are equivalent to the (signed) ratios of the areas of *PBC*, *PCA* and *PAB* to the area of the reference triangle *ABC*. Areal and <u>trilinear coordinates</u> are used for similar purposes in geometry.

Barycentric or areal coordinates are extremely useful in engineering applications involving triangular subdomains. These make analytic <u>integrals</u> often easier to evaluate, and <u>Gaussian quadrature</u> tables are often presented in terms of area coordinates.

Consider a triangle T defined by its three vertices, $\mathbf{r_1}$, $\mathbf{r_2}$ and $\mathbf{r_3}$. Each point \mathbf{r} located inside this triangle can be written as a unique convex combination of the three vertices. In other words, for each \mathbf{r} there is a unique sequence of three numbers, $\lambda_1, \lambda_2, \lambda_3 \geq 0$ such that $\lambda_1 + \lambda_2 + \lambda_3 = 1$ and

$$\mathbf{r} = \lambda_1 \mathbf{r}_1 + \lambda_2 \mathbf{r}_2 + \lambda_3 \mathbf{r}_3,$$

The three numbers $\lambda_1, \lambda_2, \lambda_3$ indicate the "barycentric" or "area" coordinates of the point ${\bf r}$ with respect to the triangle. They are often denoted as α, β, γ instead of $\lambda_1, \lambda_2, \lambda_3$. Note that although there are three coordinates, there are only two degrees of freedom, since $\lambda_1 + \lambda_2 + \lambda_3 = 1$. Thus every point is uniquely defined by any two of the barycentric coordinates.



Barycentric coordinates $(\lambda_1, \lambda_2, \lambda_3)$ on an equilateral triangle and on a right triangle.

To explain why these coordinates are **signed ratios of areas**, let us assume that we work in the <u>Euclidean</u> space \mathbf{E}^3 . Here, consider the <u>Cartesian coordinate system</u> Oxyz and its associated <u>basis</u>, namely $\{\mathbf{i}, \mathbf{j}, \mathbf{k}\}$. Consider also the positively oriented triangle ABC lying in the Oxy plane. It is known that for any basis $\{\mathbf{e}, \mathbf{f}, \mathbf{g}\}$ of \mathbf{E}^3 and any free vector \mathbf{h} one has [8]

$$\mathbf{h} = rac{1}{(\mathbf{e}, \mathbf{f}, \mathbf{g})} \cdot \left[(\mathbf{h}, \mathbf{f}, \mathbf{g}) \mathbf{e} + (\mathbf{e}, \mathbf{h}, \mathbf{g}) \mathbf{f} + (\mathbf{e}, \mathbf{f}, \mathbf{h}) \mathbf{g}
ight],$$

where $(\mathbf{e}, \mathbf{f}, \mathbf{g}) = (\mathbf{e} \times \mathbf{f}) \cdot \mathbf{g}$ stands for the <u>mixed product</u> of these three vectors.

Take $\mathbf{e} = \overrightarrow{AB}$, $\mathbf{f} = \overrightarrow{AC}$, $\mathbf{g} = \mathbf{k}$, $\mathbf{h} = \overrightarrow{AP}$, where P is an arbitrary point in the plane Oxy, and remark that

$$(\mathbf{e},\mathbf{f},\mathbf{h}) = (\overrightarrow{AB} imes \overrightarrow{AC}) \cdot \overrightarrow{AP} = (|\overrightarrow{AB} imes \overrightarrow{AC}|\mathbf{k}) \cdot \overrightarrow{AP} = 0.$$

A subtle point regarding our choice of free vectors: \mathbf{e} is, in fact, the equipollence class of the bound vector \overrightarrow{AB} .

We have obtained that

$$\overrightarrow{AP} = m_B \cdot \overrightarrow{AB} + m_C \cdot \overrightarrow{AC}, \; ext{ where } m_B = \dfrac{(\overrightarrow{AP}, \overrightarrow{AC}, \mathbf{k})}{(\overrightarrow{AB}, \overrightarrow{AC}, \mathbf{k})}, \; m_C = \dfrac{(\overrightarrow{AB}, \overrightarrow{AP}, \mathbf{k})}{(\overrightarrow{AB}, \overrightarrow{AC}, \mathbf{k})}.$$

Given the positive (<u>counterclockwise</u>) orientation of triangle ABC, the <u>denominator</u> of both m_B and m_C is precisely the double of the area of the triangle ABC. Also,

$$(\overrightarrow{AP}, \overrightarrow{AC}, \mathbf{k}) = (\overrightarrow{PC}, \overrightarrow{PA}, \mathbf{k}) \text{ and } (\overrightarrow{AB}, \overrightarrow{AP}, \mathbf{k}) = (\overrightarrow{PA}, \overrightarrow{PB}, \mathbf{k})$$

and so the <u>numerators</u> of m_B and m_C are the doubles of the **signed areas** of triangles APC and respectively ABP.

Further, we deduce that

$$\overrightarrow{OP} = (1 - m_B - m_C) \cdot \overrightarrow{OA} + m_B \cdot \overrightarrow{OB} + m_C \cdot \overrightarrow{OC}$$

which means that the numbers $1 - m_B - m_C$, m_B and m_C are the barycentric coordinates of P. Similarly, the third barycentric coordinate reads as

$$m_A = 1 - m_B - m_C = rac{(\overrightarrow{PB}, \overrightarrow{PC}, \mathbf{k})}{(\overrightarrow{AB}, \overrightarrow{AC}, \mathbf{k})}.$$

This m-letter notation of the barycentric coordinates comes from the fact that the point P may be interpreted as the center of mass for the masses m_A , m_B , m_C which are located in A, B and C.

Switching back and forth between the barycentric coordinates and other coordinate systems makes some problems much easier to solve.

Conversion between barycentric and Cartesian coordinates

Edge approach

Given a point **r** in a triangle's plane one can obtain the barycentric coordinates λ_1 , λ_2 and λ_3 from the <u>Cartesian</u> coordinates (x, y) or vice versa.

We can write the Cartesian coordinates of the point \mathbf{r} in terms of the Cartesian components of the triangle vertices \mathbf{r}_1 , \mathbf{r}_2 , \mathbf{r}_3 where $\mathbf{r}_i = (x_i, y_i)$ and in terms of the barycentric coordinates of \mathbf{r} as

$$x = \lambda_1 x_1 + \lambda_2 x_2 + \lambda_3 x_3 \ y = \lambda_1 y_1 + \lambda_2 y_2 + \lambda_3 y_3$$

That is, the Cartesian coordinates of any point are a weighted average of the Cartesian coordinates of the triangle's vertices, with the weights being the point's barycentric coordinates summing to unity.

To find the reverse transformation, from Cartesian coordinates to barycentric coordinates, we first substitute $\lambda_3 = 1 - \lambda_1 - \lambda_2$ into the above to obtain

$$x = \lambda_1 x_1 + \lambda_2 x_2 + (1 - \lambda_1 - \lambda_2) x_3$$

 $y = \lambda_1 y_1 + \lambda_2 y_2 + (1 - \lambda_1 - \lambda_2) y_3$

Rearranging, this is

$$egin{aligned} \lambda_1(x_1-x_3) + \lambda_2(x_2-x_3) + x_3 - x &= 0 \ \lambda_1(y_1-y_3) + \lambda_2(y_2-y_3) + y_3 - y &= 0 \end{aligned}$$

This linear transformation may be written more succinctly as

$$\mathbf{T} \cdot \lambda = \mathbf{r} - \mathbf{r}_3$$

where λ is the <u>vector</u> of the first two barycentric coordinates, **r** is the <u>vector</u> of <u>Cartesian coordinates</u>, and **T** is a matrix given by

$$\mathbf{T} = egin{pmatrix} x_1 - x_3 & x_2 - x_3 \ y_1 - y_3 & y_2 - y_3 \end{pmatrix}$$

Now the matrix \mathbf{T} is invertible, since $\mathbf{r_1} - \mathbf{r_3}$ and $\mathbf{r_2} - \mathbf{r_3}$ are linearly independent (if this were not the case, then $\mathbf{r_1}$, $\mathbf{r_2}$, and $\mathbf{r_3}$ would be collinear and would not form a triangle). Thus, we can rearrange the above equation to get

$$egin{pmatrix} \lambda_1 \ \lambda_2 \end{pmatrix} = \mathbf{T}^{-1}(\mathbf{r} - \mathbf{r}_3)$$

Finding the barycentric coordinates has thus been reduced to finding the $\underline{2\times2}$ inverse matrix of **T**, an easy problem.

Explicitly, the formulae for the barycentric coordinates of point \mathbf{r} in terms of its Cartesian coordinates (x, y) and in terms of the Cartesian coordinates of the triangle's vertices are:

$$\lambda_1 = rac{(y_2 - y_3)(x - x_3) + (x_3 - x_2)(y - y_3)}{\det(T)} = rac{(y_2 - y_3)(x - x_3) + (x_3 - x_2)(y - y_3)}{(y_2 - y_3)(x_1 - x_3) + (x_3 - x_2)(y_1 - y_3)} \,, \ \lambda_2 = rac{(y_3 - y_1)(x - x_3) + (x_1 - x_3)(y - y_3)}{\det(T)} = rac{(y_3 - y_1)(x - x_3) + (x_1 - x_3)(y - y_3)}{(y_2 - y_3)(x_1 - x_3) + (x_3 - x_2)(y_1 - y_3)} \,, \ \lambda_3 = 1 - \lambda_1 - \lambda_2 \,.$$

Vertex approach

Another way to solve the conversion from Cartesian to barycentric coordinates is to write the relation in the matrix form

$$\mathbf{R}\boldsymbol{\lambda} = \mathbf{r}$$

with $\mathbf{R} = (\mathbf{r}_1 | \mathbf{r}_2 | \mathbf{r}_3)$ and $\boldsymbol{\lambda} = (\lambda_1, \lambda_2, \lambda_3)^{\top}$, i.e.

$$egin{pmatrix} egin{pmatrix} x_1 & x_2 & x_3 \ y_1 & y_2 & y_3 \end{pmatrix} egin{pmatrix} \lambda_1 \ \lambda_2 \ \lambda_3 \end{pmatrix} = egin{pmatrix} x \ y \end{pmatrix}$$

To get the unique normalized solution we need to add the condition $\lambda_1 + \lambda_2 + \lambda_3 = 1$. The barycentric coordinates are thus the solution of the linear system

$$egin{pmatrix} 1 & 1 & 1 \ x_1 & x_2 & x_3 \ y_1 & y_2 & y_3 \end{pmatrix} egin{pmatrix} \lambda_1 \ \lambda_2 \ \lambda_3 \end{pmatrix} = egin{pmatrix} 1 \ x \ y \end{pmatrix}$$

which is

$$egin{pmatrix} \lambda_1 \ \lambda_2 \ \lambda_3 \end{pmatrix} = rac{1}{2A} egin{pmatrix} x_2y_3 - x_3y_2 & y_2 - y_3 & x_3 - x_2 \ x_3y_1 - x_1y_3 & y_3 - y_1 & x_1 - x_3 \ x_1y_2 - x_2y_1 & y_1 - y_2 & x_2 - x_1 \ \end{pmatrix} egin{pmatrix} 1 \ x \ y \end{pmatrix}$$

where

$$2A = \det(1|R) = x_1(y_2-y_3) + x_2(y_3-y_1) + x_3(y_1-y_2)$$

is twice the signed area of the triangle. The area interpretation of the barycentric coordinates can be recovered by applying Cramer's rule to this linear system.

Conversion between barycentric and trilinear coordinates

A point with <u>trilinear coordinates</u> x:y:z has barycentric coordinates ax:by:cz where a,b,c are the side lengths of the <u>triangle</u>. Conversely, a point with barycentrics $\lambda_1:\lambda_2:\lambda_3$ has trilinears $\lambda_1/a:\lambda_2/b:\lambda_3/c$.

Equations in barycentric coordinates

The three sides a, b, c respectively have equations [9]

$$\lambda_1=0,\quad \lambda_2=0,\quad \lambda_3=0.$$

The equation of a triangle's Euler line is [9]

$$egin{array}{|c|c|c|c|} \lambda_1 & \lambda_2 & \lambda_3 \ 1 & 1 & 1 \ an A & an B & an C \ \end{array} = 0.$$

Using the previously given conversion between barycentric and trilinear coordinates, the various other equations given in Trilinear coordinates#Formulas can be rewritten in terms of barycentric coordinates.

Distance between points

The displacement vector of two normalized points $P=(p_1,p_2,p_3)$ and $Q=(q_1,q_2,q_3)$ is $^{[10]}$

$$\overrightarrow{PQ}=(p_1-q_1,p_2-q_2,p_3-q_3).$$

The distance d between P and Q, or the length of the displacement vector $\overrightarrow{PQ} = (x,y,z)$, is [9][10]

$$d^2 = |PQ|^2 = -a^2yz - b^2zx - c^2xy = rac{1}{2}[x^2(b^2+c^2-a^2) + y^2(c^2+a^2-b^2) + z^2(a^2+b^2-c^2)].$$

where a, b, c are the sidelengths of the triangle. The equivalence of the last two expressions follows from x+y+z=0, which holds because $x+y+z=(p_1-q_1)+(p_2-q_2)+(p_3-q_3)=(p_1+p_2+p_3)-(q_1+q_2+q_3)=1-1=0$.

The barycentric coordinates of a point can be calculated based on distances d_i to the three triangle vertices by solving the equation

$$egin{pmatrix} -c^2 & c^2 & b^2-a^2 \ -b^2 & c^2-a^2 & b^2 \ 1 & 1 & 1 \end{pmatrix} oldsymbol{\lambda} = egin{pmatrix} d_A^2-d_B^2 \ d_A^2-d_C^2 \ 1 \end{pmatrix}.$$

Applications

Determining location with respect to a triangle

Although barycentric coordinates are most commonly used to handle points inside a triangle, they can also be used to describe a point outside the triangle. If the point is not inside the triangle, then we can still use the formulas above to compute the barycentric coordinates. However, since the point is outside the triangle, at least one of the coordinates will violate our original assumption that $\lambda_{1...3} \geq 0$. In fact, given any point in cartesian coordinates, we can use this fact to determine where this point is with respect to a triangle.

If a point lies in the interior of the triangle, all of the Barycentric coordinates lie in the open interval (0,1). If a point lies on an edge of the triangle but not at a vertex, one of the area coordinates $\lambda_{1...3}$ (the one associated with the opposite vertex) is zero, while the other two lie in the open interval (0,1). If the point lies on a vertex, the coordinate associated with that vertex equals 1 and the others equal zero. Finally, if the point lies outside the triangle at least one coordinate is negative.

Summarizing,

Point **r** lies inside the triangle if and only if $0 < \lambda_i < 1 \ \forall \ i \ \text{in } 1, 2, 3$. r lies on the edge or corner of the triangle if $0 \leq \lambda_i \leq 1 \; orall \; ext{i in 1, 2, 3}$ and $\lambda_i = 0$, for some i in 1, 2, 3.

Otherwise, **r** lies outside the triangle.

Amount in 5L jug

Two solutions to the 8, 5 and 3L water pouring puzzle using a barycentric plot. The yellow area denotes combinations achievable with the jugs. The solid red and dashed blue paths show pourable transitions. When a vertex lands on the dotted triangle, 4L has been measured.

In particular, if a point lies on the opposite side of a sideline from the vertex opposite that sideline, then that point's barycentric coordinate corresponding to that vertex is negative.


Interpolation on a triangular unstructured grid

If $f(\mathbf{r}_1), f(\mathbf{r}_2), f(\mathbf{r}_3)$ are known quantities, but the values of finside the triangle defined by $\mathbf{r}_1, \mathbf{r}_2, \mathbf{r}_3$ is unknown, they can be approximated using linear interpolation. Barvcentric coordinates provide a convenient way to compute this interpolation. If **r** is a point inside the triangle with barycentric coordinates λ_1 , λ_2 , λ_3 , then

$$f(\mathbf{r})pprox \lambda_1 f(\mathbf{r}_1) + \lambda_2 f(\mathbf{r}_2) + \lambda_3 f(\mathbf{r}_3)$$

In general, given any unstructured grid or polygon mesh, this kind of technique can be used to approximate the value of f at all points, as long as the function's value is known at all vertices of the mesh. In this case, we have many triangles, each corresponding to a different part of the space. To interpolate a function f at a point \mathbf{r} , first a triangle must be found that contains r. To do so, r is transformed into the barycentric coordinates of each triangle. If some triangle is found such that the coordinates satisfy $0 \le \lambda_i \le 1 \,\forall i \text{ in } 1, 2, 3$, then the point lies in that triangle or on its edge (explained in the previous section). Then the value of $f(\mathbf{r})$ can be interpolated as described above.





Surface (upper part) obtained from linear interpolation over a given triangular grid (lower part) in the x,y plane. The surface approximates a function z=f(x,y), given only the values of f on the grid's vertices.

These methods have many applications, such as the finite element method (FEM).

Integration over a triangle or tetrahedron

The integral of a function over the domain of the triangle can be annoying to compute in a cartesian coordinate system. One generally has to split the triangle up into two halves, and great messiness follows. Instead, it is often easier to make a <u>change of variables</u> to any two barycentric coordinates, e.g. λ_1, λ_2 . Under this change of variables,

$$\int_T f(\mathbf{r}) \ d\mathbf{r} = 2A \int_0^1 \int_0^{1-\lambda_2} f(\lambda_1 \mathbf{r}_1 + \lambda_2 \mathbf{r}_2 + (1-\lambda_1-\lambda_2) \mathbf{r}_3) \ d\lambda_1 \ d\lambda_2$$

where A is the <u>area</u> of the triangle. This result follows from the fact that a rectangle in barycentric coordinates corresponds to a quadrilateral in cartesian coordinates, and the ratio of the areas of the corresponding shapes in the corresponding coordinate systems is given by 2A. Similarly, for integration over a tetrahedron, instead of breaking up the integral into two or three separate pieces, one could switch to 3D tetrahedral coordinates under the change of variables

$$\int \int_T f({f r}) \; d{f r} = 6 V \int_0^1 \int_0^{1-\lambda_3} \int_0^{1-\lambda_2-\lambda_3} f(\lambda_1 {f r}_1 + \lambda_2 {f r}_2 + \lambda_3 {f r}_3 + (1-\lambda_1-\lambda_2-\lambda_3) {f r}_4) \; d\lambda_1 \; d\lambda_2 \; d\lambda_3$$

where V is the volume of the tetrahedron.

Examples of special points

The three vertices of a triangle have barycentric coordinates 1:0:0, 0:1:0, and 0:0:1.

The centroid has barycentrics 1:1:1.

The circumcenter of a triangle ABC has barycentric coordinates [9][10][11][12]

$$a^2(-a^2+b^2+c^2): b^2(a^2-b^2+c^2): c^2(a^2+b^2-c^2)$$

$$= \sin 2A : \sin 2B : \sin 2C = (1 - \cos B \cos C) : (1 - \cos C \cos A) : (1 - \cos A \cos B).$$

where a, b, c are edge lengths BC, CA, AB respectively of the triangle.

The orthocenter has barycentric coordinates [9][10]

$$(a^2+b^2-c^2)(a^2-b^2+c^2): (-a^2+b^2+c^2)(a^2+b^2-c^2): (a^2-b^2+c^2)(-a^2+b^2+c^2)$$

$$= \tan A : \tan B : \tan C = a \cos B \cos C : b \cos C \cos A : c \cos A \cos B.$$

The incenter has barycentric coordinates [10][13]

$$a:b:c=\sin A:\sin B:\sin C$$
.

The excenters' barycentrics are [13]

$$-a:b:c$$
 $a:-b:c$ $a:b:-c$.

The nine-point center has barycentric coordinates [9][13]

$$a\cos(B-C):b\cos(C-A):c\cos(A-B)=(1+\cos B\cos C):(1+\cos C\cos A):(1+\cos A\cos B)$$

$$= [a^2(b^2+c^2) - (b^2-c^2)^2] : [b^2(c^2+a^2) - (c^2-a^2)^2] : [c^2(a^2+b^2) - (a^2-b^2)^2].$$

Barycentric coordinates on tetrahedra

Barycentric coordinates may be easily extended to three dimensions. The 3D simplex is a tetrahedron, a polyhedron having four triangular faces and four vertices. Once again, the four barycentric coordinates are defined so that the first vertex \mathbf{r}_1 maps to barycentric coordinates $\lambda = (1, 0, 0, 0), \mathbf{r}_2 \rightarrow (0, 1, 0, 0)$, etc.

This is again a linear transformation, and we may extend the above procedure for triangles to find the barycentric coordinates of a point \mathbf{r} with respect to a tetrahedron:

$$egin{pmatrix} \lambda_1 \ \lambda_2 \ \lambda_3 \end{pmatrix} = \mathbf{T}^{-1}(\mathbf{r} - \mathbf{r}_4)$$

where \mathbf{T} is now a 3×3 matrix:

$$\mathbf{T} = egin{pmatrix} x_1 - x_4 & x_2 - x_4 & x_3 - x_4 \ y_1 - y_4 & y_2 - y_4 & y_3 - y_4 \ z_1 - z_4 & z_2 - z_4 & z_3 - z_4 \end{pmatrix}$$

and $\lambda_4 = 1 - \lambda_1 - \lambda_2 - \lambda_3$ with the corresponding Cartesian coordinates:

$$x = \lambda_1 x_1 + \lambda_2 x_2 + \lambda_3 x_3 + (1 - \lambda_1 - \lambda_2 - \lambda_3) x_4$$

 $y = \lambda_1 y_1 + \lambda_2 y_2 + \lambda_3 y_3 + (1 - \lambda_1 - \lambda_2 - \lambda_3) y_4$
 $z = \lambda_1 z_1 + \lambda_2 z_2 + \lambda_3 z_3 + (1 - \lambda_1 - \lambda_2 - \lambda_3) z_4$

Once again, the problem of finding the barycentric coordinates has been reduced to inverting a 3×3 matrix. 3D barycentric coordinates may be used to decide if a point lies inside a tetrahedral volume, and to interpolate a function within a tetrahedral mesh, in an analogous manner to the 2D procedure. Tetrahedral meshes are often used in finite element analysis because the use of barycentric coordinates can greatly simplify 3D interpolation.

Generalized barycentric coordinates

Barycentric coordinates $(\lambda_1, \lambda_2, \dots, \lambda_k)$ of a point $p \in \mathbb{R}^n$ that are defined with respect to a finite set of k points $x_1, x_2, \dots, x_k \in \mathbb{R}^n$ instead of a <u>simplex</u> are called **generalized barycentric coordinates**. For these, the equation

$$(\lambda_1+\lambda_2+\cdots+\lambda_k)p=\lambda_1x_1+\lambda_2x_2+\cdots+\lambda_kx_k$$

is still required to hold. Usually one uses normalized coordinates, $\lambda_1 + \lambda_2 + \cdots + \lambda_k = 1$. As for the case of a simplex, the points with nonnegative normalized generalized coordinates $(0 \le \lambda_i \le 1)$ form the <u>convex hull</u> of $x_1, ..., x_n$. If there are more points than in a full simplex (k > n + 1) the generalized barycentric coordinates of a point are *not* unique, as the defining linear system (here for n=2)

$$egin{pmatrix} 1 & 1 & 1 & \dots \ x_1 & x_2 & x_3 & \dots \ y_1 & y_2 & y_3 & \dots \end{pmatrix} egin{pmatrix} \lambda_1 \ \lambda_2 \ \lambda_3 \ dots \end{pmatrix} = egin{pmatrix} 1 \ x \ y \end{pmatrix}$$

is <u>underdetermined</u>. The simplest example is a <u>quadrilateral</u> in the plane. Various kinds of additional restrictions can be used to define unique barycentric coordinates. [14]

Abstraction

More abstractly, generalized barycentric coordinates express a convex polytope with n vertices, regardless of dimension, as the *image* of the standard (n-1)-simplex, which has n vertices – the map is onto: $\Delta^{n-1} \rightarrow P$. The map is one-to-one if and only if the polytope is a simplex, in which case the map is an isomorphism; this corresponds to a point not having *unique* generalized barycentric coordinates except when P is a simplex.

<u>Dual</u> to generalized barycentric coordinates are <u>slack variables</u>, which measure by how much margin a point satisfies the linear constraints, and gives an <u>embedding</u> $P \hookrightarrow (\mathbf{R}_{\geq 0})^f$ into the f-orthant, where f is the number of faces (dual to the vertices). This map is one-to-one (slack variables are uniquely determined) but not onto (not all combinations can be realized).

This use of the standard (n-1)-simplex and f-orthant as standard objects that map to a polytope or that a polytope maps into should be contrasted with the use of the standard vector space K^n as the standard object for vector spaces, and the standard <u>affine hyperplane</u> $\{(x_0,\ldots,x_n)\mid \sum x_i=1\}\subset K^{n+1}$ as the standard object for affine spaces, where in each case choosing a <u>linear basis</u> or <u>affine basis</u> provides an *isomorphism*, allowing all vector spaces and affine spaces to be thought of in terms of these standard spaces, rather than an onto or one-to-one map (not every polytope is a simplex). Further, the n-orthant is the standard object that maps to cones.

Applications

Generalized barycentric coordinates have applications in <u>computer graphics</u> and more specifically in <u>geometric modelling</u>. Often, a three-dimensional model can be approximated by a polyhedron such that the generalized barycentric coordinates with respect to that polyhedron have a geometric meaning. In this way, the processing of the model can be simplified by using these meaningful coordinates. Barycentric coordinates are also used in geophysics [15]

See also

- Ternary plot
- Convex combination

References

- 1. August Ferdinand Möbius: Der barycentrische Calcul, Verlag von Johann Ambrosius Barth, Leipzig, 1827.
- 2. Max Koecher, Aloys Krieg: Ebene Geometrie. Springer-Verlag, Berlin 2007, ISBN 978-3-540-49328-0, S. 76.
- 3. Hille, Einar. "Analytic Function Theory, Volume I", Second edition, fifth printing. Chelsea Publishing Company, New York, 1982, ISBN 0-8284-0269-8, page 33, footnote 1
- 4. Josef Hoschek, Dieter Lasser: *Grundlagen der geometrischen Datenverarbeitung*. Teubner-Verlag, 1989, ISBN 3-519-02962-6, S. 243.
- 5. Gerald Farin: Curves and Surfeces for Computer Aided Geometric Design. Academic Press, 1990, ISBN 0-12-249051-7, S. 20.
- 6. Deaux, Roland. "Introduction to The Geometry of Complex Numbers". Dover Publications, Inc., Mineola, 2008, ISBN 978-0-486-46629-3, page 61
- 7. Berger, Marcel (1987), Geometry I, Berlin: Springer, ISBN 3-540-11658-3
- 8. Danby, J.M.A. "Fundamentals of Celestial Mechanics", Second edition, revised & enlarged, fifth printing. Willmann-Bell, Inc., Richmond, 2003, ISBN 0-943396-20-4, page 26, problem 11
- 9. Scott, J. A. "Some examples of the use of areal coordinates in triangle geometry", *Mathematical Gazette* 83, November 1999, 472–477.
- 10. Schindler, Max; Chen, Evan (July 13, 2012). "Barycentric Coordinates in Olympiad Geometry" (https://www.mit.edu/~evanchen/handouts/bary/bary-full.pdf) (PDF). Retrieved 14 January 2016.

- 11. Clark Kimberling's Encyclopedia of Triangles "Encyclopedia of Triangle Centers" (https://web.archive.org/web/20120419171900/http://faculty.evansville.edu/ck6/encyclopedia/ETC.html). Archived from the original (http://faculty.evansville.edu/ck6/encyclopedia/ETC.html) on 2012-04-19. Retrieved 2012-06-02.
- 12. Wolfram page on barycentric coordinates (http://mathworld.wolfram.com/BarycentricCoordinates.html)
- 13. Dasari Naga, Vijay Krishna, "On the Feuerbach triangle", *Forum Geometricorum* 17 (2017), 289–300: p. 289. http://forumgeom.fau.edu/FG2017volume17/FG201731.pdf
- 14. Floater, Michael S. (2015). "Generalized barycentric coordinates and applications *" (https://www.mn.uio.no/math/english/people/aca/michaelf/papers/gbc.pdf) (PDF). *Acta Numerica*. **24**: 161–214. doi:10.1017/S0962492914000129 (https://doi.org/10.1017%2FS0962492914000129). ISSN 0962-4929 (https://www.worldcat.org/issn/0962-4929).
- 15. ONUFRIEV, VG; DENISIK, SA; FERRONSKY, VI, BARICENTRIC MODELS IN ISOTOPE STUDIES OF NATURAL-WATERS. NUCLEAR GEOPHYSICS, 4, 111-117 (1990)
 - Scott, J. A. Some examples of the use of areal coordinates in triangle geometry, Mathematical Gazette 83, November 1999, 472–477.
- Schindler, Max; Chen, Evan (July 13, 2012). *Barycentric Coordinates in Olympiad Geometry* (PDF). Retrieved 14 January 2016.
- Clark Kimberling's Encyclopedia of Triangles *Encyclopedia of Triangle Centers*. Archived from the original on 2012-04-19. Retrieved 2012-06-02.
- Bradley, Christopher J. (2007). *The Algebra of Geometry: Cartesian, Areal and Projective Co-ordinates*. Bath: Highperception. ISBN 978-1-906338-00-8.
- Coxeter, H.S.M. (1969). Introduction to geometry (https://archive.org/details/introductiontoge00coxe)
 (2nd ed.). John Wiley and Sons. pp. 216 (https://archive.org/details/introductiontoge00coxe/page/n233)–
 221. ISBN 978-0-471-50458-0. Zbl 0181.48101 (https://zbmath.org/?format=complete&q=an:0181.48101).
- Barycentric Calculus In Euclidean And Hyperbolic Geometry: A Comparative Introduction (https://web.archive.org/web/20120519111614/http://www.worldscibooks.com/mathematics/7740.html), Abraham Ungar, World Scientific, 2010
- Hyperbolic Barycentric Coordinates (http://ajmaa.org/searchroot/files/pdf/v6n1/v6i1p18.pdf), Abraham A.
 Ungar, The Australian Journal of Mathematical Analysis and Applications, Vol.6, No.1, Article 18, pp. 1–35, 2009
- Weisstein, Eric W. "Areal Coordinates" (https://mathworld.wolfram.com/ArealCoordinates.html). MathWorld.
- Weisstein, Eric W. "Barycentric Coordinates" (https://mathworld.wolfram.com/BarycentricCoordinates.html). MathWorld.
- Barycentric coordinates computation in homogeneous coordinates (http://www.sciencedirect.com/science/art icle/pii/S009784930700180X), Vaclav Skala, Computers and Graphics, Vol.32, No.1, pp. 120–127, 2008

External links

Law of the lever (https://www.math.nyu.edu/~crorres/Archimedes/Lever/LeverLaw.html)

External links

- The uses of homogeneous barycentric coordinates in plane euclidean geometry (http://www.matematicas.un am.mx/gfgf/ga20071/data/material/barycentricpaper.pdf)
- Barycentric Coordinates (http://www.inf.usi.ch/hormann/barycentric/) a collection of scientific papers about (generalized) barycentric coordinates
- Barycentric coordinates: A Curious Application (http://www.cut-the-knot.org/triangle/glasses.shtml) (solving the "three glasses" problem) at cut-the-knot
- Accurate point in triangle test (http://totologic.blogspot.fr/2014/01/accurate-point-in-triangle-test.html)
- Barycentric Coordinates in Olympiad Geometry (http://www.artofproblemsolving.com/Forum/viewtopic.php?f =721&t=475427) by Evan Chen and Max Schindler
- Barycenter command (https://www.geogebra.org/wiki/en/Barycenter_Command) and <u>TriangleCurve</u> command (https://www.geogebra.org/wiki/en/TriangleCurve Command) at Geogebra.

Retrieved from "https://en.wikipedia.org/w/index.php?title=Barycentric_coordinate_system&oldid=1064042643"

This page was last edited on 6 January 2022, at 08:10 (UTC).

Text is available under the Creative Commons Attribution-ShareAlike License 3.0; additional terms may apply. By using this site, you agree to the Terms of Use and Privacy Policy. Wikipedia® is a registered trademark of the Wikimedia Foundation, Inc., a non-profit organization.