General Second-Order Runge-Kutta — Forced Oscillation

Done in class, February 4, 2025

This is the fifth notebook for you to finish in-class. A synonym for forced oscillation is "driven oscillation."

Forced Oscillation

Problem Description

```
in[24]:= omega1 = 1;
    externalForce[t_] := 100 Sin[omega1 t]
    springConstant = 20;
    dampingConstant = 1;
    force[t_, x_, v_] := -springConstant x - dampingConstant v + externalForce[t]
    mass = 5;
    a[t_, x_, v_] := force[t, x, v] / mass;
    tInitial = 0;
    tFinal = 100;
    steps = 25000;
    deltaT = (tFinal - tInitial) / steps;
```

Initial Conditions

Let's let the spring be initially unstretched with no velocity and see what the external force does to it:

```
In[35]:= xInitial = 0.0;
    vInitial = 0.0;
    (* We also want to be able to visualize the external force,
    so let's tack it on to the quantities that will be tabulated by NestList *)
    initialConditions =
        {tInitial, xInitial, vInitial, externalForce[xInitial] / springConstant};
```

General Second-Order Runge-Kutta — Implementation

The implementation will be almost the same as in the damped oscillation notebook you completed on Friday.

There are only a few small things that have to be changed. Figure out what they are and then if you still have that code handy, you can almost completely re-use what you did in that notebook. Or just write it out again. The more times you write it out, the better you will remember it.

```
\alpha = 1; (* I am going to switch to nicer typography for the Greek letter alpha,
here and you should too. You will see my reason in the next class;
we are running out of common letters and I will want to re-use some. *)
rungeKutta2[cc_] := (
  (* Extract time, position, and velocity from the list *)
  curTime = cc[1];
  (* Compute tStar, xStar, vStar *)
  tStar = curTime + \alpha deltaT;
  (* General Second-Order Runge-Kutta *)
  newTime = curTime + deltaT;
  (* We are keeping track of the contribution
   to the acceleration due to the external force *)
  {newTime, newPosition, newVelocity, externalForce[newTime]/springConstant}
 )
```

Displaying Forced Oscillation

Nest the procedure and then transpose the results to produce position and velocity plots:

```
In[40]:= rk2Results = NestList[rungeKutta2, initialConditions, steps];
     rk2ResultsTransposed = Transpose[rk2Results];
     positionPlot = ListPlot[Transpose[rk2ResultsTransposed[[{1, 2}]]]]
In[42]:= positions = rk2ResultsTransposed[[2]];
     forces = rk2ResultsTransposed[4];
     Animate[NumberLinePlot[{positions[step]], forces[step]]}, PlotRange → {-50, 50}],
      {step, 0, steps, 1}, DefaultDuration → 20]
```

Conclusion / Commentary

Our oscillator now has the force law F(x) = -20 x - v and in addition a sinusoidal external driving force.

You will remember that in the conclusion of the previous notebook I defined ω_0 and γ . We also have the driving frequency omega1. Now you see why I put the subscript "0" on ω in the previous notebook. We now have three relevant frequencies in the damped, driven harmonic oscillator, and a fourth one which is derived from the other three, and we need to keep them all straight:

```
the external or driving frequency
\omega_1
\omega_0
             the natural frequency of the oscillator in the absence of damping
             the frequency that controls the rate of decay of the exponential
             the frequency of the oscillator including damping (which slows it down a little)
```

There is enough complexity in this system that it provides a lot to play around with. Once you all have it working, we'll adjust the input parameters to get other values for the frequencies.

Epilog — Resonance

Let's display all four of the important frequencies for easy comparison:

```
In[45]:= omega0 = Sqrt[springConstant/mass];
         gamma = dampingConstant / (2 mass);
         {omega1, omega0, gamma, Sqrt[omega0<sup>2</sup>-gamma<sup>2</sup>]}
Out[47]=
         \left\{1, 2, \frac{1}{10}, \frac{\sqrt{399}}{10}\right\}
```

At minimum, one of the things we should do as part of playing around with this system is just to jack up ω_1 so that it is almost as large as ω_0 . For example $\omega_1 = 1.8$ is good to try. That is "just below resonance."

Then put ω_1 right on resonance (in the absence of damping): $\omega_1 = 2$. When the system is driven very near resonance, it oscillates widely. It will help to make a smoother and easier-to-contemplate animation to jack up the number of steps to 50 000 and also to slow the animation duration down by doubling the animation duration: **DefaultDuration** \rightarrow 40.

Then we should try ω_1 = 2.2. That is "just above resonance."

Seeing real systems being driven near resonance was the traditional way of showing what a modern notebook like this shows before computer simulations reduced the popularity of real lecture demonstrations. I still find seeing videos of real systems helpful: https://youtu.be/aZNnwQ8HJHU.