Signals Reference

This page references **all available signals** that you can listen to, triggered by ("Public") Repository API in eZ Platform.

For more information, check the SignalSlot section and the Listening to Core events recipe.

All signals are relative to eZ\Publish\Core\SignalSlot\Signal namespace.

Transactions

Signals are sent after transactions are executed, making signals transaction safe.

In this topic:

- ContentService
- ContentTypeService
- LanguageService
- LocationService
- ObjectStateService
- RoleService
- SectionService
- TrashService
- URLAliasService
- URLWildcardService
- UserService

ContentService

Signal type	Properties	Triggered by	When
ContentService\Add RelationSignal	srcContentId (so urce contentId, aka referrer) srcVersionNo dstContentId (d estination contentId, aka target)	ContentService::ad dRelation()	After
ContentService\Add TranslationInfoSig nal	N/A	ContentService::ad dTranslationInfo()	After
ContentService\Cop yContentSignal	srcContentId (or iginal content ID) srcVersionNo dstContentId (contentId of the copy) dstVersionNo dstParentLocationId (locationId where the content has been copied)	ContentService::co pyContent()	After
ContentService\Cre ateContentDraftSig nal	contentId versionNo userId (Id of user used to create the draft, or null - current user)	<pre>ContentService::cr eateContentDraft()</pre>	After
ContentService\Cre ateContentSignal	• contentId • versionNo	ContentService::cr eateContent()	After
ContentService\Del eteContentSignal	• contentId	ContentService::de leteContent()	After
ContentService\Del eteRelationSignal	• srcContentId • srcVersionNo • dstContentId	ContentService::de leteRelation()	After
ContentService\Del eteVersionSignal	• contentId • versionNo	ContentService::de leteVersion()	After
ContentService\Pub lishVersionSignal	• contentId • versionNo	ContentService:: publishVersion()	After
ContentService\Tra nslateVersionSigna l	• contentId • versionNo • userId	ContentService::tr anslationVersion()	After

ContentService\Upd ateContentMetadata Signal	• contentId	ContentService::up dateContentMetadat a()	After
ContentService\Upd ateContentSignal	• contentId • versionNo	ContentService::up dateContent()	After

ContentTypeService

Signal type	Properties	Triggered by	When
ContentTypeService \AddFieldDefinitio nSignal	contentTypeDraftId	ContentTypeService ::addFieldDefiniti on()	After
ContentTypeService \AssignContentType GroupSignal	• contentTypeId • contentTypeGro upId	ContentTypeService ::assignContentTyp eGroup()	After
ContentTypeService \CopyContentTypeSignal	• contentTypeId • userId	ContentTypeService ::copyContentType()	After
ContentTypeService \CreateContentType DraftSignal	• contentTypeId	ContentTypeService ::createContentTyp eDraft()	After
ContentTypeService \CreateContentType GroupSignal	• groupId	ContentTypeService ::createContentTyp eGroup()	After
ContentTypeService \CreateContentType Signal	• contentTypeId	ContentTypeService ::createContentTyp e()	After
ContentTypeService \DeleteContentType GroupSignal	• contentTypeGro upId	ContentTypeService ::deleteContentTyp eGroup()	After
ContentTypeService \DeleteContentType Signal	• contentTypeId	ContentTypeService ::deleteContentTyp e()	After
ContentTypeService \PublishContentTyp eDraftSignal	• contentTypeDra ftId	ContentTypeService ::publishContentTy peDraft()	After
ContentTypeService \RemoveFieldDefini tionSignal	• contentTypeDra ftId • fieldDefinitio nId	ContentTypeService ::removeFieldDefin ition()	After
ContentTypeService \UnassignContentTy peGroupSignal	contentTypeIdcontentTypeGroupId	ContentTypeService ::unassignContentT ypeGroup()	After
ContentTypeService \UpdateContentType DraftSignal	• contentTypeDra ftId	ContentTypeService ::updateContentTyp eDraft()	After
ContentTypeService \UpdateContentType GroupSignal	• contentTypeGro upId	ContentTypeService ::updateContentTyp eGroup()	After
ContentTypeService \UpdateFieldDefini tionSignal	• contentTypeDra ftId • fieldDefinitio nId	ContentTypeService ::updateFieldDefin ition()	After

LanguageService

Signal type	Properties	Triggered by	When
LanguageService\Cr eateLanguageSignal	• languageId	LanguageService::c reateLanguage()	After

LanguageService\De leteLanguageSignal	• languageId	LanguageService::d eleteLanguage()	After
LanguageService\Di sableLanguageSigna l	• languageId	LanguageService::d isableLanguage()	After
LanguageService\En ableLanguageSignal	• languageId	LanguageService::e nableLanguage()	After
LanguageService\Up dateLanguageNameSi gnal	• languageId • newName	LanguageService::u pdateLanguageName()	After

LocationService

Signal type	Properties	Triggered by	When
LocationService\Co pySubtreeSignal	subtreeId (top locationId of the subtree to be copied) targetParentLo cationId	LocationService::c opySubtree()	After
LocationService\Cr eateLocationSignal	• contentId • locationId	LocationService::c reateLocation()	After
LocationService\De leteLocationSignal	• contentId • locationId	LocationService::d eleteLocation()	After
LocationService\Hi deLocationSignal	• contentId • locationId	LocationService::h ideLocation()	After
LocationService\Un hideLocationSignal	• contentId • locationId	LocationService::u nhideLocation()	After
LocationService\Mo veSubtreeSignal	• subtreeId • newParentLocat ionId	LocationService::m oveSubtree()	After
LocationService\Sw apLocationSignal	• content1Id • location1Id • content2Id • location2Id	LocationService::s wapLocation()	After
LocationService\Up dateLocationSignal	• contentId • locationId	LocationService::u pdateLocation()	After

ObjectStateService

Signal type	Properties	Triggered by	When
ObjectStateService \CreateObjectState GroupSignal	• objectStateGro upId	ObjectStateService ::createObjectStat eGroup()	After
ObjectStateService \CreateObjectState Signal	• objectStateGro upId • objectStateId	ObjectStateService ::createObjectStat e()	After
ObjectStateService \DeleteObjectState GroupSignal	• objectStateGro upId	ObjectStateService ::deleteObjectStat eGroup()	After
ObjectStateService \DeleteObjectState Signal	• objectStateId	ObjectStateService ::deleteObjectStat e()	After
ObjectStateService \SetContentStateSi gnal	• contentId • objectStateGro upId • objectStateId	ObjectStateService ::setContentState()	After
ObjectStateService \SetPriorityOfObje ctStateSignal	• objectStateId • priority	ObjectStateService ::setPriorityOfObj ectState()	After

ObjectStateService \UpdateObjectState GroupSignal	• objectStateGro upId	ObjectStateService ::updateObjectStat eGroup()	After
ObjectStateService \UpdateObjectState Signal	• objectStateId	ObjectStateService ::updateObjectStat e()	After

RoleService

Signal type	Properties	Triggered by	When
RoleService\AddPol icySignal	roleIdpolicyId	RoleService::addPo	After
RoleService\Assign RoleToUserGroupSig nal	• roleId • userGroupId • roleLimitation	RoleService::assig nRoleToUserGroup()	After
RoleService\Assign RoleToUserSignal	• roleId • userId • roleLimitation	RoleService::assig nRoleToUser()	After
RoleService\Create RoleSignal	• roleId	RoleService::creat eRole()	After
RoleService\Delete RoleSignal	• roleId	RoleService::delet eRole()	After
RoleService\Remove PolicySignal	roleIdpolicyId	RoleService::remov ePolicy()	After
RoleService\Unassi gnRoleFromUserGrou pSignal	• roleId • userGroupId	RoleService::unass ignRoleFromUserGro up()	After
RoleService\Unassi gnRoleFromUserSign al	• roleId • userId	RoleService::unassignRoleFromUser()	After
RoleService\Update PolicySignal	• policyId	RoleService::updat ePolicy()	After
RoleService\Update RoleSignal	• roleId	RoleService::updat eRole()	After

SectionService

Signal type	Properties	Triggered by	When
SectionService\Ass ignSectionSignal	• contentId • sectionId	SectionService::as signSection()	After
SectionService\Cre ateSectionSignal	• sectionId	SectionService::cr eateSection()	After
SectionService\Del eteSectionSignal	• sectionId	SectionService::de leteSection()	After
SectionService\Upd ateSectionSignal	• sectionId	SectionService::up dateSection()	After

TrashService

Signal type	Properties	Triggered by	When
TrashService\Delet eTrashItemSignal	• trashItemId	TrashService::dele teTrashItem()	After
TrashService\Empty TrashSignal	N/A	TrashService::empt yTrash()	After

TrashService\Recov erSignal	trashItemIdnewParentLocat ionIdnewLocationId	TrashService::reco ver()	After
TrashService\Trash Signal	• locationId	TrashService::tras	After

URLAliasService

Signal type	Properties	Triggered by	When
URLAliasService\Cr eateGlobalUrlAlias Signal	• urlAliasId	URLAliasService::c reateGlobalUrlAlia s()	After
URLAliasService\Cr eateUrlAliasSignal	• urlAliasId	URLAliasService::c reateUrlAlias()	After
URLAliasService\Re moveAliasesSignal	• aliasList	URLAliasService::r emoveAliases()	After

URLWildcardService

Signal type	Properties	Triggered by	When
URLWildcardService \CreateSignal	• urlWildcardId	URLWildcardService ::create()	After
URLWildcardService \RemoveSignal	• urlWildcardId	URLWildcardService ::remove()	After
URLWildcardService \TranslateSignal	• url	URLWildcardService ::translate()	After

UserService

Signal type	Properties	Triggered by	When
UserService\Assign UserToUserGroupSig nal	• userId • userGroupId	UserService::assig nUserToUserGroup()	After
UserService\Create UserGroupSignal	• userGroupId	UserService::creat eUserGroup()	After
UserService\Create UserSignal	• userId	UserService::creat eUser()	After
UserService\Delete UserGroupSignal	• userGroupId	UserService::delet eUserGroup()	After
UserService\Delete UserSignal	• userId	UserService::delet eUser()	After
UserService\MoveUs erGroupSignal	userGroupIdnewParentId	UserService::moveU serGroup()	After
UserService\UnAssi gnUserFromUserGrou pSignal	• userId • userGroupId	UserService::unAss ignUserFromUserGro up()	After
UserService\Update UserGroupSignal	• userGroupId	UserService::updat eUserGroup()	After
UserService\Update UserSignal	• userId	UserService::updat eUser()	After