Signals reference

This page references all available signals, triggered by Public API, you can listen to.



For more information, check SignalSlot documentation and the cookbook recipe on how to listen to signals.

Signals are ordered by Repository service:

- ContentService
- ContentTypeService
- LanguageService
- LocationService
- ObjectStateService
- RoleService
- SectionService
- TrashService
- URLAliasService
- URLWildcardService
- UserService



All signals are relative to eZ\Publish\Core\SignalSlot\Signal namespace.

ContentService

Signal type	Properties	Triggered by	When
ContentService\AddRelati onSignal	srcContentId (source contentId, aka referrer) srcVersionNo dstContentId (destination contentId, aka target)	ContentService::addRelation()	After
ContentService\AddTransl ationInfoSignal	N/A	ContentService::addTrans lationInfo()	After
ContentService\CopyConte ntSignal	 srcContentId (original content ID) srcVersionNo dstContentId (contentId of the copy) dstVersionNo dstParentLocationId (I ocationId where the content has been copied) 	ContentService::copyContent()	After
ContentService\CreateCon tentDraftSignal	contentId versionNo userId (Id of user used to create the draft, or null - current user)	ContentService::createContentDraft()	After
ContentService\CreateCon tentSignal	• contentId • versionNo	ContentService::createContent()	After
ContentService\DeleteCon tentSignal	• contentId	ContentService::deleteContent()	After
ContentService\DeleteRel ationSignal	• srcContentId • srcVersionNo • dstContentId	ContentService::deleteRe lation()	After
ContentService\DeleteVer sionSignal	• contentId • versionNo	ContentService::deleteVe rsion()	After

ContentService\PublishVe rsionSignal	• contentId • versionNo	ContentService: publishVersion()	After
ContentService\Translate VersionSignal	• contentId • versionNo • userId	ContentService::translat ionVersion()	After
ContentService\UpdateCon tentMetadataSignal	• contentId	ContentService::updateContentMetadata()	After
ContentService\UpdateCon tentSignal	• contentId • versionNo	ContentService::updateContent()	After

ContentTypeService

Signal type	Properties	Triggered by	When
ContentTypeService\AddFi eldDefinitionSignal	• contentTypeDraftId	ContentTypeService::addF ieldDefinition()	After
ContentTypeService\Assig nContentTypeGroupSignal	• contentTypeId • contentTypeGroupId	ContentTypeService::assi gnContentTypeGroup()	After
ContentTypeService\CopyC ontentTypeSignal	• contentTypeId • userId	ContentTypeService::copy ContentType()	After
ContentTypeService\Creat eContentTypeDraftSignal	• contentTypeId	ContentTypeService::crea teContentTypeDraft()	After
ContentTypeService\Creat eContentTypeGroupSignal	• groupId	ContentTypeService::crea teContentTypeGroup()	After
ContentTypeService\Creat eContentTypeSignal	• contentTypeId	ContentTypeService::crea teContentType()	After
ContentTypeService\Delet eContentTypeGroupSignal	• contentTypeGroupId	ContentTypeService::dele teContentTypeGroup()	After
ContentTypeService\Delet eContentTypeSignal	• contentTypeId	ContentTypeService::dele teContentType()	After
ContentTypeService\Publi shContentTypeDraftSignal	• contentTypeDraftId	ContentTypeService::publ ishContentTypeDraft()	After
ContentTypeService\Remov eFieldDefinitionSignal	• contentTypeDraftId • fieldDefinitionId	ContentTypeService::remo veFieldDefinition()	After
ContentTypeService\UnassignContentTypeGroupSigna	• contentTypeId • contentTypeGroupId	ContentTypeService::unas signContentTypeGroup()	After
ContentTypeService\Updat eContentTypeDraftSignal	• contentTypeDraftId	ContentTypeService::upda teContentTypeDraft()	After
ContentTypeService\Updat eContentTypeGroupSignal	• contentTypeGroupId	ContentTypeService::upda teContentTypeGroup()	After
ContentTypeService\Updat eFieldDefinitionSignal	• contentTypeDraftId • fieldDefinitionId	ContentTypeService::upda teFieldDefinition()	After

LanguageService

Signal type	Properties	Triggered by	When
LanguageService\CreateLa nguageSignal	• languageId	LanguageService::createL anguage()	After
LanguageService\DeleteLa nguageSignal	• languageId	LanguageService::deleteL anguage()	After

LanguageService\DisableL anguageSignal	• languageId	LanguageService::disable Language()	After
LanguageService\EnableLa nguageSignal	• languageId	LanguageService::enableL anguage()	After
LanguageService\UpdateLa nguageNameSignal	• languageId • newName	LanguageService::updateL anguageName()	After

LocationService

Signal type	Properties	Triggered by	When
LocationService\CopySubt reeSignal	 subtreeId (top locationId of the subtree to be copied) targetParentLocationI d 	LocationService::copySub tree()	After
LocationService\CreateLo cationSignal	• contentId • locationId	LocationService::createL ocation()	After
LocationService\DeleteLo cationSignal	• contentId • locationId	LocationService::deleteLocation()	After
LocationService\HideLoca tionSignal	• contentId • locationId	LocationService::hideLoc ation()	After
LocationService\UnhideLo cationSignal	• contentId • locationId	LocationService::unhideLocation()	After
LocationService\MoveSubt reeSignal	• subtreeId • newParentLocationId	LocationService::moveSub tree()	After
LocationService\SwapLoca tionSignal	• content1Id • location1Id • content2Id • location2Id	LocationService::swapLoc ation()	After
LocationService\UpdateLo cationSignal	• contentId • locationId	LocationService::updateL ocation()	After

ObjectStateService

Signal type	Properties	Triggered by	When
ObjectStateService\Creat eObjectStateGroupSignal	• objectStateGroupId	ObjectStateService::crea teObjectStateGroup()	After
ObjectStateService\Creat eObjectStateSignal	• objectStateGroupId • objectStateId	ObjectStateService::crea teObjectState()	After
ObjectStateService\Delet eObjectStateGroupSignal	• objectStateGroupId	ObjectStateService::dele teObjectStateGroup()	After
ObjectStateService\Delet eObjectStateSignal	• objectStateId	ObjectStateService::dele teObjectState()	After
ObjectStateService\SetCo ntentStateSignal	contentIdobjectStateGroupIdobjectStateId	ObjectStateService::setC ontentState()	After
ObjectStateService\SetPr iorityOfObjectStateSigna 1	• objectStateId • priority	ObjectStateService::setPriorityOfObjectState()	After
ObjectStateService\Updat eObjectStateGroupSignal	• objectStateGroupId	ObjectStateService::upda teObjectStateGroup()	After

ObjectStateService\Updat	• objectStateId	ObjectStateService::upda	After
eObjectStateSignal		teObjectState()	

RoleService

Signal type	Properties	Triggered by	When
RoleService\AddPolicySig nal	• roleId • policyId	RoleService::addPolicy()	After
RoleService\AssignRoleTo UserGroupSignal	roleIduserGroupIdroleLimitation	RoleService::assignRoleT oUserGroup()	After
RoleService\AssignRoleTo UserSignal	• roleId • userId • roleLimitation	RoleService::assignRoleT oUser()	After
RoleService\CreateRoleSi	• roleId	RoleService::createRole(After
RoleService\DeleteRoleSi gnal	• roleId	RoleService::deleteRole(After
RoleService\RemovePolicy Signal	• roleId • policyId	RoleService::removePolic y()	After
RoleService\UnassignRole FromUserGroupSignal	• roleId • userGroupId	RoleService::unassignRol eFromUserGroup()	After
RoleService\UnassignRole FromUserSignal	• roleId • userId	RoleService::unassignRol eFromUser()	After
RoleService\UpdatePolicy Signal	• policyId	RoleService::updatePolic y()	After
RoleService\UpdateRoleSi gnal	• roleId	RoleService::updateRole(After

SectionService

Signal type	Properties	Triggered by	When
SectionService\AssignSec tionSignal	• contentId • sectionId	SectionService::assignSection()	After
SectionService\CreateSec tionSignal	• sectionId	SectionService::createSe ction()	After
SectionService\DeleteSec tionSignal	• sectionId	SectionService::deleteSe ction()	After
SectionService\UpdateSec tionSignal	• sectionId	SectionService::updateSe ction()	After

TrashService

Signal type	Properties	Triggered by	When
TrashService\DeleteTrash ItemSignal	• trashItemId	TrashService::deleteTras hItem()	After
TrashService\EmptyTrashS ignal	N/A	TrashService::emptyTrash	After

TrashService\RecoverSign al	trashItemIdnewParentLocationIdnewLocationId	TrashService::recover()	After
TrashService\TrashSignal	• locationId	TrashService::trash()	After

URLAliasService

Signal type	Properties	Triggered by	When
URLAliasService\CreateGl obalUrlAliasSignal	• urlAliasId	URLAliasService::createG lobalUrlAlias()	After
URLAliasService\CreateUr lAliasSignal	• urlAliasId	URLAliasService::createUrlAlias()	After
URLAliasService\RemoveAl iasesSignal	• aliasList	URLAliasService::removeA liases()	After

URLWildcardService

Signal type	Properties	Triggered by	When
URLWildcardService\Creat eSignal	• urlWildcardId	URLWildcardService::crea te()	After
URLWildcardService\Remov eSignal	• urlWildcardId	URLWildcardService::remo ve()	After
URLWildcardService\Trans lateSignal	• url	URLWildcardService::tran slate()	After

UserService

Signal type	Properties	Triggered by	When
UserService\AssignUserTo UserGroupSignal	• userId • userGroupId	UserService::assignUserToUserGroup()	After
UserService\CreateUserGr oupSignal	• userGroupId	UserService::createUserG roup()	After
UserService\CreateUserSi gnal	• userId	UserService::createUser(After
UserService\DeleteUserGr oupSignal	• userGroupId	UserService::deleteUserG roup()	After
UserService\DeleteUserSi gnal	• userId	UserService::deleteUser(After
UserService\MoveUserGroupSignal	userGroupIdnewParentId	UserService::moveUserGroup()	After
UserService\UnAssignUser FromUserGroupSignal	• userId • userGroupId	UserService::unAssignUse rFromUserGroup()	After
UserService\UpdateUserGr oupSignal	• userGroupId	UserService::updateUserGroup()	After
UserService\UpdateUserSi gnal	• userId	UserService::updateUser(After