Phase 2 – Get connected

Step 3 – Test network connection

DMS Import

Onboarding mini guide for System-to-System users

Step 3
Testing network connection

The next step is to verify the network access. If you are using the same certificate that has been set-up for production on DMS Export or Transit, you can skip this step. Else coordinate with your software vendor or IT department on this step.

The verification depends on the server style and can be executed in various ways. Which method to use is determined by the availability of tools on the client setup. See the next slides for different options.

AS4 Server details for TFE:

Hostname: secureftpgatewaytest.skat.dk   Port: 6384   IP: 195.85.251.85

Send application form

Phase 1

Get the right roles and rights for TFE via Customer Portal

Phase 2

Register certificate on Certificate Portal AS4 - TFE

Testing network connection DMS

Develop/integration DMS

Phase 3

Test with clients

DMS Production

Phase 4

Onboarding process view

3

Unix

This section describes ways to test the connectivity on Unix-style servers, using common connectivity testing tools.

Method #1 – telnet

```
telnet <Hostname> 6384
```

```
brj@T470PW10BRJ:~$ telnet secureftpgatewaytest.skat.dk 6384
Trying 195.85.251.85...
Connected to secureftpgatewaytest.skat.dk.
```

Method #2 – nmap

```
Nmap –p 6384 <Hostname>
```

```
brj@T470PW10BRJ:~$ nmap -p 6384 secureftpgatewaytest.skat.dk
Nmap scan report for secureftpgatewaytest.skat.dk (195.85.251.85)
Host is up (0.0088s latency).

PORT     STATE SERVICE
6384/tcp open  unknown

Nmap done: 1 IP address (1 host up) scanned in 12.86 seconds
```

Method #3 – openssl

```
openssl s_client -connect <Hostname>:443 -showcerts
```

```
brj@T470PW10BRJ:~$ openssl s_client -connect secureftpgatewaytest.skat.dk:443 -showcerts
CONNECTED(00000003)
depth=2 OU = GlobalSign Root CA - R3, O = GlobalSign, CN = GlobalSign
verify return:1
depth=1 C = BE, O = GlobalSign nv-sa, CN = GlobalSign RSA OV SSL CA 2018
verify return:1
depth=0 C = DK, ST = Copenhagen, L = Copenhagen Oe, O = Skatteforvaltningen, CN = secureftpgatewaytest.skat.dk
verify return:1
139743226499712:error:14094410:SSL routines:ssl3_read_bytes:sslv3 alert handshake failure:../ssl/record/rec_layer_s3.c:1543:SSL alert number 40
---
Certificate chain
 0 s:C = DK, ST = Copenhagen, L = Copenhagen Oe, O = Skatteforvaltningen, CN = secureftpgatewaytest.skat.dk
   i:C = BE, O = GlobalSign nv-sa, CN = GlobalSign RSA OV SSL CA 2018
-----BEGIN CERTIFICATE-----
MIIGqjCCBZKgAwIBAgIMdnhIln5QQEDNVMGVMA0GCSqGSIb3DQEBCwUAMFAxCzAJ
BgNVBAYTAkJFMRkwFwYDVQQKExBHbG91YWxTaWduIGS2LXNhMSYwJAYDVQQDEx1H
bG91YWxTaWduIFJTQSBPV1BTU0wgQ0EgMjAxODAeFw0xOTExMTMwODIxMDhaFw0y
MjAxMDQxMDExMDZaMH8xCzAJBgNVBAYTAkRLMRMwEQYDVQQIEwpDb3BlbmhhZ2Vu
MRYwFAYDVQQHEw1Db3BlbmhhZ2VuIE91lMRwwGgYDVQQKExNTa2F0dGVmb3J2YWx0
bmluZ2VuMSUwIwYDVQQDExxzZWN1cmVmdHBnYXRld2F5dGVzdC5za2F0LmRrMIIB
IjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEAsxOnlpLz6SJN9VAP1PJD2jK9
4gSB/fYPVvCs51fReb6KRqKQA8N47LXqeIz9+q6vqh4o+WAhgzqU5QOb7TfYsI8R
Dep1f8CTbJUG/cJypbz+xODQFx2yjstOQ6DvDl2GNpctfuO/HCf9Zwk1AxKdke7w
8hwyZamao3wOwDdq5JFOQkSU0rdoqgx+zJbI+o1cFEqgazh1h8n2ge1OFRZryGl
VP1SEUT/YZT2QUwSDtqUTrfhAzHfPe5f1H2PiRp3Yhg3KTk68PAKRGrNMStT90uD
nqqs6mG7iCRTc1K2q7aExYxPwxyRBQcQ7ySM55iAFUU3o4c9sO651QFzWhzKSwID
AQABo4IDUzCCA08wDgYDVR0PAQH/BAQDAgWgMIGOBggrBgEFBQcBAQSBgTB/MEQG
CCsGAQUFBzAChjhodHRwOi8vvc2VjdXJlLmdsb2JhbHNpZ24uY29tL2NhY2VydC9
33zYW92c3NzY2EyMDE4LmNydDA3BggrBgEFBQcwAYYraHR0cDovL29jc3AuZ2xv
YmFsc2lnbi5jb2vZ3Nyc2FvdnNzbGNhMjAxODAtBgNVHSAETzBNMEEGCSsGAQQB
pDIBFDA0MDIGCCsGAQUFBwIBFiZodHRwczovL3d3dy5nbG9iYWxzaWduLmNvbS9y
ZXBvc2l0b3J5LzAIBgZngQwBAgIwCQYDVR0TBAIwADA/BgNVHR8EODA2MDSgMqAw
hi5odHRwOi8vY3JsLmdsb2JhbHNpZ24uY29tL2dzcnNhb3Zzc2xjYTIwMTguY3Js
```

Phase 1

- Send application form

Phase 2

- Get the right roles and rights for TFE via Customer Portal
- Register certificate on Certificate Portal AS4 - TFE
- Testing network connection DMS

Phase 3

- Develop/integration DMS
- Test with clients

Phase 4

- DMS Production

Onboarding process view

4

Windows

This section describes ways to test the connectivity on Windows-style servers using common connectivity testing tools.

This method requires execution in Powershell.

```
Test-NetworkConnection <Hostname>-Port 6384
```

```
PS Z:\> Test-NetConnection secureftpgatewaytest.skat.dk -Port 6384


ComputerName      : secureftpgatewaytest.skat.dk
RemoteAddress     : 195.85.251.85
RemotePort        : 6384
InterfaceAlias    : Ethernet 67
SourceAddress     : 192.168.146.12
TcpTestSucceeded  : True
```

General test

Open https://<Hostname>:6384 in a browser that has access to the internet - on a client setup that the internal network is set up as the accessing system. If it works, you will receive a 404 error.

```
←  →  C       🔒 secureftpgatewaytest.skat.dk:6384

Error status code: 404
```

Send application form

Phase 1

Get the right roles and rights for TFE via Customer Portal

Phase 2

Register certificate on Certificate Portal AS4 - TFE

Testing network connection DMS

Develop/integration DMS

Phase 3

Test with clients

DMS Production

Phase 4

Onboarding process view

Appendix

Please turn to the extended Connectivity guide if you need more information about the AS4 Gateway. Furthermore, we recommend to visit the AS4 Simple Client package made for facilitating a client which can communicate with the AS4 portal and through it, the DMS Import system.

It covers the following:

- Converting an XML format declaration to an AS4 message
- Handles connectivity to the AS4 gateway
- Encryption and signing of AS4 messages
- Sending AS4 messages to AS4 gateway
- Receiving replies from AS4 gateway

The package is written in Java and provided as Java dependency. Integration with .NET based projects is therefore not as simple. For .NET based projects we recommend building a small Java based communication middleman REST API, which utilizes the simple AS4 client, that the existing .NET code can communicate with.

https://github.com/skat/simple-as4-client

Need technical support?

Go to Customer Portal (Toolkit) to book an online session or ask your question.
Go to FAQ