

# CE 440 Introduction to Operating System

Lecture 17: File System Implementation  
Fall 2025

Prof. Yigong Hu



Slides courtesy of Manuel Egele, Ryan Huang and Baris Kasikci

# Administrivia

**Lab 3 overview session this Friday**

- 2:30 - 4:00 PM, PHO305

# Problem: How to Track File's Data

## Disk management:

- Need to keep track of where file contents are on disk
- Must be able to use this to map **byte offset** to **disk block**
- Structure tracking a file's sectors is called an **index node or inode**
- *inodes* must be stored on disk, too


## Things to keep in mind while designing file structure:

- Most files are small
- Much of the disk is allocated to large files
- Many of the I/O operations are made to large files
- Want good sequential and good random access (what do these require?)

# Straw Man: Contiguous Allocation

“Extent-based”: allocate files like segmented memory

- When creating a file, make the user pre-specify its length and allocate all space at once
- Inode contents: location and size



Example: IBM OS/360

Pros?

- Simple, fast access, both sequential and random


Cons? (Think of corresponding VM scheme)

- External fragmentation

# Straw Man #2: Linked Files

Basically a linked list on disk.

- Keep a linked list of all free blocks
- Inode contents: a pointer to file's first block
- In each block, keep a pointer to the next one



Examples (sort-of): Alto, TOPS-10, DOS FAT

Pros?


- Easy dynamic growth & sequential access, no fragmentation

Cons?

- Linked lists on disk a bad idea because of access times
- Random very slow (e.g., traverse whole file to find last block)
- Pointers take up room in block, skewing alignment

# Example: DOS FS (simplified)

Linked files with key optimization: *puts links in fixed-size “file allocation table” (FAT) rather than in each data block*



Still do pointer chasing, but can cache entire FAT so can be cheap compared to disk access

# FAT Discussion

**Entry size = 16 bits (initial **FAT16** in MS-DOS 3.0)**

- What's the maximum size of the FAT?

**65,536 entries**

- Given a 512 byte block, what's the maximum size of FS?
- One solution: go to bigger blocks. Pros? Cons?

**Space overhead of FAT is trivial:**


- 2 bytes / 512 byte block = ~ 0.4% (Compare to Unix)

**Reliability: how to protect against errors?**

- Create duplicate copies of FAT on disk
- State duplication a very common theme in reliability

**Bootstrapping: where is root directory?**

- Fixed location on disk



# Another Approach: Indexed Files

**Each file has an array holding all of its block pointers**


- Just like a page table, so will have similar issues
- Max file size fixed by array's size (**static or dynamic?**)
- Allocate array to hold file's block pointers on file creation
- Allocate actual blocks on demand using free list

**Pros?**

- Both sequential and random access easy


**Cons?**

- Mapping table requires large chunk of contiguous space
- ...Same problem we were trying to solve initially



# inodes

- type (file or dir?)**
- uid (owner)**
- rwx (permissions)**
- size (in bytes)**
- blocks**
- time (access)**
- ctime (create)**
- links\_count (# paths)**
- addrs[N] (N data blocks)**



# More About inodes


## inodes are stored in a **fixed-size** array

- Size of array fixed when disk is initialized; can't be changed
- Lives in known location, originally at one side of disk:



- The *index* of an inode in the inode array called an **i-number**
- Internally, the OS refers to files by *i-number*
- When file is opened, inode brought in memory
- Written back when modified and file closed or time elapses


# More About inodes




# Indexed Files

**Issues same as in page tables**

- Large possible file size = lots of unused entries
- Large actual size? table needs large contiguous disk chunk




**Solve identically: small regions with index array, this array with another array, ...**



# Multi-level Indexed Files: Unix inodes

**inode = 15 block pointers + “stuff”**

- first 12 are direct blocks: solve problem of first blocks access slow
- then single, double, and triple indirect block



# Unix inodes and Path Search

## Unix inodes are **not** directories


- Inodes describe where on the disk the blocks for a file are placed
- Directories are files, so inodes also describe where the blocks for directories are placed on the disk

## Directory entries map file names to inodes, e.g., to open “/a.txt”

- To open “/one”, read inode #2 (“/”) from disk into memory
- Read the *content* of “/” from disk into memory, look for entry for “a.txt”
- This entry gives the inode # for “a.txt”
- Read the inode for “a.txt” into memory
- The inode says where first data block is on disk
- Read that block into memory to access the data in the file

How many disk  
accesses are  
required?

# Unix Example: /a/b/c.c



What inode holds file for a? b? c.c?

How many disk accesses to read the first byte in c.c?

# File Buffer Cache

Disk operations are slow...

Applications exhibit locality for reading and writing files

Idea: Cache file blocks in memory to capture locality

- Called the [file buffer cache](#)
- Cache is system wide, used and shared by all processes
- Reading from the cache makes a disk perform like memory
- Even a small cache can be very effective

Issues

- The file buffer cache competes with VM (tradeoff here)
- Like VM, it has limited size
- Need replacement algorithms again (LRU usually used)

# Caching Writes

**On a write, some applications assume that data makes it through the buffer cache and onto the disk**

- As a result, writes are often slow even with caching

**OSes typically do write back caching**

- Maintain a queue of uncommitted blocks
- Periodically flush the queue to disk (30 second threshold)
- If blocks changed many times in 30 secs, only need one I/O
- If blocks deleted before 30 secs (e.g., /tmp), no I/Os needed

**Unreliable, but practical**

- On a crash, all writes within last 30 secs are lost
- **Modern OSes do this by default; too slow otherwise**
- System calls (Unix: fsync) enable apps to force data to disk

# Read Ahead



## Many file systems implement “read ahead”

- FS predicts that the process will request next block
- FS goes ahead and requests it from the disk
- This can happen while the process is computing on previous block
  - Overlap I/O with execution
- When the process requests block, it will be in cache
- Compliments the disk cache, which also is doing read ahead

## For sequentially accessed files can be a big win

- Unless blocks for the file are scattered across the disk
- File systems try to prevent that, though (during allocation)


# Recap: I/O & Disks




# Why Disks Are Different

**Disk = First state we've seen that doesn't go away**

- So: Where all important state ultimately resides



**Slow (milliseconds access vs. nanoseconds for memory)**



**Huge (100–1,000x bigger than memory)**

- How to organize large collection of ad hoc information?
- File System: Hierarchical directories, Metadata, Search

# Disk vs. Memory


	Disk	MLC NAND Flash	DRAM
<b>Smallest write</b>	sector	sector	byte
<b>Atomic write</b>	sector	sector	byte/word
<b>Random read</b>	8 ms	3-10 µs	50 ns
<b>Random write</b>	8 ms	9-11 µs*	50 ns
<b>Sequential read</b>	100 MB/s	550–2500 MB/s	> 1 GB/s
<b>Sequential write</b>	100 MB/s	520–1500 MB/s*	> 1 GB/s
<b>Cost</b>	\$0.03/GB	\$0.35/GB	\$6/GiB
<b>Persistence</b>	Non-volatile	Non-volatile	Volatile

\*: Flash write performance degrades over time

# Disk Review



**Disk reads/writes in terms of sectors, not bytes**

- Read/write single sector or adjacent groups.



**How to write a single byte? “Read-modify-write”**

- Read in sector containing the byte
- Modify that byte
- Write entire sector back to disk
- Key: if cached, don't need to read in



**Sector = unit of atomicity.**

- Sector write done completely, even if crash in middle (disk saves up enough momentum to complete)

**Larger atomic units have to be synthesized by OS**

# Some Useful Trends (1)

## Disk bandwidth and cost/bit improving exponentially

- Similar to CPU speed, memory size, etc.

## Seek time and rotational delay improving very slowly

- Why? require moving physical object (disk arm)

## Disk access is a huge system bottleneck & getting worse

- Bandwidth increase lets system (pre-)fetch large chunks for about the same cost as small chunk.
- Trade bandwidth for latency if you can get lots of related stuff.

# Some Useful Trends (2)

## Desktop memory size increasing faster than typical workloads

- More and more of workload fits in file cache
- Disk traffic changes: mostly writes and new data

## Memory and CPU resources increasing

- Use memory and CPU to make better decisions
- Complex prefetching to support more IO patterns
- Delay data placement decisions reduce random IO

# Goal

**Want: operations to have as few disk accesses as possible & have minimal space overhead (group related things)**

**What's hard about grouping blocks?**

**Like page tables, file system metadata constructs mappings**

- **Page table:** map virtual page # to physical page #
- **File metadata:** map byte offset to disk block address
- **Directory:** map name to disk address or file #

# File Systems vs. Virtual Memory

**In both settings, want location transparency**

- Application shouldn't care about particular disk blocks or physical memory locations

**In some ways, FS has easier job than VM:**

- CPU time to do FS mappings not a big deal (**why?**) → TLB
- Page tables deal with sparse address spaces and random access, files often denser (0 . . . filesize - 1), ~sequentially accessed

**In some ways, FS's problem is harder:**

- Each layer of translation = potential disk access
- Space a huge premium! (But disk is huge?!?!)
  - Cache space never enough; amount of data you can get in one fetch never enough
- Range very extreme: Many files < 10 KB, some files GB

# Some Working Intuitions

## FS performance dominated by # of disk accesses

- Say each access costs ~10 milliseconds
- Touch the disk **100** times = 1 second
- Can do a **billion** ALU ops in same time!

## Access cost dominated by movement, not transfer:

- 1 sector:  $5ms + 4ms + 5\mu s (\approx 512 B/(100 MB/s)) \approx 9ms$
- 50 sectors:  $5ms + 4ms + .25ms = 9.25ms$
- Can get **50x the data for only ~3% more overhead!**

## Observations that might be helpful:

- All blocks in file tend to be used together, sequentially
- All files in a directory tend to be used together
- All names in a directory tend to be used together

# File Systems Examples

## BSD Fast File System (FFS)

- What were the problems with the original Unix FS?
- How did FFS solve these problems?

## Log-Structured File system (LFS) – next lecture

- What was the motivation of LFS?
- How did LFS work?

# Summary

## File System Layouts

- Unix inodes

## File Buffer Cache

- Strategies for handling writes

# **Next Time...**

Read Chapter 41