

GumNaaM_Helpers



Mega File for FinaL TerM

All Files in ONE FILE

(Handouts_waqar_moaz_junaid_vu toper_orange monkey)

الحمدللہ گمنام ہیلپرز ان تمام کتابوں میں مدد کرتے ہیں جن کے لنکس نیچے دیئے گئے ہیں
لیٰذا ہم سے صرف انہی کتابوں کی مدد کا سوال کیا جائے جن کے لنکس نیچے موجود ہیں

Groups Join Krty hi Description Read krna na bhoolyn

جزاک اللہ خیرا و احسن الجزاء

GumNaaM_Helpers All What's App Group Links

Cs101 https://chat.whatsapp.com/KCQ3jK6FcoYEvDYTF1gnBS	Eng101 https://chat.whatsapp.com/Cwp4Ag9TG6ZKxyRqThqM6S
Cs201 https://chat.whatsapp.com/DrYV1FAXmppImVZFwI6V2R	Eng201 https://chat.whatsapp.com/EvvxcPtmrM22VTZhz5NCTw
Cs301 https://chat.whatsapp.com/EPLvHztf8EB7aH8e1AtidV	Eco401 https://chat.whatsapp.com/K3NLvyue6BdK0sVMqDFoU2
Cs302 https://chat.whatsapp.com/BaYfW0P67vNIsl2n36otZM	Mcm301 https://chat.whatsapp.com/GUyzfdHzu8r43TW16vhZWF
Cs304 https://chat.whatsapp.com/C0mk0wdo0BU46dlhcd67IO	Mgt101 https://chat.whatsapp.com/BmrYaQYuIBOKguHOiT6t2Y
Cs401 https://chat.whatsapp.com/Jz9WDdHX84lKgkrMPAV0Mf	Mgt201 https://chat.whatsapp.com/DZwztlUyxV50D6AshnvWCD
Cs402 https://chat.whatsapp.com/DW9AZLb4i1P9la4XmcCsRz	Mgt211 https://chat.whatsapp.com/EmX9xloZnbI12pX9m2DZwa
Cs403 https://chat.whatsapp.com/HXV25Lc6MnLKZgrA7xOqjF	Mgt301 https://chat.whatsapp.com/G62QTipycoXFrpOZxfDIBK
Cs408 https://chat.whatsapp.com/EFy2mrYJodx5dB5W1jtII7	Mgt501 https://chat.whatsapp.com/H0dTUINbesw0GS4LLSt0W4
Cs411 https://chat.whatsapp.com/IrOaF8Q3tkJKzeVTHapHR9	Mgt502 https://chat.whatsapp.com/L3GSMFgwDl7DAsu9r0vAxI
Cs501 https://chat.whatsapp.com/Eggxx3X0SH2LhOysM57SII	Mgt503 https://chat.whatsapp.com/G7BNxqyLYwP48jfPTofkbJ
Cs502 https://chat.whatsapp.com/FbLU96Xhmr2FI99fnbz5Yw	Mgt602 https://chat.whatsapp.com/HXRpOrEL18vD7lb91nLHTB
Cs504 https://chat.whatsapp.com/Gn7w0UzNCQ2FzRK7ZzY4Io	Mgt610 https://chat.whatsapp.com/BxMcR1ouiao0wuqLlLj5dB
Cs506 https://chat.whatsapp.com/BL4FFmDKf2S3WIoLsAD2JK	Mth101 https://chat.whatsapp.com/LHsbl65FbwGH2SNFF9ipSb
Cs507 https://chat.whatsapp.com/EINDZkV4e4zGLGqL8imozR	Mth202 https://chat.whatsapp.com/GevRebusRaxFh6dgnzRJuM
Cs508 https://chat.whatsapp.com/HTMAwnJ4Bic2ky8MbT3PuW	Mth301 https://chat.whatsapp.com/EFm472nc2woDPrOEqnY1Ij
Cs601 https://chat.whatsapp.com/KYoaAutdXRlDNS0Mm5XfzP	Mth401 https://chat.whatsapp.com/EP7tlcc17TzLtNaOgD4AcA
Cs602 https://chat.whatsapp.com/FpJkLAFNQpZHRyi6vhl5n8	Mth501 https://chat.whatsapp.com/Dy7XUVFqqD5LLw4i5X4Xzi
Cs604 https://chat.whatsapp.com/KjDhHjxawtU43Veo9Eawa4	Mth601 https://chat.whatsapp.com/BoD3akuXGK25MFB4UEZcRr
Cs605 https://chat.whatsapp.com/BoF34LtMlYK1l4nQaEO2Ce	isL201 https://chat.whatsapp.com/BtoqaMbbELW99MLLtQMGwC
Cs610 https://chat.whatsapp.com/FcNcztKyYfd9szsJEJino2	Pak301 https://chat.whatsapp.com/KuR9Y7YWeA32enRwKeZJaR
Cs615 https://chat.whatsapp.com/HLVjBNcorFN9bwZhGEkFl3	Phy101 https://chat.whatsapp.com/GjC6e47vF1zHwRs5iOc13J
Cs619 https://chat.whatsapp.com/FEklYr700uj0ihxqnk55A6	Phy301 https://chat.whatsapp.com/IBrOdznEHDi92fGa76Dqmr
	Sta301 https://chat.whatsapp.com/BchodAnjbydKXLuxFfKGxr

...Paid Service Available for LMS Activities...

Only for those students who are so busy in office or work or job that they can't watch their LMS due to their Busyness

FOR MORE INFO. CONTACT US ONLY WHAT'S APP 0302-1400084

Assembly Language Programming
Lecture Notes

Delivered by
Belal Hashmi

Compiled by
Junaid Haroon

Preface

Assembly language programming develops a very basic and low level understanding of the computer. In higher level languages there is a distance between the computer and the programmer. This is because higher level languages are designed to be closer and friendlier to the programmer, thereby creating distance with the machine. This distance is covered by translators called compilers and interpreters. The aim of programming in assembly language is to bypass these intermediates and talk directly with the computer.

There is a general impression that assembly language programming is a difficult chore and not everyone is capable enough to understand it. The reality is in contrast, as assembly language is a very simple subject. The wrong impression is created because it is very difficult to realize that the real computer can be so simple. Assembly language programming gives a freehand exposure to the computer and lets the programmer talk with it in its language. The only translator that remains between the programmer and the computer is there to symbolize the computer's numeric world for the ease of remembering.

To cover the practical aspects of assembly language programming, IBM PC based on Intel architecture will be used as an example. However this course will not be tied to a particular architecture as it is often done. In our view such an approach does not create versatile assembly language programmers. The concepts of assembly language that are common across all platforms will be developed in such a manner as to emphasize the basic low level understanding of the computer instead of the peculiarities of one particular architecture. Emphasis will be more on assembly language and less on the IBM PC.

Before attempting this course you should know basic digital logic operations of AND, OR, NOT etc. You should know binary numbers and their arithmetic. Apart from these basic concepts there is nothing much you need to know before this course. In fact if you are not an expert, you will learn assembly language quickly, as non-experts see things with simplicity and the basic beauty of assembly language is that it is exceptionally simple. Do not ever try to find a complication, as one will not be there. In assembly language what is written in the program is all that is there, no less and no more.

After successful completion of this course, you will be able to explain all the basic operations of the computer and in essence understand the psychology of the computer. Having seen the computer from so close, you will understand its limitations and its capabilities. Your logic will become fine grained and this is one of the basic objectives of teaching assembly language programming.

Then there is the question that why should we learn assembly language when there are higher level languages one better than the other; C, C++, Java, to name just a few, with a neat programming environment and a simple way to write programs. Then why do we need such a freehand with the computer that may be dangerous at times? The answer to this lies in a very simple example. Consider a translator translating from English to Japanese. The problem faced by the translator is that every language has its own vocabulary and grammar. He may need to translate a word into a sentence and destroy the beauty of the topic. And given that we do not know

Japanese, so we cannot verify that our intent was correctly conveyed or not. Compiler is such a translator, just a lot dumber, and having a scarce number of words in its target language, it is bound to produce a lot of garbage and unnecessary stuff as a result of its ignorance of our program logic. In normal programs such garbage is acceptable and the ease of programming overrides the loss in efficiency but there are a few situations where this loss is unbearable.

Think about a four color picture scanned at 300 dots per inch making 90000 pixels per square inch. Now a processing on this picture requires 360000 operations per square inch, one operation for each color of each pixel. A few extra instructions placed by the translator can cost hours of extra time. The only way to optimize this is to do it directly in assembly language. But this doesn't mean that the whole application has to be written in assembly language, which is almost never the case. It's only the performance critical part that is coded in assembly language to gain the few extra cycles that matter at that point.

Consider an arch just like the ones in mosques. It cannot be made of big stones alone as that would make the arch wildly jagged, not like the fine arch we are used to see. The fine grains of cement are used to smooth it to the desired level of perfection. This operation of smoothing is optimization. The core structure is built in a higher level language with the big blocks it provides and the corners that need optimization are smoothed with the fine grain of assembly language which allows extreme control.

Another use of assembly language is in a class of time critical systems called real time systems. Real time systems have time bound responses, with an upper limit of time on certain operations. For such precise timing requirement, we must keep the instructions in our total control. In higher level languages we cannot even tell how many computer instructions were actually used, but in assembly language we can have precise control over them. Any reasonable sized application or a serious development effort has nooks and corners where assembly language is needed. And at these corners if there is no assembly language, there can be no optimization and when there is no optimization, there is no beauty. Sometimes a useful application becomes useless just because of the carelessness of not working on these jagged corners.

The third major reason for learning assembly language and a major objective for teaching it is to produce fine grained logic in programmers. Just like big blocks cannot produce an arch, the big thick grained logic learnt in a higher level language cannot produce the beauty and fineness assembly language can deliver. Each and every grain of assembly language has a meaning; nothing is presumed (e.g. div and mul for input and out put of decimal number). You have to put together these grains, the minimum number of them to produce the desired outcome. Just like a "for" loop in a higher level language is a block construct and has a hundred things hidden in it, but using the grains of assembly language we do a similar operation with a number of grains but in the process understand the minute logic hidden beside that simple "for" construct.

Assembly language cannot be learnt by reading a book or by attending a course. It is a language that must be tasted and enjoyed. There is no other way to learn it. You will need to try every example, observe and verify the things you are told about it, and experiment a lot with the computer. Only then you will know and become able to appreciate how powerful, versatile, and simple this language is; the three properties that are hardly ever present together.

Whether you program in C/C++ or Java, or in any programming paradigm be it object oriented or declarative, everything has to boil down to the bits and bytes of assembly language before the computer can even understand it.

Table of Contents

Preface i

Table of Contents iii

1 Introduction to Assembly Language 1

1.1. Basic Computer Architecture 1
1.2. Registers 3
1.3. Instruction Groups 5
1.4. Intel iapx88 Architecture 6
1.5. History 6
1.6. Register Architecture 7
1.7. Our First Program 9
1.8. Segmented Memory Model 12

2 Addressing Modes 17

2.1. Data Declaration 17
2.2. Direct Addressing 17
2.3. Size Mismatch Errors 21
2.4. Register Indirect Addressing 22
2.5. Register + Offset Addressing 25
2.6. Segment Association 25
2.7. Address Wraparound 26
2.8. Addressing Modes Summary 27

3 Branching 31

3.1. Comparison and Conditions 31
3.2. Conditional Jumps 33
3.3. Unconditional Jump 36
3.4. Relative Addressing 37
3.5. Types of Jump 37
3.6. Sorting Example 38

4 Bit Manipulations 43

4.1. Multiplication Algorithm 43
4.2. Shifting and Rotations 43
4.3. Multiplication in Assembly Language 46
4.4. Extended Operations 47
4.5. Bitwise Logical Operations 50
4.6. Masking Operations 51

5 Subroutines 55

5.1. Program Flow 55
5.2. Our First Subroutine 57
5.3. Stack 59
5.4. Saving and Restoring Registers 62
5.5. Parameter Passing Through Stack 64
5.6. Local Variables 67

6 Display Memory 71

6.1. ASCII Codes 71
6.2. Display Memory Formation 72
6.3. Hello World in Assembly Language 74
6.4. Number Printing in Assembly 76
6.5. Screen Location Calculation 79

7 String Instructions 83

7.1. String Processing 83
7.2. STOS Example – Clearing the Screen 85
7.3. LODS Example – String Printing 86
7.4. SCAS Example – String Length 87
7.5. LES and LDS Example 89
7.6. MOVS Example – Screen Scrolling 90
7.7. CMPS Example – String Comparison 92

8 Software Interrupts 95

8.1. Interrupts 95
8.2. Hooking an Interrupt 98
8.3. BIOS and DOS Interrupts 99

9 Real Time Interrupts and Hardware Interfacing 105

9.1. Hardware Interrupts 105
9.2. I/O Ports 106
9.3. Terminate and Stay Resident 111
9.4. Programmable Interval Timer 114
9.5. Parallel Port 116

10 Debug Interrupts 125

10.1. Debugger using single step interrupt 125
10.2. Debugger using breakpoint interrupt 128

11 Multitasking 131

11.1. Concepts of Multitasking 131
11.2. Elaborate Multitasking 133
11.3. Multitasking Kernel as TSR 135

12 Video Services 141

12.1. BIOS Video Services 141
12.2. DOS Video Services 144

13 Secondary Storage 147

13.1. Physical Formation 147
13.2. Storage Access Using BIOS 148
13.3. Storage Access using DOS 153
13.4. Device Drivers 158

14 Serial Port Programming 163

14.1. Introduction 163
14.2. Serial Communication 165

15 Protected Mode Programming 167

15.1. Introduction 167
15.2. 32bit Programming 170
15.3. VESA Linear Frame Buffer 172
15.4. Interrupt Handling 174

16 Interfacing with High Level Languages 179

16.1. Calling Conventions 179
16.2. Calling C from Assembly 179
16.3. Calling Assembly from C 181

17 Comparison with Other Processors 183

17.1. Motorolla 68K Processors 183
17.2. Sun SPARC Processor 184

1
Introduction to Assembly Language

1.1. BASIC COMPUTER ARCHITECTURE

Address, Data, and Control Buses

A computer system comprises of a processor, memory, and I/O devices. I/O is used for interfacing with the external world, while memory is the processor's internal world. Processor is the core in this picture and is responsible for performing operations. The operation of a computer can be fairly described with processor and memory only. I/O will be discussed in a later part of the course. Now the whole working of the computer is performing an operation by the processor on data, which resides in memory.

The scenario that the processor executes operations and the memory contains data elements requires a mechanism for the processor to read that data from the memory. "That data" in the previous sentence much be rigorously explained to the memory which is a dumb device. Just like a postman, who must be told the precise address on the letter, to inform him where the destination is located. Another significant point is that if we only want to read the data and not write it, then there must be a mechanism to inform the memory that we are interested in reading data and not writing it. Key points in the above discussion are:


- There must be a mechanism to inform memory that we want to do the read operation
- There must be a mechanism to inform memory that we want to read precisely which element
- There must be a mechanism to transfer that data element from memory to processor

The group of bits that the processor uses to inform the memory about which element to read or write is collectively known as the *address bus*. Another important bus called the *data bus* is used to move the data from the memory to the processor in a read operation and from the processor to the memory in a write operation. The third group consists of miscellaneous independent lines used for control purposes. For example, one line of the bus is used to inform the memory about whether to do the read operation or the write operation. These lines are collectively known as the *control bus*.

These three buses are the eyes, nose, and ears of the processor. It uses them in a synchronized manner to perform a meaningful operation. Although the programmer specifies the meaningful operation, but to fulfill it the processor needs the collaboration of other units and peripherals. And that collaboration is made available using the three buses. This is the very basic description of a computer and it can be extended on the same lines to I/O but we are leaving it out just for simplicity for the moment.

The address bus is unidirectional and address always travels from processor to memory. This is because memory is a dumb device and cannot predict which element the processor at a particular instant of time needs. Data moves from both, processor to memory and memory to processor, so the data bus is bidirectional. Control bus is special and relatively complex, because different lines comprising it behave differently. Some take

information from the processor to a peripheral and some take information from the peripheral to the processor. There can be certain events outside the processor that are of its interest. To bring information about these events the data bus cannot be used as it is owned by the processor and will only be used when the processor grants permission to use it. Therefore certain processors provide control lines to bring such information to processor's notice in the control bus. Knowing these signals in detail is unnecessary but the general idea of the control bus must be conceived in full.



We take an example to explain the collaboration of the processor and memory using the address, control, and data buses. Consider that you want your uneducated servant to bring a book from the shelf. You order him to bring the fifth book from top of the shelf. All the data movement operations are hidden in this one sentence. Such a simple everyday phenomenon seen from this perspective explains the seemingly complex working of the three buses. We told the servant to "bring a book" and the one which is "fifth from top," precise location even for the servant who is much more intelligent then our dumb memory. The dumb servant follows the steps one by one and the book is in your hand as a result. If however you just asked him for a book or you named the book, your uneducated servant will stand there gazing at you and the book will never come in your hand.

Even in this simplest of all examples, mathematics is there, "fifth from top." Without a number the servant would not be able to locate the book. He is unable to understand your will. Then you tell him to put it with the seventh book on the right shelf. Precision is involved and only numbers are precise in this world. One will always be one and two will always be two. So we tell in the form of a number on the address bus which cell is needed out of say the 2000 cells in the whole memory.

A binary number is generated on the address bus, fifth, seventh, eighth, tenth; the cell which is needed. So the cell number is placed on the address bus. A memory cell is an n-bit location to store data, normally 8-bit also called a byte. The number of bits in a cell is called the *cell width*. The two dimensions, cell width and number of cells, define the memory completely just like the width and depth of a well defines it completely. 200 feet deep by 15 feet wide and the well is completely described. Similarly for memory we define two dimensions. The first dimension defines how many parallel bits are there in a single memory cell. The memory is called 8-bit or 16-bit for this reason and this is also the word size of the memory. This need not match the size of a processor word which has other parameters to define it. In general the memory cell cannot be wider than the width of the data bus. Best and simplest operation requires the same size of data bus and memory cell width.

As we previously discussed that the control bus carries the intent of the processor that it wants to read or to write. Memory changes its behavior in response to this signal from the processor. It defines the direction of data flow. If processor wants to read but memory wants to write, there will be no communication or useful flow of information. Both must be synchronized, like a speaker speaks and the listener listens. If both speak simultaneously or both listen there will be no communication. This precise synchronization between the processor and the memory is the responsibility of the control bus.

Control bus is only the mechanism. The responsibility of sending the appropriate signals on the control bus to the memory is of the processor. Since the memory never wants to listen or to speak of itself. Then why is the control bus bidirectional. Again we take the same example of the servant and the book further to elaborate this situation. Consider that the servant went to fetch the book just to find that the drawing room door is locked. Now the servant can wait there indefinitely keeping us in surprise or come back and inform us about the situation so that we can act accordingly. The servant even though he was obedient was unable to fulfill our orders so in all his obedience, he came back to inform us about the problem. Synchronization is still important, as a result of our orders either we got the desired cell or we came to know that the memory is locked for the moment. Such information cannot be transferred via the address or the data bus. For such situations when peripherals want to talk to the processor when the processor wasn't expecting them to speak, special lines in the control bus are used. The information in such signals is usually to indicate the incapability of the peripheral to do something for the moment. For these reasons the control bus is a bidirectional bus and can carry information from processor to memory as well as from memory to processor.

1.2. REGISTERS

The basic purpose of a computer is to perform operations, and operations need operands. Operands are the data on which we want to perform a certain operation. Consider the addition operation; it involves adding two numbers to get their sum. We can have precisely one address on the address bus and consequently precisely one element on the data bus. At the very same instant the second operand cannot be brought inside the processor. As soon as the second is selected, the first operand is no longer there. For this reason there are temporary storage places inside the processor called *registers*. Now one operand can be read in a register and added into the other which is read directly from the memory. Both are made accessible at one instance of time, one from inside the processor and one from outside on the data bus. The result can be written to at a distinct location as the operation has completed and we can access a different memory cell. Sometimes we hold both operands in registers for the sake of efficiency as what we can do inside the processor is undoubtedly faster than if we have to go outside and bring the second operand.

Registers are like a scratch pad ram inside the processor and their operation is very much like normal memory cells. They have precise locations and remember what is placed inside them. They are used when we need more than one data element inside the processor at one time. The concept of registers will be further elaborated as we progress into writing our first program.

Memory is a limited resource but the number of memory cells is large. Registers are relatively very small in number, and are therefore a very scarce and precious resource. Registers are more than one in number, so we have to precisely identify or name them. Some manufacturers number their registers like r0, r1, r2, others name them like A, B, C, D etc. Naming is useful since the registers are few in number. This is called the nomenclature of the

particular architecture. Still other manufacturers name their registers according to their function like X stands for an index register. This also informs us that there are special functions of registers as well, some of which are closely associated to the particular architecture. For example index registers do not hold data instead they are used to hold the address of data. There are other functions as well and the whole spectrum of register functionalities is quite large. However most of the details will become clear as the registers of the Intel architecture are discussed in detail.

Accumulator

There is a central register in every processor called the accumulator. Traditionally all mathematical and logical operations are performed on the accumulator. The word size of a processor is defined by the width of its accumulator. A 32bit processor has an accumulator of 32 bits.

Pointer, Index, or Base Register

The name varies from manufacturer to manufacturer, but the basic distinguishing property is that it does not hold data but holds the address of data. The rationale can be understood by examining a "for" loop in a higher level language, zeroing elements in an array of ten elements located in consecutive memory cells. The location to be zeroed changes every iteration. That is the address where the operation is performed is changing. Index register is used in such a situation to hold the address of the current array location. Now the value in the index register cannot be treated as data, but it is the address of data. In general whenever we need access to a memory location whose address is not known until runtime we need an index register. Without this register we would have needed to explicitly code each iteration separately.

In newer architectures the distinction between accumulator and index registers has become vague. They have general registers which are more versatile and can do both functions. They do have some specialized behaviors but basic operations can be done on all general registers.

Flags Register or Program Status Word

This is a special register in every architecture called the flags register or the program status word. Like the accumulator it is an 8, 16, or 32 bits register but unlike the accumulator it is meaningless as a unit, rather the individual bits carry different meanings. The bits of the accumulator work in parallel as a unit and each bit mean the same thing. The bits of the flags register work independently and individually, and combined its value is meaningless.

An example of a bit commonly present in the flags register is the carry flag. The carry can be contained in a single bit as in binary arithmetic the carry can only be zero or one. If a 16bit number is added to a 16bit accumulator, and the result is of 17 bits the 17th bit is placed in the carry bit of the flags register. Without this 17th bit the answer is incorrect. More examples of flags will be discussed when dealing with the Intel specific register set.

Program Counter or Instruction Pointer

Everything must translate into a binary number for our dumb processor to understand it, be it an operand or an operation itself. Therefore the instructions themselves must be translated into numbers. For example to add numbers we understand the word "add." We translate this word into a number to make the processor understand it. This number is the actual instruction for the computer. All the objects, inheritance and encapsulation constructs in higher level languages translate down to just a number in assembly language in the end. Addition, multiplication, shifting; all big

programs are made using these simple building blocks. A number is at the bottom line since this is the only thing a computer can understand.

A program is defined to be "an ordered set of instructions." Order in this definition is a key part. Instructions run one after another, first, second, third and so on. Instructions have a positional relationship. The whole logic depends on this positioning. If the computer executes the fifth instructions after the first and not the second, all our logic is gone. The processor should ensure this ordering of instructions. A special register exists in every processor called the program counter or the instruction pointer that ensures this ordering. "The program counter holds the address of the next instruction to be executed." A number is placed in the memory cell pointed to by this register and that number tells the processor which instruction to execute; for example 0xEA, 255, or 152. For the processor 152 might be the add instruction. Just this one number tells it that it has to add, where its operands are, and where to store the result. This number is called the *opcode*. The instruction pointer moves from one opcode to the next. This is how our program executes and progresses. One instruction is picked, its operands are read and the instruction is executed, then the next instruction is picked from the new address in instruction pointer and so on.

Remembering 152 for the add operation or 153 for the subtract operation is difficult. To make a simple way to remember difficult things we associate a symbol to every number. As when we write "add" everyone understands what we mean by it. Then we need a small program to convert this "add" of ours to 152 for the processor. Just a simple search and replace operation to translate all such symbols to their corresponding opcodes. We have mapped the numeric world of the processor to our symbolic world. "Add" conveys a meaning to us but the number 152 does not. We can say that add is closer to the programmer's thinking. This is the basic motive of adding more and more translation layers up to higher level languages like C++ and Java and Visual Basic. These symbols are called *instruction mnemonics*. Therefore the mnemonic "add a to b" conveys more information to the reader. The dumb translator that will convert these mnemonics back to the original opcodes is a key program to be used throughout this course and is called the *assembler*.

1.3. INSTRUCTION GROUPS

Usual opcodes in every processor exist for moving data, arithmetic and logical manipulations etc. However their mnemonics vary depending on the will of the manufacturer. Some manufacturers name the mnemonics for data movement instructions as "move," some call it "load" and "store" and still other names are present. But the basic set of instructions is similar in every processor. A grouping of these instructions makes learning a new processor quick and easy. Just the group an instruction belongs tells a lot about the instruction.

Data Movement Instructions

These instructions are used to move data from one place to another. These places can be registers, memory, or even inside peripheral devices. Some examples are:

```
mov  ax, bx
lad  1234
```

Arithmetic and Logic Instructions

Arithmetic instructions like addition, subtraction, multiplication, division and Logical instructions like logical and, logical or, logical xor, or complement are part of this group. Some examples are:

```
and  ax, 1234
add  bx, 0534
add  bx, [1200]
```

The bracketed form is a complex variation meaning to add the data placed at address 1200. Addressing data in memory is a detailed topic and is discussed in the next chapter.

Program Control Instructions

The instruction pointer points to the next instruction and instructions run one after the other with the help of this register. We can say that the instructions are tied with one another. In some situations we don't want to follow this implied path and want to order the processor to break its flow if some condition becomes true instead of the spatially placed next instruction. In certain other cases we want the processor to first execute a separate block of code and then come back to resume processing where it left.

These are instructions that control the program execution and flow by playing with the instruction pointer and altering its normal behavior to point to the next instruction. Some examples are:

```
cmp  ax, 0
jne  1234
```

We are changing the program flow to the instruction at 1234 address if the condition that we checked becomes true.

Special Instructions

Another group called special instructions works like the special service commandos. They allow changing specific processor behaviors and are used to play with it. They are used rarely but are certainly used in any meaningful program. Some examples are:

```
cli
sti
```

Where cli clears the interrupt flag and sti sets it. Without delving deep into it, consider that the cli instruction instructs the processor to close its ears from the outside world and never listen to what is happening outside, possibly to do some very important task at hand, while sti restores normal behavior. Since these instructions change the processor behavior they are placed in the special instructions group.

1.4. INTEL IAPX88 ARCHITECTURE

Now we select a specific architecture to discuss these abstract ideas in concrete form. We will be using IBM PC based on Intel architecture because of its wide availability, because of free assemblers and debuggers available for it, and because of its wide use in a variety of domains. However the concepts discussed will be applicable on any other architecture as well; just the mnemonics of the particular language will be different.

Technically iAPX88 stands for "Intel Advanced Processor Extensions 88." It was a very successful processor also called 8088 and was used in the very first IBM PC machines. Our discussion will revolve around 8088 in the first half of the course while in the second half we will use iAPX386 which is very advanced and powerful processor. 8088 is a 16bit processor with its accumulator and all registers of 16 bits. 386 on the other hand, is a 32bit processor. However it is downward compatible with iAPX88 meaning that all code written for 8088 is valid on the 386. The architecture of a processor means the organization and functionalities of the registers it contains and the instructions that are valid on the processor. We will discuss the register architecture of 8088 in detail below while its instructions are discussed in the rest of the book at appropriate places.

1.5. HISTORY

Intel did release some 4bit processors in the beginning but the first meaningful processor was 8080, an 8bit processor. The processor became


popular due to its simplistic design and versatile architecture. Based on the experience gained from 8080, an advanced version was released as 8085. The processor became widely popular in the engineering community again due to its simple and logical nature.

Intel introduced the first 16bit processor named 8088 at a time when the concept of personal computer was evolving. With a maximum memory of 64K on the 8085, the 8088 allowed a whole mega byte. IBM embedded this processor in their personal computer. The first machines ran at 4.43 MHz; a blazing speed at that time. This was the right thing at the right moment. No one expected this to become the biggest success of computing history. IBM PC XT became so popular and successful due to its open architecture and easily available information.

The success was unexpected for the developers themselves. As when Intel introduced the processor it contained a timer tick count which was valid for five years only. They never anticipated the architecture to stay around for more than five years but the history took a turn and the architecture is there at every desk even after 25 years and the tick is to be specially handled every now and then.

1.6. REGISTER ARCHITECTURE

The iAPX88 architecture consists of 14 registers.



General Registers (AX, BX, CX, and DX)

The registers AX, BX, CX, and DX behave as general purpose registers in Intel architecture and do some specific functions in addition to it. X in their names stand for extended meaning 16bit registers. For example AX means we are referring to the extended 16bit "A" register. Its upper and lower byte are separately accessible as AH (A high byte) and AL (A low byte). All general purpose registers can be accessed as one 16bit register or as two 8bit registers. The two registers AH and AL are part of the big whole AX. Any change in AH or AL is reflected in AX as well. AX is a composite or extended register formed by gluing together the two parts AH and AL.

The A of AX stands for Accumulator. Even though all general purpose registers can act as accumulator in most instructions there are some specific variations which can only work on AX which is why it is named the accumulator. The B of BX stands for Base because of its role in memory addressing as discussed in the next chapter. The C of CX stands for Counter as there are certain instructions that work with an automatic count in the CX register. The D of DX stands for Destination as it acts as the destination in I/O operations. The A, B, C, and D are in letter sequence as well as depict some special functionality of the register.

Index Registers (SI and DI)

SI and DI stand for source index and destination index respectively. These are the index registers of the Intel architecture which hold address of data and used in memory access. Being an open and flexible architecture, Intel allows many mathematical and logical operations on these registers as well like the general registers. The source and destination are named because of their implied functionality as the source or the destination in a special class of instructions called the string instructions. However their use is not at all restricted to string instructions. SI and DI are 16bit and cannot be used as 8bit register pairs like AX, BX, CX, and DX.

Instruction Pointer (IP)

This is the special register containing the address of the next instruction to be executed. No mathematics or memory access can be done through this register. It is out of our direct control and is automatically used. Playing with it is dangerous and needs special care. Program control instructions change the IP register.

Stack Pointer (SP)

It is a memory pointer and is used indirectly by a set of instructions. This register will be explored in the discussion of the system stack.

Base Pointer (BP)

It is also a memory pointer containing the address in a special area of memory called the stack and will be explored alongside SP in the discussion of the stack.

Flags Register

The flags register as previously discussed is not meaningful as a unit rather it is bit wise significant and accordingly each bit is named separately. The bits not named are unused. The Intel FLAGS register has its bits organized as follows:

15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
				O	D	I	T	S	Z		A		P		C

The individual flags are explained in the following table.

C	Carry	When two 16bit numbers are added the answer can be 17 bits long or when two 8bit numbers are added the answer can be 9 bits long. This extra bit that won't fit in the target register is placed in the carry flag where it can be used and tested.
P	Parity	Parity is the number of "one" bits in a binary number. Parity is either odd or even. This information is normally used in communications to verify the integrity of data sent from the sender to the receiver.
A	Auxiliary Carry	A number in base 16 is called a hex number and can be represented by 4 bits. The collection of 4 bits is called a nibble. During addition or subtraction if a carry goes from one nibble to the next this flag is set. Carry flag is for the carry from the whole addition while auxiliary carry is the carry from the first nibble to the second.
Z	Zero Flag	The Zero flag is set if the last mathematical or logical instruction has produced a zero in its destination.

S	Sign Flag	A signed number is represented in its two's complement form in the computer. The most significant bit (MSB) of a negative number in this representation is 1 and for a positive number it is zero. The sign bit of the last mathematical or logical operation's destination is copied into the sign flag.
T	Trap Flag	The trap flag has a special role in debugging which will be discussed later.
I	Interrupt Flag	It tells whether the processor can be interrupted from outside or not. Sometimes the programmer doesn't want a particular task to be interrupted so the Interrupt flag can be zeroed for this time. The programmer rather than the processor sets this flag since the programmer knows when interruption is okay and when it is not. Interruption can be disabled or enabled by making this bit zero or one, respectively, using special instructions.
D	Direction Flag	Specifically related to string instructions, this flag tells whether the current operation has to be done from bottom to top of the block (D=0) or from top to bottom of the block (D=1).
O	Overflow Flag	The overflow flag is set during signed arithmetic, e.g. addition or subtraction, when the sign of the destination changes unexpectedly. The actual process sets the overflow flag whenever the carry into the MSB is different from the carry out of the MSB

Segment Registers (CS, DS, SS, and ES)

The code segment register, data segment register, stack segment register, and the extra segment register are special registers related to the Intel segmented memory model and will be discussed later.

1.7. OUR FIRST PROGRAM

The first program that we will write will only add three numbers. This very simple program will clarify most of the basic concepts of assembly language. We will start with writing our algorithm in English and then moving on to convert it into assembly language.

English Language Version

"Program is an ordered set of instructions for the processor." Our first program will be instructions manipulating AX and BX in plain English.

```
move 5 to ax
move 10 to bx
add bx to ax
move 15 to bx
add bx to ax
```

Even in this simple reflection of thoughts in English, there are some key things to observe. One is the concept of destination as every instruction has a "to destination" part and there is a source before it as well. For example the second line has a constant 10 as its source and the register BX as its destination. The key point in giving the first program in English is to convey that the concepts of assembly language are simple but fine. Try to understand them considering that all above is everyday English that you know very well and every concept will eventually be applicable to assembly language.

Assembly Language Version

Intel could have made their assembly language exactly identical to our program in plain English but they have abbreviated a lot of symbols to avoid unnecessarily lengthy program when the meaning could be conveyed with less effort. For example Intel has named their move instruction "mov" instead of "move." Similarly the Intel order of placing source and destination is opposite to what we have used in our English program, just a change of interpretation. So the Intel way of writing things is:

```
operation destination, source
operation destination
operation source
operation
```

The later three variations are for instructions that have one or both of their operands implied or they work on a single or no operand. An implied operand means that it is always in a particular register say the accumulator, and it need not be mentioned in the instruction. Now we attempt to write our program in actual assembly language of the iapx88.

Example 1.1

```
001     ; a program to add three numbers using registers
002     [org 0x0100]
003                 mov  ax, 5              ; load first number in ax
004                 mov  bx, 10             ; load second number in bx
005                 add  ax, bx             ; accumulate sum in ax
006                 mov  bx, 15             ; load third number in bx
007                 add  ax, bx             ; accumulate sum in ax
008
009                 mov  ax, 0x4c00         ; terminate program
010                 int  0x21
```

001	To start a comment a semicolon is used and the assembler ignores everything else on the same line. Comments must be extensively used in assembly language programs to make them readable.
002	Leave the org directive for now as it will be discussed later.
003	The constant 5 is loaded in one register AX.
004	The constant 10 is loaded in another register BX.
005	Register BX is added to register AX and the result is stored in register AX. Register AX should contain 15 by now.
006	The constant 15 is loaded in the register BX.
007	Register BX is again added to register AX now producing 15+15=30 in the AX register. So the program has computed 5+10+15=30.
008	Vertical spacing must also be used extensively in assembly language programs to separate logical blocks of code.
009-010	The ending lines are related more to the operating system than to assembly language programming. It is a way to inform DOS that our program has terminated so it can display its command prompt again. The computer may reboot or behave improperly if this termination is not present.

Assembler, Linker, and Debugger

We need an assembler to assemble this program and convert this into executable binary code. The assembler that we will use during this course is "Netwide Assembler" or NASM. It is a free and open source assembler. And the tool that will be most used will be the debugger. We will use a free debugger called "A fullscreen debugger" or AFD. These are the whole set of

weapons an assembly language programmer needs for any task whatsoever at hand.

To assemble we will give the following command to the processor assuming that our input file is named EX01.ASM.

```
nasm ex01.asm –o ex01.com –l ex01.lst
```

This will produce two files EX01.COM that is our executable file and EX01.LST that is a special listing file that we will explore now. The listing file produced for our example above is shown below with comments removed for neatness.

```
    1
    2                                   [org 0x0100]
    3 00000000 B80500                               mov  ax, 5
    4 00000003 BB0A00                               mov  bx, 10
    5 00000006 01D8                                 add  ax, bx
    6 00000008 BB0F00                               mov  bx, 15
    7 0000000B 01D8                                 add  ax, bx
    8
    9 0000000D B8004C                               mov  ax, 0x4c00
   10 00000010 CD21                                 int  0x21
```

The first column in the above listing is offset of the listed instruction in the output file. Next column is the opcode into which our instruction was translated. In this case this opcode is B8. Whenever we move a constant into AX register the opcode B8 will be used. After it 0500 is appended which is the immediate operand to this instruction. An immediate operand is an operand which is placed directly inside the instruction. Now as the AX register is a word sized register, and one hexadecimal digit takes 4 bits so 4 hexadecimal digits make one word or two bytes. Which of the two bytes should be placed first in the instruction, the least significant or the most significant? Similarly for 32bit numbers either the order can be most significant, less significant, lesser significant, and least significant called the big-endian order used by Motorola and some other companies or it can be least significant, more significant, more significant, and most significant called the little-endian order and is used by Intel. The big-endian have the argument that it is more natural to read and comprehend while the little-endian have the argument that this scheme places the less significant value at a lesser address and more significant value at a higher address.

Because of this the constant 5 in our instruction was converted into 0500 with the least significant byte of 05 first and the most significant byte of 00 afterwards. When read as a word it is 0005 but when written in memory it will become 0500. As the first instruction is three bytes long, the listing file shows that the offset of the next instruction in the file is 3. The opcode BB is for moving a constant into the BX register, and the operand 0A00 is the number 10 in little-endian byte order. Similarly the offsets and opcodes of the remaining instructions are shown in order. The last instruction is placed at offset 0x10 or 16 in decimal. The size of the last instruction is two bytes, so the size of the complete COM file becomes 18 bytes. This can be verified from the directory listing, using the DIR command, that the COM file produced is exactly 18 bytes long.

Now the program is ready to be run inside the debugger. The debugger shows the values of registers, flags, stack, our code, and one or two areas of the system memory as data. Debugger allows us to step our program one instruction at a time and observe its effect on the registers and program data. The details of using the AFD debugger can be seen from the AFD manual.

After loading the program in the debugger observe that the first instruction is now at 0100 instead of absolute zero. This is the effect of the org directive at the start of our program. The first instruction of a COM file must be at

offset 0100 (decimal 255) as a requirement. Also observe that the debugger is showing your program even though it was provided only the COM file and neither of the listing file or the program source. This is because the translation from mnemonic to opcode is reversible and the debugger mapped back from the opcode to the instruction mnemonic. This will become apparent for instructions that have two mnemonics as the debugger might not show the one that was written in the source file.

As a result of program execution either registers or memory will change. Since our program yet doesn't touch memory the only changes will be in the registers. Keenly observe the registers AX, BX, and IP change after every instruction. IP will change after every instruction to point to the next instruction while AX will accumulate the result of our addition.

1.8. SEGMENTED MEMORY MODEL

Rationale

In earlier processors like 8080 and 8085 the linear memory model was used to access memory. In linear memory model the whole memory appears like a single array of data. 8080 and 8085 could access a total memory of 64K using the 16 lines of their address bus. When designing iAPX88 the Intel designers wanted to remain compatible with 8080 and 8085 however 64K was too small to continue with, for their new processor. To get the best of both worlds they introduced the segmented memory model in 8088.

There is also a logical argument in favor of a segmented memory model in addition to the issue of compatibility discussed above. We have two logical parts of our program, the code and the data, and actually there is a third part called the program stack as well, but higher level languages make this invisible to us. These three logical parts of a program should appear as three distinct units in memory, but making this division is not possible in the linear memory model. The segmented memory model does allow this distinction.

Mechanism


The segmented memory model allows multiple functional windows into the main memory, a code window, a data window etc. The processor sees code from the code window and data from the data window. The size of one window is restricted to 64K. 8085 software fits in just one such window. It sees code, data, and stack from this one window, so downward compatibility is attained.

However the maximum memory iAPX88 can access is 1MB which can be accessed with 20 bits. Compare this with the 64K of 8085 that were accessed using 16 bits. The idea is that the 64K window just discussed can be moved anywhere in the whole 1MB. The four segment registers discussed in the Intel register architecture are used for this purpose. Therefore four windows can exist at one time. For example one window that is pointed to by the CS register contains the currently executing code.

To understand the concept, consider the windows of a building. We say that a particular window is 3 feet above the floor and another one is 20 feet above the floor. The reference point, the floor is the base of the segment called the datum point in a graph and all measurement is done from that datum point considering it to be zero. So CS holds the zero or the base of code. DS holds the zero of data. Or we can say CS tells how high code from the floor is, and DS tells how high data from the floor is, while SS tells how high the stack is. One extra segment ES can be used if we need to access two distant areas of memory at the same time that both cannot be seen through the same window. ES also has special role in string instructions. ES is used as an extra data segment and cannot be used as an extra code or stack segment.


Revisiting the concept again, like the datum point of a graph, the segment registers tell the start of our window which can be opened anywhere in the megabyte of memory available. The window is of a fixed size of 64KB. Base and offset are the two key variables in a segmented address. Segment tells the base while offset is added into it. The registers IP, SP, BP, SI, DI, and BX all can contain a 16bit offset in them and access memory relative to a segment base.

The IP register cannot work alone. It needs the CS register to open a 64K window in the 1MB memory and then IP works to select code from this window as offsets. IP works only inside this window and cannot go outside of this 64K in any case. If the window is moved i.e. the CS register is changed, IP will change its behavior accordingly and start selecting from the new window. The IP register always works relatively, relative to the segment base stored in the CS register. IP is a 16bit register capable of accessing only 64K memory so how the whole megabyte can contain code anywhere. Again the same concept is there, it can access 64K at one instance of time. As the base is changed using the CS register, IP can be made to point anywhere in the whole megabyte. The process is illustrated with the following diagram.



Physical Address Calculation

Now for the whole megabyte we need 20 bits while CS and IP are both 16bit registers. We need a mechanism to make a 20bit number out of the two 16bit numbers. Consider that the segment value is stored as a 20 bit number with the lower four bits zero and the offset value is stored as another 20 bit number with the upper four bits zeroed. The two are added to produce a 20bit absolute address. A carry if generated is dropped without being stored anywhere and the phenomenon is called address wraparound. The process is explained with the help of the following diagram.



Therefore memory is determined by a segment-offset pair and not alone by any one register which will be an ambiguous reference. Every offset register is assigned a default segment register to resolve such ambiguity. For example the program we wrote when loaded into memory had a value of 0100 in IP register and some value say 1DDD in the CS register. Making both 20 bit numbers, the segment base is 1DDD0 and the offset is 00100 and adding them we get the physical memory address of 1DED0 where the opcode B80500 is placed.

Paragraph Boundaries


As the segment value is a 16bit number and four zero bits are appended to the right to make it a 20bit number, segments can only be defined a 16byte boundaries called paragraph boundaries. The first possible segment value is 0000 meaning a physical base of 00000 and the next possible value of 0001 means a segment base of 00010 or 16 in decimal. Therefore segments can only be defined at 16 byte boundaries.

Overlapping Segments

We can also observe that in the case of our program CS, DS, SS, and ES all had the same value in them. This is called overlapping segments so that we can see the same memory from any window. This is the structure of a COM file.

Using partially overlapping segments we can produce a number of segment, offset pairs that all access the same memory. For example 1DDD:0100 and IDED:0000 both point to the same physical memory. To test this we can open a data window at 1DED:0000 in the debugger and change the first three bytes to “90” which is the opcode for NOP (no operation). The change is immediately visible in the code window which is pointed to by CS containing 1DDD. Similarly IDCD:0200 also points to the same memory location. Consider this like a portion of wall that three different people on three different floors are seeing through their own windows. One of them painted the wall red; it will be changed for all of them though their perspective is different. It is the same phenomenon occurring here.

The segment, offset pair is called a logical address, while the 20bit address is a physical address which is the real thing. Logical addressing is a mechanism to access the physical memory. As we have seen three different logical addresses accessed the same physical address.



EXERCISES

1. How the processor uses the address bus, the data bus, and the control bus to communicate with the system memory?
2. Which of the following are unidirectional and which are bidirectional?
   a. Address Bus
   b. Data Bus
   c. Control Bus
3. What are registers and what are the specific features of the accumulator, index registers, program counter, and program status word?
4. What is the size of the accumulator of a 64bit processor?
5. What is the difference between an instruction mnemonic and its opcode?
6. How are instructions classified into groups?
7. A combination of 8bits is called a byte. What is the name for 4bits and for 16bits?
8. What is the maximum memory 8088 can access?
9. List down the 14 registers of the 8088 architecture and briefly describe their uses.
10. What flags are defined in the 8088 FLAGS register? Describe the function of the zero flag, the carry flag, the sign flag, and the overflow flag.
11. Give the value of the zero flag, the carry flag, the sign flag, and the overflow flag after each of the following instructions if AX is initialized with 0x1254 and BX is initialized with 0x0FFF.
    a. add ax, 0xEDAB
    b. add ax, bx
    c. add bx, 0xF001
12. What is the difference between little endian and big endian formats? Which format is used by the Intel 8088 microprocessor?
13. For each of the following words identify the byte that is stored at lower memory address and the byte that is stored at higher memory address in a little endian computer.
    a. 1234
    b. ABFC
    c. B100
    d. B800

14. What are the contents of memory locations 200, 201, 202, and 203 if the word 1234 is stored at offset 200 and the word 5678 is stored at offset 202?
15. What is the offset at which the first executable instruction of a COM file must be placed?
16. Why was segmentation originally introduced in 8088 architecture?
17. Why a segment start cannot start from the physical address 55555.
18. Calculate the physical memory address generated by the following segment offset pairs.
    a. 1DDD:0436
    b. 1234:7920
    c. 74F0:2123
    d. 0000:6727
    e. FFFF:4336
    f. 1080:0100
    g. AB01:FFFF
19. What are the first and the last physical memory addresses accessible using the following segment values?
    a. 1000
    b. 0FFF
    c. 1002
    d. 0001
    e. E000
20. Write instructions that perform the following operations.
    a. Copy BL into CL
    b. Copy DX into AX
    c. Store 0x12 into AL
    d. Store 0x1234 into AX
    e. Store 0xFFFF into AX
21. Write a program in assembly language that calculates the square of six by adding six to the accumulator six times.

2
Addressing Modes

2.1. DATA DECLARATION

The first instruction of our first assembly language program was “mov ax, 5.” Here MOV was the opcode; AX was the destination operand, while 5 was the source operand. The value of 5 in this case was stored as part of the instruction encoding. In the opcode B80500, B8 was the opcode and 0500 was the operand stored immediately afterwards. Such an operand is called an immediate operand. It is one of the many types of operands available.

Writing programs using just the immediate operand type is difficult. Every reasonable program needs some data in memory apart from constants. Constants cannot be changed, i.e. they cannot appear as the destination operand. In fact placing them as destination is meaningless and illegal according to assembly language syntax. Only registers or data placed in memory can be changed. So real data is the one stored in memory, with a very few constants. So there must be a mechanism in assembly language to store and retrieve data from memory.

To declare a part of our program as holding data instead of instructions we need a couple of very basic but special assembler directives. The first directive is “define byte” written as “db.”

```
db   somevalue
```

As a result a cell in memory will be reserved containing the desired value in it and it can be used in a variety of ways. Now we can add variables instead of constants. The other directive is “define word” or “dw” with the same syntax as “db” but reserving a whole word of 16 bits instead of a byte. There are directives to declare a double or a quad word as well but we will restrict ourselves to byte and word declarations for now. For single byte we use db and for two bytes we use dw.

To refer to this variable later in the program, we need the address occupied by this variable. The assembler is there to help us. We can associate a symbol with any address that we want to remember and use that symbol in the rest of the code. The symbol is there for our own comprehension of code. The assembler will calculate the address of that symbol using our origin directive and calculating the instruction lengths or data declarations in-between and replace all references to the symbol with the corresponding address. This is just like variables in a higher level language, where the compiler translates them into addresses; just the process is hidden from the programmer one level further. Such a symbol associated to a point in the program is called a label and is written as the label name followed by a colon.

2.2. DIRECT ADDRESSING

Now we will rewrite our first program such that the numbers 5, 10, and 15 are stored as memory variables instead of constants and we access them from there.

Example 2.1

```
001     ; a program to add three numbers using memory variables
002     [org 0x0100]
003                 mov  ax, [num1]         ; load first number in ax
```

```
004                 mov  bx, [num2]         ; load second number in bx
005                 add  ax, bx             ; accumulate sum in ax
006                 mov  bx, [num3]         ; load third number in bx
007                 add  ax, bx             ; accumulate sum in ax
008                 mov  [num4], ax         ; store sum in num4
009
010                 mov  ax, 0x4c00         ; terminate program
011                 int  0x21
012
013     num1:       dw   5
014     num2:       dw   10
015     num3:       dw   15
016     num4:       dw   0
```

002	Originate our program at 0100. The first executable instruction should be placed at this offset.
003	The source operand is changed from constant 5 to [num1]. The bracket is signaling that the operand is placed in memory at address num1. The value 5 will be loaded in ax even though we did not specified it in our program code, rather the value will be picked from memory. The instruction should be read as "read the contents of memory location num1 in the ax register." The label num1 is a symbol for us but an address for the processor while the conversion is done by the assembler.
013	The label num1 is defined as a word and the assembler is requested to place 5 in that memory location. The colon signals that num1 is a label and not an instruction.

Using the same process to assemble as discussed before we examine the listing file generated as a result with comments removed.

```
 1
 2                                  [org 0x0100]
 3 00000000 A1[1700]                             mov  ax, [num1]
 4 00000003 8B1E[1900]                           mov  bx, [num2]
 5 00000007 01D8                                 add  ax, bx
 6 00000009 8B1E[1B00]                           mov  bx, [num3]
 7 0000000D 01D8                                 add  ax, bx
 8 0000000F A3[1D00]                             mov  [num4], ax
 9
10 00000012 B8004C                               mov  ax, 0x4c00
11 00000015 CD21                                 int  0x21
12
13 00000017 0500                   num1:         dw   5
14 00000019 0A00                   num2:         dw   10
15 0000001B 0F00                   num3:         dw   15
16 0000001D 0000                   num4:         dw   0
```

The first instruction of our program has changed from B80500 to A11700. The opcode B8 is used to move constants into AX, while the opcode A1 is used when moving data into AX from memory. The immediate operand to our new instruction is 1700 or as a word 0017 (23 decimal) and from the bottom of the listing file we can observe that this is the offset of num1. The assembler has calculated the offset of num1 and used it to replace references to num1 in the whole program. Also the value 0500 can be seen at offset 0017 in the file. We can say contents of memory location 0017 are 0005 as a word. Similarly num2, num3, and num4 are placed at 0019, 001B, and 001D addresses.

When the program is loaded in the debugger, it is loaded at offset 0100, which displaces all memory accesses in our program. The instruction A11700 is changed to A11701 meaning that our variable is now placed at 0117 offset. The instruction is shown as mov ax, [0117]. Also the data window can be used to verify that offset 0117 contains the number 0005.

Execute the program step by step and examine how the memory is read and the registers are updated, how the instruction pointer moves forward, and how the result is saved back in memory. Also observe inside the debugger code window below the code for termination, that the debugger is interpreting our data as code and showing it as some meaningless instructions. This is because the debugger sees everything as code in the code window and cannot differentiate our declared data from opcodes. It is our responsibility that we terminate execution before our data is executed as code.

Also observe that our naming of num1, num2, num3, and num4 is no longer there inside the debugger. The debugger is only showing the numbers 0117, 0119, 011B, and 011D. Our numerical machine can only work with numbers. We used symbols for our ease to label or tag certain positions in our program. The assembler converts these symbols into the appropriate numbers automatically. Also observe that the effect of "dw" is to place 5 in two bytes as 0005. Had we used "db" this would have been stored as 05 in one byte.

Given the fact that the assembler knows only numbers we can write the same program using a single label. As we know that num2 is two ahead of num1, we can use num1+2 instead of num2 and let the assembler calculate the sum during assembly process.

Example 2.2

```
001     ; a program to add three numbers accessed using a single label
002     [org 0x0100]
003                 mov  ax, [num1]         ; load first number in ax
004                 mov  bx, [num1+2]       ; load second number in bx
005                 add  ax, bx             ; accumulate sum in ax
006                 mov  bx, [num1+4]       ; load third number in bx
007                 add  ax, bx             ; accumulate sum in ax
008                 mov  [num1+6], ax       ; store sum at num1+6
009
010                 mov  ax, 0x4c00         ; terminate program
011                 int  0x21
012
013     num1:       dw   5
014                 dw   10
015                 dw   15
016                 dw   0
```

004	The second number is read from num1+2. Similarly the third number is read from num1+4 and the result is accessed at num1+6.
013-016	The labels num2, num3, and num4 are removed and the data there will be accessed with reference to num1.

Every location is accessed with reference to num1 in this example. The expression "num1+2" comprises of constants only and can be evaluated at the time of assembly. There are no variables involved in this expression. As we open the program inside the debugger we see a verbatim copy of the previous program. There is no difference at all since the assembler catered for the differences during assembly. It calculated 0117+2=0119 while in the previous it directly knew from the value of num2 that it has to write 0119, but the end result is a ditto copy of the previous execution.

Another way to declare the above data and produce exactly same results is shown in the following example.

Example 2.3

```
001     ; a program to add three numbers accessed using a single label
002     [org 0x0100]
003                 mov  ax, [num1]         ; load first number in ax
004                 mov  bx, [num1+2]       ; load second number in bx
```

```
005                 add  ax, bx             ; accumulate sum in ax
006                 mov  bx, [num1+4]       ; load third number in bx
007                 add  ax, bx             ; accumulate sum in ax
008                 mov  [num1+6], ax       ; store sum at num1+6
009
010                 mov  ax, 0x4c00         ; terminate program
011                 int  0x21
012
013 num1:           dw   5, 10, 15, 0
```

013 As we do not need to place labels on individual variables we can save space and declare all data on a single line separated by commas. This declaration will declare four words in consecutive memory locations while the address of first one is num1.

The method used to access memory in the above examples is called direct addressing. In direct addressing the memory address is fixed and is given in the instruction. The actual data used is placed in memory and now that data can be used as the destination operand as well. Also the source and destination operands must have the same size. For example a word defined memory is read in a word sized register. A last observation is that the data 0500 in memory was corrected to 0005 when read in a register. So registers contain data in proper order as a word.

A last variation using direct addressing shows that we can directly add a memory variable and a register instead of adding a register into another that we were doing till now.

Example 2.4

```
01  ; a program to add three numbers directly in memory
02  [org 0x0100]
03                  mov  ax, [num1]         ; load first number in ax
04                  mov  [num1+6], ax       ; store first number in result
05                  mov  ax, [num1+2]       ; load second number in ax
06                  add  [num1+6], ax       ; add second number to result
07                  mov  ax, [num1+4]       ; load third number in ax
08                  add  [num1+6], ax       ; add third number to result
09
10                  mov  ax, 0x4c00         ; terminate program
11                  int  0x21
12
13  num1:           dw   5, 10, 15, 0
```

We generate the following listing file as a result of the assembly process described previously. Comments are again removed.

```
    1
    2                                   [org 0x0100]
    3 00000000 A1[1900]                             mov  ax, [num1]
    4 00000003 A3[1F00]                             mov  [num1+6], ax
    5 00000006 A1[1B00]                             mov  ax, [num1+2]
    6 00000009 0106[1F00]                           add  [num1+6], ax
    7 0000000D A1[1D00]                             mov  ax, [num1+4]
    8 00000010 0106[1F00]                           add  [num1+6], ax
    9
   10 00000014 B8004C                               mov  ax, 0x4c00
   11 00000017 CD21                                 int  0x21
   12
   13 00000019 05000A000F000000        num1:       dw   5, 10, 15, 0
```

The opcode of add is changed because the destination is now a memory location instead of a register. No other significant change is seen in the listing file. Inside the debugger we observe that few opcodes are longer now and the location num1 is now translating to 0119 instead of 0117. This is done automatically by the assembler as a result of using labels instead of

hard coding addresses. During execution we observe that the word data as it is read into a register is read in correct order. The significant change in this example is that the destination of addition is memory. Method to access memory is direct addressing, whether it is the MOV instruction or the ADD instruction.

The first two instructions of the last program read a number into AX and placed it at another memory location. A quick thought reveals that the following might be a possible single instruction to replace the couple.

```
mov  [num1+6], [num1]   ; ILLEGAL
```

However this form is illegal and not allowed on the Intel architecture. None of the general operations of mov add, sub etc. allow moving data from memory to memory. Only register to register, register to memory, memory to register, constant to memory, and constant to register operations are allowed. The other register to constant, memory to constant, and memory to memory are all disallowed. Only string instructions allow moving data from memory to memory and will be discussed in detail later. As a rule one instruction can have at most one operand in brackets, otherwise assembler will give an error.

2.3. SIZE MISMATCH ERRORS

If we change the directive in the last example from DW to DB, the program will still assemble and debug without errors, however the results will not be the same as expected. When the first operand is read 0A05 will be read in the register which was actually two operands place in consecutive byte memory locations. The second number will be read as 000F which is the zero byte of num4 appended to the 15 of num3. The third number will be junk depending on the current state of the machine. According to our data declaration the third number should be at 0114 but it is accessed at 011D calculated with word offsets. This is a logical error of the program. To keep the declarations and their access synchronized is the responsibility of the programmer and not the assembler. The assembler allows the programmer to do everything he wants to do, and that can possibly run on the processor. The assembler only keeps us from writing illegal instructions which the processor cannot execute. This is the difference between a syntax error and a logic error. So the assembler and debugger have both done what we asked them to do but the programmer asked them to do the wrong chore.

The programmer is responsible for accessing the data as word if it was declared as a word and accessing it as a byte if it was declared as a byte. The word case is shown in lot of previous examples. If however the intent is to treat it as a byte the following code shows the appropriate way.

Example 2.5

```
001     ; a program to add three numbers using byte variables
002     [org 0x0100]
003                 mov  al, [num1]         ; load first number in al
004                 mov  bl, [num1+1]       ; load second number in bl
005                 add  al, bl             ; accumulate sum in al
006                 mov  bl, [num1+2]       ; load third number in bl
007                 add  al, bl             ; accumulate sum in al
008                 mov  [num1+3], al       ; store sum at num1+3
009
010                 mov  ax, 0x4c00         ; terminate program
011                 int  0x21
012
013     num1:       db   5, 10, 15, 0
```

003 The number is read in AL register which is a byte register since the memory location read is also of byte size.

005 The second number is now placed at num1+1 instead of num1+2 because of byte offsets.

013	To declare data db is used instead of dw so that each data declared occupies one byte only.

Inside the debugger we observe that the AL register takes appropriate values and the sum is calculated and stored in num1+3. This time there is no alignment or synchronization error. The key thing to understand here is that the processor does not match defines to accesses. It is the programmer's responsibility. In general assembly language gives a lot of power to the programmer but power comes with responsibility. Assembly language programming is not a difficult task but a responsible one.

In the above examples, the processor knew the size of the data movement operation from the size of the register involved, for example in "mov ax, [num1]" memory can be accessed as byte or as word, it has no hard and fast size, but the AX register tells that this operation has to be a word operation. Similarly in "mov al, [num1]" the AL register tells that this operation has to be a byte operation. However in "mov ax, bl" the AX register tells that the operation has to be a word operation while BL tells that this has to be a byte operation. The assembler will declare that this is an illegal instruction. A 5Kg bag cannot fit inside a 1Kg bag and according to Intel a 1Kg cannot also fit in a 5Kg bag. They must match in size. The instruction "mov [num1], [num2]" is illegal as previously discussed not because of data movement size but because memory to memory moves are not allowed at all.

The instruction "mov [num1], 5" is legal but there is no way for the processor to know the data movement size in this operation. The variable num1 can be treated as a byte or as a word and similarly 5 can be treated as a byte or as a word. Such instructions are declared ambiguous by the assembler. The assembler has no way to guess the intent of the programmer as it previously did using the size of the register involved but there is no register involved this time. And memory is a linear array and label is an address in it. There is no size associated with a label. Therefore to resolve its ambiguity we clearly tell our intent to the assembler in one of the following ways.

```
mov  byte [num1], 5
mov  word [num1], 5
```

2.4. REGISTER INDIRECT ADDRESSING

We have done very elementary data access till now. Assume that the numbers we had were 100 and not just three. This way of adding them will cost us 200 instructions. There must be some method to do a task repeatedly on data placed in consecutive memory cells. The key to this is the need for some register that can hold the address of data. So that we can change the address to access some other cell of memory using the same instruction. In direct addressing mode the memory cell accessed was fixed inside the instruction. There is another method in which the address can be placed in a register so that it can be changed. For the following example we will take 10 instead of 100 numbers but the algorithm is extensible to any size.

There are four registers in iAPX88 architecture that can hold address of data and they are BX, BP, SI, and DI. There are minute differences in their working which will be discussed later. For the current example, we will use the BX register and we will take just three numbers and extend the concept with more numbers in later examples.

Example 2.6

```
001     ; a program to add three numbers using indirect addressing
002     [org 0x100]
003                 mov  bx, num1           ; point bx to first number
004                 mov  ax, [bx]           ; load first number in ax
005                 add  bx, 2              ; advance bx to second number
```

```
006                 add  ax, [bx]           ; add second number to ax
007                 add  bx, 2              ; advance bx to third number
008                 add  ax, [bx]           ; add third number to ax
009                 add  bx, 2              ; advance bx to result
010                 mov  [bx], ax           ; store sum at num1+6
011
012                 mov  ax, 0x4c00         ; terminate program
013                 int  0x21
014
015 num1:           dw   5, 10, 15, 0
```

003 Observe that no square brackets around num1 are used this time. The address is loaded in bx and not the contents. Value of num1 is 0005 and the address is 0117. So BX will now contain 0117.

004 Brackets are now used around BX. In iapx88 architecture brackets can be used around BX, BP, SI, and DI only. In iapx386 more registers are allowed. The instruction will be read as "move into ax the contents of the memory location whose address is in bx." Now since bx contains the address of num1 the contents of num1 are transferred to the ax register. Without square brackets the meaning of the instruction would have been totally different.

005 This instruction is changing the address. Since we have words not bytes, we add two to bx so that it points to the next word in memory. BX now contains 0119 the address of the second word in memory. This was the mechanism to change addresses that we needed.

Inside the debugger we observe that the first instruction is "mov bx, 011C." A constant is moved into BX. This is because we did not use the square brackets around "num1." The address of "num1" has moved to 011C because the code size has changed due to changed instructions. In the second instruction BX points to 011C and the value read in AX is 0005 which can be verified from the data window. After the addition BX points to 011E containing 000A, our next word, and so on. This way the BX register points to our words one after another and we can add them using the same instruction "mov ax, [bx]" without fixing the address of our data in the instructions. We can also subtract from BX to point to previous cells. The address to be accessed is now in total program control.

One thing that we needed in our problem to add hundred numbers was the capability to change address. The second thing we need is a way to repeat the same instruction and a way to know that the repetition is done a 100 times, a terminal condition for the repetition. For the task we are introducing two new instructions that you should read and understand as simple English language concepts. For simplicity only 10 numbers are added in this example. The algorithm is extensible to any size.

Example 2.7

```
001 ; a program to add ten numbers
002 [org 0x0100]
003                 mov  bx, num1           ; point bx to first number
004                 mov  cx, 10             ; load count of numbers in cx
005                 mov  ax, 0              ; initialize sum to zero
006
007 l1:             add  ax, [bx]           ; add number to ax
008                 add  bx, 2              ; advance bx to next number
009                 sub  cx, 1              ; numbers to be added reduced
010                 jnz  l1                 ; if numbers remain add next
011
012                 mov  [total], ax        ; write back sum in memory
013
014                 mov  ax, 0x4c00         ; terminate program
015                 int  0x21
016
017 num1:           dw   10, 20, 30, 40, 50, 10, 20, 30, 40, 50
```

018	`total:  dw  0`
006	Labels can be used on code as well. Just like data labels they remember the address at which they are used. The assembler does not differentiate between code labels and data labels. The programmer is responsible for using a data label as data and a code label as code. The label l1 in this case is the address of the following instruction.
009	SUB is the counterpart to ADD with the same rules as that of the ADD instruction.
010	JNZ stands for “jump if not zero.” NZ is the condition in this instruction. So the instruction is read as “jump to the location l1 if the zero flag is not set.” And revisiting the zero flag definition “the zero flag is set if the last mathematical or logical operation has produced a zero in its destination.” For example “mov ax, 0” will not set the zero flag as it is not a mathematical or logical instruction. However subtraction and addition will set it. Also it is set even when the destination is not a register. Now consider the subtraction immediately preceding it. As long as the CX register is non zero after this subtraction the zero flag will not be set and the jump will be taken. And jump to l1, the processor needs to be told each and everything and the destination is an important part of every jump. Just like when we ask someone to go, we mention go to this market or that house. The processor is much more logical than us and needs the destination in every instruction that asks it to go somewhere. The processor will load l1 in the IP register and resume execution from there. The processor will blindly go to the label we mention even if it contains data and not code.

The CX register is used as a counter in this example, BX contains the changing address, while AX accumulates the result. We have formed a loop in assembly language that executes until its condition remains true. Inside the debugger we can observe that the subtract instruction clears the zero flag the first nine times and sets it on the tenth time. While the jump instruction moves execution to address l1 the first nine times and to the following line the tenth time. The jump instruction breaks program flow.

The JNZ instruction is from the program control group and is a conditional jump, meaning that if the condition NZ is true (ZF=0) it will jump to the address mentioned and otherwise it will progress to the next instruction. It is a selection between two paths. If the condition is true go right and otherwise go left. Or we can say if the weather is hot, go this way, and if it is cold, go this way. Conditional jump is the most important instruction, as it gives the processor decision making capability, so it must be given a careful thought. Some processors call it branch, probably a more logical name for it, however the functionality is same. Intel chose to name it “jump.”

An important thing in the above example is that a register is used to reference memory so this form of access is called register indirect memory access. We used the BX register for it and the B in BX and BP stands for base therefore we call register indirect memory access using BX or BP, “based addressing.” Similarly when SI or DI is used we name the method “indexed addressing.” They have the same functionality, with minor differences because of which the two are called base and index. The differences will be explained later, however for the above example SI or DI could be used as well, but we would name it indexed addressing instead of based addressing.

2.5. REGISTER + OFFSET ADDRESSING

Direct addressing and indirect addressing using a single register are two basic forms of memory access. Another possibility is to use different combinations of direct and indirect references. In the above example we used BX to access different array elements which were placed consecutively in memory like an array. We can also place in BX only the array index and not the exact address and form the exact address when we are going to access the actual memory. This way the same register can be used for accessing different arrays and also the register can be used for index comparison like the following example does.

Example 2.8

```
001     ; a program to add ten numbers using register + offset addressing
002     [org 0x0100]
003                 mov  bx, 0              ; initialize array index to zero
004                 mov  cx, 10             ; load count of numbers in cx
005                 mov  ax, 0              ; initialize sum to zero
006
007     l1:         add  ax, [num1+bx]      ; add number to ax
008                 add  bx, 2              ; advance bx to next index
009                 sub  cx, 1              ; numbers to be added reduced
010                 jnz  l1                 ; if numbers remain add next
011
012                 mov  [total], ax        ; write back sum in memory
013
014                 mov  ax, 0x4c00         ; terminate program
015                 int  0x21
016
017     num1:       dw   10, 20, 30, 40, 50, 10, 20, 30, 40, 50
018     total:      dw   0
```

003	This time BX is initialized to zero instead of array base
007	The format of memory access has changed. The array base is added to BX containing array index at the time of memory access.
008	As the array is of words, BX jumps in steps of two, i.e. 0, 2, 4. Higher level languages do appropriate incrementing themselves and we always use sequential array indexes. However in assembly language we always calculate in bytes and therefore we need to take care of the size of one array element which in this case is two.

Inside the debugger we observe that the memory access instruction is shown as “mov ax, [011F+bx]” and the actual memory accessed is the one whose address is the sum of 011F and the value contained in the BX register. This form of access is of the register indirect family and is called base + offset or index + offset depending on whether BX or BP is used or SI or DI is used.

2.6. SEGMENT ASSOCIATION

All the addressing mechanisms in iAPX88 return a number called *effective address*. For example in base + offset addressing, neither the base nor the offset alone tells the desired cell in memory to be accessed. It is only after the addition is done that the processor knows which cell to be accessed. This number which came as the result of addition is called the effective address. But the effective address is just an offset and is meaningless without a segment. Only after the segment is known, we can form the physical address that is needed to access a memory cell.

We discussed the segmented memory model of iAPX88 in reasonable detail at the end of previous chapter. However during the discussion of addressing modes we have not seen the effect of segments. Segmentation is there and it’s all happening relative to a segment base. We saw DS, CS, SS, and ES

inside the debugger. Everything is relative to its segment base, even though we have not explicitly explained its functionality. An offset alone is not complete without a segment. As previously discussed there is a default segment associated to every register which accesses memory. For example CS is associated to IP by default; rather it is tied with it. It cannot access memory in any other segment.

In case of data, there is a bit relaxation and nothing is tied. Rather there is a default association which can be overridden. In the case of register indirect memory access, if the register used is one of SI, DI, or BX the default segment is DS. If however the register used is BP the default segment used is SS. The stack segment has a very critical and fine use and there is a reason why BP is attached to SS by default. However these will be discussed in detail in the chapter on stack. IP is tied to CS while SP is tied to SS. The association of these registers cannot be changed; they are locked with no option. Others are not locked and can be changed.

To override the association for one instruction of one of the registers BX, BP, SI or DI, we use the segment override prefix. For example "mov ax, [cs:bx]" associates BX with CS for this one instruction. For the next instruction the default association will come back to act. The processor places a special byte before the instruction called a prefix, just like prefixes and suffixes in English language. No prefix is needed or placed for default association. For example for CS the byte 2E is placed and for ES the byte 26 is placed. Opcode has not changed, but the prefix byte has modified the default association to association with the desired segment register for this one instruction.

In all our examples, we never declared a segment or used it explicitly, but everything seemed to work fine. The important thing to note is that CS, DS, SS, and ES all had the same value. The value itself is not important but the fact that all had the same value is important. All four segment windows exactly overlap. Whatever segment register we use the same physical memory will be accessed. That is why everything was working without the mention of a single segment register. This is the formation of COM files in IBM PC. A single segment contains code, data, and the stack. This format is operating system dependant, in our case defined by DOS. And our operating system defines the format of COM files such that all segments have the same value. Thus the only meaningful thing that remains is the offset.

For example if BX=0100, SI=0200, and CS=1000 and the memory access under consideration is [cs:bx+si+0x0700], the effective address formed is bx+si+0700 = 0100 + 0200 + 0700 = 0A00. Now multiplying the segment value by 16 makes it 10000 and adding the effective address 00A00 forms the physical address 10A00.

2.7. ADDRESS WRAPAROUND

There are two types of wraparounds. One is within a single segment and the other is inside the whole physical memory. Segment wraparound occurs when during the effective address calculation a carry is generated. This carry is dropped giving the effect that when we try to access beyond the segment limit, we are actually wrapped around to the first cell in the segment. For example if BX=9100, DS=1500 and the access is [bx+0x7000] we form the effective address 9100 + 7000 = 10100. The carry generated is dropped forming the actual effective address of 0100. Just like a circle when we reached the end we started again from the beginning. An arc at 370 degrees is the same as an arc at 10 degrees. We tried to cross the segment boundary and it pushed us back to the start. This is called segment wraparound. The physical address in the above example will be 15100.

The same can also happen at the time of physical address calculation. For example BX=0100, DS=FFF0 and the access under consideration is [bx+0x0100]. The effective address will be 0200 and the physical address will

be 100100. This is a 21bit answer and cannot be sent on the address bus which is 20 bits wide. The carry is dropped and just like the segment wraparound our physical memory has wrapped around at its very top. When we tried to access beyond limits the actual access is made at the very start. This second wraparound is a bit different in newer processor with more address lines but that will be explained in later chapters.

2.8. ADDRESSING MODES SUMMARY

The iAPX88 processor supports seven modes of memory access. Remember that immediate is not an addressing mode but an operand type. Operands can be immediate, register, or memory. If the operand is memory one of the seven addressing modes will be used to access it. The memory access mechanisms can also be written in the general form "base + index + offset" and we can define the possible addressing modes by saying that any one, two, or none can be skipped from the general form to form a legal memory access.

There are a few common mistakes done in forming a valid memory access. Part of a register cannot be used to access memory. Like BX is allowed to hold an address but BL or BH are not. Address is 16bit and must be contained in a 16bit register. BX-SI is not possible. The only thing that we can do is addition of a base register with an index register. Any other operation is disallowed. BS+BP and SI+DI are both disallowed as we cannot have two base or two index registers in one memory access. One has to be a base register and the other has to be an index register and that is the reason of naming them differently.

Direct

A fixed offset is given in brackets and the memory at that offset is accessed. For example "mov [1234], ax" stores the contents of the AX registers in two bytes starting at address 1234 in the current data segment. The instruction "mov [1234], al" stores the contents of the AL register in the byte at offset 1234.

Based Register Indirect

A base register is used in brackets and the actual address accessed depends on the value contained in that register. For example "mov [bx], ax" moves the two byte contents of the AX register to the address contained in the BX register in the current data segment. The instruction "mov [bp], al" moves the one byte content of the AL register to the address contained in the BP register in the current stack segment.

Indexed Register Indirect

An index register is used in brackets and the actual address accessed depends on the value contained in that register. For example "mov [si], ax" moves the contents of the AX register to the word starting at address contained in SI in the current data segment. The instruction "mov [di], ax" moves the word contained in AX to the offset stored in DI in the current data segment.

Based Register Indirect + Offset

A base register is used with a constant offset in this addressing mode. The value contained in the base register is added with the constant offset to get the effective address. For example "mov [bx+300], ax" stores the word contained in AX at the offset attained by adding 300 to BX in the current data segment. The instruction "mov [bp+300], ax" stores the word in AX to the offset attained by adding 300 to BP in the current stack segment.

Indexed Register Indirect + Offset

An index register is used with a constant offset in this addressing mode. The value contained in the index register is added with the constant offset to get the effective address. For example "mov [si+300], ax" moves the word contained in AX to the offset attained by adding 300 to SI in the current data segment and the instruction "mov [di+300], al" moves the byte contained in AL to the offset attained by adding 300 to DI in the current data segment.

Base + Index

One base and one index register is used in this addressing mode. The value of the base register and the index register are added together to get the effective address. For example "mov [bx+si], ax" moves the word contained in the AX register to offset attained by adding BX and SI in the current data segment. The instruction "mov [bp+di], al" moves the byte contained in AL to the offset attained by adding BP and DI in the current stack segment. Observe that the default segment is based on the base register and not on the index register. This is why base registers and index registers are named separately. Other examples are "mov [bx+di], ax" and "mov [bp+si], ax." This method can be used to access a two dimensional array such that one dimension is in a base register and the other is in an index register.

Base + Index + Offset

This is the most complex addressing method and is relatively infrequently used. A base register, an index register, and a constant offset are all used in this addressing mode. The values of the base register, the index register, and the constant offset are all added together to get the effective address. For example "mov [bx+si+300], ax" moves the word contents of the AX register to the word in memory starting at offset attained by adding BX, SI, and 300 in the current data segment. Default segment association is again based on the base register. It might be used with the array base of a two dimensional array as the constant offset, one dimension in the base register and the other in the index register. This way all calculation of location of the desired element has been delegated to the processor.

EXERCISES

1. What is a label and how does the assembler differentiates between code labels and data labels?
2. List the seven addressing modes available in the 8088 architecture.
3. Differentiate between effective address and physical address.
4. What is the effective address generated by the following instructions? Every instruction is independent of others. Initially BX=0x0100, num1=0x1001, [num1]=0x0000, and SI=0x0100
    a. mov ax, [bx+12]
    b. mov ax, [bx+num1]
    c. mov ax, [num1+bx]
    d. mov ax, [bx+si]
5. What is the effective address generated by the following combinations if they are valid. If not give reason. Initially BX=0x0100, SI=0x0010, DI=0x0001, BP=0x0200, and SP=0xFFFF
    a. bx-si
    b. bx-bp
    c. bx+10
    d. bx-10
    e. bx+sp
    f. bx+di
6. Identify the problems in the following instructions and correct them by replacing them with one or two instruction having the same effect.

a. mov [02], [22]
b. mov [wordvar], 20
c. mov bx, al
d. mov ax, [si+di+100]

7. What is the function of segment override prefix and what changes it brings to the opcode?
8. What are the two types of address wraparound? What physical address is accessed with [BX+SI] if FFFF is loaded in BX, SI, and DS.
9. Write instructions to do the following.
    a. Copy contents of memory location with offset 0025 in the current data segment into AX.
    b. Copy AX into memory location with offset 0FFF in the current data segment.
    c. Move contents of memory location with offset 0010 to memory location with offset 002F in the current data segment.
10. Write a program to calculate the square of 20 by using a loop that adds 20 to the accumulator 20 times.

3
Branching

3.1. COMPARISON AND CONDITIONS

Conditional jump was introduced in the last chapter to loop for the addition of a fixed number of array elements. The jump was based on the zero flag. There are many other conditions possible in a program. For example an operand can be greater than another operand or it can be smaller. We use comparisons and boolean expressions extensively in higher level languages. They must be available is some form in assembly language, otherwise they could not possibly be made available in a higher level language. In fact they are available in a very fine and purified form.

The basic root instruction for all comparisons is CMP standing for compare. The operation of CMP is to subtract the source operand from the destination operand, updating the flags without changing either the source or the destination. CMP is one of the key instructions as it introduces the capability of conditional routing in the processor.

A closer thought reveals that with subtraction we can check many different conditions. For example if a larger number is subtracted from a smaller number then borrow is needed. The carry flag plays the role of borrow during the subtraction operation. And in this condition the carry flag will be set. If two equal numbers are subtracted the answer is zero and the zero flag will be set. Every significant relation between the destination and source is evident from the sign flag, carry flag, zero flag, and the overflow flag. CMP is meaningless without a conditional jump immediately following it.

Another important distinction at this point is the difference between signed and unsigned numbers. In unsigned numbers only the magnitude of the number is important, whereas in signed numbers both the magnitude and the sign are important. For example -2 is greater than -3 but 2 is smaller than 3. The sign has affected our comparisons.

Inside the computer signed numbers are represented in two's complement notation. In essence a number in this representation is still a number, just that now our interpretation of this number will be signed. Whether we use jump above and below or we use jump greater or less will convey our intention to the processor. The jump above and greater operations at first sight seem to be doing the same operation, and similarly below and less operations seem to be similar. However for signed numbers JG and JL will work properly and for unsigned JA and JB will work properly and not the other way around.

It is important to note that at the time of comparison, the intent of the programmer to treat the numbers as signed or unsigned is not clear. The subtraction in CMP is a normal subtraction. It is only after the comparison, during the conditional jump operation, that the intent is conveyed. At that time with a specific combination of flags checked the intent is satisfied.

For example a number 2 is represented in a word as 0002 while the number -2 is represented as FFFE. In a byte they would be represented as 02 and FE. Now both have the same magnitude however the different sign has caused very different representation in two's complement form. Now if the intent is to use FFFE or decimal 65534 then the same data would be placed in the word as in case of -2. In fact if -2 and 65534 are compared the processor will set the zero flag signaling that they are exactly equal. As regards an unsigned comparison the number 65534 is much greater than 2.

So if a JA is taken after comparing -2 in the destination with 2 in the source the jump will be taken. If however JG is used after the same comparison the jump will not be taken as it will consider the sign and with the sign -2 is smaller than 2. The key idea is that -2 and 65534 were both stored in memory in the same form. It was the interpretation that treated it as a signed or as an unsigned number.

The unsigned comparisons see the numbers as 0 being the smallest and 65535 being the largest with the order that 0 < 1 < 2 … < 65535. The signed comparisons see the number -32768 which has the same memory representation as 32768 as the smallest number and 32767 as the largest with the order -32768 < -32767 < … < -1 < 0 < 1 < 2 < … < 32767. All the negative numbers have the same representation as an unsigned number in the range 32768 … 65535 however the signed interpretation of the signed comparisons makes them be treated as negative numbers smaller than zero.

All meaningful situations both for signed and unsigned numbers that occur after a comparison are detailed in the following table.

DEST = SRC	ZF = 1	When the source is subtracted from the destination and both are equal the result is zero and therefore the zero flag is set. This works for both signed and unsigned numbers.
UDEST < USRC	CF = 1	When an unsigned source is subtracted from an unsigned destination and the destination is smaller, borrow is needed which sets the carry flag.
UDEST ≤ USRC	ZF = 1 OR CF = 1	If the zero flag is set, it means that the source and destination are equal and if the carry flag is set it means a borrow was needed in the subtraction and therefore the destination is smaller.
UDEST ≥ USRC	CF = 0	When an unsigned source is subtracted from an unsigned destination no borrow will be needed either when the operands are equal or when the destination is greater than the source.
UDEST > USRC	ZF = 0 AND CF = 0	The unsigned source and destination are not equal if the zero flag is not set and the destination is not smaller since no borrow was taken. Therefore the destination is greater than the source.
SDEST < SSRC	SF ≠ OF	When a signed source is subtracted from a signed destination and the answer is negative with no overflow than the destination is smaller than the source. If however there is an overflow meaning that the sign has changed unexpectedly, the meanings are reversed and a

		positive number signals that the destination is smaller.
SDEST ≤ SSRC	ZF = 1 OR SF ≠ OF	If the zero flag is set, it means that the source and destination are equal and if the sign and overflow flags differ it means that the destination is smaller as described above.
SDEST ≥ SSRC	SF = OF	When a signed source is subtracted from a signed destination and the answer is positive with no overflow than the destination is greater than the source. When an overflow is there signaling that sign has changed unexpectedly, we interpret a negative answer as the signal that the destination is greater.
SDEST > SSRC	ZF = 0 AND SF = OF	If the zero flag is not set, it means that the signed operands are not equal and if the sign and overflow match in addition to this it means that the destination is greater than the source.

3.2. CONDITIONAL JUMPS

For every interesting or meaningful situation of flags, a conditional jump is there. For example JZ and JNZ check the zero flag. If in a comparison both operands are same, the result of subtraction will be zero and the zero flag will be set. Thus JZ and JNZ can be used to test equality. That is why there are renamed versions JE and JNE read as jump if equal or jump if not equal. They seem more logical in writing but mean exactly the same thing with the same opcode. Many jumps are renamed with two or three names for the same jump, so that the appropriate logic can be conveyed in assembly language programs. This renaming is done by Intel and is a standard for iAPX88. JC and JNC test the carry flag. For example we may need to test whether there was an overflow in the last unsigned addition or subtraction. Carry flag will also be set if two unsigned numbers are subtracted and the first is smaller than the second. Therefore the renamed versions JB, JNAE, and JNB, JAE are there standing for jump if below, jump if not above or equal, jump if not below, and jump if above or equal respectively. The operation of all jumps can be seen from the following table.

JC JB JNAE	Jump if carry Jump if below Jump if not above or equal	CF = 1	This jump is taken if the last arithmetic operation generated a carry or required a borrow. After a CMP it is taken if the unsigned destination is smaller than the unsigned source.
JNC JNB JAE	Jump if not carry Jump if not below Jump if above or equal	CF = 0	This jump is taken if the last arithmetic operation did not

			generated a carry or required a borrow. After a CMP it is taken if the unsigned destination is larger or equal to the unsigned source.
JE JZ	Jump if equal Jump if zero	ZF = 1	This jump is taken if the last arithmetic operation produced a zero in its destination. After a CMP it is taken if both operands were equal.
JNE JNZ	Jump if not equal Jump if not zero	ZF = 0	This jump is taken if the last arithmetic operation did not produce a zero in its destination. After a CMP it is taken if both operands were different.
JA JNBE	Jump if above Jump if not below or equal	ZF = 0 AND CF = 0	This jump is taken after a CMP if the unsigned destination is larger than the unsigned source.
JNA JBE	Jump if not above Jump if below or equal	ZF = 1 OR CF = 1	This jump is taken after a CMP if the unsigned destination is smaller than or equal to the unsigned source.
JL JNGE	Jump if less Jump if not greater or equal	SF ≠ OF	This jump is taken after a CMP if the signed destination is smaller than the signed source.
JNL JGE	Jump if not less Jump if greater or equal	SF = OF	This jump is taken after a CMP if the signed destination is larger than or equal to the signed source.
JG JNLE	Jump if greater Jump if not less or equal	ZF = 0 AND SF = OF	This jump is taken after a CMP if the signed destination is larger than the signed source.
JNG JLE	Jump if not greater Jump if less or equal	ZF = 1 OR SF ≠ OF	This jump is taken after a CMP if the signed destination is smaller than or equal to the signed source.

JO	Jump if overflow.	OF = 1	This jump is taken if the last arithmetic operation changed the sign unexpectedly.
JNO	Jump if not overflow	OF = 0	This jump is taken if the last arithmetic operation did not change the sign unexpectedly.
JS	Jump if sign	SF = 1	This jump is taken if the last arithmetic operation produced a negative number in its destination.
JNS	Jump if not sign	SF = 0	This jump is taken if the last arithmetic operation produced a positive number in its destination.
JP JPE	Jump if parity Jump if even parity	PF = 1	This jump is taken if the last arithmetic operation produced a number in its destination that has even parity.
JNP JPO	Jump if not parity Jump if odd parity	PF = 0	This jump is taken if the last arithmetic operation produced a number in its destination that has odd parity.
JCXZ	Jump if CX is zero	CX = 0	This jump is taken if the CX register is zero.

The CMP instruction sets the flags reflecting the relation of the destination to the source. This is important as when we say jump if above, then what is above what. The destination is above the source or the source is above the destination.

The JA and JB instructions are related to unsigned numbers. That is our interpretation for the destination and source operands is unsigned. The 16th bit holds data and not the sign. In the JL and JG instructions standing for jump if lower and jump if greater respectively, the interpretation is signed. The 16th bit holds the sign and not the data. The difference between them will be made clear as an elaborate example will be given to explain the difference.

One jump is special that it is not dependant on any flag. It is JCXZ, jump if the CX register is zero. This is because of the special treatment of the CX register as a counter. This jump is regardless of the zero flag. There is no counterpart or not form of this instruction.

The adding numbers example of the last chapter can be a little simplified using the compare instruction on the BX register and eliminating the need for a separate counter as below.

Example 3.1

```
001     ; a program to add ten numbers without a separate counter
002     [org 0x0100]
003                     mov  bx, 0              ; initialize array index to zero
004                     mov  ax, 0              ; initialize sum to zero
005
006     l1:             add  ax, [num1+bx]      ; add number to ax
007                     add  bx, 2              ; advance bx to next index
008                     cmp  bx, 20             ; are we beyond the last index
009                     jne  l1                 ; if not add next number
010
011                     mov  [total], ax        ; write back sum in memory
012
013                     mov  ax, 0x4c00         ; terminate program
014                     int  0x21
015
016     num1:           dw   10, 20, 30, 40, 50, 10, 20, 30, 40, 50
017     total:          dw   0
```

006 The format of memory access is still base + offset.

008 BX is used as the array index as well as the counter. The offset of 11th number will be 20, so as soon as BX becomes 20 just after the 10th number has been added, the addition is stopped.

009 The jump is displayed as JNZ in the debugger even though we have written JNE in our example. This is because it is a renamed jump with the same opcode as JNZ and the debugger has no way of knowing the mnemonic that we used after looking just at the opcode. Also every code and data reference that we used till now is seen in the opcode as well. However for the jump instruction we see an operand of F2 in the opcode and not 0116. This will be discussed in detail with unconditional jumps. It is actually a short relative jump and the operand is stored in the form of positive or negative offset from this instruction.

With conditional branching in hand, there are just a few small things left in assembly language that fills some gaps. Now there is just imagination and the skill to conceive programs that can make you write any program.

3.3. UNCONDITIONAL JUMP

Till now we have been placing data at the end of code. There is no such restriction and we can define data anywhere in the code. Taking the previous example, if we place data at the start of code instead of at the end and we load our program in the debugger. We can see our data placed at the start but the debugger is intending to start execution at our data. The COM file definition said that the first executable instruction is at offset 0100 but we have placed data there instead of code. So the debugger will try to interpret that data as code and showed whatever it could make up out of those opcodes.

We introduce a new instruction called JMP. It is the unconditional jump that executes regardless of the state of all flags. So we write an unconditional jump as the very first instruction of our program and jump to the next instruction that follows our data declarations. This time 0100 contains a valid first instruction of our program.

Example 3.2

```
001     ; a program to add ten numbers without a separate counter
002     [org 0x0100]
003                     jmp start               ; unconditionally jump over data
004
005     num1:           dw   10, 20, 30, 40, 50, 10, 20, 30, 40, 50
006     total:          dw   0
```

```
007
008     start:      mov  bx, 0              ; initialize array index to zero
009                 mov  ax, 0              ; initialize sum to zero
010
011     l1:         add  ax, [num1+bx]      ; add number to ax
012                 add  bx, 2              ; advance bx to next index
013                 cmp  bx, 20             ; are we beyond the last index
014                 jne  l1                 ; if not add next number
015
016                 mov  [total], ax        ; write back sum in memory
017
018                 mov  ax, 0x4c00         ; terminate program
019                 int  0x21
```

003 JMP jumps over the data declarations to the start label and execution resumes from there.

3.4. RELATIVE ADDRESSING

Inside the debugger the instruction is shown as JMP 0119 and the location 0119 contains the original first instruction of the logic of our program. This jump is unconditional, it will always be taken. Now looking at the opcode we see F21600 where F2 is the opcode and 1600 is the operand to it. 1600 is 0016 in proper word order. 0119 is not given as a parameter rather 0016 is given.

This is position relative addressing in contrast to absolute addressing. It is not telling the exact address rather it is telling how much forward or backward to go from the current position of IP in the current code segment. So the instruction means to add 0016 to the IP register. At the time of execution of the first instruction at 0100 IP was pointing to the next instruction at 0103, so after adding 16 it became 0119, the desired target location. The mechanism is important to know, however all calculations in this mechanism are done by the assembler and by the processor. We just use a label with the JMP instruction and are ensured that the instruction at the target label will be the one to be executed.

3.5. TYPES OF JUMP

The three types of jump, near, short, and far, differ in the size of instruction and the range of memory they can jump to with the smallest short form of two bytes and a range of just 256 bytes to the far form of five bytes and a range covering the whole memory.

Short Jump

EB	Disp

Near Jump

E9	Disp Low	Disp High

Far Jump

EA	IP Low	IP High	CS Low	CS High

Near Jump

When the relative address stored with the instruction is in 16 bits as in the last example the jump is called a near jump. Using a near jump we can jump anywhere within a segment. If we add a large number it will wrap around to

the lower part. A negative number actually is a large number and works this way using the wraparound behavior.

Short Jump

If the offset is stored in a single byte as in 75F2 with the opcode 75 and operand F2, the jump is called a short jump. F2 is added to IP as a signed byte. If the byte is negative the complement is negated from IP otherwise the byte is added. Unconditional jumps can be short, near, and far. The far type is yet to be discussed. Conditional jumps can only be short. A short jump can go +127 bytes ahead in code and -128 bytes backwards and no more. This is the limitation of a byte in singed representation.

Far Jump

Far jump is not position relative but is absolute. Both segment and offset must be given to a far jump. The previous two jumps were used to jump within a segment. Sometimes we may need to go from one code segment to another, and near and short jumps cannot take us there. Far jump must be used and a two byte segment and a two byte offset are given to it. It loads CS with the segment part and IP with the offset part. Execution therefore resumes from that location in physical memory. The three instructions that have a far form are JMP, CALL, and RET, are related to program control. Far capability makes intra segment control possible.

3.6. SORTING EXAMPLE

Moving ahead from our example of adding numbers we progress to a program that can sort a list of numbers using the tools that we have accumulated till now. Sorting can be ascending or descending like if the largest number comes at the top, followed by a smaller number and so on till the smallest number the sort will be called descending. The other order starting with the smallest number and ending at the largest is called ascending sort. This is a common problem and many algorithms have been developed to solve it. One simple algorithm is the bubble sort algorithm.

In this algorithm we compare consecutive numbers. If they are in required order e.g. if it is a descending sort and the first is larger then the second, then we leave them as it is and if they are not in order, we swap them. Then we do the same process for the next two numbers and so on till the last two are compared and possibly swapped.

A complete iteration is called a pass over the array. We need N passes at least in the simplest algorithm if N is the number of elements to be sorted. A finer algorithm is to check if any swap was done in this pass and stop as soon as a pass goes without a swap. The array is now sorted as every pair of elements is in order.

For example if our list of numbers is 60, 55, 45, and 58 and we want to sort them in ascending order, the first comparison will be of 60 and 55 and as the order will be reversed to 55 and 60. The next comparison will be of 60 and 45 and again the two will be swapped. The next comparison of 60 and 58 will also cause a swap. At the end of first pass the numbers will be in order of 55, 45, 58, and 60. Observe that the largest number has bubbled down to the bottom. Just like a bubble at bottom of water. In the next pass 55 and 45 will be swapped. 55 and 58 will not be swapped and 58 and 60 will also not be swapped. In the next pass there will be no swap as the elements are in order i.e. 45, 55, 58, and 60. The passes will be stopped as the last pass did not cause any swap. The application of bubble sort on these numbers is further explained with the following illustration.

State of Data	Swap Done	Swap Flag
Pass 1		Off
60 55 45 58	Yes	On
55 60 45 58	Yes	On
55 45 60 58	Yes	On
Pass 2		Off
55 45 58 60	Yes	On
45 55 58 60	No	On
45 55 58 60	No	On
Pass 3		Off
45 55 58 60	No	Off
45 55 58 60	No	Off
45 55 58 60	No	Off

No more passes since swap flag is Off

Example 3.3

```
001     ; sorting a list of ten numbers using bubble sort
002     [org 0x0100]
003                 jmp  start
004
005     data:       dw   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
006     swap:       db   0
007
008     start:      mov  bx, 0              ; initialize array index to zero
009                 mov  byte [swap], 0     ; rest swap flag to no swaps
010
011     loop1:      mov  ax, [data+bx]      ; load number in ax
012                 cmp  ax, [data+bx+2]    ; compare with next number
013                 jbe  noswap             ; no swap if already in order
014
015                 mov  dx, [data+bx+2]    ; load second element in dx
016                 mov  [data+bx+2], ax    ; store first number in second
017                 mov  [data+bx], dx      ; store second number in first
018                 mov  byte [swap], 1     ; flag that a swap has been done
019
020     noswap:     add  bx, 2              ; advance bx to next index
021                 cmp  bx, 18             ; are we at last index
022                 jne  loop1              ; if not compare next two
023
024                 cmp  byte [swap], 1     ; check if a swap has been done
025                 je   start              ; if yes make another pass
026
027                 mov  ax, 0x4c00         ; terminate program
028                 int  0x21
```

003	The jump instruction is placed to skip over data.
006	The swap flag can be stored in a register but as an example it is stored in memory and also to extend the concept at a later stage.
011-012	One element is read in AX and it is compared with the next element because memory to memory comparisons are not allowed.
013	If the JBE is changed to JB, not only the unnecessary swap on equal will be performed, there will be a major algorithmic flaw due to a logical error as in the case of equal elements the algorithm will never stop. JBE won't swap in the case of equal elements.
015-017	The swap is done using DX and AX registers in such a way that the values are crossed. The code uses the information that one of the elements is already in the AX register.
021	This time BX is compared with 18 instead of 20 even though the number of elements is same. This is because we pick an element and compare it with the next element. When we pick the 9th element we compare it with the next element and this is the last comparison, since if we pick the 10th element we will compare it with the 11th element and there is no 11th element in our case.
024-025	If a swap is done we repeat the whole process for possible more swaps.

Inside the debugger we observe that the JBE is changed to JNA due to the same reason as discussed for JNE and JNZ. The passes change the data in the same manner as we presented in our illustration above. If JBE in the code is changed to JAE the sort will change from ascending to descending. For signed numbers we can use JLE and JGE respectively for ascending and descending sort.

To clarify the difference of signed and unsigned jumps we change the data array in the last program to include some negative numbers as well. When JBE will be used on this data, i.e. with unsigned interpretation of the data and an ascending sort, the negative numbers will come at the end after the largest positive number. However JLE will bring the negative numbers at the very start of the list to bring them in proper ascending order according to a signed interpretation, even though they are large in magnitude. The data used is shown as below.

```
data:        dw 60, 55, 45, 50, -40, -35, 25, 30, 10, 0
```

This data includes some signed numbers as well. The JBE instruction will treat this data as an unsigned number and will cater only for the magnitude ignoring the sign. If the program is loaded in the debugger, the numbers will appear in their hexadecimal equivalent. The two numbers -40 and -35 are especially important as they are represented as FFD8 and FFDD. This data is not telling whether it is signed or unsigned. Our interpretation will decide whether it is a very large unsigned number or a signed number in two's complement form.

If the sorting algorithm is applied on the above data with JBE as the comparison instruction to sort in ascending order with unsigned interpretation, observe the comparisons of the two numbers FFD8 and FFDD. For example it will decide that FFDD > FFD8 since the first is larger in magnitude. At the end of sorting FFDD will be at the end of the list being declared the largest number and FFD8 will precede it to be the second largest.

If however the comparison instruction is changed to JLE and sorting is done on the same data it works similarly except on the two numbers FFDD and FFD8. This time JLE declares them to be smaller than every other number and also declares FFDD < FFD8. At the end of sorting, FFDD is

declared to be the smallest number followed by FFD8 and then 0000. This is in contrast to the last example where JBE was used. This happened because JLE interpreted our data as signed numbers, and as a signed number FFDD has its sign bit on signaling that it is a negative number in two's complement form which is smaller than 0000 and every positive number. However JBE did not give any significance to the sign bit and included it in the magnitude. Therefore it declared the negative numbers to be the largest numbers.

If the required interpretation was of signed numbers the result produced by JLE is correct and if the required interpretation was of unsigned numbers the result produced by JBE is correct. This is the very difference between signed and unsigned integers in higher level languages, where the compiler takes the responsibility of making the appropriate jump depending on the type of integer used. But it is only at this level that we can understand the actual mechanism going on. In assembly language, use of proper jump is the responsibility of the programmer, to convey the intentions to use the data as signed or as unsigned.

The remaining possibilities of signed descending sort and unsigned descending sort can be done on the same lines and are left as an exercise. Other conditional jumps work in the same manner and can be studied from the reference at the end. Several will be discussed in more detail when they are used in subsequent chapters.

EXERCISES

1. Which registers are changed by the CMP instruction?
2. What are the different types of jumps available? Describe position relative addressing.
3. If AX=8FFF and BX=0FFF and "cmp ax, bx" is executed, which of the following jumps will be taken? Each part is independent of others. Also give the value of Z, S, and C flags.
    a. jg greater
    b. jl smaller
    c. ja above
    d. jb below
4. Write a program to find the maximum number and the minimum number from an array of ten numbers.
5. Write a program to search a particular element from an array using binary search. If the element is found set AX to one and otherwise to zero.
6. Write a program to calculate the factorial of a number where factorial is defined as:

```
factorial(x) = x*(x-1)*(x-2)*...*1
factorial(0) = 1
```

4
Bit Manipulations

4.1. MULTIPLICATION ALGORITHM

With the important capability of decision making in our repertoire we move on to the discussion of an algorithm, which will help us uncover an important set of instructions in our processor used for bit manipulations.

Multiplication is a common process that we use, and we were trained to do in early schooling. Remember multiplying by a digit and then putting a cross and then multiplying with the next digit and putting two crosses and so on and summing the intermediate results in the end. Very familiar process but we never saw the process as an algorithm, and we need to see it as an algorithm to convey it to the processor.

To highlight the important thing in the algorithm we revise it on two 4bit binary numbers. The numbers are 1101 i.e. 13 and 0101 i.e. 5. The answer should be 65 or in binary 01000001. Observe that the answer is twice as long as the multiplier and the multiplicand. The multiplication is shown in the following figure.

```
    1101 = 13
    0101 = 5
    -----
    1101
   0000x
  1101xx
 0000xxx
--------
01000001 = 65
```

We take the first digit of the multiplier and multiply it with the multiplicand. As the digit is one the answer is the multiplicand itself. So we place the multiplicand below the bar. Before multiplying with the next digit a cross is placed at the right most place on the next line and the result is placed shifted one digit left. However since the digit is zero, the result is zero. Next digit is one, multiplying with which, the answer is 1101. We put two crosses on the next line at the right most positions and place the result there shifted two places to the left. The fourth digit is zero, so the answer 0000 is placed with three crosses to its right.

Observe the beauty of binary base, as no real multiplication is needed at the digit level. If the digit is 0 the answer is 0 and if the digit is 1 the answer is the multiplicand itself. Also observe that for every next digit in the multiplier the answer is written shifted one more place to the left. No shifting for the first digit, once for the second, twice for the third and thrice for the fourth one. Adding all the intermediate answers the result is 01000001=65 as desired. Crosses are treated as zero in this addition.

Before formulating the algorithm for this problem, we need some more instructions that can shift a number so that we use this instruction for our multiplicand shifting and also some way to check the bits of the multiplier one by one.


4.2. SHIFTING AND ROTATIONS

The set of shifting and rotation instructions is one of the most useful set in any processor's instruction set. They simplify really complex tasks to a very

neat and concise algorithm. The following shifting and rotation operations are available in our processor.

Shift Logical Right (SHR)


The shift logical right operation inserts a zero from the left and moves every bit one position to the right and copies the rightmost bit in the carry flag. Imagine that there is a pipe filled to capacity with eight balls. The pipe is open from both ends and there is a basket at the right end to hold anything dropping from there. The operation of shift logical right is to force a white ball from the left end. The operation is depicted in the following illustration.



White balls represent zero bits while black balls represent one bits. Sixteen bit shifting is done the same way with a pipe of double capacity.

Shift Logical Left (SHL) / Shift Arithmetic Left (SAL)


The shift logical left operation is the exact opposite of shift logical right. In this operation the zero bit is inserted from the right and every bit moves one position to its left with the most significant bit dropping into the carry flag. Shift arithmetic left is just another name for shift logical left. The operation is again exemplified with the following illustration of ball and pipes.



Shift Arithmetic Right (SAR)

A signed number holds the sign in its most significant bit. If this bit was one a logical right shifting will change the sign of this number because of insertion of a zero from the left. The sign of a signed number should not change because of shifting.


The operation of shift arithmetic right is therefore to shift every bit one place to the right with a copy of the most significant bit left at the most significant place. The bit dropped from the right is caught in the carry basket. The sign bit is retained in this operation. The operation is further illustrated below.



The left shifting operation is basically multiplication by 2 while the right shifting operation is division by two. However for signed numbers division by two can be accomplished by using shift arithmetic right and not shift logical right. The left shift operation is equivalent to multiplication except when an important bit is dropped from the left. The overflow flag will signal this condition if it occurs and can be checked with JO. For division by 2 of a signed number logical right shifting will give a wrong answer for a negative number as the zero inserted from the left will change its sign. To retain the sign flag and still effectively divide by two the shift arithmetic right instruction must be used on signed numbers.


Rotate Right (ROR)

In the rotate right operation every bit moves one position to the right and the bit dropped from the right is inserted at the left. This bit is also copied into the carry flag. The operation can be understood by imagining that the pipe used for shifting has been molded such that both ends coincide. Now when the first ball is forced to move forward, every ball moves one step forward with the last ball entering the pipe from its other end occupying the first ball's old position. The carry basket takes a snapshot of this ball leaving one end of the pipe and entering from the other.



Rotate Left (ROL)


In the operation of rotate left instruction, the most significant bit is copied to the carry flag and is inserted from the right, causing every bit to move one position to the left. It is the reverse of the rotate right instruction. Rotation can be of eight or sixteen bits. The following illustration will make the concept clear using the same pipe and balls example.



Rotate Through Carry Right (RCR)


In the rotate through carry right instruction, the carry flag is inserted from the left, every bit moves one position to the right, and the right most bit is dropped in the carry flag. Effectively this is a nine bit or a seventeen bit rotation instead of the eight or sixteen bit rotation as in the case of simple rotations.

Imagine the circular molded pipe as used in the simple rotations but this time the carry position is part of the circle between the two ends of the pipe. Pushing the carry ball from the left causes every ball to move one step to its right and the right most bit occupying the carry place. The idea is further illustrated below.



Rotate Through Carry Left (RCL)

The exact opposite of rotate through carry right instruction is the rotate through carry left instruction. In its operation the carry flag is inserted from the right causing every bit to move one location to its left and the most significant bit occupying the carry flag. The concept is illustrated below in the same manner as in the last example.



4.3. MULTIPLICATION IN ASSEMBLY LANGUAGE

In the multiplication algorithm discussed above we revised the way we multiplied number in lower classes, and gave an example of that method on binary numbers. We make a simple modification to the traditional algorithm before we proceed to formulate it in assembly language.

In the traditional algorithm we calculate all intermediate answers and then sum them to get the final answer. If we add every intermediate answer to accumulate the result, the result will be same in the end, except that we do not have to remember a lot of intermediate answers during the whole multiplication. The multiplication with the new algorithm is shown below.

```
    1101 = 13       Accumulated Result
    0101 = 5
    -----                     0 (Initial Value)
    1101 = 13       0 + 13  = 13
   0000x = 0        13 + 0  = 13
  1101xx = 52       13 + 52 = 65
 0000xxx = 0        65 + 0  = 65 (Answer)
```

We try to identify steps of our algorithm. First we set the result to zero. Then we check the right most bit of multiplier. If it is one add the multiplicand to the result, and if it is zero perform no addition. Left shift the multiplicand before the next bit of multiplier is tested. The left shifting of the multiplicand is performed regardless of the value of the multiplier's right most bit. Just like the crosses in traditional multiplication are always placed to mark the ones, tens, thousands, etc. places. Then check the next bit and if it is one add the shifted value of the multiplicand to the result. Repeat for as many digits as there are in the multiplier, 4 in our example. Formulating the steps of the algorithm we get:

- Shift the multiplier to the right.
- If CF=1 add the multiplicand to the result.
- Shift the multiplicand to the left.
- Repeat the algorithm 4 times.

For an 8bit multiplication the algorithm will be repeated 8 times and for a sixteen bit multiplication it will be repeated 16 times, whatever the size of the multiplier is.

The algorithm uses the fact that shifting right forces the right most bit to drop in the carry flag. If we test the carry flag using JC we are effectively testing the right most bit of the multiplier. Another shifting will cause the next bit to drop in the next iteration and so on. So our task of checking bits one by one is satisfied using the shift operation. There are many other methods to do this bit testing as well, however we exemplify one of the methods in this example.

In the first iteration there is no shifting just like there is no cross in traditional multiplication in the first pass. Therefore we placed the left shifting of the multiplicand after the addition step. However the right shifting of multiplier must be before the addition as the addition step's execution depends upon its result.

We introduce an assembly language program to perform this 4bit multiplication. The algorithm is extensible to more bits but there are a few complications, which are left to be discussed later. For now we do a 4bit multiplication to keep the algorithm simple.

Example 4.1

```
01      ; 4bit multiplication algorithm
02      [org 0x100]
03                  jmp  start
04
05      multiplicand: db   13                ; 4bit multiplicand (8bit space)
06      multiplier:   db   5                 ; 4bit multiplier
```

```
07      result:       db   0                  ; 8bit result
08
09      start:        mov  cl, 4              ; initialize bit count to four
10                    mov  bl, [multiplicand] ; load multiplicand in bl
11                    mov  dl, [multiplier]   ; load multiplier in dl
12
13      checkbit:     shr  dl, 1              ; move right most bit in carry
14                    jnc  skip               ; skip addition if bit is zero
15
16                    add  [result], bl       ; accumulate result
17
18      skip:         shl  bl, 1              ; shift multiplicand left
19                    dec  cl                 ; decrement bit count
20                    jnz  checkbit           ; repeat if bits left
21
22                    mov  ax, 0x4c00         ; terminate program
23                    int  0x21
```

04-06	The numbers to be multiplied are constants for now. The multiplication is four bit so the answer is stored in an 8bit register.
07	If the operands were 8bit the answer would be 16bit and if the operands were 16bit the answer would be 32bit. Since eight bits can fit in a byte we have used 4bit multiplication as our first example.
14-16	Since addition by zero means nothing we skip the addition step if the rightmost bit of the multiplier is zero. If the jump is not taken the shifted value of the multiplicand is added to the result.
18	The multiplicand is left shifted in every iteration regardless of the multiplier bit.
19	DEC is a new instruction but its operation should be immediately understandable with the knowledge gained till now. It simply subtracts one from its single operand.
20	The JNZ instruction causes the algorithm to repeat till any bits of the multiplier are left

Inside the debugger observe the working of the SHR and SHL instructions. The SHR instruction is effectively dividing its operand by two and the remainder is stored in the carry flag from where we test it. The SHL instruction is multiplying its operand by two so that it is added at one place more towards the left in the result.

4.4. EXTENDED OPERATIONS

We performed a 4bit multiplication to explain the algorithm however the real advantage of the computer is when we ask it to multiply large numbers, Numbers whose multiplication takes real time. If we have an 8bit number we can do the multiplication in word registers, but are we limited to word operations? What if we want to multiply 32bit or even larger numbers? We are certainly not limited. Assembly language only provides us the basic building blocks. We build a plaza out of these blocks, or a building, or a classic piece of architecture is only dependant upon our imagination. With our logic we can extend these algorithms as much as we want.

Our next example will be multiplication of 16bit numbers to produce a 32bit answer. However for a 32bit answer we need a way to shift a 32bit number and a way to add 32bit numbers. We cannot depend on 16bit shifting as we have 16 significant bits in our multiplicand and shifting any bit towards the left may drop a valuable bit causing a totally wrong result. A valuable bit means any bit that is one. Dropping a zero bit doesn't cause any difference. So we place the 16it number in 32bit space with the upper 16 bits zeroed so that the sixteen shift operations don't cause any valuable bit to drop. Even though the numbers were 16bit we need 32bit operations to multiply correctly.

To clarify this necessity, we take example of a number 40000 or 9C40 in hexadecimal. In binary it is represented as 1001110001000000. To multiply

by two we shift it one place to the left. The answer we get is 0011100010000000 and the left most one is dropped in the carry flag. The answer should be the 17bit number 0x13880 but it is 0x3880, which are 14464 in decimal instead of the expected 80000. We should be careful of this situation whenever shifting is used.

Extended Shifting


Using our basic shifting and rotation instructions we can effectively shift a 32bit number in memory word by word. We cannot shift the whole number at once since our architecture is limited to word operations. The algorithm we use consists of just two instructions and we name it extended shifting.

```
num1:       dd   40000
            shl  word [num1], 1
            rcl  word [num1+2], 1
```

The DD directive reserves a 32bit space in memory, however the value we placed there will fit in 16bits. So we can safely shift the number left 16 times. The least significant word is accessible at num1 and the most significant word is accessible at num1+2.

The two instructions are carefully crafted such that the first one shifts the lower word towards the left and the most significant bit of that word is dropped in carry. With the next instruction we push that dropped bit into the least significant bit of the next word effectively joining the two 16bit words. The final carry after the second instruction will be the most significant bit of the higher word, which for this number will always be zero.

The following illustration will clarify the concept. The pipe on the right contains the lower half and the pipe on the left contains the upper half. The first instruction forced a zero from the right into the lower half and the left most bit is saved in carry, and from there it is pushed into the upper half and the upper half is shifted as well.



For shifting right the exact opposite is done however care must be taken to shift right the upper half first and then rotate through carry right the lower half for obvious reasons. The instructions to do this are.

```
num1:       dd   40000
            shr  word [num1+2], 1
            rcr  word [num1], 1
```

The same logic has worked. The shift placed the least significant bit of the upper half in the carry flag and it was pushed from right into the lower half. For a singed shift we would have used the shift arithmetic right instruction instead of the shift logical right instruction.

The extension we have done is not limited to 32bits. We can shift a number of any size say 1024 bits. The second instruction will be repeated a number of times and we can achieve the desired effect. Using two simple instructions we have increased the capability of the operation to effectively an unlimited number of bits. The actual limit is the available memory as even the segment limit can be catered with a little thought.

Extended Addition and Subtraction

We also needed 32bit addition for multiplication of 16bit numbers. The idea of extension is same here. However we need to introduce a new instruction at this place. The instruction is ADC or “add with carry.” Normal addition has two operands and the second operand is added to the first

operand. However ADC has three operands. The third implied operand is the carry flag. The ADC instruction is specifically placed for extending the capability of ADD. Numbers of any size can be added using a proper combination of ADD and ADC. All basic building blocks are provided for the assembly language programmer, and the programmer can extend its capabilities as much as needed by using these fine instructions in appropriate combinations.

Further clarifying the operation of ADC, consider an instruction "ADC AX, BX." Normal addition would have just added BX to AX, however ADC first adds the carry flag to AX and then adds BX to AX. Therefore the last carry is also included in the result.

The algorithm should be apparent by now. The lower halves of the two numbers to be added are first added with a normal addition. For the upper halves a normal addition would lose track of a possible carry from the lower halves and the answer would be wrong. If a carry was generated it should go to the upper half. Therefore the upper halves are added with an addition with carry instruction.

Since one operand must be in register, ax is used to read the lower and upper halves of the source one by one. The destination is directly updated. The set of instructions goes here.

```
dest:       dd   40000
src:        dd   80000

            mov  ax, [src]
            add  word [dest], ax
            mov  ax, [src+2]
            adc  word [dest+2], ax
```

To further extend it more addition with carries will be used. However the carry from last addition will be wasted as there will always be a size limit where the results and the numbers are stored. This carry will remain in the carry flag to be tested for a possible overflow.

For subtraction the same logic will be used and just like addition with carry there is an instruction to subtract with borrows called SBB. Borrow in the name means the carry flag and is used just for clarity. Or we can say that the carry flag holds the carry for addition instructions and the borrow for subtraction instructions. Also the carry is generated at the 17th bit and the borrow is also taken from the 17th bit. Also there is no single instruction that needs borrow and carry in their independent meanings at the same time. Therefore it is logical to use the same flag for both tasks.

We extend subtraction with a very similar algorithm. The lower halves must be subtracted normally while the upper halves must be subtracted with a subtract with borrow instruction so that if the lower halves needed a borrow, a one is subtracted from the upper halves. The algorithm is as under.

```
dest:       dd   40000
src:        dd   80000

            mov  ax, [src]
            sub  word [dest], ax
            mov  ax, [src+2]
            sbb  word [dest+2], ax
```

Extended Multiplication

We use extended shifting and extended addition to formulate our algorithm to do extended multiplication. The multiplier is still stored in 16bits since we only need to check its bits one by one. The multiplicand however cannot be stored in 16bits otherwise on left shifting its significant bits might get lost. Therefore it has to be stored in 32bits and the shifting and addition used to accumulate the result must be 32bits as well.

Example 4.2

```
01      ; 16bit multiplication
02      [org 0x0100]
03                  jmp  start
04
05      multiplicand: dd   1300              ; 16bit multiplicand 32bit space
06      multiplier:   dw   500               ; 16bit multiplier
07      result:       dd   0                 ; 32bit result
08
09      start:        mov  cl, 16            ; initialize bit count to 16
10                    mov  dx, [multiplier]  ; load multiplier in dx
11
12      checkbit:     shr  dx, 1             ; move right most bit in carry
13                    jnc  skip              ; skip addition if bit is zero
14
15                    mov  ax, [multiplicand]
16                    add  [result], ax      ; add less significant word
17                    mov  ax, [multiplicand+2]
18                    adc  [result+2], ax    ; add more significant word
19
20      skip:         shl  word [multiplicand], 1
21                    rcl  word [multiplicand+2], 1 ; shift multiplicand left
22                    dec  cl                ; decrement bit count
23                    jnz  checkbit          ; repeat if bits left
24
25                    mov  ax, 0x4c00        ; terminate program
26                    int  0x21
```

05-07	The multiplicand and the result are stored in 32bit space while the multiplier is stored as a word.
10	The multiplier is loaded in DX where it will be shifted bit by bit. It can be directly shifted in memory as well.
15-18	The multiplicand is added to the result using extended 32bit addition.
20-21	The multiplicand is shifted left as a 32bit number using extended shifting operation.

The multiplicand will occupy the space from 0103-0106, the multiplier will occupy space from 0107-0108 and the result will occupy the space from 0109-010C. Inside the debugger observe the changes in these memory locations during the course of the algorithm. The extended shifting and addition operations provide the same effect as would be provided if there were 32bit addition and shifting operations available in the instruction set.

At the end of the algorithm the result memory locations contain the value 0009EB10 which is 65000 in decimal; the desired answer. Also observe that the number 00000514 which is 1300 in decimal, our multiplicand, has become 05140000 after being left shifted 16 times. Our extended shifting has given the same result as if a 32bit number is left shifted 16 times as a unit.

There are many other important applications of the shifting and rotation operations in addition to this example of the multiplication algorithm. More examples will come in coming chapters.

4.5. BITWISE LOGICAL OPERATIONS

The 8088 processor provides us with a few logical operations that operate at the bit level. The logical operations are the same as discussed in computer logic design; however our perspective will be a little different. The four basic operations are AND, OR, XOR, and NOT.

The important thing about these operations is that they are bitwise. This means that if “and ax, bx” instruction is given, then the operation of AND is applied on corresponding bits of AX and BX. There are 16 AND operations as a result; one for every bit of AX. Bit 0 of AX will be set if both its original value and Bit 0 of BX are set, bit 1 will be set if both its original value and Bit 1 of BX are set, and so on for the remaining bits. These operations are conducted in parallel on the sixteen bits. Similarly the operations of other logical operations are bitwise as well.

AND operation

AND performs the logical bitwise *and* of the two operands (byte or word) and returns the result to the destination operand. A bit in the result is set if both corresponding bits of the original operands are set; otherwise the bit is cleared as shown in the truth table. Examples are "and ax, bx" and "and byte [mem], 5." All possibilities that are legal for addition are also legal for the AND operation. The different thing is the bitwise behavior of this operation.

X	Y	X and Y
0	0	0
0	1	0
1	0	0
1	1	1

OR operation

OR performs the logical bitwise "inclusive or" of the two operands (byte or word) and returns the result to the destination operand. A bit in the result is set if either or both corresponding bits in the original operands are set otherwise the result bit is cleared as shown in the truth table. Examples are "or ax, bx" and "or byte [mem], 5."

X	Y	X or Y
0	0	0
0	1	1
1	0	1
1	1	1

XOR operation

XOR (Exclusive Or) performs the logical bitwise "exclusive or" of the two operands and returns the result to the destination operand. A bit in the result is set if the corresponding bits of the original operands contain opposite values (one is set, the other is cleared) otherwise the result bit is cleared as shown in the truth table. XOR is a very important operation due to the property that it is a reversible operation. It is used in many cryptography algorithms, image processing, and in drawing operations. Examples are "xor ax, bx" and "xor byte [mem], 5."

X	Y	X xor Y
0	0	0
0	1	1
1	0	1
1	1	0

NOT operation

NOT inverts the bits (forms the one's complement) of the byte or word operand. Unlike the other logical operations, this is a single operand instruction, and is not purely a logical operation in the sense the others are, but it is still traditionally counted in the same set. Examples are "not ax" and "not byte [mem]".

4.6. MASKING OPERATIONS

Selective Bit Clearing

Another use of AND is to make selective bits zero in its destination operand. The source operand is loaded with a mask containing one at positions which are retain their old value and zero at positions which are to be zeroed. The effect of applying this operation on the destination with mask in the source is to clear the desired bits. This operation is called masking. For example if the lower nibble is to be cleared then the operation can be applied with F0 in the source. The upper nibble will retain its old value and the lower nibble will be cleared.

Selective Bit Setting

The OR operation can be used as a masking operation to set selective bits. The bits in the mask are cleared at positions which are to retain their values, and are set at positions which are to be set. For example to set the lower nibble of the destination operand, the operation should be applied with a mask of 0F in the source. The upper nibble will retain its value and the lower nibble will be set as a result.

Selective Bit Inversion

XOR can also be used as a masking operation to invert selective bits. The bits in the mask are cleared at positions, which are to retain their values, and are set at positions, which are to be inverted. For example to invert the lower nibble of the destination operand, the operand should be applied with a mask of 0F in the source. The upper nibble will retain its value and the lower nibble will be set as a result. Compare this with NOT which inverts everything. XOR on the other hand allows inverting selective bits.

Selective Bit Testing

AND can be used to check whether particular bits of a number are set or not. Previously we used shifting and JC to test bits one by one. Now we introduce another way to test bits, which is more powerful in the sense that any bit can be tested anytime and not necessarily in order. AND can be applied on a destination with a 1-bit in the desired position and a source, which is to be checked. If the destination is zero as a result, which can be checked with a JZ instruction, the bit at the desired position in the source was clear.

However the AND operation destroys the destination mask, which might be needed later as well. Therefore Intel provided us with another instruction analogous to CMP, which is non-destructive subtraction. This is the TEST instruction and is a non-destructive AND operation. It doesn't change the destination and only sets the flags according to the AND operation. By checking the flags, we can see if the desired bit was set or cleared.

We change our multiplication algorithm to use selective bit testing instead of checking bits one by one using the shifting operations.

Example 4.3

```
01      ; 16bit multiplication using test for bit testing
02      [org 0x0100]
03                  jmp  start
04
05      multiplicand: dd   1300               ; 16bit multiplicand 32bit space
06      multiplier:   dw   500                ; 16bit multiplier
07      result:       dd   0                  ; 32bit result
08
09      start:        mov  cl, 16             ; initialize bit count to 16
10                    mov  bx, 1              ; initialize bit mask
11
12      checkbit:     test bx, [multiplier]   ; test right most bit
13                    jz   skip               ; skip addition if bit is zero
14
15                    mov  ax, [multiplicand]
16                    add  [result], ax       ; add less significant word
17                    mov  ax, [multiplicand+2]
18                    adc  [result+2], ax     ; add more significant word
19
20      skip:         shl  word [multiplicand], 1
21                    rcl  word [multiplicand+2], 1 ; shift multiplicand left
22                    shl  bx, 1              ; shift mask towards next bit
23                    dec  cl                 ; decrement bit count
24                    jnz  checkbit           ; repeat if bits left
25
26                    mov  ax, 0x4c00         ; terminate program
27                    int  0x21
```

12	The test instruction is used for bit testing. BX holds the mask and in every next iteration it is shifting left, as our concerned bit is now the next bit.
22-24	We can do without counting in this example. We can stop as soon as our mask in BX becomes zero. These are the small tricks that assembly allows us to do and optimize our code as a result.

Inside the debugger observe that both the memory location and the mask in BX do not change as a result of TEST instruction. Also observe how our mask is shifting towards the left so that the next TEST instruction tests the next bit. In the end we get the same result of 0009EB10 as in the previous example.

EXERCISES

1. Write a program to swap every pair of bits in the AX register.
2. Give the value of the AX register and the carry flag after each of the following instructions.

```
stc
mov ax, <your rollnumber>
adc ah, <first character of your name>
cmc
xor ah, al
mov cl, 4
shr al, cl
rcr ah, cl
```

3. Write a program to swap the nibbles in each byte of the AX register.
4. Calculate the number of one bits in BX and complement an equal number of least significant bits in AX.
   HINT: Use the XOR instruction
5. Write a program to multiply two 32bit numbers and store the answer in a 64bit location.
6. Declare a 32byte buffer containing random data. Consider for this problem that the bits in these 32 bytes are numbered from 0 to 255. Declare another byte that contains the starting bit number. Write a program to copy the byte starting at this starting bit number in the AX register. Be careful that the starting bit number may not be a multiple of 8 and therefore the bits of the desired byte will be split into two bytes.
7. AX contains a number between 0-15. Write code to complement the corresponding bit in BX. For example if AX contains 6; complement the 6th bit of BX.
8. AX contains a non-zero number. Count the number of ones in it and store the result back in AX. Repeat the process on the result (AX) until AX contains one. Calculate in BX the number of iterations it took to make AX one. For example BX should contain 2 in the following case:
   AX = 1100 0101 1010 0011 (input – 8 ones)
   AX = 0000 0000 0000 1000 (after first iteration – 1 one)
   AX = 0000 0000 0000 0001 (after second iteration – 1 one) STOP

5
Subroutines

5.1. PROGRAM FLOW

Till now we have accumulated the very basic tools of assembly language programming. A very important weapon in our arsenal is the conditional jump instruction. During the course of last two chapters we used these tools to write two very useful algorithms of sorting and multiplication. The multiplication algorithm is useful even though there is a MUL instruction in the 8088 instruction set, which can multiply 8bit and 16bit operands. This is because of the extensibility of our algorithm, as it is not limited to 16bits and can do 32bit or 64bit multiplication with minor changes.


Both of these algorithms will be used a number of times in any program of a reasonable size and complexity. An application does not only need to multiply at a single point in code; it multiplies at a number of places. If multiplication or sorting is needed at 100 places in code, copying it 100 times is a totally infeasible solution. Maintaining such a code is an impossible task.

The straightforward solution to this problem using the concepts we have acquainted till now is to write the code at one place with a label, and whenever we need to sort we jump to this label. But there is problem with this logic, and the problem is that after sorting is complete how the processor will know where to go back. The immediate answer is to jump back to a label following the jump to bubble sort. But we have jumped to bubble sort from 100 places in code. Which of the 100 positions in code should we jump back? Jump back at the first invocation, but jump has a single fixed target. How will the second invocation work? The second jump to bubble sort will never have control back at the next line.

Instruction are tied to one another forming an execution thread, just like a knitted thread where pieces of cotton of different sizes are twisted together to form a thread. This thread of execution is our program. The jump instruction breaks this thread permanently, making a permanent diversion, like a turn on a highway. The conditional jump selects one of the two possible directions, like right or left turn on a road. So there is no concept of returning.

However there are roundabouts on roads as well that take us back from where we started after having traveled on the boundary of the round. This is the concept of a temporary diversion. Two or more permanent diversions can take us back from where we started, just like two or more road turns can take us back to the starting point, but they are still permanent diversions in their nature.

We need some way to implement the concept of temporary diversion in assembly language. We want to create a roundabout of bubble sort, another roundabout of our multiplication algorithm, so that we can enter into the roundabout whenever we need it and return back to wherever we left from after completing the round.



Key point in the above discussion is returning to where we left from, like a loop in a knitted thread. Diversion should be temporary and not permanent. The code of bubble sort written at one place, multiply at another, and we temporarily divert to that place, thus avoiding a repetition of code at a 100 places.

CALL and RET

In every processor, instructions are available to divert temporarily and to divert permanently. The instructions for permanent diversion in 8088 are the jump instructions, while the instruction for temporary diversion is the CALL instruction. The word call must be familiar to the readers from subroutine call in higher level languages. The CALL instruction allows temporary diversion and therefore reusability of code. Now we can place the code for bubble sort at one place and reuse it again and again. This was not possible with permanent diversion. Actually the 8088 permanent diversion mechanism can be tricked to achieve temporary diversion. However it is not possible without getting into a lot of trouble. The key idea in doing it this way is to use the jump instruction form that takes a register as argument. Therefore this is not impossible but this is not the way it is done.

The natural way to do this is to use the CALL instruction followed by a label, just like JMP is followed by a label. Execution will divert to the code following the label. Till now the operation has been similar to the JMP instruction. When the subroutine completes we need to return. The RET instruction is used for this purpose. The word return holds in its meaning that we are to return from where we came and need no explicit destination. Therefore RET takes no arguments and transfers control back to the instruction following the CALL that took us in this subroutine. The actual technical process that informs RET where to return will be discussed later after we have discussed the system stack.

CALL takes a label as argument and execution starts from that label, until the RET instruction is encountered and it takes execution back to the instruction following the CALL. Both the instructions are commonly used as a pair, however technically they are independent in their operation. The RET works regardless of the CALL and the CALL works regardless of the RET. If you CALL a subroutine it will not complain if there is no RET present and similarly if you RET without being called it won't complain. It is a logical pair and is used as a pair in every decent code. However sometimes we play tricks with the processor and we use CALL or RET alone. This will become clear when we need to play such tricks in later chapters.

Parameters

We intend to write the bubble sort code at one place and CALL it whenever needed. An immediately visible problem is that whenever we call this subroutine it will sort the same array in the same order. However in a real application we will need to sort various arrays of various sizes. We might sometimes need an ascending sort and descending at other times. Similarly our data may be signed or unsigned. Such pieces of information that may change from invocation to invocation and should be passed from the caller to the subroutine are called parameters.

There must be some way of passing these parameters to the subroutine. Revising the subroutine temporary flow breakage mechanism, the most straightforward way is to use registers. The CALL mechanism breaks the thread of execution and does not change registers, except IP which must change for processor to start executing at another place, and SP whose change will be discussed in detail later. Any of the other registers can hold parameters for the subroutine.

5.2. OUR FIRST SUBROUTINE

Now we want to modify the bubble sort code so that it works as a subroutine. We place a label at the start of bubble sort code, which works as the anchor point and will be used in the CALL instruction to call the subroutine. We also place a RET at the end of the algorithm to return from where we called the subroutine.

Example 5.1

```
01      ; bubble sort algorithm as a subroutine
02      [org 0x0100]
03                  jmp start
04
05      data:       dw   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
06      swap:       db   0
07
08      bubblesort: dec  cx                ; last element not compared
09                  shl  cx, 1             ; turn into byte count
10
11      mainloop:   mov  si, 0             ; initialize array index to zero
12                  mov  byte [swap], 0    ; reset swap flag to no swaps
13
14      innerloop:  mov  ax, [bx+si]       ; load number in ax
15                  cmp  ax, [bx+si+2]     ; compare with next number
16                  jbe  noswap            ; no swap if already in order
17
18                  mov  dx, [bx+si+2]     ; load second element in dx
19                  mov  [bx+si], dx       ; store first number in second
20                  mov  [bx+si+2], ax     ; store second number in first
21                  mov  byte [swap], 1    ; flag that a swap has been done
22
23      noswap:     add  si, 2             ; advance si to next index
24                  cmp  si, cx            ; are we at last index
25                  jne  innerloop         ; if not compare next two
26
27                  cmp  byte [swap], 1    ; check if a swap has been done
28                  je   mainloop          ; if yes make another pass
29
30                  ret                    ; go back to where we came from
31
32      start:      mov  bx, data          ; send start of array in bx
33                  mov  cx, 10            ; send count of elements in cx
34                  call bubblesort        ; call our subroutine
35
36                  mov  ax, 0x4c00        ; terminate program
37                  int  0x21
```

08-09 The routine has received the count of elements in CX. Since it makes one less comparison than the number of elements it decrements it. Then it multiplies it by two since this a word array and each element

14	takes two bytes. Left shifting has been used to multiply by two. Base+index+offset addressing has been used. BX holds the start of array, SI the offset into it and an offset of 2 when the next element is to be read. BX can be directly changed but then a separate counter would be needed, as SI is directly compared with CX in our case.
32-37	The code starting from the start label is our main program analogous to the main in the C language. BX and CX hold our parameters for the bubblesort subroutine and the CALL is made to invoke the subroutine.

Inside the debugger we observe the same unsigned data that we are so used to now. The number 0103 is passed via BX to the subroutine which is the start of our data and the number 000A via CX which is the number of elements in our data. If we step over the CALL instruction we see our data sorted in a single step and we are at the termination instructions. The processor has jumped to the bubblesort routine, executed it to completion, and returned back from it but the process was hidden due to the step over command. If however we trace into the CALL instruction, we land at the first instruction of our routine. At the end of the routine, when the RET instruction is executed, we immediately land back to our termination instructions, to be precise the instruction following the CALL.

Also observe that with the CALL instruction SP is decremented by two from FFFE to FFFC, and the stack windows shows 0150 at its top. As the RET is executed SP is recovered and the 0150 is also removed from the stack. Match it with the address of the instruction following the CALL which is 0150 as well. The 0150 removed from the stack by the RET instruction has been loaded into the IP register thereby resuming execution from address 0150. CALL placed where to return on the stack for the RET instruction. The stack is automatically used with the CALL and RET instructions. Stack will be explained in detail later, however the idea is that the one who is departing stores the address to return at a known place. This is the place using which CALL and RET coordinate. How this placed is actually used by the CALL and RET instructions will be described after the stack is discussed.

After emphasizing reusability so much, it is time for another example which uses the same bubblesort routine on two different arrays of different sizes.

Example 5.2

```
01      ; bubble sort subroutine called twice
02      [org 0x0100]
03                  jmp start
04
05      data:       dw   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
06      data2:      dw   328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
07                  dw   888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
08      swap:       db   0
09
10      bubblesort: dec  cx                ; last element not compared
11                  shl  cx, 1             ; turn into byte count
12
13      mainloop:   mov  si, 0             ; initialize array index to zero
14                  mov  byte [swap], 0    ; reset swap flag to no swaps
15
16      innerloop:  mov  ax, [bx+si]       ; load number in ax
17                  cmp  ax, [bx+si+2]     ; compare with next number
18                  jbe  noswap            ; no swap if already in order
19
20                  mov  dx, [bx+si+2]     ; load second element in dx
21                  mov  [bx+si], dx       ; store first number in second
22                  mov  [bx+si+2], ax     ; store second number in first
23                  mov  byte [swap], 1    ; flag that a swap has been done
24
25      noswap:     add  si, 2             ; advance si to next index
```

```
26                cmp  si, cx             ; are we at last index
27                jne  innerloop          ; if not compare next two
28
29                cmp  byte [swap], 1     ; check if a swap has been done
30                je   mainloop           ; if yes make another pass
31
32                ret                     ; go back to where we came from
33
34      start:    mov  bx, data           ; send start of array in bx
35                mov  cx, 10             ; send count of elements in cx
36                call bubblesort         ; call our subroutine
37
38                mov bx, data2           ; send start of array in bx
39                mov cx, 20              ; send count of elements in cx
40                call bubblesort         ; call our subroutine again
41
42                mov  ax, 0x4c00         ; terminate program
43                int  0x21
```

05-07	There are two different data arrays declared. One of 10 elements and the other of 20 elements. The second array is declared on two lines, where the second line is continuation of the first. No additional label is needed since they are situated consecutively in memory.
34-40	The other change is in the main where the bubblesort subroutine is called twice, once on the first array and once on the second.

Inside the debugger observe that stepping over the first call, the first array is sorted and stepping over the second call the second array is sorted. If however we step in SP is decremented and the stack holds 0178 which is the address of the instruction following the call. The RET consumes that 0178 and restores SP. The next CALL places 0181 on the stack and SP is again decremented. The RET consumes this number and execution resumes from the instruction at 0181. This is the coordinated function of CALL and RET using the stack.

In both of the above examples, there is a shortcoming. The subroutine to sort the elements is destroying the registers AX, CX, DX, and SI. That means that the caller of this routine has to make sure that it does not hold any important data in these registers before calling this function, because after the call has returned the registers will be containing meaningless data for the caller. With a program containing thousands of subroutines expecting the caller to remember the set of modified registers for each subroutine is unrealistic and unreasonable. Also registers are limited in number, and restricting the caller on the use of register will make the caller's job very tough. This shortcoming will be removed using the very important system stack.

5.3. STACK

Stack is a data structure that behaves in a first in last out manner. It can contain many elements and there is only one way in and out of the container. When an element is inserted it sits on top of all other elements and when an element is removed the one sitting at top of all others is removed first. To visualize the structure consider a test tube and put some balls in it. The second ball will come above the first and the third will come above the second. When a ball is taken out only the one at the top can be removed. The operation of placing an element on top of the stack is called pushing the element and the operation of removing an element from the top of the stack is called popping the element. The last thing pushed is popped out first; the last in first out behavior.

We can peek at any ball inside the test tube but we cannot remove it without removing every ball on top of it. Similarly we can read any element from the stack but cannot remove it without removing everything above it. The stack operations of pushing and popping only work at the top of the

stack. This top of stack is contained in the SP register. The physical address of the stack is obtained by the SS:SP combination. The stack segment registers tells where the stack is located and the stack pointer marks the top of stack inside this segment.

Whenever an element is pushed on the stack SP is decremented by two as the 8088 stack works on word sized elements. Single bytes cannot be pushed or popped from the stack. Also it is a decrementing stack. Another possibility is an incrementing stack. A decrementing stack moves from higher addresses to lower addresses as elements are added in it while an incrementing stack moves from lower addresses to higher addresses as elements are added. There is no special reason or argument in favor of one or another, and more or less depends on the choice of the designers. Another processor 8051 by the same manufacturer has an incrementing stack while 8088 has a decrementing one.

Memory is like a shelf numbered as zero at the top and the maximum at the bottom. If a decrementing stack starts at shelf 5, the first item is placed in shelf 5, the next item is placed in shelf 4, the next in shelf 3 and so on. The operations of placing items on the stack and removing them from there are called push and pop. The push operation copies its operand on the stack, while the pop operation makes a copy from the top of the stack into its operand. When an item is pushed on a decrementing stack, the top of the stack is first decremented and the element is then copied into this space. With a pop the element at the top of the stack is copied into the pop operand and the top of stack is incremented afterwards.

The basic use of the stack is to save things and recover from there when needed. For example we discussed the shortcoming in our last example that it destroyed the caller's registers, and the callers are not supposed to remember which registers are destroyed by the thousand routines they use. Using the stack the subroutine can save the caller's value of the registers on the stack, and recover them from there before returning. Meanwhile the subroutine can freely use the registers. From the caller's point of view if the registers contain the same value before and after the call, it doesn't matter if the subroutine used them meanwhile.

Similarly during the CALL operation, the current value of the instruction pointer is automatically saved on the stack, and the destination of CALL is loaded in the instruction pointer. Execution therefore resumes from the destination of CALL. When the RET instruction is executed, it recovers the value of the instruction pointer from the stack. The next instruction executed is therefore the one following the CALL. Observe how playing with the instruction pointer affects the program flow.

There is a form of the RET instruction called "RET n" where n is a numeric argument. After performing the operation of RET, it further increments the stack pointer by this number, i.e. SP is first incremented by two and then by n. Its function will become clear when parameter passing is discussed.

Now we describe the operation of the stack in CALL and RET with an example. The top of stack stored in the stack pointer is initialized at 2000. The space above SP is considered empty and free. When the stack pointer is decremented by two, we took a word from the empty space and can use it for our purpose. The unit of stack operations is a word. Some instructions push multiple words; however byte pushes cannot be made. Now the value 017B is stored in the word reserved on the stack. The RET will copy this value in the instruction pointer and increment the stack pointer by two making it 2000 again, thereby reverting the operation of CALL.

This is how CALL and RET behave for near calls. There is also a far version of these functions when the target routine is in another segment. This version of CALL takes a segment offset pair just like the far jump instruction. The CALL will push both the segment and the offset on the stack in this case, followed by loading CS and IP with the values given in the instruction.

The corresponding instruction RETF will pop the offset in the instruction pointer followed by popping the segment in the code segment register.

Apart from CALL and RET, the operations that use the stack are PUSH and POP. Two other operations that will be discussed later are INT and IRET. Regarding the stack, the operation of PUSH is similar to CALL however with a register other than the instruction pointer. For example "push ax" will push the current value of the AX register on the stack. The operation of PUSH is shown below.

```
SP ← SP – 2
[SP] ← AX
```

The operation of POP is the reverse of this. A copy of the element at the top of the stack is made in the operand, and the top of the stack is incremented afterwards. The operation of "pop ax" is shown below.

```
AX ← [SP]
SP ← SP + 2
```

Making corresponding PUSH and POP operations is the responsibility of the programmer. If "push ax" is followed by "pop dx" effectively copying the value of the AX register in the DX register, the processor won't complain. Whether this sequence is logically correct or not should be ensured by the programmer. For example when PUSH and POP are used to save and restore registers from the stack, order must be correct so that the saved value of AX is reloaded in the AX register and not any other register. For this the order of POP operations need to be the reverse of the order of PUSH operations.

Now we consider another example that is similar to the previous examples, however the code to swap the two elements has been extracted into another subroutine, so that the formation of stack can be observed during nested subroutine calls.

Example 5.3

```
01      ; bubble sort subroutine using swap subroutine
02      [org 0x0100]
03                      jmp start
04
05      data:           dw   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
06      data2:          dw   328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
07                      dw   888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
08      swapflag:       db   0
09
10      swap:           mov  ax, [bx+si]        ; load first number in ax
11                      xchg ax, [bx+si+2]      ; exchange with second number
12                      mov  [bx+si], ax        ; store second number in first
13                      ret                     ; go back to where we came from
14
15      bubblesort:     dec  cx                 ; last element not compared
16                      shl  cx, 1              ; turn into byte count
17
18      mainloop:       mov  si, 0              ; initialize array index to zero
19                      mov  byte [swapflag], 0 ; reset swap flag to no swaps
20
21      innerloop:      mov  ax, [bx+si]        ; load number in ax
22                      cmp  ax, [bx+si+2]      ; compare with next number
23                      jbe  noswap             ; no swap if already in order
24
25                      call swap               ; swaps two elements
26                      mov  byte [swapflag], 1 ; flag that a swap has been done
27
28      noswap:         add  si, 2              ; advance si to next index
29                      cmp  si, cx             ; are we at last index
30                      jne  innerloop          ; if not compare next two
31
32                      cmp  byte [swapflag], 1 ; check if a swap has been done
33                      je   mainloop           ; if yes make another pass
34                      ret                     ; go back to where we came from
35
36      start:          mov  bx, data           ; send start of array in bx
37                      mov  cx, 10             ; send count of elements in cx
```

```
38                call bubblesort         ; call our subroutine
39
40                mov bx, data2           ; send start of array in bx
41                mov cx, 20              ; send count of elements in cx
42                call bubblesort         ; call our subroutine again
43
44                mov  ax, 0x4c00         ; terminate program
45                int  0x21
```

11 A new instruction XCHG has been introduced. The instruction swaps its source and its destination operands however at most one of the operands could be in memory, so the other has to be loaded in a register. The instruction has reduced the code size by one instruction.

13 The RET at the end of swap makes it a subroutine.

Inside the debugger observe the use of stack by CALL and RET instructions, especially the nested CALL.

5.4. SAVING AND RESTORING REGISTERS

The subroutines we wrote till now have been destroying certain registers and our calling code has been carefully written to not use those registers. However this cannot be remembered for a good number of subroutines. Therefore our subroutines need to implement some mechanism of retaining the callers' value of any registers used.

The trick is to use the PUSH and POP operations and save the callers' value on the stack and recover it from there on return. Our swap subroutine destroyed the AX register while the bubblesort subroutine destroyed AX, CX, and SI. BX was not modified in the subroutine. It had the same value at entry and at exit; it was only used by the subroutine. Our next example improves on the previous version by saving and restoring any registers that it will modify using the PUSH and POP operations.

Example 5.4

```
01      ; bubble sort and swap subroutines saving and restoring registers
02      [org 0x0100]
03                jmp start
04
05      data:     dw   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
06      data2:    dw   328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
07                dw   888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
08      swapflag: db   0
09
10      swap:     push ax                 ; save old value of ax
11
12                mov  ax, [bx+si]        ; load first number in ax
13                xchg ax, [bx+si+2]      ; exchange with second number
14                mov  [bx+si], ax        ; store second number in first
15
16                pop  ax                 ; restore old value of ax
17                ret                     ; go back to where we came from
18
19      bubblesort: push ax               ; save old value of ax
20                push cx                 ; save old value of cx
21                push si                 ; save old value of si
22
23                dec  cx                 ; last element not compared
24                shl  cx, 1              ; turn into byte count
25
26      mainloop: mov  si, 0              ; initialize array index to zero
27                mov  byte [swapflag], 0 ; reset swap flag to no swaps
28
29      innerloop: mov  ax, [bx+si]       ; load number in ax
30                cmp  ax, [bx+si+2]      ; compare with next number
31                jbe  noswap             ; no swap if already in order
32
```

```
33                call swap               ; swaps two elements
34                mov  byte [swapflag], 1 ; flag that a swap has been done
35
36      noswap:   add  si, 2              ; advance si to next index
37                cmp  si, cx             ; are we at last index
38                jne  innerloop          ; if not compare next two
39
40                cmp  byte [swapflag], 1 ; check if a swap has been done
41                je   mainloop           ; if yes make another pass
42
43                pop  si                 ; restore old value of si
44                pop  cx                 ; restore old value of cx
45                pop  ax                 ; restore old value of ax
46                ret                     ; go back to where we came from
47
48      start:    mov  bx, data           ; send start of array in bx
49                mov  cx, 10             ; send count of elements in cx
50                call bubblesort         ; call our subroutine
51
52                mov  bx, data2          ; send start of array in bx
53                mov  cx, 20             ; send count of elements in cx
54                call bubblesort         ; call our subroutine again
55
56                mov  ax, 0x4c00         ; terminate program
57                int  0x21
```

19-21	When multiple registers are pushed, order is very important. If AX, CX, and SI are pushed in this order, they must be popped in the reverse order of SI, CX, and AX. This is again because the stack behaves in a Last In First Out manner.

Inside the debugger we can observe that the registers before and after the CALL operation are exactly identical. Effectively the caller can assume the registers are untouched. By tracing into the subroutines we can observe how their value is saved on the stack by the PUSH instructions and recovered from their before exit. Saving and restoring registers this way in subroutines is a standard way and must be followed.

PUSH

PUSH decrements SP (the stack pointer) by two and then transfers a word from the source operand to the top of stack now pointed to by SP. PUSH often is used to place parameters on the stack before calling a procedure; more generally, it is the basic means of storing temporary data on the stack.

POP

POP transfers the word at the current top of stack (pointed to by SP) to the destination operand and then increments SP by two to point to the new top of stack. POP can be used to move temporary variables from the stack to registers or memory.

Observe that the operand of PUSH is called a source operand since the data is moving to the stack from the operand, while the operand of POP is called destination since data is moving from the stack to the operand.

CALL

CALL activates an out-of-line procedure, saving information on the stack to permit a RET (return) instruction in the procedure to transfer control back to the instruction following the CALL. For an intra segment direct CALL, SP is decremented by two and IP is pushed onto the stack. The target procedure's relative displacement from the CALL instruction is then added to the instruction pointer. For an inter segment direct CALL, SP is decremented by two, and CS is pushed onto the stack. CS is replaced by the segment word contained in the instruction. SP again is decremented by two. IP is pushed onto the stack and replaced by the offset word in the instruction.

The out-of-line procedure is the temporary division, the concept of roundabout that we discussed. Near calls are also called intra segment calls, while far calls are called inter-segment calls. There are also versions that are called indirect calls; however they will be discuss later when they are used.

RET

RET (Return) transfers control from a procedure back to the instruction following the CALL that activated the procedure. RET pops the word at the top of the stack (pointed to by register SP) into the instruction pointer and increments SP by two. If RETF (inter segment RET) is used the word at the top of the stack is popped into the IP register and SP is incremented by two. The word at the new top of stack is popped into the CS register, and SP is again incremented by two. If an optional pop value has been specified, RET adds that value to SP. This feature may be used to discard parameters pushed onto the stack before the execution of the CALL instruction.

5.5. PARAMETER PASSING THROUGH STACK

Due to the limited number of registers, parameter passing by registers is constrained in two ways. The maximum parameters a subroutine can receive are seven when all the general registers are used. Also, with the subroutines are themselves limited in their use of registers, and this limited increases when the subroutine has to make a nested call thereby using certain registers as its parameters. Due to this, parameter passing by registers is not expandable and generalizable. However this is the fastest mechanism available for passing parameters and is used where speed is important.

Considering stack as an alternate, we observe that whatever data is placed there, it stays there, and across function calls as well. For example the bubble sort subroutine needs an array address and the count of elements. If we place both of these on the stack, and call the subroutine afterwards, it will stay there. The subroutine is invoked with its return address on top of the stack and its parameters beneath it.

To access the arguments from the stack, the immediate idea that strikes is to pop them off the stack. And this is the only possibility using the given set of information. However the first thing popped off the stack would be the return address and not the arguments. This is because the arguments were first pushed on the stack and the subroutine was called afterwards. The arguments cannot be popped without first popping the return address. If a heaving thing falls on someone's leg, the heavy thing is removed first and the leg is not pulled out to reduce the damage. Same is the case with our parameters on which the return address has fallen.

To handle this using PUSH and POP, we must first pop the return address in a register, then pop the operands, and push the return address back on the stack so that RET will function normally. However so much effort doesn't seem to pay back the price. Processor designers should have provided a logical and neat way to perform this operation. They did provided a way and infact we will do this without introducing any new instruction.

Recall that the default segment association of the BP register is the stack segment and the reason for this association had been deferred for now. The reason is to peek inside the stack using the BP register and read the parameters without removing them and without touching the stack pointer. The stack pointer could not be used for this purpose, as it cannot be used in an effective address. It is automatically used as a pointer and cannot be explicitly used. Also the stack pointer is a dynamic pointer and sometimes changes without telling us in the background. It is just that whenever we touch it, it is where we expect it to be. The base pointer is provided as a replacement of the stack pointer so that we can peek inside the stack without modifying the structure of the stack.

When the bubble sort subroutine is called, the stack pointer is pointing to the return address. Two bytes below it is the second parameter and four bytes below is the first parameter. The stack pointer is a reference point to these parameters. If the value of SP is captured in BP, then the return address is located at [bp+0], the second parameter is at [bp+2], and the first parameter is at [bp+4]. This is because SP and BP both had the same value and they both defaulted to the same segment, the stack segment.

This copying of SP into BP is like taking a snapshot or like freezing the stack at that moment. Even if more pushes are made on the stack decrementing the stack pointer, our reference point will not change. The parameters will still be accessible at the same offsets from the base pointer. If however the stack pointer increments beyond the base pointer, the references will become invalid. The base pointer will act as the datum point to access our parameters. However we have destroyed the original value of BP in the process, and this will cause problems in nested calls where both the outer and the inner subroutines need to access their own parameters. The outer subroutine will have its base pointer destroyed after the call and will be unable to access its parameters.

To solve both of these problems, we reach at the standard way of accessing parameters on the stack. The first two instructions of any subroutines accessing its parameters from the stack are given below.

```
push bp
mov  bp, sp
```

As a result our datum point has shifted by a word. Now the old value of BP will be contained in [bp] and the return address will be at [bp+2]. The second parameters will be [bp+4] while the first one will be at [bp+6]. We give an example of bubble sort subroutine using this standard way of argument passing through stack.

Example 5.5

```
01      ; bubble sort subroutine taking parameters from stack
02      [org 0x0100]
03                      jmp start
04
05      data:           dw   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
06      data2:          dw   328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
07                      dw   888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
08      swapflag:       db   0
09
10      bubblesort:     push bp                 ; save old value of bp
11                      mov  bp, sp             ; make bp our reference point
12                      push ax                 ; save old value of ax
13                      push bx                 ; save old value of bx
14                      push cx                 ; save old value of cx
15                      push si                 ; save old value of si
16
17                      mov  bx, [bp+6]         ; load start of array in bx
18                      mov  cx, [bp+4]         ; load count of elements in cx
19                      dec  cx                 ; last element not compared
20                      shl  cx, 1              ; turn into byte count
21
22      mainloop:       mov  si, 0              ; initialize array index to zero
23                      mov  byte [swapflag], 0 ; reset swap flag to no swaps
24
25      innerloop:      mov  ax, [bx+si]        ; load number in ax
26                      cmp  ax, [bx+si+2]      ; compare with next number
27                      jbe  noswap             ; no swap if already in order
28
29                      xchg ax, [bx+si+2]      ; exchange ax with second number
30                      mov  [bx+si], ax        ; store second number in first
31                      mov  byte [swapflag], 1 ; flag that a swap has been done
32
33      noswap:         add  si, 2              ; advance si to next index
34                      cmp  si, cx             ; are we at last index
35                      jne  innerloop          ; if not compare next two
36
```

```
37                cmp  byte [swapflag], 1 ; check if a swap has been done
38                je   mainloop           ; if yes make another pass
39
40                pop  si                 ; restore old value of si
41                pop  cx                 ; restore old value of cx
42                pop  bx                 ; restore old value of bx
43                pop  ax                 ; restore old value of ax
44                pop  bp                 ; restore old value of bp
45                ret  4                  ; go back and remove two params
46
47        start:  mov  ax, data
48                push ax                 ; place start of array on stack
49                mov  ax, 10
50                push ax                 ; place element count on stack
51                call bubblesort         ; call our subroutine
52
53                mov  ax, data2
54                push ax                 ; place start of array on stack
55                mov  ax, 20
56                push ax                 ; place element count on stack
57                call bubblesort         ; call our subroutine again
58
59                mov  ax, 0x4c00         ; terminate program
60                int  0x21
```

11	The value of the stack pointer is captured in the base pointer. With further pushes SP will change but BP will not and therefore we will read parameters from bp+4 and bp+6.
45	The form of RET that takes an argument is used causing four to be added to SP after the return address has been popped in the instruction pointer. This will effectively discard the parameters that are still there on the stack.
47-50	We push the address of the array we want to sort followed by the count of elements. As immediate cannot be directly pushed in the 8088 architecture, we first load it in the AX register and then push the AX register on the stack.

Inside the debugger, concentrate on the operation of BP and the stack. The parameters are placed on the stack by the caller, the subroutine accesses them using the base pointer, and the special form of RET removes them without any extra instruction. The value of stack pointer of FFF6 is turned into FFFE by the RET instruction. This was the value in SP before any of the parameters was pushed.

Stack Clearing by Caller or Callee

Parameters pushed for a subroutine are a waste after the subroutine has returned. They have to be cleared from the stack. Either of the caller and the callee can take the responsibility of clearing them from there. If the callee has to clear the stack it cannot do this easily unless RET n exists. That is why most general processors have this instruction. Stack clearing by the caller needs an extra instruction on behalf of the caller after every call made to the subroutine, unnecessarily increasing instructions in the program. If there are thousand calls to a subroutine the code to clear the stack is repeated a thousand times. Therefore the prevalent convention in most high level languages is stack clearing by the callee; even though the other convention is still used in some languages.

If RET n is not available, stack clearing by the callee is a complicated process. It will have to save the return address in a register, then remove the parameters, and then place back the return address so that RET will function. When this instruction was introduced in processors, only then high level language designers switched to stack clearing by the callee. This is also exactly why RET n adds n to SP after performing the operation of RET. The other way around would be totally useless for our purpose. Consider the stack condition at the time of RET and this will become clear why this will be

useless. Also observe that RET n has discarded the arguments rather than popping them as they were no longer of any use either of the caller or the callee.

The strong argument in favour of callee cleared stacks is that the arguments were placed on the stack for the subroutine, the caller did not needed them for itself, so the subroutine is responsible for removing them. Removing the arguments is important as if the stack is not cleared or is partially cleared the stack will eventually become full, SP will reach 0, and thereafter wraparound producing unexpected results. This is called stack overflow. Therefore clearing anything placed on the stack is very important.

5.6. LOCAL VARIABLES

Another important role of the stack is in the creation of local variables that are only needed while the subroutine is in execution and not afterwards. They should not take permanent space like global variables. Local variables should be created when the subroutine is called and discarded afterwards. So that the spaced used by them can be reused for the local variables of another subroutine. They only have meaning inside the subroutine and no meaning outside it.

The most convenient place to store these variables is the stack. We need some special manipulation of the stack for this task. We need to produce a gap in the stack for our variables. This is explained with the help of the swapflag in the bubble sort example.

The swapflag we have declared as a word occupying space permanently is only needed by the bubble sort subroutine and should be a local variable. Actually the variable was introduced with the intent of making it a local variable at this time. The stack pointer will be decremented by an extra two bytes thereby producing a gap in which a word can reside. This gap will be used for our temporary, local, or automatic variable; however we name it. We can decrement it as much as we want producing the desired space, however the decrement must be by an even number, as the unit of stack operation is a word. In our case we needed just one word. Also the most convenient position for this gap is immediately after saving the value of SP in BP. So that the same base pointer can be used to access the local variables as well; this time using negative offsets. The standard way to start a subroutine which needs to access parameters and has local variables is as under.

```
push bp
mov  bp, sp
sub  sp, 2
```

The gap could have been created with a dummy push, but the subtraction makes it clear that the value pushed is not important and the gap will be used for our local variable. Also gap of any size can be created in a single instruction with subtraction. The parameters can still be accessed at bp+4 and bp+6 and the swapflag can be accessed at bp-2. The subtraction in SP was after taking the snapshot; therefore BP is above the parameters but below the local variables. The parameters are therefore accessed using positive offsets from BP and the local variables are accessed using negative offsets.

We modify the bubble sort subroutine to use a local variable to store the swap flag. The swap flag remembered whether a swap has been done in a particular iteration of bubble sort.

Example 5.6

```
01      ; bubble sort subroutine using a local variable
02      [org 0x0100]
03                      jmp start
04
05      data:           dw   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
06      data2:          dw   328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
```

```
07                  dw   888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
08
09      bubblesort: push bp                 ; save old value of bp
10                  mov  bp, sp             ; make bp our reference point
11                  sub sp, 2               ; make two byte space on stack
12                  push ax                 ; save old value of ax
13                  push bx                 ; save old value of bx
14                  push cx                 ; save old value of cx
15                  push si                 ; save old value of si
16
17                  mov  bx, [bp+6]         ; load start of array in bx
18                  mov  cx, [bp+4]         ; load count of elements in cx
19                  dec  cx                 ; last element not compared
20                  shl  cx, 1              ; turn into byte count
21
22      mainloop:   mov  si, 0              ; initialize array index to zero
23                  mov  word [bp-2], 0     ; reset swap flag to no swaps
24
25      innerloop:  mov  ax, [bx+si]        ; load number in ax
26                  cmp  ax, [bx+si+2]      ; compare with next number
27                  jbe  noswap             ; no swap if already in order
28
29                  xchg ax, [bx+si+2]      ; exchange ax with second number
30                  mov  [bx+si], ax        ; store second number in first
31                  mov  word [bp-2], 1     ; flag that a swap has been done
32
33      noswap:     add  si, 2              ; advance si to next index
34                  cmp  si, cx             ; are we at last index
35                  jne  innerloop          ; if not compare next two
36
37                  cmp  word [bp-2], 1     ; check if a swap has been done
38                  je   mainloop           ; if yes make another pass
39
40                  pop  si                 ; restore old value of si
41                  pop  cx                 ; restore old value of cx
42                  pop  bx                 ; restore old value of bx
43                  pop  ax                 ; restore old value of ax
44                  mov  sp, bp             ; remove space created on stack
45                  pop  bp                 ; restore old value of bp
46                  ret  4                  ; go back and remove two params
47
48      start:      mov  ax, data
49                  push ax                 ; place start of array on stack
50                  mov  ax, 10
51                  push ax                 ; place element count on stack
52                  call bubblesort         ; call our subroutine
53
54                  mov  ax, data2
55                  push ax                 ; place start of array on stack
56                  mov  ax, 20
57                  push ax                 ; place element count on stack
58                  call bubblesort         ; call our subroutine again
59
60                  mov  ax, 0x4c00         ; terminate program
61                  int  0x21
```

11	A word gap has been created for swap flag. This is equivalent to a dummy push. The registers are pushed above this gap.
23	The swapflag is accessed with [bp-2]. The parameters are accessed in the same manner as the last examples.
44	We are removing the hole that we created. The hole is removed by restoring the value of SP that it had at the time of snapshot or at the value it had before the local variable was created. This can be replaced with “add sp, 2” however the one used in the code is preferred since it does not require to remember how much space for local variables was allocated in the start. After this operation SP points to the old value of BP from where we can proceed as usual.

We needed memory to store the swap flag. The fact that it is in the stack segment or the data segment doesn’t bother us. This will just change the addressing scheme.

EXERCISES

1. Replace the following valid instruction with a single instruction that has the same effect. Don't consider the effect on flags.

```
    push word L1
    jmp L2
L1:
```

2. Replace the following invalid instructions with a single instruction that has the same effect.

```
a.  pop  ip
b.  mov  ip, L5
c.  sub  sp, 2
    mov  [ss:sp], ax
d.  mov ax, [ss:sp]
    add sp, 2
e.  add  sp, 6
    mov  ip, [ss:sp-6]
```

3. Write a recursive function to calculate the Fibonacci of a number. The number is passed as a parameter via the stack and the calculated Fibonacci number is returned in the AX register. A local variable should be used to store the return value from the first recursive call. Fibonacci function is defined as follows:

```
Fibonacci(0) = 0
Fibonacci(1) = 1
Fibonacci(n) = Fibonacci(n-1) + Fibonacci(n-2)
```

4. Write the above Fibonacci function iteratively.
   HINT: Use two registers to hold the current and the previous Fibonacci numbers in a loop.
5. Write a function switch_stack meant to change the current stack and will be called as below. The function should destroy no registers.

```
push word [new_stack_segment]
push word [new_stack_offset]
call switch_stack
```

6. Write a function "addtoset" that takes offset of a function and remembers this offset in an array that can hold a maximum of 8 offsets. It does nothing if there are already eight offsets in the set. Write another function "callset" that makes a call to all functions in the set one by one.
7. Do the above exercise such that "callset" does not use a CALL or a JMP to invoke the functions.
   HINT: Setup the stack appropriately such that the RET will execute the first function, its RET execute the next and so on till the last RET returns to the caller of "callset."
8. Make an array of 0x80 bytes and treat it as one of 0x400 bits. Write a function myalloc that takes one argument, the number of bits. It finds that many consecutive zero bits in the array, makes them one, and returns in AX the index of the first bit. Write another function myfree that takes two arguments, index of a bit in the array, and the number of bits. It makes that many consecutive bits zero, whatever their previous values are, starting from the index in the first argument.
9. [Circular Queue] Write functions to implement circular queues. Declare 16x32 words of data for 16 queues numbered from 0 to 15. Each queue has a front index, a rear index and 30 locations for data totaling to 32 words. Declare another word variable whose 16 bits correspond to the 16 queues and a 1 bit signals that the corresponding queue is used and a 0 bit signals that it is free. Write a function "qcreate" that returns a queue number after finding a free queue or -1 if it failed. Write a function "qdestroy" that marks the queue as free. Write two other functions "qadd" and "qremove" that

can add and remove items from the circular queue. The two functions return 0 if they failed and 1 otherwise.

10. [Linked List] Declare 1024 nodes of four bytes each. The first 2 bytes will be used for data and the next 2 bytes for storing the offset of another node. Also declare a word variable “firstfree” to store the offset of the first free node. Write the following five functions:
    a. “init” chains all 1024 nodes into a list with offset of first node in firstfree, offset of the second node in the later two bytes of the first node and so on. The later two bytes of the last node contains zero.
    b. “createlist” returns the offset of the node stored in firstfree through AX. It sets firstfree to the offset stored in the later two bytes of that node, and it sets the later two bytes of that node to zero.
    c. “insertafter” takes two parameters, the offset of a node and a word data. It removes one node from freelist just like “createlist” and inserts it after the said node and updates the new node’s data part.
    d. “deleteafter” takes a node as its parameter and removes the node immediately after it in the linked list if there is one.
    e. “deletelist” takes a node as its parameters and traverses the linked list starting at this node and removes all nodes from it and add them back to the free list.

6
Display Memory

The debugger gives a very close vision of the processor. That is why every program written till now was executed inside the debugger. Also the debugger is a very useful tool in assembly language program development, since many bugs only become visible when each instruction is independently monitored the way the debugger allows us to do. We will now be using the display screen in character mode, the way DOS uses this screen. The way we will access this screen is specific to the IBM PC.

6.1. ASCII CODES

The computer listens, sees, and speaks in numbers. Even a character is a number inside the computer. For example the keyboard is labeled with characters however when we press 'A', a specific number is transferred from the keyboard to the computer. Our program interprets that number as the character 'A'. When the same number comes on display, the Video Graphics Adapter (VGA) in our computer shows the shape of 'A'. Even the shape is stored in binary numbers with a one bit representing a pixel on the screen that is turned on and a zero bit representing a pixel that is not glowing. This example is considering a white on black display and no colors. This is the way a shape is drawn on the screen. The interpretation of 'A' is performed by the VGA card, while the monitor or CRT (cathode ray tube) only glows the pixels on and turns them off. The keyboard has a key labeled 'A' and pressing it the screen shows 'A' but all that happened inside was in numbers.

An 'A' on any computer and any operating system is an 'A' on every other computer and operating system. This is because a standard numeric representation of all commonly used characters has been developed. This is called the ASCII code, where ASCII stands for American Standard Code for Information Interchange. The name depicts that this is a code that allows the interchange of information; 'A' written on one computer will remain an 'A' on another. The ASCII table lists all defined characters and symbols and their standardized numbers. All ASCII based computers use the same code. There are few other standards like EBCDIC and gray codes, but ASCII has become the most prevalent standard and is used for Internet communication as well. It has become the de facto standard for global communication. The character mode displays of our computer use the ASCII standard. Some newer operating systems use a new standard Unicode but it is not relevant to us in the current discussion.

Standard ASCII has 128 characters with numbers assigned from 0 to 127. When IBM PC was introduced, they extended the standard ASCII and defined 128 more characters. Thus extending the total number of symbols from 128 to 256 numbered from 0 to 255 fitting in an 8-bit byte. The newer characters were used for line drawing, window corners, and some non-English characters. The need for these characters was never felt on teletype terminals, but with the advent of IBM PC and its full screen display, these semi-graphics characters were the need of the day. Keep in mind that at that time there was no graphics mode available.

The extended ASCII code is just a de facto industry standard but it is not defined by an organization like the standard ASCII. Printers, displays, and all other peripherals related to the IBM PC understand the ASCII code. If the

code for 'A' is sent to the printer, the printer will print the shape of 'A', if it is sent to the display, the VGA card will form the shape of 'A' on the CRT. If it is sent to another computer via the serial port, the other computer will understand that this is an 'A'.

The important thing to observe in the ASCII table is the contiguous arrangement of the uppercase alphabets (41-5A), the lowercase alphabets (61-7A), and the numbers (30-39). This helps in certain operations with ASCII, for example converting the case of characters by adding or subtracting 0x20 from it. It also helps in converting a digit into its ASCII representation by adding 0x30 to it.

6.2. DISPLAY MEMORY FORMATION

We will explore the working of the display with ASCII codes, since it is our immediately accessible hardware. When 0x40 is sent to the VGA card, it will turn pixels on and off in such a way that a visual representation of 'A' appears on the screen. It has no reality, just an interpretation. In later chapters we will program the VGA controller to display a new shape when the ASCII of 'A' is received by it.

The video device is seen by the computer as a memory area containing the ASCII codes that are currently displayed on the screen and a set of I/O ports controlling things like the resolution, the cursor height, and the cursor position. The VGA memory is seen by the computer just like its own memory. There is no difference; rather the computer doesn't differentiate, as it is accessible on the same bus as the system memory. Therefore if that appropriate block of the screen is cleared, the screen will be cleared. If the ASCII of 'A' is placed somewhere in that block, the shape of 'A' will appear on the screen at a corresponding place.

This correspondence must be defined as the memory is a single dimensional space while the screen is two dimensional having 80 rows and 25 columns. The memory is linearly mapped on this two dimensional space, just like a two dimensional is mapped in linear memory. There is one word per character in which a byte is needed for the ASCII code and the other byte is used for the character's attributes discussed later. Now the first 80 words will correspond to the first row of the screen and the next 80 words will correspond to the next row. By making the memory on the video controller accessible to the processor via the system bus, the processor is now in control of what is displayed on the screen.

The three important things that we discussed are.

- One screen location corresponds to a word in the video memory
- The video controller memory is accessible to the processor like its own memory.
- ASCII code of a character placed at a cell in the VGA memory will cause the corresponding ASCII shape to be displayed on the corresponding screen location.

Display Memory Base Address

The memory at which the video controller's memory is mapped must be a standard, so that the program can be written in a video card independent manner. Otherwise if different vendors map their video memory at different places in the address space, as was the problem in the start, writing software was a headache. BIOS vendors had a problem of dealing with various card vendors. The IBM PC text mode color display is now fixed so that system software can work uniformly. It was fixed at the physical memory location of B8000. The first byte at this location contains the ASCII for the character displayed at the top left of the video screen. Dropping the zero we can load the rest in a segment register to access the video memory. If we do something in this memory, the effect can be seen on the screen. For example we can

write a virus that makes any character we write drop to the bottom of the screen.

Attribute Byte

The second byte in the word designated for one screen location holds the foreground and background colors for the character. This is called its video attribute. So the pair of the ASCII code in one byte and the attribute in the second byte makes the word that corresponds to one location on the screen. The lower address contains the code while the higher one contains the attribute. The attribute byte as detailed below has the RGB for the foreground and the background. It has an intensity bit for the foreground color as well thus making 16 possible colors of the foreground and 8 possible colors for the background. When bit 7 is set the character keeps on blinking on the screen. This bit has some more interpretations like background intensity that has to be activated in the video controller through its I/O ports.

7	6	5	4	3	2	1	0

7 – Blinking of foreground character
6 – Red component of background color
5 – Green component of background color
4 – Blue component of background color
3 – Intensity component of foreground color
2 – Red component of foreground color
1 – Green component of foreground color
0 – Blue component of foreground color

Display Examples

Both DS and ES can be used to access the video memory. However we commonly keep DS for accessing our data, and load ES with the segment of video memory. Loading a segment register with an immediate operand is not allowed in the 8088 architecture. We therefore load the segment register via a general purpose register. Other methods are loading from a memory location and a combination of push and pop.

```
mov  ax, 0xb800
mov  es, ax
```

This operation has opened a window to the video memory. Now the following instruction will print an ‘A’ on the top left of the screen in white color on black background.

```
mov  word [es:0], 0x0741
```

The segment override is used since ES is pointing to the video memory. Since the first word is written to, the character will appear at the top left of the screen. The 41 that goes in the lower byte is the ASCII code for ‘A’. The 07 that goes in the higher byte is the attribute with I=0, R=1, G=1, B=1 for the foreground, meaning white color in low intensity and R=0, G=0, B=0 for the background meaning black color and the most significant bit cleared so that there is no blinking. Now consider the following instruction.

```
mov  word [es:160], 0x1230
```

This is displayed 80 words after the start and there are 80 characters in one screen row. Therefore this is displayed on the first column of the second line. The ASCII code used is 30, which represents a ‘0’ while the attribute byte is 12 meaning green color on blue background.

We take our first example to clear the screen.

Example 6.1

```
01      ; clear the screen
02      [org 0x0100]
03                  mov  ax, 0xb800         ; load video base in ax
04                  mov  es, ax             ; point es to video base
05                  mov  di, 0              ; point di to top left column
06
07      nextchar:   mov  word [es:di], 0x0720 ; clear next char on screen
08                  add  di, 2              ; move to next screen location
09                  cmp  di, 4000           ; has the whole screen cleared
10                  jne  nextchar           ; if no clear next position
11
12                  mov  ax, 0x4c00         ; terminate program
13                  int  0x21
```

07	The code for space is 20 while 07 is the normal attribute of low intensity white on black with no blinking. Even to clear the screen or put a blank on a location there is a numeric code.
08	DI is incremented twice since each screen location corresponds to two byte in video memory.
09	DI is compared with 80*25*2=4000. The last word location that corresponds to the screen is 3998.

Inside the debugger the operation of clearing the screen cannot be observed since the debugger overwrites whatever is displayed on the screen. Directly executing the COM file from the command prompt*, we can see that the screen is cleared. The command prompt that reappeared is printed after the termination of our application. This is the first application that can be directly executed to see some output on the screen.

6.3. HELLO WORLD IN ASSEMBLY LANGUAGE

To declare a character in assembly language, we store its ASCII code in a byte. The assembler provides us with another syntax that doesn't forces us to remember the ASCII code. The assembler also provides a syntax that simplifies declaration of consecutive characters, usually called a string. The three ways used below are identical in their meaning.

```
db   0x61, 0x62, 0x63
db   'a', 'b', 'c'
db   'abc'
```

When characters are stored in any high level or low level language the actual thing stored in a byte is their ASCII code. The only thing the language helps in is a simplified declaration.

Traditionally the first program in higher level languages is to print "hello world" on the screen. However due to the highly granular nature of assembly language, we are only now able to write it in assembly language. In writing this program, we make a generic routine that can print any string on the screen.

Example 6.2

```
01      ; hello world in assembly
02      [org 0x0100]
03                  jmp  start
04
05      message:    db   'hello world'      ; string to be printed
06      length:     dw   11                 ; length of the string
07
08      ; subroutine to clear the screen
09      clrscr:     push es
10                  push ax
11                  push di
```

* Remember that if this example is run in a DOS window on some newer operating systems, a full screen DOS application must be run before this program so that screen access is enabled.

```
12
13                  mov  ax, 0xb800
14                  mov  es, ax             ; point es to video base
15                  mov  di, 0              ; point di to top left column
16
17      nextloc:    mov  word [es:di], 0x0720 ; clear next char on screen
18                  add  di, 2              ; move to next screen location
19                  cmp  di, 4000           ; has the whole screen cleared
20                  jne  nextloc            ; if no clear next position
21
22                  pop  di
23                  pop  ax
24                  pop  es
25                  ret
26
27      ; subroutine to print a string at top left of screen
28      ; takes address of string and its length as parameters
29      printstr:   push bp
30                  mov  bp, sp
31                  push es
32                  push ax
33                  push cx
34                  push si
35                  push di
36
37                  mov  ax, 0xb800
38                  mov  es, ax             ; point es to video base
39                  mov  di, 0              ; point di to top left column
40                  mov  si, [bp+6]         ; point si to string
41                  mov  cx, [bp+4]         ; load length of string in cx
42                  mov  ah, 0x07           ; normal attribute fixed in al
43
44      nextchar:   mov  al, [si]           ; load next char of string
45                  mov  [es:di], ax        ; show this char on screen
46                  add  di, 2              ; move to next screen location
47                  add  si, 1              ; move to next char in string
48                  loop nextchar           ; repeat the operation cx times
49
50                  pop  di
51                  pop  si
52                  pop  cx
53                  pop  ax
54                  pop  es
55                  pop  bp
56                  ret  4
57
58      start:      call clrscr             ; call the clrscr subroutine
59
60                  mov  ax, message
61                  push ax                 ; push address of message
62                  push word [length]      ; push message length
63                  call printstr           ; call the printstr subroutine
64
65                  mov  ax, 0x4c00         ; terminate program
66                  int  0x21
```

05-06 The string definition syntax discussed above is used to declare a string “hello world” of 11 bytes and the length is stored in a separate variable.

09-25 The code to clear the screen from the last example is written in the form of a subroutine. Since the subroutine had no parameters, only modified registers are saved and restored from the stack.

29-35 The standard subroutine format with parameters received via stack and all registers saved and restored is used.

37-42 ES is initialized to point to the video memory via the AX register. Two pointer registers are used; SI to point to the string and DI to point to the top left location of the screen. CX is loaded with the length of the string. Normal attribute of low intensity white on black with no blinking is loaded in the AH register.

44-45 The next character from the string is loaded into AL. Now AH holds the attribute and AL the ASCII code of the character. This pair is

46-47	written on the video memory using DI with the segment override prefix for ES to access the video memory segment.
48	The string pointer is incremented by one while the video memory pointer is incremented by two since one char corresponds to a word on the screen.
50-56	The loop instruction used is equivalent to a combination of “dec cx” and “jnz nextchar.” The loop is executed CX times.
62	The registers pushed on the stack are recovered in opposite order and the “ret 4” instruction removes the two parameters placed on the stack. Memory can be directly pushed on the stack.

When the program is executed, screen is cleared and the greetings is displayed on the top left of the screen. This screen location and the attribute used were hard coded in the program and can also be made variable. Then we will be able to print anywhere on the screen.

6.4. NUMBER PRINTING IN ASSEMBLY

Another problem related to the display is printing numbers. Every high level language allows some simple way to print numbers on the screen. As we have seen, everything on the screen is a pair of ASCII code and its attribute and a number is a raw binary number and not a collection of ASCII codes. For example a 10 is stored as a 10 and not as the ASCII code of 1 followed by the ASCII code of 0. If this 10 is stored in a screen location, the output will be meaningless, as the character associate to ASCII code 10 will be shown on the screen. So there is a process that converts a number in its ASCII representation. This process works for any number in any base. We will discuss our examples with respect to the decimal base and later observe the effect of changing to different bases.

Number Printing Algorithm

The key idea is to divide the number by the base number, 10 in the case of decimal. The remainder can be from 0-9 and is the right most digit of the original number. The remaining digits fall in the quotient. The remainder can be easily converted into its ASCII equivalent and printed on the screen. The other digits can be printed in a similar manner by dividing the quotient again by 10 to separate the next digit and so on.

However the problem with this approach is that the first digit printed is the right most one. For example 253 will be printed as 352. The remainder after first division was 3, after second division was 5 and after the third division was 2. We have to somehow correct the order so that the actual number 253 is displayed, and the trick is to use the stack since the stack is a Last In First Out structure so if 3, 5, and 2 are pushed on it, 2, 5, and 3 will come out in this order. The steps of our algorithm are outlined below.

- Divide the number by base (10 in case of decimal)
- The remainder is its right most digit
- Convert the digit to its ASCII representation (Add 0x30 to the remainder in case of decimal)
- Save this digit on stack
- If the quotient is non-zero repeat the whole process to get the next digit, otherwise stop
- Pop digits one by one and print on screen left to right

DIV Instruction

The division used in the process is integer division and not floating point division. Integer division gives an integer quotient and an integer remainder. A division algorithm is now needed. Fortunately or unfortunately there is a

DIV instruction available in the 8088 processor. There are two forms of the DIV instruction. The first form divides a 32bit number in DX:AX by its 16bit operand and stores the 16bit quotient in AX and the 16bit remainder in DX. The second form divides a 16bit number in AX by its 8bit operand and stores the 8bit quotient in AL and the 8bit remainder in AH. For example "DIV BL" has an 8bit operand, so the implied dividend is 16bit and is stored in the AX register and "DIV BX" has a 16bit operand, so the implied dividend is 32bit and is therefore stored in the concatenation of the DX and AX registers. The higher word is stored in DX and the lower word in AX.

If a large number is divided by a very small number it is possible that the quotient is larger than the space provided for it in the implied destination. In this case an interrupt is automatically generated and the program is usually terminated as a result. This is called a divide overflow error; just like the calculator shows an –E– when the result cannot be displayed. This interrupt will be discussed later in the discussion of interrupts.

DIV (divide) performs an unsigned division of the accumulator (and its extension) by the source operand. If the source operand is a byte, it is divided into the two-byte dividend assumed to be in registers AL and AH. The byte quotient is returned in AL, and the byte remainder is returned in AH. If the source operand is a word, it is divided into the two-word dividend in registers AX and DX. The word quotient is returned in AX, and the word remainder is returned in DX. If the quotient exceeds the capacity of its destination register (FF for byte source, FFFF for word source), as when division by zero is attempted, a type 0 interrupt is generated, and the quotient and remainder are undefined.

Number Printing Example

The next example introduces a subroutine that can print a number received as its only argument at the top left of the screen using the algorithm just discussed.

Example 6.3

```
001      ; number printing algorithm
002      [org 0x0100]
003                  jmp  start
004
005-022  ;;;;; COPY LINES 008-025 FROM EXAMPLE 6.2 (clrscr) ;;;;;
023
024      ; subroutine to print a number at top left of screen
025      ; takes the number to be printed as its parameter
026      printnum:    push bp
027                  mov  bp, sp
028                  push es
029                  push ax
030                  push bx
031                  push cx
032                  push dx
033                  push di
034
035                  mov  ax, 0xb800
036                  mov  es, ax             ; point es to video base
037                  mov  ax, [bp+4]         ; load number in ax
038                  mov  bx, 10             ; use base 10 for division
039                  mov  cx, 0              ; initialize count of digits
040
041      nextdigit:  mov  dx, 0              ; zero upper half of dividend
042                  div  bx                 ; divide by 10
043                  add  dl, 0x30           ; convert digit into ascii value
044                  push dx                 ; save ascii value on stack
045                  inc  cx                 ; increment count of values
046                  cmp  ax, 0              ; is the quotient zero
047                  jnz  nextdigit          ; if no divide it again
048
049                  mov  di, 0              ; point di to top left column
050
```

```
051     nextpos:      pop  dx                 ; remove a digit from the stack
052                   mov  dh, 0x07           ; use normal attribute
053                   mov [es:di], dx         ; print char on screen
054                   add  di, 2              ; move to next screen location
055                   loop nextpos            ; repeat for all digits on stack
056
057                   pop  di
058                   pop  dx
059                   pop  cx
060                   pop  bx
061                   pop  ax
062                   pop  es
063                   pop  bp
064                   ret  2
065
066     start:        call  clrscr            ; call the clrscr subroutine
067
068                   mov ax, 4529
069                   push ax                 ; place number on stack
070                   call printnum           ; call the printnum subroutine
071
072                   mov ax, 0x4c00          ; terminate program
073                   int 0x21
```

026-033	The registers are saved as an essential practice. The only parameter received is the number to be printed.
035-039	ES is initialized to video memory. AX holds the number to be printed. BX is the desired base, and can be loaded from a parameter. CX holds the number of digits pushed on the stack. This count is initialized to zero, incremented with every digit pushed and is used when the digits are popped one by one.
041-042	DX must be zeroed as our dividend is in AX and we want a 32bit division. After the division AX holds the quotient and DX holds the remainder. Actually the remainder is only in DL since the remainder can be from 0 to 9.
043-045	The remainder is converted into its ASCII representation and saved on the stack. The count of digits on the stack is incremented as well.
046-047	If the quotient is zero, all digits have been saved on the stack and if it is non-zero, we have to repeat the process to print the next digit.
049	DI is initialized to point to the top left of the screen, called the cursor home. If the screen location is to become a parameter, the value loaded in DI will change.
051-053	A digit is popped off the stack, the attribute byte is appended to it and it is displayed on the screen.
054-055	The next screen location is two bytes ahead so DI is incremented by two. The process is repeated CX times which holds the number of digits pushed on the stack.
057-064	We pop the registers pushed and “ret 2” to discard the only parameter on the stack.
066-070	The main program clears the screen and calls the printnum subroutine to print 4529 on the top left of the screen.

When the program is executed 4529 is printed on the top left of the screen. This algorithm is versatile in that the base number can be changed and the printing will be in the desired base. For example if “mov bx, 10” is changed to “mov bx, 2” the output will be in binary as 001000110110001. Similarly changing it to “mov bx, 8” outputs the number in octal as 10661. Printing it in hexadecimal is a bit tricky, as the ASCII codes for A-F do not consecutively start after the codes for 0-9. Inside the debugger observe the working of the algorithm is just as described in the above illustration. The digits are

separated one by one and saved on the stack. From bottom to top, the stack holds 0034, 0035, 0032, and 0039 after the first loop is completed. The next loop pops them one by one and routes them to the screen.

6.5. SCREEN LOCATION CALCULATION

Until now our algorithms used a fixed attribute and displayed at a fixed screen location. We will change that to use any position on the screen and any attribute. For mapping from the two dimensional coordinate system of the screen to the one dimensional memory, we need to multiply the row number by 80 since there are 80 columns per row and add the column number to it and again multiply by two since there are 2 bytes for each character.

For this purpose the multiplication routine written previously can be used. However we introduce an instruction of the 8088 microprocessor at this time that can multiply 8bit or 16bit numbers.

MUL Instruction

MUL (multiply) performs an unsigned multiplication of the source operand and the accumulator. If the source operand is a byte, then it is multiplied by register AL and the double-length result is returned in AH and AL. If the source operand is a word, then it is multiplied by register AX, and the double-length result is returned in registers DX and AX.

String Printing at Desired Location

We modify the string printing program to take the x-position, the y-position, and the attribute as parameters. The desired location on the screen can be calculated with the following formulae.

```
location = ( hypos * 80 + epos ) * 2
```

Example 6.4

```
01      ; hello world at desired screen location
02      [org 0x0100]
03                  jmp  start
04
05      message:    db   'hello world'      ; string to be printed
06      length:     dw   11                 ; length of the string
07
08-25   ;;;;; COPY LINES 008-025 FROM EXAMPLE 6.2 (clrscr) ;;;;;
26
27      ; subroutine to print a string at top left of screen
28      ; takes x position, y position, string attribute, address of string
29      ; and its length as parameters
30      printstr:   push bp
31                  mov  bp, sp
32                  push es
33                  push ax
34                  push cx
35                  push si
36                  push di
37
38                  mov  ax, 0xb800
39                  mov  es, ax             ; point es to video base
40                  mov  al, 80             ; load al with columns per row
41                  mull  byte [bp+10]       ; multiply with y position
42                  add  ax, [bp+12]        ; add x position
43                  shl  ax, 1              ; turn into byte offset
44                  mov  dial              ; point di to required location
45                  mov  si, [bp+6]         ; point si to string
46                  mov  cx, [bp+4]         ; load length of string in cx
47                  mov  ah, [bp+8]         ; load attribute in ah
48
49      nextchar:   mov  al, [si]           ; load next char of string
50                  mov  [es:di], ax        ; show this char on screen
51                  add  di, 2              ; move to next screen location
```

```
52                  add  si, 1              ; move to next char in string
53                  loop nextchar           ; repeat the operation cx times
54
55                  pop  di
56                  pop  si
57                  pop  cx
58                  pop  ax
59                  pop  es
60                  pop  bp
61                  ret  10
62
63      start:      call clrscr             ; call the clrscr subroutine
64
65                  mov  ax, 30
66                  push ax                 ; push x position
67                  mov  ax, 20
68                  push ax                 ; push y position
69                  mov  ax, 1              ; blue on black attribute
70                  push ax                 ; push attribute
71                  mov  ax, message
72                  push ax                 ; push address of message
73                  push word [length]      ; push message length
74                  call printstr           ; call the printstr subroutine
75
76                  mov  ax, 0x4c00         ; terminate program
77                  int  0x21
```

41	Push and pop operations always operate on words; however data can be read as a word or as a byte. For example we read the lower byte of the parameter y-position in this case.
43	Shifting is used for multiplication by two, which should always be the case when multiplication or division by a power of two is desired.
61	The subroutine had 5 parameters so “ret 10” is used.
65-74	The main program pushes 30 as x-position, 20 as y-position meaning 30th column on 20th row. It pushes 1 as the attribute meaning low intensity blue on black with no blinking.

When the program is executed hello world is displayed at the desired screen location in the desired color. The x-position, y-position, and attribute parameters can be changed and their effect be seen on the screen. The important difference in this example is the use of MUL instruction and the calculation of screen location given the x and y positions.

EXERCISES

1. Replace the following valid instruction with a single instruction that has the same effect. Don’t consider the effect on flags.

   ```
   dec cx
   jnz L3
   ```

2. Write an infinite loop that shows two asterisks moving from right and left centers of the screen to the middle and then back. Use two empty nested loops with large counters to introduce some delay so that the movement is noticeable.
3. Write a function “printaddr” that takes two parameters, the segment and offset parts of an address, via the stack. The function should print the physical address corresponding to the segment offset pair passed at the top left of the screen. The address should be printed in hex and will therefore occupy exactly five columns. For example, passing 5600 and 7800 as parameters should result in 5D800 printed at the top left of the screen.
4. Write code that treats an array of 500 bytes as one of 4000 bits and for each blank position on the screen (i.e. space) sets the corresponding bit to zero and the rest to one.

5. Write a function “drawrect” that takes four parameters via the stack. The parameters are top, left, bottom, and right in this order. The function should display a rectangle on the screen using the characters + - and |.

7
String Instructions

7.1. STRING PROCESSING

Till now very simple instructions of the 8088 microprocessor have been introduced. In this chapter we will discuss a bit more powerful instructions that can process blocks of data in one go. They are called block processing or string instructions. This is the appropriate place to discuss these instructions as we have just introduced a block of memory, which is the video memory. The vision of this memory for the processor is just a block of memory starting at a special address. For example the clear screen operation initializes this whole block to 0720.

There are just 5 block processing instructions in 8088. In the primitive form, the instructions themselves operate on a single cell of memory at one time. However a special prefix repeats the instruction in hardware called the REP prefix. The REP prefix allows these instructions to operate on a number of data elements in one instruction. This is not like a loop; rather this repetition is hard coded in the processor. The five instructions are STOS, LODS, CMPS, SCAS, and MOVS called store string, load string, compare string, scan string, and move string respectively. MOVS is the instruction that allows memory to memory moves, as was discussed in the exceptions to the memory to memory movement rules. String instructions are complex instruction in that they perform a number of tasks against one instruction. And with the REP prefix they perform the task of a complex loop in one instruction. This causes drastic speed improvements in operations on large blocks of memory. The reduction in code size and the improvement in speed are the two reasons why these instructions were introduced in the 8088 processor.

There are a number of common things in these instructions. Firstly they all work on a block of data. DI and SI are used to access memory. SI and DI are called source index and destination index because of string instructions. Whenever an instruction needs a memory source, DS:SI holds the pointer to it. An override is possible that can change the association from DS but the default is DS. Whenever a string instruction needs a memory destination, ES:DI holds the pointer to it. No override is possible in this case. Whenever a byte register is needed, AL holds the value. Whenever a word register is used AX holds the value. For example STOS stores a register in memory so AL or AX is the register used and ES:DI points to the destination. The LODS instruction loads from memory to register so the source is pointed to by DS:SI and the register used is AL or AX.

String instructions work on a block of data. A block has a start and an end. The instructions can work from the start towards the end and from the end towards the start. In fact they can work in both directions, and they must be allowed to work in both directions otherwise certain operations with overlapping blocks become impossible. This problem is discussed in detail later. The direction of movement is controlled with the Direction Flag (DF) in the flags register. If this flag is cleared the direction is from lower addresses towards higher addresses and if this flag is set the direction is from higher addresses to lower addresses. If DF is cleared, this is called the auto-increment mode of string instruction, and if DF is set, this is called the auto-decrement mode. There are two instructions to set and clear the direction flag.

```
cld     ; clear direction flag
std     ; set direction flag
```

Every string instruction has two variants; a byte variant and a word variant. For example the two variants of STOS are STOSB and STOSW. Similarly the variants for the other string instructions are attained by appending a B or a W to the instruction name. The operation of each of the string instructions and each of the repetition prefixes is discussed below.

STOS

STOS transfers a byte or word from register AL or AX to the string element addressed by ES:DI and updates DI to point to the next location. STOS is often used to clear a block of memory or fill it with a constant.

The implied source will always be in AL or AX. If DF is clear, DI will be incremented by one or two depending of whether STOSB or STOSW is used. If DF is set DI will be decremented by one or two depending of whether STOSB or STOSW is used. If REP is used before this instruction, the process will be repeated CX times. CX is called the counter register because of the special treatment given to it in the LOOP and JCXZ instructions and the REP set of prefixes. So if REP is used with STOS the whole block of memory will be filled with a constant value. REP will always decrement CX like the LOOP instruction and this cannot be changed with the direction flag. It is also independent of whether the byte or the word variant is used. It always decrements by one; therefore CX has count of repetitions and not the count of bytes.

LODS

LODS transfers a byte or word from the source location DS:SI to AL or AX and updates SI to point to the next location. LODS is generally used in a loop and not with the REP prefix since the value previously loaded in the register is overwritten if the instruction is repeated and only the last value of the block remains in the register.

SCAS

SCAS compares a source byte or word in register AL or AX with the destination string element addressed by ES:DI and updates the flags. DI is updated to point to the next location. SCAS is often used to locate equality or in-equality in a string through the use of an appropriate prefix.

SCAS is a bit different from the other instructions. This is more like the CMP instruction in that it does subtraction of its operands. The prefixes REPE (repeat while equal) and REPNE (repeat while not equal) are used with this instruction. The instruction is used to locate a byte in AL in the block of memory. When the first equality or inequality is encountered; both have uses. For example this instruction can be used to search for a 0 in a null terminated string to calculate the length of the string. In this form REPNE will be used to repeat while the null is not there.

MOVS

MOVS transfers a byte or word from the source location DS:SI to the destination ES:DI and updates SI and DI to point to the next locations. MOVS is used to move a block of memory. The DF is important in the case of overlapping blocks. For example when the source and destination blocks overlap and the source is below the destination copy must be done upwards while if the destination is below the source copy must be done downwards. We cannot perform both these copy operations properly if the direction flag was not provided. If the source is below the destination and an upwards copy is used the source to be copied is destroyed. If however the copy is done downwards the portion of source destroyed is the one that has already been

copied. Therefore we need the control of the direction flag to handle this problem. This problem is further detailed in a later example.

CMPS

CMPS subtracts the source location DS:SI from the destination location ES:DI. Source and Destination are unaffected. SI and DI are updated accordingly. CMPS compares two blocks of memory for equality or inequality of the block. It subtracts byte by byte or word by word. If used with a REPE or a REPNE prefix is repeats as long as the blocks are same or as long as they are different. For example it can be used for find a substring. A substring is a string that is contained in another string. For example "has" is contained in "Mary has a little lamp." Using CMPS we can do the operation of a complex loop in a single instruction. Only the REPE and REPNE prefixes are meaningful with this instruction.

REP Prefix

REP repeats the following string instruction CX times. The use of CX is implied with the REP prefix. The decrement in CX doesn't affect any flags and the jump is also independent of the flags, just like JCXZ.

REPE and REPNE Prefixes

REPE or REPZ repeat the following string instruction while the zero flag is set and REPNE or REPNZ repeat the following instruction while the zero flag is not set. REPE or REPNE are used with the SCAS or CMPS instructions. The other string instructions have nothing to do with the condition since they are performing no comparison. Also the initial state of flags before the string instruction does not affect the operation. The most complex operation of the string instruction is with these prefixes.

7.2. STOS EXAMPLE – CLEARING THE SCREEN

We take the example of clearing the screen and observe that how simple and fast this operation is with the string instructions. Even if there are three instructions in a loop they have to be fetched and decoded with every iteration and the time of three instructions is multiplied by the number of iterations of the loop. In the case of string instructions, many operations are short circuited. The instruction is fetched and decoded once and only the execution is repeated CX times. That is why string instructions are so efficient in their operation. The program to clear the screen places 0720 on the 2000 words on the screen.

Example 7.1

```
001     ; clear screen using string instructions
002     [org 0x0100]
003                 jmp  start
004
005     ; subroutine to clear the screen
006     clrscr:     push es
007                 push ax
008                 push cx
009                 push di
010
011                 mov  ax, 0xb800
012                 mov  es, ax             ; point es to video base
013                 xor  di, di             ; point di to top left column
014                 mov  ax, 0x0720         ; space char in normal attribute
015                 mov  cx, 2000           ; number of screen locations
016
017                 cld                     ; auto increment mode
018                 rep  stosw              ; clear the whole screen
019
020                 pop  di
```

```
021                 pop  cx
022                 pop  ax
023                 pop  es
024                 ret
025
026     start:      call clrscr             ; call clrscr subroutine
027
028                 mov  ax, 0x4c00         ; terminate program
029                 int  0x21
```

013 A space efficient way to zero a 16bit register is to XOR it with itself. Remember that exclusive or results in a zero whenever the bits at the source and at the destination are same. This instruction takes just two bytes compared to "mov di, 0" which would take three. This is a standard way to zero a 16bit register.

Inside the debugger the operation of the string instruction can be monitored. The trace into command can be used to monitor every repetition of the string instruction. However screen will not be cleared inside the debugger as the debugger overwrites its display on the screen so CX decrements with every iteration, DI increments by 2. The first access is made at B800:0000 and the second at B800:0002 and so on. A complex and inefficient loop is replaced with a fast and simple instruction that does the same operation many times faster.

7.3. LODS EXAMPLE – STRING PRINTING

The use of LODS with the REP prefix is not meaningful as only the last value loaded will remain in the register. It is normally used in a loop paired with a STOS instruction to do some block processing. We use LODS to pick the data, do the processing, and then use STOS to put it back or at some other place. For example in string printing, we will use LODS to read a character of the string, attach the attribute byte to it, and use STOS to write it on the video memory.

The following example will print the string using string instructions.

Example 7.2

```
001     ; hello world printing using string instructions
002     [org 0x0100]
003                 jmp  start
004
005     message:    db   'hello world'     ; string to be printed
006     length:     dw   11                ; length of string
007
008-027 ;;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;;
028
029     ; subroutine to print a string
030     ; takes the x position, y position, attribute, address of string and
031     ; its length as parameters
032     printstr:   push bp
033                 mov  bp, sp
034                 push es
035                 push ax
036                 push cx
037                 push si
038                 push di
039
040                 mov  ax, 0xb800
041                 mov  es, ax            ; point es to video base
042                 mov  al, 80            ; load al with columns per row
043                 mul  byte [bp+10]      ; multiply with y position
044                 add  ax, [bp+12]       ; add x position
045                 shl  ax, 1             ; turn into byte offset
046                 mov  di,ax             ; point di to required location
047                 mov  si, [bp+6]        ; point si to string
048                 mov  cx, [bp+4]        ; load length of string in cx
049                 mov  ah, [bp+8]        ; load attribute in ah
```

```
050
051                 cld                     ; auto increment mode
052     nextchar:   lodsb                   ; load next char in al
053                 stosw                   ; print char/attribute pair
054                 loop nextchar           ; repeat for the whole string
055
056                 pop  di
057                 pop  si
058                 pop  cx
059                 pop  ax
060                 pop  es
061                 pop  bp
062                 ret  10
063
064     start:      call clrscr             ; call the clrscr subroutine
065
066                 mov  ax, 30
067                 push ax                 ; push x position
068                 mov  ax, 20
069                 push ax                 ; push y position
070                 mov  ax, 1              ; blue on black attribute
071                 push ax                 ; push attribute
072                 mov  ax, message
073                 push ax                 ; push address of message
074                 push word [length]      ; push message length
075                 call printstr           ; call the printstr subroutine
076
077                 mov  ax, 0x4c00         ; terminate program
078                 int  0x21
```

051	Both operations are in auto increment mode.
052-053	DS is automatically initialized to our segment. ES points to video memory. SI points to the address of our string. DI points to the screen location. AH holds the attribute. Whenever we read a character from the string in AL, the attribute byte is implicitly attached and the pair is present in AX. The same effect could not be achieved with a REP prefix as the REP will repeat LODS and then start repeating STOS, but we need to alternate them.
054	CX holds the length of the string. Therefore LOOP repeats for each character of the string.

Inside the debugger we observe how LODS and STOS alternate and CX is only used by the LOOP instruction. In the original code there were four instructions inside the loop; now there are only two. This is how string instructions help in reducing code size.

7.4. SCAS EXAMPLE – STRING LENGTH

Many higher level languages do not explicitly store string length; rather they use a null character, a character with an ASCII code of zero, to signal the end of a string. In assembly language programs, it is also easier to store a zero at the end of the string, instead of calculating the length of string, which is very difficult process for longer strings. So we delegate length calculation to the processor and modify our string printing subroutine to take a null terminated string and no length. We use SCASB with REPNE and a zero in AL to find a zero byte in the string. In CX we load the maximum possible size, which is 64K bytes. However actual strings will be much smaller. An important thing regarding SCAS and CMPS is that if they stop due to equality or inequality, the index registers have already incremented. Therefore when SCAS will stop DI would be pointing past the null character.

Example 7.3

```
001     ; hello world printing with a null terminated string
002     [org 0x0100]
```

```
003                 jmp  start
004
005     message:    db   'hello world', 0    ; null terminated string
006
007-026 ;;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;;
027
028     ; subroutine to print a string
029     ; takes the x position, y position, attribute, and address of a null
030     ; terminated string as parameters
031     printstr:   push bp
032                 mov  bp, sp
033                 push es
034                 push ax
035                 push cx
036                 push si
037                 push di
038
039                 push ds
040                 pop  es                 ; load ds in es
041                 mov  di, [bp+4]         ; point di to string
042                 mov  cx, 0xffff         ; load maximum number in cx
043                 xor  al, al             ; load a zero in al
044                 repne scasb             ; find zero in the string
045                 mov  ax, 0xffff         ; load maximum number in ax
046                 sub  ax, cx             ; find change in cx
047                 dec  ax                 ; exclude null from length
048                 jz   exit               ; no printing if string is empty
049
050                 mov  cx, ax             ; load string length in cx
051                 mov  ax, 0xb800
052                 mov  es, ax             ; point es to video base
053                 mov  al, 80             ; load al with columns per row
054                 mul  byte [bp+8]        ; multiply with y position
055                 add  ax, [bp+10]        ; add x position
056                 shl  ax, 1              ; turn into byte offset
057                 mov  di,ax              ; point di to required location
058                 mov  si, [bp+4]         ; point si to string
059                 mov  ah, [bp+6]         ; load attribute in ah
060
061                 cld                     ; auto increment mode
062     nextchar:   lodsb                   ; load next char in al
063                 stosw                   ; print char/attribute pair
064                 loop nextchar           ; repeat for the whole string
065
066     exit:       pop  di
067                 pop  si
068                 pop  cx
069                 pop  ax
070                 pop  es
071                 pop  bp
072                 ret  8
073
074     start:      call clrscr             ; call the clrscr subroutine
075
076                 mov  ax, 30
077                 push ax                 ; push x position
078                 mov  ax, 20
079                 push ax                 ; push y position
080                 mov  ax, 1              ; blue on black attribute
081                 push ax                 ; push attribute
082                 mov  ax, message
083                 push ax                 ; push address of message
084                 call printstr           ; call the printstr subroutine
085
086                 mov  ax, 0x4c00         ; terminate program
                    int  0x21
```

039-040 Another way to load a segment register is to use a combination of push and pop. The processor doesn't match pushes and pops. ES is equalized to DS in this pair of instructions.

Inside the debugger observe the working of the code for length calculation after SCASB has completed its operation.

LES and LDS Instructions

Since the string instructions need their source and destination in the form of a segment offset pair, there are two special instructions that load a segment register and a general purpose register from two consecutive memory locations. LES loads ES while LDS loads DS. Both these instructions have two parameters, one is the general purpose register to be loaded and the other is the memory location from which to load these registers. The major application of these instructions is when a subroutine receives a segment offset pair as an argument and the pair is to be loaded in a segment and an offset register. According to Intel rules of significance the word at higher address is loaded in the segment register while the word at lower address is loaded in the offset register. As parameters segment should be pushed first so that it ends up at a higher address and the offset should be pushed afterwards. When loading the lower address will be given. For example "lds si, [bp+4]" will load SI from BP+4 and DS from BP+6.

7.5. LES AND LDS EXAMPLE

We modify the string length calculation subroutine to take the segment and offset of the string and use the LES instruction to load that segment offset pair in ES and DI.

Example 7.4

```
001      ; hello world printing with length calculation subroutine
002      [org 0x0100]
003                   jmp  start
004
005      message:     db   'hello world', 0    ; null terminated string
006
007-026  ;;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;;
027
028      ; subroutine to calculate the length of a string
029      ; takes the segment and offset of a string as parameters
030      strlen:      push bp
031                   mov  bp,sp
032                   push es
033                   push cx
034                   push di
035
036                   les  di, [bp+4]         ; point es:di to string
037                   mov  cx, 0xffff         ; load maximum number in cx
038                   xor  al, al             ; load a zero in al
039                   repne scasb             ; find zero in the string
040                   mov  ax, 0xffff         ; load maximum number in ax
041                   sub  ax, cx             ; find change in cx
042                   dec  ax                 ; exclude null from length
043
044                   pop  di
045                   pop  cx
046                   pop  es
047                   pop  bp
048                   ret  4
049
050      ; subroutine to print a string
051      ; takes the x position, y position, attribute, and address of a null
052      ; terminated string as parameters
053      printstr:    push bp
054                   mov  bp, sp
055                   push es
056                   push ax
057                   push cx
058                   push si
059                   push di
060
061                   push ds                 ; push segment of string
062                   mov  ax, [bp+4]
063                   push ax                 ; push offset of string
064                   call strlen             ; calculate string length
```

```
065                 cmp  ax, 0              ; is the string empty
066                 jz   exit               ; no printing if string is empty
067                 mov  cx, ax             ; save length in cx
068
069                 mov  ax, 0xb800
070                 mov  es, ax             ; point es to video base
071                 mov  al, 80             ; load al with columns per row
072                 mul  byte [bp+8]        ; multiply with y position
073                 add  ax, [bp+10]        ; add x position
074                 shl  ax, 1              ; turn into byte offset
075                 mov  di,ax              ; point di to required location
076                 mov  si, [bp+4]         ; point si to string
077                 mov  ah, [bp+6]         ; load attribute in ah
078
079                 cld                     ; auto increment mode
080     nextchar:   lodsb                   ; load next char in al
081                 stosw                   ; print char/attribute pair
082                 loop nextchar           ; repeat for the whole string
083
084     exit:       pop  di
085                 pop  si
086                 pop  cx
087                 pop  ax
088                 pop  es
089                 pop  bp
090                 ret  8
091
092     start:      call clrscr             ; call the clrscr subroutine
093
094                 mov  ax, 30
095                 push ax                 ; push x position
096                 mov  ax, 20
097                 push ax                 ; push y position
098                 mov  ax, 0x71           ; blue on white attribute
099                 push ax                 ; push attribute
100                 mov  ax, message
101                 push ax                 ; push address of message
102                 call printstr           ; call the printstr subroutine
103
104                 mov  ax, 0x4c00         ; terminate program
105                 int  0x21
```

036	The LES instruction is used to load the DI register from BP+4 and the ES register from BP+6.
065	The convention to return a value from a subroutine is to use the AX register. That is why AX is not saved and restored in the subroutine.

Inside the debugger observe that the segment register is pushed followed by the offset. The higher address FFE6 contains the segment and the lower address FFE4 contains the offset. This is because we have a decrementing stack. Then observe the loading of ES and DI from the stack.

7.6. MOVS EXAMPLE – SCREEN SCROLLING

MOVS has the two forms MOVSB and MOVSW. REP allows the instruction to be repeated CX times allowing blocks of memory to be copied. We will perform this copy of the video screen.

Scrolling is the process when all the lines on the screen move one or more lines towards the top of towards the bottom and the new line that appears on the top or the bottom is cleared. Scrolling is a process on which string movement is naturally applicable. REP with MOVS will utilize the full processor power to do the scrolling in minimum time.

In this example we want to scroll a variable number of lines given as argument. Therefore we have to calculate the source address, which is 160 times the number of lines to clear. The destination address is 0, which is the top left of the screen. The lines that scroll up are discarded so the source pointer is placed after them. An equal number of lines at the bottom are cleared. These lines have actually been copied above.

Example 7.5

```
001     ; scroll up the screen
002     [org 0x0100]
003                 jmp  start
004
005     ; subroutine to scroll up the screen
006     ; take the number of lines to scroll as parameter
007     scrollup:     push bp
008                   mov  bp,sp
009                   push ax
010                   push cx
011                   push si
012                   push di
013                   push es
014                   push ds
015
016                   mov  ax, 80             ; load chars per row in ax
017                   mul  byte [bp+4]        ; calculate source position
018                   mov  si, ax             ; load source position in si
019                   push si                 ; save position for later use
020                   shl  si, 1              ; convert to byte offset
021                   mov  cx, 2000           ; number of screen locations
022                   sub  cx, ax             ; count of words to move
023                   mov  ax, 0xb800
024                   mov  es, ax             ; point es to video base
025                   mov  ds, ax             ; point ds to video base
026                   xor  di, di             ; point di to top left column
027                   cld                     ; set auto increment mode
028                   rep  movsw              ; scroll up
029                   mov  ax, 0x0720         ; space in normal attribute
030                   pop  cx                 ; count of positions to clear
031                   rep  stosw              ; clear the scrolled space
032
033                   pop  ds
034                   pop  es
035                   pop  di
036                   pop  si
037                   pop  cx
038                   pop  ax
039                   pop  bp
040                   ret  2
041
042     start:        mov  ax,5
043                   push ax                 ; push number of lines to scroll
044                   call scrollup           ; call the scroll up subroutine
045
046                   mov  ax, 0x4c00         ; terminate program
047                   int  0x21
```

The beauty of this example is that the two memory blocks are overlapping. If the source and destination in the above algorithm are swapped in an expectation to scroll down the result is strange. For example if 5 lines were to scroll down, the top five lines of the screen are repeated on the whole screen. This is where the use of the direction flag comes in.

When the source is five lines below the destination, the first five lines are copied on the first five lines of the destination. However the next five lines to be copied from the source have been destroyed in the process; because they were the same as the first five lines of the destination. The same is the problem with every set of five lines as the source is destroyed during the previous copy. In this situation we must go from bottom of the screen towards the top. Now the last five lines are copied to the last five lines of the destination. The next five lines are copied to next five lines of the destination destroying the last five lines of source; but now these lines are no longer needed and have been previously copied. Therefore the copy will be appropriately done in this case.

We give an example of scrolling down with this consideration. Now we have to calculate the end of the block instead of the start.

Example 7.6

```
001     ; scroll down the screen
002     [org 0x0100]
003                 jmp  start
004
005     ; subroutine to scrolls down the screen
006     ; take the number of lines to scroll as parameter
007     scrolldown:   push bp
008                   mov  bp,sp
009                   push ax
010                   push cx
011                   push si
012                   push di
013                   push es
014                   push ds
015
016                   mov  ax, 80             ; load chars per row in ax
017                   mul  byte [bp+4]        ; calculate source position
018                   push ax                 ; save position for later use
019                   shl  ax, 1              ; convert to byte offset
020                   mov  si, 3998           ; last location on the screen
021                   sub  si, ax             ; load source position in si
022                   mov  cx, 2000           ; number of screen locations
023                   sub  cx, ax             ; count of words to move
024                   mov  ax, 0xb800
025                   mov  es, ax             ; point es to video base
026                   mov  ds, ax             ; point ds to video base
027                   mov  di, 3998           ; point di to lower right column
028                   std                     ; set auto decrement mode
029                   rep  movsw              ; scroll up
030                   mov  ax, 0x0720         ; space in normal attribute
031                   pop  cx                 ; count of positions to clear
032                   rep  stosw              ; clear the scrolled space
033
034                   pop  ds
035                   pop  es
036                   pop  di
037                   pop  si
038                   pop  cx
039                   pop  ax
040                   pop  bp
041                   ret  2
042
043     start:        mov  ax,5
044                   push ax                 ; push number of lines to scroll
045                   call scrolldown         ; call scroll down subroutine
046
047                   mov  ax, 0x4c00         ; terminate program
048                   int  0x21
```

7.7. CMPS EXAMPLE – STRING COMPARISON

For the last string instruction, we take string comparison as an example. The subroutine will take two segment offset pairs containing the address of the two null terminated strings. The subroutine will return 0 if the strings are different and 1 if they are same. The AX register will be used to hold the return value.

Example 7.7

```
001     ; comparing null terminated strings
002     [org 0x0100]
003                 jmp  start
004
005     msg1:         db   'hello world', 0
006     msg2:         db   'hello WORLD', 0
007     msg3:         db   'hello world', 0
008
009-031 ;;;;; COPY LINES 028-050 FROM EXAMPLE 7.4 (strlen) ;;;;;
032
033     ; subroutine to compare two strings
034     ; takes segment and offset pairs of two strings to compare
```

```
035     ; returns 1 in ax if they match and 0 other wise
036     strcmp:       push bp
037                   mov  bp,sp
038                   push cx
039                   push si
040                   push di
041                   push es
042                   push ds
043
044                   lds  si, [bp+4]         ; point ds:si to first string
045                   les  di, [bp+8]         ; point es:di to second string
046
047                   push ds                 ; push segment of first string
048                   push si                 ; push offset of first string
049                   call strlen             ; calculate string length
050                   mov  cx, ax             ; save length in cx
051
052                   push es                 ; push segment of second string
053                   push di                 ; push offset of second string
054                   call strlen             ; calculate string length
055                   cmp  cx, ax             ; compare length of both strings
056                   jne  exitfalse          ; return 0 if they are unequal
057
058                   mov  ax, 1              ; store 1 in ax to be returned
059                   repe cmpsb              ; compare both strings
060                   jcxz exitsimple         ; are they successfully compared
061
062     exitfalse:    mov  ax, 0              ; store 0 to mark unequal
063
064     exitsimple:   pop  ds
065                   pop  es
066                   pop  di
067                   pop  si
068                   pop  cx
069                   pop  bp
070                   ret  8
071
072     start:        push ds                 ; push segment of first string
073                   mov  ax, msg1
074                   push ax                 ; push offset of first string
075                   push ds                 ; push segment of second string
076                   mov  ax, msg2
077                   push ax                 ; push offset of second string
078                   call strcmp             ; call strcmp subroutine
079
080                   push ds                 ; push segment of first string
081                   mov  ax, msg1
082                   push ax                 ; push offset of first string
083                   push ds                 ; push segment of third string
084                   mov  ax, msg3
085                   push ax                 ; push offset of third string
086                   call strcmp             ; call strcmp subroutine
087
088                   mov  ax, 0x4c00         ; terminate program
089                   int  0x21
```

005-007	Three strings are declared out of which two are equal and one is different.
044-045	LDS and LES are used to load the pointers to the two strings in DS:SI and ES:DI.
070	Since there are 4 parameters to the subroutine “ret 8” is used.

Inside the debugger we observe that REPE is shown as REP. This is because REP and REPE are represented with the same prefix byte. When used with STOS, LODS, and MOVS it functions as REP and when used with SCAS and CMPS it functions as REPE.

EXERCISES

1. Write code to find the byte in AL in the whole megabyte of memory such that each memory location is compared to AL only once.

2. Write a far procedure to reverse an array of 64k words such that the first element becomes the last and the last becomes the first and so on. For example if the first word contained 0102h, this value is swapped with the last word. The next word is swapped with the second last word and so on. The routine will be passed two parameters through the stack; the segment and offset of the first element of the array.
3. Write a near procedure to copy a given area on the screen at the center of the screen without using a temporary array. The routine will be passed top, left, bottom, and right in that order through the stack. The parameters passed will always be within range the height will be odd and the width will be even so that it can be exactly centered.
4. Write code to find two segments in the whole memory that are exactly the same. In other words find two distinct values which if loaded in ES and DS then for every value of SI [DS:SI]=[ES:SI].
5. Write a function writechar that takes two parameters. The first parameter is the character to write and the second is the address of a memory area containing top, left, bottom, right, current row, current column, normal attribute, and cursor attribute in 8 consecutive bytes. These define a virtual window on the screen.
   The function writes the passed character at (current row, current column) using the normal attribute. It then increments current column, If current column goes outside the window, it makes it zero and increments current row. If current row gets out of window, it scrolls the window one line up, and blanks out the new line in the window. In the end, it sets the attribute of the new (current row, current column) to cursor attribute.
6. Write a function “strcpy” that takes the address of two parameters via stack, the one pushed first is source and the second is the destination. The function should copy the source on the destination including the null character assuming that sufficient space is reserved starting at destination.

8
Software Interrupts

8.1. INTERRUPTS

Interrupts in reality are events that occurred outside the processor and the processor must be informed about them. Interrupts are asynchronous and unpredictable. Asynchronous means that the interrupts occur, independent of the working of the processor, i.e. independent of the instruction currently executing. Synchronous events are those that occur side by side with another activity. Interrupts must be asynchronous as they are generated by the external world which is unaware of the happenings inside the processor. True interrupts that occur in real time are asynchronous with the execution. Also it is unpredictable at which time an interrupt will come. The two concepts of being unpredictable and asynchronous are overlapping. Unpredictable means the time at which an interrupt will come cannot be predicted, while asynchronous means that the interrupt has nothing to do with the currently executing instruction and the current state of the processor.

The 8088 processor divides interrupts into two classes. Software interrupts and hardware interrupts. Hardware interrupts are the real interrupts generated by the external world as discussed above. Software interrupts on the contrary are not generated from outside the processor. They just provide an extended far call mechanism. Far call allows us to jump anywhere in the whole megabyte of memory. To return from the target we place both the segment and offset on the stack. Software interrupts show a similar behavior. It however pushes one more thing before both the segment and offset and that is the FLAGS register. Just like the far call loads new values in CS and IP, the interrupt call loads new values in CS, IP, and FLAGS. Therefore the only way to retain the value of original FLAGS register is to push and pop as part of interrupt call and return instructions. Pushing and popping inside the routine will not work as the routine started with an already tampered value.

The discussion of real time interrupts is deferred till the next chapter. They play the critical part in control applications where external hardware must be control and events and changes therein must be appropriately responded by the processor. To generate an interrupt the INT instruction is used. The routine that executes in response to an INT instruction is called the interrupt service routine (ISR) or the interrupt handler. Taking example from real time interrupts the routine to instruct an external hardware to close the valve of a boiler in response to an interrupt from the pressure sensor is an interrupt routine.

The software interrupt mechanism in 8088 uses vectored interrupts meaning that the address of the interrupt routine is not directly mentioned in an interrupt call, rather the address is lookup up from a table. 8088 provides a mechanism for mapping interrupts to interrupt handlers. Introducing a new entry in this mapping table is called hooking an interrupt.

Syntax of the INT instruction is very simple. It takes a single byte argument varying from 0-255. This is the interrupt number informing the processor, which interrupt is currently of interest. This number correlates to the interrupt handler routine by a routing or vectoring mechanism. A few interrupt numbers in the start are reserved and we generally do not use them. They are related to the processor working. For example INT 0 is the

divide by zero interrupt. A list of all reserved interrupts is given later. Such interrupts are programmed in the hardware to generate the designated interrupt when the specified condition arises. The remaining interrupts are provided by the processor for our use. Some of these were reserved by the IBM PC designers to interface user programs with system software like DOS and BIOS. This was the logical choice for them as interrupts provided a very flexible architecture. The remaining interrupts are totally free for use in user software.

The correlation process from the interrupt number to the interrupt handler uses a table called interrupt vector table. Its location is fixed to physical memory address zero. Each entry of the table is four bytes long containing the segment and offset of the interrupt routine for the corresponding interrupt number. The first two bytes in the entry contain the offset and the next two bytes contain the segment. The little endian rule of putting the more significant part (segment) at a higher address is seen here as well. Mathematically offset of the interrupt n will be at nx4 while the segment will be at nx4+2. One entry in this table is called a vector. If the vector is changed for interrupt 0 then INT 0 will take execution to the new handler whose address is now placed at those four bytes. INT 1 vector occupies location 4, 5, 6, and 7 and similarly vector for INT 2 occupies locations 8, 9, 10, and 11. As the table is located in RAM it can be changed anytime. Immediately after changing it the interrupt mapping is changed and now the interrupt will result in execution of the new routine. This indirection gives the mechanism extreme flexibility.

The operation of interrupt is same whether it is the result of an INT instruction (software interrupt) or it is generated by an external hardware which passes the interrupt number by a different mechanism. The currently executing instruction is completed, the current value of FLAGS is pushed on the stack, then the current code segment is pushed, then the offset of the next instruction is pushed. After this it automatically clears the trap flag and the interrupt flag to disallow further interrupts until the current routine finishes. After this it loads the word at nx4 in IP and the word at nx4+2 in CS if interrupt n was generated. As soon as these values are loaded in CS and IP execution goes to the start of the interrupt handler. When the handler finishes its work it uses the IRET instruction to return to the caller. IRET pops IP, then CS, and then FLAGS. The original value of IF and TF is restored which re-enables further interrupts. IF and TF will be discussed in detail in the discussion of real time interrupts. We have discussed three things till now.

1. The INT and IRET instruction format and syntax
2. The formation of IVT (interrupt vector table)
3. Operation of the processor when an interrupt in generated

Just as discussed in the subroutines chapter, the processor will not match interrupt calls to interrupt returns. If a RETF is used in the end of an ISR the processor will still return to the caller but the FLAGS will remain on the stack which will destroy the expectations of the caller with the stack. If we know what we are doing we may use such different combination of instructions. Generally we will use IRET to return from an interrupt routine. Apart from indirection the software interrupt mechanism is similar to CALL and RET. Indirection is the major difference.

The operation of INT can be written as:

- sp ← sp-2
- [sp] ← flag
- sp ← sp-2
- if ← 0
- tf ← 0
- [sp] ← cs
- sp ← sp-2
- [sp] ← ip

- ip ← [0:N*4]
- cs ← [0:N*4+2]

The operation of IRET can be written as:

- ip ← [sp]
- sp ← sp+2
- cs ← [sp]
- sp ← sp+2
- flag ← [sp]
- sp ← sp+2

The above is the microcode description of INT and IRET. To obey an assembly language instruction the processor breaks it down into small operations. By reading the microcode of an instruction its working can be completely understood.

The interrupt mechanism we have studied is an extended far call mechanism. It pushes FLAGS in addition to CS and IP and it loads CS and IP with a special mechanism of indirection. It is just like the table of contents that is located at a fixed position and allows going directly to chapter 3, to chapter 4 etc. If this association is changed in the table of contents the direction of the reader changes. For example if Chapter 2 starts at page 220 while 240 is written in the table of contents, the reader will go to page 240 and not 220. The table of contents entry is a vector to point to map the chapter number to page number. IVT has 256 chapters and the interrupt mechanism looks up the appropriate chapter number to reach the desired page to find the interrupt routine.

Another important similarity is that table of contents is always placed at the start of the book, a well known place. Its physical position is fixed. If some publishers put it at some place, others at another place, the reader will be unable to find the desired chapter. Similarly in 8088 the physical memory address zero is fixed for the IVT and it occupies exactly a kilobyte of memory as the 256x4=1K where 256 is the number of possible interrupt vectors while the size of one vector is 4 bytes.

Interrupts introduce temporary breakage in the program flow, sometimes programmed (software interrupts) and un-programmed at other times (hardware interrupts). By hooking interrupts various system functionalities can be controlled. The interrupts reserved by the processor and having special functions in 8088 are listed below:

- INT 0, Division by zero
  Meaning the quotient did not fit in the destination register. This is a bit different as this interrupt does not return to the next instruction, rather it returns to the same instruction that generated it, a DIV instruction of course. Here INT 0 is automatically generated by a DIV when a specific situation arises, there is no INT 0 instruction.
- INT 1, Trap, Single step Interrupt
  This interrupt is used in debugging with the trap flag. If the trap flag is set the Single Step Interrupt is generated after every instruction. By hooking this interrupt a debugger can get control after every instruction and display the registers etc. 8088 was the first processor that has this ability to support debugging.
- INT 2, NMI-Non Maskable Interrupt
  Real interrupts come from outside the processor. INT 0 is not real as it is generated from inside. For real interrupts there are two pins in the processor, the INT pin and the NMI pin. The processor can be directed to listen or not to listen to the INT pin. Consider a recording studio, when the recording is going on, doors are closed so that no interruption occurs, and when there is a break, the doors are opened so that if someone is waiting outside can come it. However if there is an urgency like fire outside then the door must be broken and the recording must not be catered for. For such situations is the NMI pin

which informs about fatal hardware failures in the system and is tied to interrupt 2. INT pin can be masked but NMI cannot be masked.

- INT 3, Debug Interrupt
  The only special thing about this interrupt is that it has a single byte opcode and not a two byte combination where the second byte tells the interrupt number. This allows it to replace any instruction whatsoever. It is also used by the debugger and will be discussed in detail with the debugger working.
- INT 4, Arithmetic Overflow, change of sign bit
  The overflow flag is set if the sign bit unexpectedly changes as a result of a mathematical or logical instruction. However the overflow flag signals a real overflow only if the numbers in question are treated as signed numbers. So this interrupt is not automatically generated but as a result of a special instruction INTO (interrupt on overflow) if the overflow flag is set. Otherwise the INTO instruction behaves like a NOP (no operation).

These are the five interrupts reserved by Intel and are generally not used in our operations.

8.2. HOOKING AN INTERRUPT

To hook an interrupt we change the vector corresponding to that interrupt. As soon as the interrupt vector changes, that interrupt will be routed to the new handler. Our first example is with the divide by zero interrupt. The normal system defined behavior in response to divide by zero is to display an error message and terminate the program. We will change it to display our own message.

Example 8.1

```
001      ; hooking divide by zero interrupt
002      [org 0x0100]
003                  jmp  start
004
005      message:    db   'You divided something by zero.', 0
006
007-029  ;;;;; COPY LINES 028-050 FROM EXAMPLE 7.4 (strlen) ;;;;;
030-049  ;;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;;
050-090  ;;;;; COPY LINES 050-090 FROM EXAMPLE 7.4 (printstr) ;;;;;
091
092      ; divide by zero interrupt handler
093      myisrfor0:  push ax                ; push all regs
094                  push bx
095                  push cx
096                  push dx
097                  push si
098                  push di
099                  push bp
100                  push ds
101                  push es
102
103                  push cs
104                  pop  ds               ; point ds to our data segment
105
106                  call clrscr           ; clear the screen
107                  mov  ax, 30
108                  push ax               ; push x position
109                  mov  ax, 20
110                  push ax               ; push y position
111                  mov  ax, 0x71         ; white on blue attribute
112                  push ax               ; push attribute
113                  mov  ax, message
114                  push ax               ; push offset of message
115                  call printstr         ; print message
116
117                  pop  es
118                  pop  ds
119                  pop  bp
```

```
120                 pop  di
121                 pop  si
123                 pop  dx
124                 pop  cx
125                 pop  bx
126                 pop  ax
127                 iret                    ; return from interrupt
128
129     ; subroutine to generate a divide by zero interrupt
130     genint0:    mov  ax, 0x8432         ; load a big number in ax
131                 mov  bl, 2              ; use a very small divisor
132                 div  bl                 ; interrupt 0 will be generated
133                 ret
134
135     start:      xor  ax, ax
136                 mov  es, ax             ; load zero in es
137                 mov  word [es:0*4], myisrfor0 ; store offset at n*4
138                 mov  [es:0*4+2], cs     ; store segment at n*4+2
139                 call  genint0           ; generate interrupt 0
140
141                 mov ax, 0x4c00          ; terminate program
142                 int 0x21
```

93-101	We often push all registers in an interrupt service routine just to be sure that no unintentional modification to any register is made. Since any code may be interrupted an unintentional modification will be hard to debug
103-104	Since interrupt can be called from anywhere we are not sure about the value in DS so we reset it to our code segment.

When this program is executed our desired message will be shown instead of the default message and the computer will hang thereafter. The first thing to observe is that there is no INT 0 call anywhere in the code. INT 0 was invoked automatically by an internal mechanism of the processor as a result of the DIV instruction producing a result that cannot fit in the destination register. Just by changing the vector we have changed the response of the system to divide overflow situations.

However the system stuck instead of returning to the next instruction. This is because divide overflow is a special type of interrupt that returns to the same instruction instead of the next instruction. This is why the default handler forcefully terminates the program instead of returning. Now the IRET will take control back to the DIV instruction which will again generate the same interrupt. So the computer is stuck in an infinite loop.

8.3. BIOS AND DOS INTERRUPTS

In IBM PC there are certain interrupts designated for user programs to communicate with system software to access various standard services like access to the floppy drive, hard drive, vga, clock etc. If the programmer does not use these services he has to understand the hardware details like which particular controller is used and how it works. To avoid this and provide interoperability a software interface to basic hardware devices is provided except in very early computers. Since the manufacturer knows the hardware it burns the software to control its hardware in ROM. Such software is called firmware and access to this firmware is provided through specified interrupts.

This basic interface to the hardware is called BIOS (basic input output services). When the computer is switched on, BIOS gets the control at a specified address. The messages at boot time on the screen giving BIOS version, detecting different hardware are from this code. BIOS has the responsibility of testing the basic hardware including video, keyboard, floppy drive, hard drive etc and a special program to bootstrap. Bootstrap means to load OS from hard disk and from there OS takes control and proceeds to load its components and display a command prompt in the end. There are two

important programs; BIOS and OS. OS services are high level and build upon the BIOS services. BIOS services are very low level. A level further lower is only directly controlling the hardware. BIOS services provide a hardware independent layer above the hardware and OS services provide another higher level layer over the BIOS services. We have practiced direct hardware access with the video device directly without using BIOS or DOS. The layer of BIOS provides services like display a character, clear the screen, etc. All these layers are optional in that we can skip to whatever lower layer we want.

The most logical way to provide access to firmware is to use the interrupt mechanism. Specific services are provided at specific interrupts. CALL could also have been used but in that case every manufacturer would be required to place specific routines at specific addresses, which is not a flexible mechanism. Interrupts provide standard interrupt number for the caller and flexibility to place the interrupt routine anywhere in the memory for the manufacturer. Now for the programmer it is decided that video services will be provided at INT 10 but the actual address of the video services can and do vary on computers from different manufacturers. Any computer that is IBM compatible must make the video services accessible through INT 10. Similarly keyboard services are available at INT 16 and this is standard in every IBM compatible. Manufacturers place the code wherever they want and the services are exported through this interrupt.

BIOS exports its various services through different interrupts. Keyboard services are exported through INT 16, parallel port services through INT 17 and similarly others through different interrupts. DOS has a single entry point through INT 21 just like a pin hole camera, this single entry points leads to a number of DOS services. So how one interrupt provides a number of different services. A concept of service number is used here which is a defecto standard in providing multiple services through an interrupt. INT 10 is for video services and each of character printing service, screen clearing service, cursor movement service etc. has a service number associated to it. So we say INT 10 service 0 is used for this purpose and INT 10 service 1 is used for that purpose etc. Service numbers for different standard services are also fixed for every IBM compatible. The concept of exported services through interrupts is expanded with the service numbering scheme.

The service number is usually given in the AH register. Sometimes these 256 services seem less. For example DOS exports thousands of services. So will be often seen an extension to a level further with sub-services. For examples INT 10 character generator services are all provided through a single service number and the services are distinguished with a sub-service number.

The finally selected service would need some arguments for it to work. In interrupts arguments are usually not given through stack, rather registers are used. The BIOS and DOS specifications list which register contains which argument for a particular service of a particular interrupt.

We will touch some important BIOS and DOS services and not cover it completely neither is it possible to cover it in this space. A very comprehensive reference of interrupts is the Ralph Brown List. It is just a reference and not to be studied from end to end. All interrupts cannot be remembered and there is no need to remember them.

The service number is almost always in AH while the sub-service number is in AL or BL and sometimes in other registers. The documentation of the service we are using will list which register should hold what when the interrupt is invoked for that particular service.

Our first target using BIOS is video so let us proceed to our first program that uses INT 10 service 13 to print a string on the screen. BIOS will work even if the video memory is not at B8000 (a very old video card) since BIOS knows everything about the hardware and is hardware specific.

Example 8.2

```
001     ; print string using bios service
002     [org 0x0100]
003                     jmp  start
004     message:        db   'Hello World'
005
006     start:          mov  ah, 0x13           ; service 13 - print string
007                     mov  al, 1              ; subservice 01 – update cursor
008                     mov  bh, 0              ; output on page 0
009                     mov  bl, 7              ; normal attrib
010                     mov  dx, 0x0A03         ; row 10 column 3
011                     mov  cx, 11             ; length of string
012                     push cs
013                     pop  es                 ; segment of string
014                     mov  bp, message        ; offset of string
015                     int  0x10               ; call BIOS video service
016
017                     mov  ax, 0x4c00         ; terminate program
018                     int  0x21
```

007 The sub-service are versions of printstring that update and do not update the cursor after printing the string etc.

008 Text video screen is in the form of pages which can be upto 32. At one time one page is visible which is by default the zeroth page unless we change it.

When we execute it the string is printed and the cursor is updated as well. With direct access to video memory we had no control over the cursor. To control cursor a different mechanism to access the hardware was needed.

Our next example uses the keyboard service to read a key. The combination of keyboard and video services is used in almost every program that we see and use. We will wait for four key presses; clear the screen after the first, and draw different strings after the next key presses and exiting after the last. We will use INT 16 service 1 for this purpose. This is a blocking service so it does not return until a key has been pressed. We also used the blinking attribute in this example.

Example 8.3

```
001      ; print string and keyboard wait using BIOS services
002      [org 0x100]
003                  jmp  start
004
005      msg1:       db   'hello world', 0
006      msg2:       db   'hello world again', 0
007      msg3:       db   'hello world again and again', 0
008
009-028  ;;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;;
029-069  ;;;;; COPY LINES 050-090 FROM EXAMPLE 7.4 (printstr) ;;;;;
070-092  ;;;;; COPY LINES 028-050 FROM EXAMPLE 7.4 (strlen) ;;;;;
093
094      start:      mov  ah, 0x10           ; service 10 – vga attributes
095                  mov  al, 03             ; subservice 3 – toggle blinking
096                  mov  bl, 01             ; enable blinking bit
097                  int  0x10               ; call BIOS video service
098
099                  mov  ah, 0              ; service 0 – get keystroke
100                  int  0x16               ; call BIOS keyboard service
101
102                  call clrscr             ; clear the screen
103
104                  mov  ah, 0              ; service 0 – get keystroke
105                  int  0x16               ; call BIOS keyboard service
106
107                  mov  ax, 0
108                  push ax                 ; push x position
109                  mov  ax, 0
110                  push ax                 ; push y position
111                  mov  ax, 1              ; blue on black
112                  push ax                 ; push attribute
113                  mov  ax, msg1
114                  push ax                 ; push offset of string
115                  call printstr           ; print the string
116
117                  mov  ah, 0              ; service 0 – get keystroke
118                  int  0x16               ; call BIOS keyboard service
119
120                  mov  ax, 0
121                  push ax                 ; push x position
123                  mov  ax, 0
124                  push ax                 ; push y position
125                  mov  ax, 0x71           ; blue on white
126                  push ax                 ; push attribute
127                  mov  ax, msg2
128                  push ax                 ; push offset of string
129                  call printstr           ; print the string
130
131                  mov  ah, 0              ; service 0 – get keystroke
132                  int  0x16               ; call BIOS keyboard service
133
134                  mov  ax, 0
135                  push ax                 ; push x position
136                  mov  ax, 0
137                  push ax                 ; push y position
138                  mov  ax, 0xF4           ; red on white blinking
139                  push ax                 ; push attribute
140                  mov  ax, msg3
141                  push ax                 ; push offset of string
142                  call printstr           ; print the string
143
144                  mov  ah, 0              ; service 0 – get keystroke
145                  int  0x16               ; call BIOS keyboard service
146
147                  mov  ax, 0x4c00         ; terminate program
148                  int  0x21
```

099-100 This service has no parameters so only the service number is initialized in AH. This is the only service so there is no sub-service number as well. The ASCII code of the char pressed is returned in AL after this service.

EXERCISES

1. Write a TSR that forces a program to exit when it tries to become a TSR using INT 21h/Service 31h by converting its call into INT 21h/Service 4Ch.
2. Write a function to clear the screen whose only parameter is always zero. The function is hooked at interrupt 80h and may also be called directly both as a near call and as a far call. The function should detect how it is called and return appropriately. It is provided that the direction flag will be set before the function is called.
3. Write a function that takes three parameters, the interrupt number (N) and the segment and offset of an interrupt handler XISR. The arguments are pushed in the order N, XISR's offset and XISR's segment. It is known that the first two instructions of XISR are PUSHF and CALL 0:0 followed by the rest of the interrupt handler. PUSHF instruction is of one byte and far call is of 5 bytes with the first byte being the op-code, the next two containing the target offset and the last two containing the target segment. The function should hook XISR at interrupt N and chain it to the interrupt handler previously hooked at N by manipulating the call 0:0 instruction placed near the start of XISR.
4. Write a TSR that provide the circular queue services via interrupt 0x80 using the code written in Exercise 5.XX. The interrupt procedure should call one of qcreate, qdestroy, qempty, qadd, qremove, and uninstall based on the value in AH. The uninstall function should restore the old interrupt 0x80 handler and remove the TSR from memory.

9
Real Time Interrupts and Hardware Interfacing

9.1. HARDWARE INTERRUPTS

The same mechanism as discussed in the previous chapter is used for real interrupts that are generated by external hardware. However there is a single pin outside the processor called the INT pin that is used by external hardware to generate interrupts. The detailed operation that happens outside the process when an interrupt is generated is complex and only a simplified view will be discussed here; the view that is relevant to an assembly language programmer. There are many external devices that need the processor's attention like the keyboard, hard disk, floppy disk, sound card. All of them need real time interrupts at some point in their operation. For example if a program is busy in some calculations for three minutes the key strokes that are hit meanwhile should not be wasted. Therefore when a key is pressed, the INT signal is sent, an interrupt generated and the interrupt handler stores the key for later use. Similarly when the printer is busy printing we cannot send it more data. As soon as it gets free from the previous job it interrupts the processor to inform that it is free now. There are many other examples where the processor needs to be informed of an external event. If the processor actively monitors all devices instead of being automatically interrupted then it there won't be any time to do meaningful work.

Since there are many devices generating interrupts and there is only one pin going inside the processor and one pin cannot be technically derived by more than one source a controller is used in between called the Programmable Interrupt Controller (PIC). It has eight input signals and one output signal. It assigns priorities to its eight input pins from 0 to 7 so that if more than one interrupt comes at the same times, the highest priority one is forwarded and the rest are held till that is serviced. The rest are forwarded one by one according to priority after the highest priority one is completed. The original IBM XT computer had one PIC so there were 8 possible interrupt sources. However IBM AT and later computers have two PIC totaling 16 possible interrupt sources. They are arrange is a special cascade master slave arrangement so that only one output signal comes towards the processor. However we will concentrate on the first interrupt controller only.

The priority can be understood with the following example. Consider eight parallel switches which are all closed and connected to form the output signal. When a signal comes on one of the switches, it is passed on to the output and this switch and all below it are opened so that no further signals can pass through it. The higher priority switches are still closed and the signal on them can be forwarded. When the processor signals that it is finished with the processing the switches are closed again and any waiting interrupts may be forwarded. The way the processor signals ending of the interrupt service routine is by using a special mechanism discussed later.

The eight input signals to the PIC are called Interrupt Requests (IRQ). The eight lines are called IRQ 0 to IRQ 7. These are the input lines of the 8451.† For example IRQ 0 is derived by a timer device. The timer device keeps

† 8259 is the technical number of the PIC.

generating interrupts with a specified frequency. IRQ 1 is derived by the keyboard when generates an interrupts when a key is pressed or released. IRQ 2 is the cascading interrupt connected to the output of the second 8451 in the machine. IRQ 3 is connected to serial port COM 2 while IRQ 4 is connected to serial port COM 1. IRQ 5 is used by the sound card or the network card or the modem. An IRQ conflict means that two devices in the system want to use the same IRQ line. IRQ 6 is used by the floppy disk drive while IRQ 7 is used by the parallel port.

Each IRQ is mapped to a specific interrupt in the system. This is called the IRQ to INT mapping. IRQ 0 to IRQ 7 are consecutively mapped on interrupts 8 to F. This mapping is done by the PIC and not the processor. The actual mechanism fetches one instruction from the PIC whenever the INT pin is signaled instead of the memory. We can program the PIC to generate a different set of interrupts on the same interrupt requests. From the perspective of an assembly language programmer an IRQ 0 is translated into an INT 8 without any such instruction in the program and that's all. Therefore an IRQ 0, the highest priority interrupt, is generated by the timer chip at a precise frequency and the handler at INT 8 is invoked which updates the system time. A key press generates IRQ 1 and the INT 9 handler is invoked which stores this key. To handler the timer and keyboard interrupts one can replace the vectors corresponding to interrupt 8 and 9 respectively. For example if the timer interrupt is replaced and the floppy is accessed by some program, the floppy motor and its light will remain on for ever as in the normal case it is turned off by the timer interrupt after two seconds in anticipation that another floppy access might be needed otherwise the time motor takes to speed up will be needed again.‡

We have seen that an interrupt request from a device enters the PIC as an IRQ, from there it reaches the INT pin of the processor, the processor receives the interrupt number from the PIC, generates the designated interrupt, and finally the interrupt handler gain control and can do whatever is desired. At the end of servicing the interrupt the handler should inform the PIC that it is completed so that lower priority interrupts can be sent from the PIC. This signal is called an End Of Interrupt (EOI) signal and is sent through the I/O ports of the interrupt controller.

9.2. I/O PORTS

There are hundreds of peripheral devices in the system, PIC is one example. The processor needs to communicate with them, give and take data from them, otherwise their presence is meaningless. Memory has a totally different purpose. It contains the program to be executed and its data. It does not control any hardware. For communicating with peripheral devices the processor uses I/O ports. There are only two operations with the external world possible, read or write. Similarly with I/O ports the processor can read or write an I/O port. When an I/O port is read or written to, the operation is not as simple as it happens in memory. Some hardware changes it functionality or performs some operation as a result.

IBM PC has separate memory address space and peripheral address space. Some processors use memory mapped I/O in which case designated memory cells work as ports for specific devices. In case of Intel a special pin on the control bus signals whether the current read or write is from the memory address space or from the peripheral address space. The same address and data buses are used to select a port and to read or write data from that port. However with I/O only the lower 16 bits of the address bus are used meaning that there are a total of 65536 possible I/O ports. Now keyboard has special

‡ The programs discussed from now onwards in the book must be executed in pure DOS and not in a DOS window so that we are in total control of the PIC and other devices.

I/O ports designated to it, PIC has others, DMA, sound card, network card, each has some ports.

If the two address spaces are differentiated in hardware, they must also have special instructions to select the other address space. We have the IN and OUT instructions to read or write from the peripheral address space. When MOV is given the processor selects the memory address space, when IN is given the processor selects the peripheral address space.

IN and OUT instructions

The IN and OUT instructions have a byte form and a word form but the byte form is almost always used. The source register in OUT and destination register in IN is AL or AX depending on which form is used. The port number can be directly given in the instruction if it fits in a byte otherwise it has to be given in the DX register. Port numbers for specific devices are fixed by the IBM standard. For example 20 and 21 are for PIC, 60 to 64 for Keyboard, 378 for the parallel port etc. A few example of IN and OUT are below:

```
in al, 0x21

mov dx, 0x378
in al, dx

out 0x21, al

mov dx, 0x378
out dx, al
```

PIC Ports

Programmable interrupt controller has two ports 20 and 21. Port 20 is the control port while port 21 is the interrupt mask register which can be used for selectively enabling or disabling interrupts. Each of the bits at port 21 corresponds to one of the IRQ lines. We first write a small program to disable the keyboard using this port. As we know that the keyboard IRQ is 1, we place a 1 bit at its corresponding position. A 0 bit will enable an interrupt and a 1 bit disables it. As soon as we write it on the port keyboard interrupts will stop arriving and the keyboard will effectively be disabled. Even Ctrl-Alt-Del would not work; the reset power button has to be used.

Example 9.1

```
001     ; disable keyboard interrupt in PIC mask register
002     [org 0x0100]
003                 in   al, 0x21           ; read interrupt mask register
004                 or   al, 2              ; set bit for IRQ2
005                 out  0x21, al           ; write back mask register
006
007                 mov  ax, 0x4c00         ; terminate program
008                 int  0x21
```

After this three line mini program is executed the computer will not understand anything else. Its ears are closed. No keystrokes are making their way to the processor. Ports always make something happen on the system. A properly designed system can launch a missile on writing a bit on some port. Memory is simple in that it is all that it is. In ports every bit has a meaning that changes something in the system.

As we previously discussed every interrupt handler invoked because of an IRQ must signal an EOI otherwise lower priority interrupts will remain disabled.

Keyboard Controller

We will go in further details of the keyboard and its relation to the computer. We will not discuss how the keyboard communicates with the keyboard controller in the computer rather we will discuss how the keyboard

controller communicates with the processor. Keyboard is a collection of labeled buttons and every button is designated a number (not the ASCII code). This number is sent to the processor whenever the key is pressed. From this number called the scan code the processor understands which key was pressed. For each key the scan code comes twice, once for the key press and once for the key release. Both are scan codes and differ in one bit only. The lower seven bits contain the key number while the most significant bit is clear in the press code and set in the release code. The IBM PC standard gives a table of the scan codes of all keys.

If we press Shift-A resulting in a capital A on the screen, the controller has sent the press code of Shift, the press code of A, the release code of A, the release code of Shift and the interrupt handler has understood that this sequence should result in the ASCII code of 'A'. The 'A' key always produces the same scan code whether or not shift is pressed. It is the interrupt handler's job to remember that the press code of Shift has come and release code has not yet come and therefore to change the meaning of the following key presses. Even the caps lock key works the same way.

An interesting thing is that the two shift keys on the left and right side of the keyboard produce different scan codes. The standard way implemented in BIOS is to treat that similarly. That's why we always think of them as identical. If we leave BIOS and talk directly with the hardware we can differentiate between left and right shift keys with their scan code. Now this scan code is available from the keyboard data port which is 60. The keyboard generates IRQ 1 whenever a key is pressed so if we hook INT 9 and inside it read port 60 we can tell which of the shift keys was hit. Our first program will do precisely this. It will output an L if the left shift key was pressed and R if the right one was pressed. The hooking method is the same as done in the previous chapter.

Example 9.2

```
001     ; differentiate left and right shift keys with scancodes
002     [org 0x0100]
003                 jmp  start
004
005     ; keyboard interrupt service routine
006     kbisr:      push ax
007                 push es
008
009                 mov  ax, 0xb800
010                 mov  es, ax             ; point es to video memory
011
012                 in   al, 0x60           ; read a char from keyboard port
013                 cmp  al, 0x2a           ; is the key left shift
014                 jne  nextcmp            ; no, try next comparison
015
016                 mov  byte [es:0], 'L'   ; yes, print L at top left
017                 jmp  nomatch            ; leave interrupt routine
018
019     nextcmp:    cmp  al, 0x36           ; is the key right shift
020                 jne  nomatch            ; no, leave interrupt routine
021
022                 mov  byte [es:0], 'R'   ; yes, print R at top left
023
024     nomatch:    mov  al, 0x20
025                 out  0x20, al           ; send EOI to PIC
026
027                 pop  es
028                 pop  ax
029                 iret
030
031     start:      xor  ax, ax
032                 mov  es, ax             ; point es to IVT base
033                 cli                     ; disable interrupts
034                 mov  word [es:9*4], kbisr ; store offset at n*4
035                 mov  [es:9*4+2], cs     ; store segment at n*4+2
036                 sti                     ; enable interrupts
```

```
037
038     l1:          jmp  l1                ; infinite loop
```

033-036	CLI clears the interrupt flag to disable the interrupt system completely. The processor closes its ears and does not care about the state of the INT pin. Interrupt hooking is done in two instructions, placing the segment and placing the offset. If an interrupt comes in between and the vector is in an indeterminate state, the system will go to a junk address and eventually crash. So we stop all interruptions while changing a real time interrupt vector. We set the interrupt flag afterwards to renewable interrupts.
038	The program hangs in an infinite loop. The only activity can be caused by a real time interrupt. The kbisr routine is not called from anywhere; it is only automatically invoked as a result of IRQ 1.

When the program is executed the left and right shift keys can be distinguished with the L or R on the screen. As no action was taken for the rest of the keys, they are effectively disabled and the computer has to be rebooted. To check that the keyboard is actually disabled we change the program and add the INT 16 service 0 at the end to wait for an Esc key press. As soon as Esc is pressed we want to terminate our program.

Example 9.3

```
001     ; attempt to terminate program with Esc that hooks keyboard interrupt
002     [org 0x0100]
003                  jmp  start
004
005-029 ;;;;; COPY LINES 005-029 FROM EXAMPLE 9.2 (kbisr) ;;;;;
030
031     start:       xor  ax, ax
032                  mov  es, ax            ; point es to IVT base
033                  cli                    ; disable interrupts
034                  mov  word [es:9*4], kbisr ; store offset at n*4
035                  mov  [es:9*4+2], cs    ; store segment at n*4+2
036                  sti                    ; enable interrupts
037
038     l1:          mov  ah, 0             ; service 0 – get keystroke
039                  int  0x16              ; call BIOS keyboard service
040
041                  cmp al, 27             ; is the Esc key pressed
042                  jne l1                 ; if no, check for next key
043
044                  mov ax, 0x4c00         ; terminate program
045                  int 0x21
```

When the program is executed the behavior is same. Esc does not work. This is because the original IRQ 1 handler was written by BIOS that read the scan code, converted into an ASCII code and stored in the keyboard buffer. The BIOS INT 16 read the key from there and gives in AL. When we hooked the keyboard interrupt BIOS is no longer in control, it has no information, it will always see the empty buffer and INT 16 will never return.

Interrupt Chaining

We can transfer control to the original BIOS ISR in the end of our routine. This way the normal functioning of INT 16 can work as well. We can retrieve the address of the BIOS routine by saving the values in vector 9 before hooking our routine. In the end of our routine we will jump to this address using a special indirect form of the JMP FAR instruction.

Example 9.4

```
001     ; another attempt to terminate program with Esc that hooks
002     ; keyboard interrupt
003     [org 0x100]
004                 jmp  start
005
006     oldisr:     dd   0                  ; space for saving old isr
007
008     ; keyboard interrupt service routine
009     kbisr:      push ax
010                 push es
011
012                 mov  ax, 0xb800
013                 mov  es, ax             ; point es to video memory
014
015                 in   al, 0x60           ; read a char from keyboard port
016                 cmp  al, 0x2a           ; is the key left shift
017                 jne  nextcmp            ; no, try next comparison
018
019                 mov  byte [es:0], 'L'   ; yes, print L at top left
020                 jmp  nomatch            ; leave interrupt routine
021
022     nextcmp:    cmp  al, 0x36           ; is the key right shift
023                 jne  nomatch            ; no, leave interrupt routine
024
025                 mov  byte [es:0], 'R'   ; yes, print R at top left
026
027     nomatch:    ; mov  al, 0x20
028                 ; out  0x20, al
029
030                 pop es
031                 pop ax
032                 jmp far [cs:oldisr]     ; call the original ISR
033                 ; iret
034
035     start:      xor  ax, ax
036                 mov  es, ax             ; point es to IVT base
037                 mov ax, [es:9*4]
038                 mov [oldisr], ax        ; save offset of old routine
039                 mov ax, [es:9*4+2]
040                 mov [oldisr+2], ax      ; save segment of old routine
041                 cli                     ; disable interrupts
042                 mov  word [es:9*4], kbisr ; store offset at n*4
043                 mov  [es:9*4+2], cs     ; store segment at n*4+2
044                 sti                     ; enable interrupts
045
046     l1:         mov  ah, 0              ; service 0 – get keystroke
047                 int  0x16               ; call BIOS keyboard service
048
049                 cmp al, 27              ; is the Esc key pressed
050                 jne l1                  ; if no, check for next key
051
052                 mov ax, 0x4c00          ; terminate program
053                 int 0x21
```

027-028	EOI is no longer needed as the original BIOS routine will have it at its end.
033	IRET has been removed and an unconditional jump is introduced. At time of JMP the stack has the exact formation as was when the interrupt came. So the original BIOS routine's IRET will take control to the interrupted program. We have been careful in restoring every register we modified and retained the stack in the same form as it was at the time of entry into the routine.

When the program is executed L and R are printed as desired and Esc terminates the program as well. Normal commands like DIR work now and shift keys still show L and R as our routine did even after the termination of our program. Now start some application like the editor, it open well but as soon as a key is pressed the computer crashes.

Actually our hooking and chaining was fine. When Esc was pressed we signaled DOS that our program has terminated. DOS will take all our

memory as a result. The routine is still in memory and functioning but the memory is free according to DOS. As soon as we load EDIT the same memory is allocated to EDIT and our routine as overwritten. Now when a key is pressed our routine's address is in the vector but at that address some new code is placed that is not intended to be an interrupt handler. That may be data or some part of the EDIT program. This results in crashing the computer.

Unhooking Interrupt

We now add the interrupt restoring part to our program. This code resets the interrupt vector to the value it had before the start of our program.

Example 9.5

```
001      ; terminate program with Esc that hooks keyboard interrupt
002      [org 0x100]
003                   jmp  start
004
005      oldisr:      dd   0                  ; space for saving old isr
006
007-032  ;;;;; COPY LINES 005-029 FROM EXAMPLE 9.4 (kbisr) ;;;;;
033
034      start:       xor  ax, ax
035                   mov  es, ax             ; point es to IVT base
036                   mov ax, [es:9*4]
037                   mov [oldisr], ax        ; save offset of old routine
038                   mov ax, [es:9*4+2]
039                   mov [oldisr+2], ax      ; save segment of old routine
040                   cli                     ; disable interrupts
041                   mov  word [es:9*4], kbisr ; store offset at n*4
042                   mov  [es:9*4+2], cs     ; store segment at n*4+2
043                   sti                     ; enable interrupts
044
045      l1:          mov  ah, 0              ; service 0 – get keystroke
046                   int  0x16               ; call BIOS keyboard service
047
048                   cmp al, 27              ; is the Esc key pressed
049                   jne l1                  ; if no, check for next key
050
051                   mov ax, [oldisr]        ; read old offset in ax
052                   mov bx, [oldisr+2]      ; read old segment in bx
053                   cli                     ; disable interrupts
054                   mov [es:9*4], ax        ; restore old offset from ax
055                   mov [es:9*4+2], bx      ; restore old segment from bx
056                   sti                     ; enable interrupts
057
058                   mov ax, 0x4c00          ; terminate program
059                   int 0x21
```

9.3. TERMINATE AND STAY RESIDENT

We change the display to show L only while the left shift is pressed and R only while the right shift is pressed to show the use of the release codes. We also changed that shift keys are not forwarded to BIOS. The effect will be visible with A and Shift-A both producing small 'a' but caps lock will work.


There is one major difference from all the programs we have been writing till now. The termination is done using INT 21 service 31 instead of INT 21 service 4C. The effect is that even after termination the program is there and is legally there.

Example 9.6

```
001      ; TSR to show status of shift keys on top left of screen
002      [org 0x0100]
003                   jmp  start
004
005      oldisr:      dd   0                  ; space for saving old isr
006
```

```
007     ; keyboard interrupt service routine
008     kbisr:        push ax
009                   push es
010
011                   mov  ax, 0xb800
012                   mov  es, ax             ; point es to video memory
013
014                   in   al, 0x60           ; read a char from keyboard port
015                   cmp  al, 0x2a           ; has the left shift pressed
016                   jne  nextcmp            ; no, try next comparison
017
018                   mov  byte [es:0], 'L'   ; yes, print L at first column
019                   jmp  exit               ; leave interrupt routine
020
021     nextcmp:      cmp  al, 0x36           ; has the right shift pressed
022                   jne  nextcmp2           ; no, try next comparison
023
024                   mov  byte [es:0], 'R'   ; yes, print R at second column
025                   jmp  exit               ; leave interrupt routine
026
027     nextcmp2:     cmp  al, 0xaa           ; has the left shift released
028                   jne  nextcmp3           ; no, try next comparison
029
030                   mov  byte [es:0], ' '   ; yes, clear the first column
031                   jmp  exit               ; leave interrupt routine
032
033     nextcmp3:     cmp  al, 0xb6           ; has the right shift released
034                   jne  nomatch            ; no, chain to old ISR
035
036                   mov  byte [es:2], ' '   ; yes, clear the second column
037                   jmp  exit               ; leave interrupt routine
038
039     nomatch:      pop  es
040                   pop  ax
041                   jmp  far [cs:oldisr]    ; call the original ISR
042
043     exit:         mov  al, 0x20
044                   out  0x20, al           ; send EOI to PIC
045
046                   pop  es
047                   pop  ax
048                   iret                    ; return from interrupt
049
050     start:        xor  ax, ax
051                   mov  es, ax             ; point es to IVT base
052                   mov  ax, [es:9*4]
053                   mov  [oldisr], ax       ; save offset of old routine
054                   mov  ax, [es:9*4+2]
055                   mov  [oldisr+2], ax     ; save segment of old routine
056                   cli                     ; disable interrupts
057                   mov  word [es:9*4], kbisr ; store offset at n*4
058                   mov  [es:9*4+2], cs     ; store segment at n*4+2
059                   sti                     ; enable interrupts
060
061                   mov  dx, start          ; end of resident portion
062                   add  dx, 15             ; round up to next para
063                   mov  cl, 4
064                   shr  dx, cl             ; number of paras
065                   mov  ax, 0x3100         ; terminate and stay resident
066                   int  0x21
```

When this program is executed the command prompt immediately comes. DIR can be seen. EDIT can run and keypresses do not result in a crash. And with all that left and right shift keys shown L and R on top left of the screen while they are pressed but the shift keys do not work as usual since we did not forwarded the key to BIOS. This is selective chaining.



To understand Terminate and Stay Resident (TSR) programs the DOS memory formation and allocation procedure must be understood. At physical address zero is the interrupt vector table. Then are the BIOS data area, DOS data area, IO.SYS, MSDOS.SYS and other device drivers. In the end there is COMMAND.COM command interpreter. The remaining space is called the transient program area as programs are loaded and executed in this area and the space reclaimed on their exit. A freemem pointer in DOS points where the free memory begins. When DOS loads a program the freemem pointer is moved to the end of memory, all the available space is allocated to it, and when it exits the freemem pointer comes back to its original place thereby reclaiming all space. This action is initiated by the DOS service 4C.

The second method to legally terminate a program and give control back to DOS is using the service 31. Control is still taken back but the memory releasing part is modified. A portion of the allocated memory can be retained. So the difference in the two methods is that the freemem pointer goes back to the original place or a designated number of bytes ahead of that old position. Remember that our program crashed because the interrupt routine was overwritten. If we can tell DOS not to reclaim the memory of the interrupt routine, then it will not crash. In the last program we have told DOS to make a number of bytes resident. It becomes a part of the operation system, an extension to it. Just like DOSKEY[§] is an extension to the operation system.

The number of paragraphs to reserve is given in the DX register. Paragraph is a unit just like byte, word, and double word. A paragraph is 16 bytes. Therefore we can reserve in multiple of 16 bytes. We write TSRs in such a way that the initialization code and data is located at the end as it is not necessary to make it resident and therefore to save space.

To calculate the number of paragraphs a label is placed after the last line that is to be made resident. The value of that label is the number of bytes needed to be made resident. A simple division by 16 will not give the correct number of paras as we want our answer to be rounded up and not down. For example 100 bytes should need 7 pages but division gives 6 and a remainder of 4. A standard technique to get rounded up integer division is to add divisor-1 to the dividend and then divide. So we add 15 to the number of bytes and then divide by 16. We use shifting for division as the divisor is a power of 2. We use a form of SHR that places the count in the CL register so that we can shift by 4 in just two instructions instead of 4 if we shift one by one.

In our program anything after start label is not needed after the program has become a TSR. We can observe that our program has become a part of DOS by giving the following command.

```
mem /c
```

[§] DOSKEY is a TSR that shows the previous commands on the command prompt with up and down arrows and allows editing of the command

This command displays all currently loaded drivers and the current state of memory. We will be able to see our program in the list of DOS drivers.

9.4. PROGRAMMABLE INTERVAL TIMER

Another very important peripheral device is the Programmable Interval Timer (PIT), the chip numbered 8254. This chip has a precise input frequency of 1.19318 MHz. This frequency is fixed regardless of the processor clock. Inside the chip is a 16bit divisor which divides this input frequency and the output is connected to the IRQ 0 line of the PIC. The special number 0 if placed in the divisor means a divisor of 65536 and not 0. The standard divisor is 0 unless we change it. Therefore by default IRQ 0 is generated 1193180/65536=18.2 times per second. This is called the timer tick. There is an interval of about 55ms between two timer ticks. The system time is maintained with the timer interrupt. This is the highest priority interrupt and breaks whatever is executing. Time can be maintained with this interrupt as this frequency is very precise and is part of the IBM standard.

When writing a TSR we give control back to DOS so TSR activation, reactivation and action is solely interrupt based, whether this is a hardware interrupt or a software one. Control is never given back; it must be caught, just like we caught control by hooking the keyboard interrupt. Our next example will hook the timer interrupt and display a tick count on the screen.

Example 9.7

```
001     ; display a tick count on the top right of screen
002     [org 0x0100]
003                 jmp  start
004
005     tickcount:    dw   0
006
007     ; subroutine to print a number at top left of screen
008     ; takes the number to be printed as its parameter
009     printnum:     push bp
010                   mov  bp, sp
011                   push es
012                   push ax
013                   push bx
014                   push cx
015                   push dx
016                   push di
017
018                   mov  ax, 0xb800
019                   mov  es, ax             ; point es to video base
020                   mov  ax, [bp+4]         ; load number in ax
021                   mov  bx, 10             ; use base 10 for division
022                   mov  cx, 0              ; initialize count of digits
023
024     nextdigit:    mov  dx, 0              ; zero upper half of dividend
025                   div  bx                 ; divide by 10
026                   add  dl, 0x30           ; convert digit into ascii value
027                   push dx                 ; save ascii value on stack
028                   inc  cx                 ; increment count of values
029                   cmp  ax, 0              ; is the quotient zero
030                   jnz  nextdigit          ; if no divide it again
031
032                   mov  di, 140            ; point di to 70th column
033
034     nextpos:      pop  dx                 ; remove a digit from the stack
035                   mov  dh, 0x07           ; use normal attribute
036                   mov  [es:di], dx        ; print char on screen
037                   add  di, 2              ; move to next screen location
038                   loop nextpos            ; repeat for all digits on stack
039
040                   pop  di
041                   pop  dx
042                   pop  cx
043                   pop  bx
044                   pop  ax
```

```
045                 pop  es
046                 pop  bp
047                 ret  2
048
049     ; timer interrupt service routine
050     timer:      push ax
051
052                 inc  word [cs:tickcount]; increment tick count
053                 push word [cs:tickcount]
054                 call printnum           ; print tick count
055
056                 mov  al, 0x20
057                 out  0x20, al           ; end of interrupt
058
059                 pop  ax
060                 iret                    ; return from interrupt
061
062     start:      xor  ax, ax
063                 mov  es, ax             ; point es to IVT base
064                 cli                     ; disable interrupts
065                 mov  word [es:8*4], timer; store offset at n*4
066                 mov  [es:8*4+2], cs     ; store segment at n*4+2
067                 sti                     ; enable interrupts
068
069                 mov  dx, start          ; end of resident portion
070                 add  dx, 15             ; round up to next para
071                 mov  cl, 4
072                 shr  dx, cl             ; number of paras
073                 mov  ax, 0x3100         ; terminate and stay resident
074                 int  0x21
```

When we execute the program the counter starts on the screen. Whatever we do, take directory, open EDIT, the debugger etc. the counter remains running on the screen. No one is giving control to the program; the program is getting executed as a result of timer generating INT 8 after every 55ms.

Our next example will hook both the keyboard and timer interrupts. When the shift key is pressed the tick count starts incrementing and as soon as the shift key is released the tick count stops. Both interrupt handlers are communicating through a common variable. The keyboard interrupt sets this variable while the timer interrupts modifies its behavior according to this variable.

Example 9.8

```
001     ; display a tick count while the left shift key is down
002     [org 0x0100]
003                 jmp  start
004
005     seconds:    dw   0
006     timerflag:  dw   0
007     oldkb:      dd   0
008
009-049 ;;;;; COPY LINES 007-047 FROM EXAMPLE 9.7 (printnum) ;;;;;
050
051     ; keyboard interrupt service routine
052     kbisr:      push ax
053
054                 in   al, 0x60           ; read char from keyboard port
055                 cmp  al, 0x2a           ; has the left shift pressed
056                 jne  nextcmp            ; no, try next comparison
057
058                 cmp  word [cs:timerflag], 1; is the flag already set
059                 je   exit               ; yes, leave the ISR
060
061                 mov  word [cs:timerflag], 1; set flag to start printing
062                 jmp  exit               ; leave the ISR
063
064     nextcmp:    cmp  al, 0xaa           ; has the left shift released
065                 jne  nomatch            ; no, chain to old ISR
066
067                 mov  word [cs:timerflag], 0; reset flag to stop printing
```

```
068                 jmp  exit               ; leave the interrupt routine
069
070     nomatch:    pop  ax
071                 jmp  far [cs:oldkb]     ; call original ISR
072
073     exit:       mov  al, 0x20
074                 out  0x20, al           ; send EOI to PIC
075
076                 pop  ax
077                 iret                    ; return from interrupt
078
079     ; timer interrupt service routine
080     timer:      push ax
081
082                 cmp  word [cs:timerflag], 1 ; is the printing flag set
083                 jne  skipall            ; no, leave the ISR
084
085                 inc  word [cs:seconds]  ; increment tick count
086                 push word [cs:seconds]
087                 call printnum           ; print tick count
088
089     skipall:    mov  al, 0x20
090                 out  0x20, al           ; send EOI to PIC
091
092                 pop  ax
093                 iret                    ; return from interrupt
094
095     start:      xor  ax, ax
096                 mov  es, ax             ; point es to IVT base
097                 mov  ax, [es:9*4]
098                 mov  [oldkb], ax        ; save offset of old routine
099                 mov  ax, [es:9*4+2]
100                 mov  [oldkb+2], ax      ; save segment of old routine
101                 cli                     ; disable interrupts
102                 mov  word [es:9*4], kbisr ; store offset at n*4
103                 mov  [es:9*4+2], cs     ; store segment at n*4+2
104                 mov  word [es:8*4], timer ; store offset at n*4
105                 mov  [es:8*4+2], cs     ; store segment at n*4+
106                 sti                     ; enable interrupts
107
108                 mov  dx, start          ; end of resident portion
109                 add  dx, 15             ; round up to next para
110                 mov  cl, 4
111                 shr  dx, cl             ; number of paras
112                 mov  ax, 0x3100         ; terminate and stay resident
113                 int  0x21
```

006	This flag is one when the timer interrupt should increment and zero when it should not.
058-059	As the keyboard controller repeatedly generates the press code if the release code does not come in a specified time, we have placed a check to not repeatedly set it to one.
058	Another way to access TSR data is using the CS override instead of initializing DS. It is common mistake not to initialize DS and also not put in CS override in a real time interrupt handler.

When we execute the program and the shift key is pressed, the counter starts incrementing. When the key is released the counter stops. When it is pressed again the counter resumes counting. As this is made as a TSR any other program can be loaded and will work properly alongside the TSR.

9.5. PARALLEL PORT

Computers can control external hardware through various external ports like the parallel port, the serial port, and the new additions USB and FireWire. Using this, computers can be used to control almost anything. For our examples we will use the parallel port. The parallel port has two views, the connector that the external world sees and the parallel port controller

ports through which the processor communicates with the device connected to the parallel port.

The parallel port connector is a 25pin connector called DB-25. Different pins of this connector have different meanings. Some are meaningful only with the printer[**]. This is a bidirectional port so there are some pins to take data from the processor to the parallel port and others to take data from the parallel port to the processor. Important pins for our use are the data pins from pin 2 to pin 9 that take data from the processor to the device. Pin 10, the ACK pin, is normally used by the printer to acknowledge the receipt of data and show the willingness to receive more data. Signaling this pin generates IRQ 7 if enabled in the PIC and in the parallel port controller. Pin 18-25 are ground and must be connected to the external circuit ground to provide the common reference point otherwise they won't understand each other voltage levels. Like the datum point in a graph this is the datum point of an electrical circuit. The remaining pins are not of our concern in these examples.

This is the external view of the parallel port. The processor cannot see these pins. The processor uses the I/O ports of the parallel port controller. The first parallel port LPT1[††] has ports designated from 378 to 37A. The first port 378 is the data port. If we use the OUT instruction on this port, 1 bits result in a 5V signal on the corresponding pin and a 0 bits result in a 0V signal on the corresponding pin.

Port 37A is the control port. Our interest is with bit 4 of this port which enables the IRQ 7 triggering by the ACK pin. We have attached a circuit that connects 8 LEDs with the parallel port pins. The following examples sends the scancode of the key pressed to the parallel port so that it is visible on LEDs.

Example 9.9

```
001     ; show scancode on external LEDs connected through parallel port
002     [org 0x0100]
003                 jmp  start
004
005     oldisr:     dd   0                  ; space for saving old ISR
006
007     ; keyboard interrupt service routine
008     kbisr:      push ax
009                 push dx
010
011                 in   al, 0x60           ; read char from keyboard port
012                 mov  dx, 0x378
013                 out  dx, al             ; write char to parallel port
014
015                 pop  ax
016                 pop  dx
017                 jmp  far [cs:oldisr]    ; call original ISR
018
019     start:      xor  ax, ax
020                 mov  es, ax             ; point es to IVT base
021                 mov  ax, [es:9*4]
022                 mov  [oldisr], ax       ; save offset of old routine
023                 mov  ax, [es:9*4+2]
024                 mov  [oldisr+2], ax     ; save segment of old routine
025                 cli                     ; disable interrupts
026                 mov  word [es:9*4], kbisr ; store offset at n*4
027                 mov  [es:9*4+2], cs     ; store segment at n*4+2
028                 sti                     ; enable interrupts
029
030                 mov  dx, start          ; end of resident portion
031                 add  dx, 15             ; round up to next para
```

[**] The parallel port is most commonly used with the printer. However some new printers have started using the USB port.

[††] Older computer had more than one parallel port named LPT2 and having ports from 278-27A.

```
032                 mov  cl, 4
033                 shr  dx, cl             ; number of paras
034                 mov  ax, 0x3100         ; terminate and stay resident
035                 int  0x21
```

The following example uses the same LED circuit and sends data such that LEDs switch on and off turn by turn so that it looks like light is moving back and forth.

Example 9.10

```
001     ; show lights moving back and forth on external LEDs
002     [org 0x0100]
003                 jmp  start
004
005     signal:     db   1                 ; current state of lights
006     direction:  db   0                 ; current direction of motion
007
008     ; timer interrupt service routine
009     timer:      push ax
010                 push dx
011                 push ds
012
013                 push cs
014                 pop  ds                ; initialize ds to data segment
015
016                 cmp  byte [direction], 1; are moving in right direction
017                 je   moveright         ; yes, go to shift right code
018
019                 shl  byte [signal], 1  ; shift left state of lights
020                 jnc  output            ; no jump to change direction
021
022                 mov  byte [direction], 1; change direction to right
023                 mov  byte [signal], 0x80; turn on left most light
024                 jmp  output            ; proceed to send signal
025
026     moveright:  shr  byte [signal], 1  ; shift right state of lights
027                 jnc  output            ; no jump to change direction
028
029                 mov  byte [direction], 0; change direction to left
030                 mov  byte [signal], 1  ; turn on right most light
031
032     output:     mov  al, [signal]      ; load lights state in al
033                 mov  dx, 0x378         ; parallel port data port
034                 out  dx, al            ; send light state of port
035
036                 mov  al, 0x20
037                 out  0x20, al          ; send EOI on PIC
038
039                 pop  ds
040                 pop  dx
041                 pop  ax
042                 iret                   ; return from interrupt
043
044     start:      xor  ax, ax
045                 mov  es, ax            ; point es to IVT base
046                 cli                    ; disable interrupts
047                 mov  word [es:8*4], timer ; store offset at n*4
048                 mov  [es:8*4+2], cs    ; store segment at n*4+2
049                 sti                    ; enable interrupts
050
051                 mov  dx, start         ; end of resident portion
052                 add  dx, 15            ; round up to next para
053                 mov  cl, 4
054                 shr  dx, cl            ; number of paras
055                 mov  ax, 0x3100        ; terminate and stay resident
056                 int  0x21
```

We will now use the parallel port to control a slightly complicated circuit. This time we will also use the parallel port interrupt. We are using a 220 V bulb with AC input. AC current is 50Hz sine wave. We have made our circuit such that it triggers the parallel port interrupt whenever the since wave

crosses zero. We have control of passing the AC current to the bulb. We control it such that in every cycle only a fixed percentage of time the current passes on to the bulb. Using this we can control the intensity or glow of the bulb.

Our first example will slowly turn on the bulb by increasing the power provided using the mechanism just described.

Example 9.11

```
001     ; slowly turn on a bulb by gradually increasing the power provided
002     [org 0x0100]
003                 jmp  start
004
005     flag:       db   0                  ; next time turn on or turn off
006     stop:       db   0                  ; flag to terminate the program
007     divider:    dw   11000              ; divider for minimum intensity
008     oldtimer:   dd   0                  ; space for saving old isr
009
010     ; timer interrupt service routine
011     timer:      push ax
012                 push dx
013
014                 cmp  byte [cs:flag], 0  ; are we here to turn off
015                 je   switchoff          ; yes, go to turn off code
016
017     switchon:   mov  al, 1
018                 mov  dx, 0x378
019                 out  dx, al             ; no, turn the bulb on
020
021                 mov  ax, 0x0100
022                 out  0x40, al           ; set timer divisor LSB to 0
023                 mov  al, ah
024                 out  0x40, al           ; set timer divisor MSB to 1
025                 mov  byte [cs:flag], 0  ; flag next timer to switch off
026                 jmp  exit               ; leave the interrupt routine
027
028     switchoff:  xor  ax, ax
029                 mov  dx, 0x378
030                 out  dx, al             ; turn the bulb off
031
032     exit:       mov  al, 0x20
033                 out  0x20, al           ; send EOI to PIC
034
035                 pop  dx
036                 pop  ax
037                 iret                    ; return from interrupt
038
039     ; parallel port interrupt service routine
040     parallel:   push ax
041
042                 mov  al, 0x30           ; set timer to one shot mode
043                 out  0x43, al
044
045                 cmp  word [cs:divider], 100; is the current divisor 100
046                 je   stopit             ; yes, stop
047
048                 sub  word [cs:divider], 10; decrease the divisor by 10
049                 mov  ax, [cs:divider]
050                 out  0x40, al           ; load divisor LSB in timer
051                 mov  al, ah
052                 out  0x40, al           ; load divisor MSB in timer
053                 mov  byte [cs:flag], 1  ; flag next timer to switch on
054
055                 mov  al, 0x20
056                 out  0x20, al           ; send EOI to PIC
057                 pop  ax
058                 iret                    ; return from interrupt
059
060     stopit:     mov  byte [stop], 1     ; flag to terminate the program
061                 mov  al, 0x20
062                 out  0x20, al           ; send EOI to PIC
063                 pop  ax
064                 iret                    ; return from interrupt
065
```

```
066     start:        xor  ax, ax
067                   mov  es, ax             ; point es to IVT base
068                   mov  ax, [es:0x08*4]
069                   mov  [oldtimer], ax     ; save offset of old routine
070                   mov  ax, [es:0x08*4+2]
071                   mov  [oldtimer+2], ax   ; save segment of old routine
072                   cli                     ; disable interrupts
073                   mov  word [es:0x08*4], timer ; store offset at n*4
074                   mov  [es:0x08*4+2], cs  ; store segment at n*4+2
075                   mov  word [es:0x0F*4], parallel ; store offset at n*4
076                   mov  [es:0x0F*4+2], cs  ; store segment at n*4+2
077                   sti                     ; enable interrupts
078
079                   mov dx, 0x37A
080                   in al, dx               ; parallel port control register
081                   or al, 0x10             ; turn interrupt enable bit on
082                   out dx, al              ; write back register
083
084                   in al, 0x21             ; read interrupt mask register
085                   and al, 0x7F            ; enable IRQ7 for parallel port
086                   out 0x21, al            ; write back register
087
088     recheck:      cmp byte [stop], 1      ; is the termination flag set
089                   jne recheck             ; no, check again
090
091                   mov dx, 0x37A
092                   in al, dx               ; parallel port control register
093                   and al, 0xEF            ; turn interrupt enable bit off
094                   out dx, al              ; write back register
095
096                   in al, 0x21             ; read interrupt mask register
097                   or al, 0x80             ; disable IRQ7 for parallel port
098                   out 0x21, al            ; write back regsiter
099
100                   cli                     ; disable interrupts
101                   mov ax, [oldtimer]      ; read old timer ISR offset
102                   mov [es:0x08*4], ax     ; restore old timer ISR offset
103                   mov ax, [oldtimer+2]    ; read old timer ISR segment
104                   mov [es:0x08*4+2], ax   ; restore old timer ISR segment
105                   sti                     ; enable interrupts
106
107                   mov ax, 0x4c00          ; terminate program
108                   int 0x21
```

The next example is simply the opposite of the previous. It slowly turns the bulb off from maximum glow to no glow.

Example 9.12

```
001     ; slowly turn off a bulb by gradually decreasing the power provided
002     [org 0x0100]
003                   jmp  start
004
005     flag:         db   0                  ; next time turn on or turn off
006     stop:         db   0                  ; flag to terminate the program
007     divider:      dw   0                  ; divider for maximum intensity
008     oldtimer:     dd   0                  ; space for saving old isr
009
010-037 ;;;;; COPY LINES 009-036 FROM EXAMPLE 9.11 (timer) ;;;;;
038
039     ; parallel port interrupt service routine
040     parallel:     push ax
041
042                   mov  al, 0x30           ; set timer to one shot mode
043                   out  0x43, al
044
045                   cmp  word [cs:divider], 11000; current divisor is 11000
046                   je   stopit             ; yes, stop
047
048                   add  word [cs:divider], 10; increase the divisor by 10
049                   mov  ax, [cs:divider]
050                   out  0x40, al           ; load divisor LSB in timer
051                   mov  al, ah
052                   out  0x40, al           ; load divisor MSB in timer
```

```
053                 mov  byte [cs:flag], 1  ; flag next timer to switch on
054
055                 mov  al, 0x20
056                 out  0x20, al           ; send EOI to PIC
057                 pop  ax
058                 iret                    ; return from interrupt
059
060     stopit:     mov  byte [stop], 1     ; flag to terminate the program
061                 mov  al, 0x20
062                 out  0x20, al           ; send EOI to PIC
063                 pop  ax
064                 iret                    ; return from interrupt
065
066     start:      xor  ax, ax
067                 mov  es, ax             ; point es to IVT base
068                 mov  ax, [es:0x08*4]
069                 mov  [oldtimer], ax     ; save offset of old routine
070                 mov  ax, [es:0x08*4+2]
071                 mov  [oldtimer+2], ax   ; save segment of old routine
072                 cli                     ; disable interrupts
073                 mov  word [es:0x08*4], timer ; store offset at n*4
074                 mov  [es:0x08*4+2], cs  ; store segment at n*4+2
075                 mov  word [es:0x0F*4], parallel ; store offset at n*4
076                 mov  [es:0x0F*4+2], cs  ; store segment at n*4+2
077                 sti                     ; enable interrupts
078
079                 mov  dx, 0x37A
080                 in   al, dx             ; parallel port control register
081                 or   al, 0x10           ; turn interrupt enable bit on
082                 out  dx, al             ; write back register
083
084                 in   al, 0x21           ; read interrupt mask register
085                 and  al, 0x7F           ; enable IRQ7 for parallel port
086                 out  0x21, al           ; write back register
087
088     recheck:    cmp  byte [stop], 1     ; is the termination flag set
089                 jne  recheck            ; no, check again
090
091                 mov  dx, 0x37A
092                 in   al, dx             ; parallel port control register
093                 and  al, 0xEF           ; turn interrupt enable bit off
094                 out  dx, al             ; write back register
095
096                 in   al, 0x21           ; read interrupt mask register
097                 or   al, 0x80           ; disable IRQ7 for parallel port
098                 out  0x21, al           ; write back regsiter
099
100                 cli                     ; disable interrupts
101                 mov  ax, [oldtimer]     ; read old timer ISR offset
102                 mov  [es:0x08*4], ax    ; restore old timer ISR offset
103                 mov  ax, [oldtimer+2]   ; read old timer ISR segment
104                 mov  [es:0x08*4+2], ax  ; restore old timer ISR segment
105                 sti                     ; enable interrupts
106
107                 mov  ax, 0x4c00         ; terminate program
108                 int  0x21
```

This example is a mix of the previous two. Here we can increase the bulb intensity with F11 and decrease it with F12.

Example 9.13

```
001     ; control external bulb intensity with F11 and F12
002     [org 0x0100]
003                 jmp  start
004
005     flag:       db   0                  ; next time turn on or turn off
006     divider:    dw   100                ; initial timer divider
007     oldkb:      dd   0                  ; space for saving old ISR
008
009-036 ;;;;; COPY LINES 009-036 FROM EXAMPLE 9.11 (timer) ;;;;;
037
038     ; keyboard interrupt service routine
039     kbisr:      push ax
```

```
040
041                 in   al, 0x60
042                 cmp  al, 0x57
043                 jne  nextcmp
044                 cmp  word [cs:divider], 11000
045                 je   exitkb
046                 add  word [cs:divider], 100
047                 jmp  exitkb
048
049     nextcmp:    cmp  al, 0x58
050                 jne  chain
051                 cmp  word [cs:divider], 100
052                 je   exitkb
053                 sub  word [cs:divider], 100
054                 jmp  exitkb
055
056     exitkb:     mov  al, 0x20
057                 out  0x20, al
058
059                 pop  ax
060                 iret
061
062     chain:      pop  ax
063                 jmp  far [cs:oldkb]
064
065     ; parallel port interrupt service routine
066     parallel:   push ax
067
068                 mov  al, 0x30           ; set timer to one shot mode
069                 out  0x43, al
070
071                 mov  ax, [cs:divider]
072                 out  0x40, al           ; load divisor LSB in timer
073                 mov  al, ah
074                 out  0x40, al           ; load divisor MSB in timer
075                 mov  byte [cs:flag], 1  ; flag next timer to switch on
076
077                 mov  al, 0x20
078                 out  0x20, al           ; send EOI to PIC
079                 pop  ax
080                 iret                    ; return from interrupt
081
082     start:      xor  ax, ax
083                 mov  es, ax             ; point es to IVT base
084                 mov  ax, [es:0x09*4]
085                 mov  [oldkb], ax        ; save offset of old routine
086                 mov  ax, [es:0x09*4+2]
087                 mov  [oldkb+2], ax      ; save segment of old routine
088                 cli                     ; disable interrupts
089                 mov word [es:0x08*4], timer ; store offset at n*4
090                 mov [es:0x08*4+2], cs   ; store segment at n*4+2
091                 mov word [es:0x09*4], kbisr ; store offset at n*4
092                 mov [es:0x09*4+2], cs   ; store segment at n*4+2
093                 mov word [es:0x0F*4], parallel ; store offset at n*4
094                 mov [es:0x0F*4+2], cs   ; store segment at n*4+2
095                 sti                     ; enable interrupts
096
097                 mov  dx, 0x37A
098                 in   al, dx             ; parallel port control register
099                 or   al, 0x10           ; turn interrupt enable bit on
100                 out  dx, al             ; write back register
101
102                 in   al, 0x21           ; read interrupt mask register
103                 and  al, 0x7F           ; enable IRQ7 for parallel port
104                 out  0x21, al           ; write back register
105
106                 mov  dx, start          ; end of resident portion
107                 add  dx, 15             ; round up to next para
108                 mov  cl, 4
109                 shr  dx, cl             ; number of paras
110                 mov  ax, 0x3100         ; terminate and stay resident
111                 int  0x21
```

EXERCISES

1. Suggest a reason for the following. The statements are all true.
    a. We should disable interrupts while hooking interrupt 8h. I.e. while placing its segment and offset in the interrupt vector table.
    b. We need not do this for interrupt 80h.
    c. We need not do this when hooking interrupt 8h from inside the interrupt handler of interrupt 80h.
    d. We should disable interrupts while we are changing the stack (SS and SP).
    e. EOI is not sent from an interrupt handler which does interrupt chaining.
    f. If no EOI is sent from interrupt 9h and no chaining is done, interrupt 8h still comes if the interrupt flag is on.
    g. After getting the size in bytes by putting a label at the end of a COM TSR, 0fh is added before dividing by 10h.
    h. Interrupts are disabled but divide by zero interrupt still comes.
2. If no hardware interrupts are coming, what are all possible reasons?
3. Write a program to make an asterisks travel the border of the screen, from upper left to upper right to lower right to lower left and back to upper left indefinitely, making each movement after one second.
4. [Musical Arrow] Write a TSR to make an arrow travel the border of the screen from top left to top right to bottom right to bottom left and back to top left at the speed of 36.4 locations per second. The arrow should not destroy the data beneath it and should be restored as soon as the arrow moves forward.
   The arrow head should point in the direction of movement using the characters > V < and ^. The journey should be accompanied by a different tone from the pc speaker for each side of the screen. Do interrupt chaining so that running the TSR 10 times produces 10 arrows traveling at different locations.
   HINT: At the start you will need to reprogram channel 0 for 36.4 interrupts per second, double the normal. You will have to reprogram channel 2 at every direction change, though you can enable the speaker once at the very start.
5. In the above TSR hook the keyboard interrupt as well and check if 'q' is pressed. If not chain to the old interrupt, if yes restore everything and remove the TSR from memory. The effect should be that pressing 'q' removes one moving arrow. If you do interrupt chaining when pressing 'q' as well, it will remove all arrows at once.
6. Write a TSR to rotate the screen (scroll up and copy the old top most line to the bottom) while F10 is pressed. The screen will keep rotating while F10 is pressed at 18.2 rows per second. As soon as F10 is released the rotation should stop and the original screen restored. A secondary buffer of only 160 bytes (one line of screen) can be used.
7. Write a TSR that hooks software interrupt 0x80 and the timer interrupt. The software interrupt is called by other programs with the address of a far function in ES:DI and the number of timer ticks after which to call back that function in CX. The interrupt records this information and returns to the caller. The function will actually be called by the timer interrupt after the desired number of ticks. The maximum number of functions and their ticks can be fixed to 8.
8. Write a TSR to clear the screen when CTRL key is pressed and restore it when it is released.
9. Write a TSR to disable all writes to the hard disk when F10 is pressed and re-enable when pressed again like a toggle.

HINT: To write to the hard disk programs call the BIOS service INT 0x13 with AH=3.

10. Write a keyboard interrupt handler that disables the timer interrupt (no timer interrupt should come) while Q is pressed. It should be re-enabled as soon as Q is released.
11. Write a TSR to calculate the current typing speed of the user. Current typing speed is the number of characters typed by the user in the last five seconds. The speed should be represented by printing asterisks at the right border (80th column) of the screen starting from the upper right to the lower right corner (growing downwards). Draw n asterisks if the user typed n characters in the last five seconds. The count should be updated every second.
12. Write a TSR to show a clock in the upper right corner of the screen in the format HH:MM:SS.DD where HH is hours in 24 hour format, MM is minutes, SS is seconds and DD is hundredth of second. The clock should beep twice for one second each time with half a second interval in between at the start of every minute at a frequency of your choice.

    HINT: IBM PC uses a Real Time Clock (RTC) chip to keep track of time while switched off. It provides clock and calendar functions through its two I/O ports 70h and 71h. It is used as follows:

```
            mov  al, <command>
            out  0x70, al        ; command byte written at first port
            jmp  D1              ; waste one instruction time
D1:         in   al, 0x71        ; result of command is in AL now
```

    Following are few commands

    00 Get current second
    02 Get current minute
    04 Get current hour

    All numbers returned by RTC are in BCD. E.g. if it is 6:30 the second and third command will return 0x30 and 0x06 respectively in al.

10
Debug Interrupts

10.1. DEBUGGER USING SINGLE STEP INTERRUPT

The use of the trap flag has been deferred till now. The three flags not used for mathematical operations are the direction flag, the interrupt flag and the trap flag. The direction and interrupt flags have been previously discussed.

If the the trap flag is set, the after every instruction a type 1 interrupt will be automatically generated. When the IVT and reserved interrupts were discussed this was named as the single step interrupt. This is like the divide by zero interrupt which was never explicitly invoked but it came itself. The single step interrupt behaves in the same manner.

The debugger is made using this interrupt. It allows one instruction to be executed and then return control to us. It has its display code and its code to wait for the key in the INT 1 handler. Therefore after every instruction the values of all registers are shown and the debugger waits for a key. Another interrupt used by the debugger is the break point interrupt INT 3. Apart from single stepping debugger has the breakpoint feature. INT 3 is used for this feature. INT 3 has a single byte opcode so it can replace any instruction. To put a breakpoint the instruction is replaced with INT 3 opcode and restored in the INT 3 handler. The INT 3 opcode is placed again by a single step interrupt that is set up for this purpose after the replaced instruction has been executed.

There is no instruction to set or clear the trap flag like there are instructions for the interrupt and direction flags. We use two special instructions PUSHF and POPF to push and pop the flag from the stack. We use PUSHF to place flags on the stack, change TF in this image on the stack and then reload into the flags register with POPF. The single step interrupt will come after the first instruction after POPF. The interrupt mechanism automatically clears IF and TF otherwise there would an infinite recursion of the single step interrupt. The TF is set in the flags on the stack so another interrupt will comes after one more instruction is executed after the return of the interrupt.

The following example is a very elementary debugger using the trap flag and the single step interrupt.

Example 10.1

```
001      ; single stepping using the trap flag and single step interrupt
002      [org 0x0100]
003                   jmp start
004
005      flag:        db   0                  ; flag whether a key pressed
006      oldisr:      dd   0                  ; space for saving old ISR
007      names:       db   'FL =CS =IP =BP =AX =BX =CX =DX =SI =DI =DS =ES ='
008
009-026  ;;;;; COPY LINES 008-025 FROM EXAMPLE 6.2 (clrscr) ;;;;;
027
028      ; subroutine to print a number on screen
029      ; takes the row no, column no, and number to be printed as parameters
030      printnum:    push bp
031                   mov  bp, sp
032                   push es
033                   push ax
034                   push bx
035                   push cx
```

```
036                 push dx
037                 push di
038
039                 mov  di, 80             ; load di with columns per row
040                 mov  ax, [bp+8]         ; load ax with row number
041                 mul  di                 ; multiply with columns per row
042                 mov  di, ax             ; save result in di
043                 add  di, [bp+6]         ; add column number
044                 shl  di, 1              ; turn into byte count
045                 add  di, 8              ; to end of number location
046
047                 mov  ax, 0xb800
048                 mov  es, ax             ; point es to video base
049                 mov  ax, [bp+4]         ; load number in ax
050                 mov  bx, 16             ; use base 16 for division
051                 mov  cx, 4              ; initialize count of digits
052
053     nextdigit:  mov  dx, 0              ; zero upper half of dividend
054                 div  bx                 ; divide by 10
055                 add  dl, 0x30           ; convert digit into ascii value
056                 cmp  dl, 0x39           ; is the digit an alphabet
057                 jbe  skipalpha          ; no, skip addition
058                 add  dl, 7              ; yes, make in alphabet code
059     skipalpha:  mov  dh, 0x07           ; attach normal attribute
060                 mov [es:di], dx         ; print char on screen
061                 sub  di, 2              ; to previous screen location
062                 loop nextdigit          ; if no divide it again
063
064                 pop  di
065                 pop  dx
066                 pop  cx
067                 pop  bx
068                 pop  ax
069                 pop  es
070                 pop  bp
071                 ret  6
072
073     ; subroutine to print a string
074     ; takes row no, column no, address of string, and its length
075     ; as parameters
076     printstr:   push bp
077                 mov bp, sp
078                 push es
079                 push ax
080                 push bx
081                 push cx
082                 push dx
083                 push si
084                 push di
085
086                 mov  ax, 0xb800
087                 mov  es, ax             ; point es to video base
088
089                 mov  di, 80             ; load di with columns per row
090                 mov  ax, [bp+10]        ; load ax with row number
091                 mul  di                 ; multiply with columns per row
092                 mov  di, ax             ; save result in di
093                 add  di, [bp+8]         ; add column number
094                 shl  di, 1              ; turn into byte count
095
096                 mov  si, [bp+6]         ; string to be printed
097                 mov  cx, [bp+4]         ; length of string
098                 mov  ah, 0x07           ; normal attribute is fixed
099
100     nextchar:   mov  al, [si]           ; load next char of string
101                 mov  [es:di], ax        ; show next char on screen
102                 add  di, 2              ; move to next screen location
103                 add  si, 1              ; move to next char
104                 loop nextchar           ; repeat the operation cx times
105
106                 pop  di
107                 pop  si
108                 pop  dx
109                 pop  cx
110                 pop  bx
111                 pop  ax
```

```
112                 pop  es
113                 pop  bp
114                 ret  8
115
116     ; keyboard interrupt service routine
117     kbisr:      push ax
118
119                 in   al, 0x60           ; read a char from keyboard port
120                 test al, 0x80           ; is it a press code
121                 jnz  skipflag           ; no, leave the interrupt
123                 add  byte [cs:flag], al ; yes, set flag to proceed
124
125     skipflag:   mov  al, 0x20
126                 out  0x20, al
127                 pop  ax
128                 iret
129
130     ; single step interrupt service routine
131     trapisr:    push bp
132                 mov bp, sp              ; to read cs, ip and flags
133                 push ax
134                 push bx
135                 push cx
136                 push dx
137                 push si
138                 push di
139                 push ds
140                 push es
141
142                 sti                     ; waiting for keyboard interrupt
143                 push cs
144                 pop  ds                 ; initialize ds to data segment
145
146                 mov  byte [flag], 0     ; set flag to wait for key
147                 call clrscr             ; clear the screen
148
149                 mov  si, 6              ; first register is at bp+6
150                 mov  cx, 12             ; total 12 registers to print
151                 mov  ax, 0              ; start from row 0
152                 mov  bx, 5              ; print at column 5
153
154     l3:         push ax                 ; row number
155                 push bx                 ; column number
156                 mov  dx, [bp+si]
157                 push dx                 ; number to be printed
158                 call printnum           ; print the number
159                 sub  si, 2              ; point to next register
160                 inc  ax                 ; next row number
161                 loop l3                 ; repeat for the 12 registers
162
163                 mov  ax, 0              ; start from row 0
164                 mov  bx, 0              ; start from column 0
165                 mov  cx, 12             ; total 12 register names
166                 mov  si, 4              ; each name length is 4 chars
167                 mov  dx, names          ; offset of first name in dx
168
169     l1:         push ax                 ; row number
170                 push bx                 ; column number
171                 push dx                 ; offset of string
172                 push si                 ; length of string
173                 call printstr           ; print the string
174                 add  dx, 4              ; point to start of next string
175                 inc  ax                 ; new row number
176                 loop l1                 ; repeat for 12 register names
177
178     keywait:    cmp  byte [flag], 0     ; has a key been pressed
179                 je   keywait            ; no, check again
180
181                 pop  es
182                 pop  ds
183                 pop  di
184                 pop  si
185                 pop  dx
186                 pop  cx
187                 pop  bx
188                 pop  ax
```

```
189                 pop  bp
190                 iret
191
192     start:      xor  ax, ax
193                 mov  es, ax             ; point es to IVT base
194                 mov ax, [es:9*4]
195                 mov [oldisr], ax        ; save offset of old routine
196                 mov ax, [es:9*4+2]
197                 mov [oldisr+2], ax      ; save segment of old routine
198                 mov word [es:1*4], trapisr ; store offset at n*4
199                 mov [es:1*4+2], cs      ; store segment at n*4+2
200                 cli                     ; disable interrupts
201                 mov  word [es:9*4], kbisr ; store offset at n*4
202                 mov  [es:9*4+2], cs     ; store segment at n*4+2
203                 sti                     ; enable interrupts
204
205                 pushf                   ; save flags on stack
206                 pop  ax                 ; copy flags in ax
207                 or   ax, 0x100          ; set bit corresponding to TF
208                 push ax                 ; save ax on stack
209                 popf                    ; reload into flags register
210
211     ; the trap flag bit is on now, INT 1 will come after next instruction
212     ; sample code to check the working of our elementary debugger
213                 mov  ax, 0
214                 mov  bx, 0x10
215                 mov  cx, 0x20
216                 mov  dx, 0x40
217
218     l2:         inc  ax
219                 add  bx, 2
220                 dec  cx
221                 sub  dx, 2
222                 jmp  l2
```

10.2. DEBUGGER USING BREAKPOINT INTERRUPT

We now write a debugger using INT 3. This debugger stops at the same point every time where the breakpoint has been set up unlike the previous one which stopped at every instruction. The single step interrupt in this example is used only to restore the breakpoint interrupt which was removed by the breakpoint interrupt handler temporarily so that the original instruction can be executed.

Example 10.2

```
001     ; elementary debugger using breakpoint interrupt
002     [org 0x0100]
003                 jmp start
004
005     flag:       db   0                  ; flag whether a key pressed
006     oldisr:     dd   0                  ; space for saving old ISR
007     names:      db   'FL =CS =IP =BP =AX =BX =CX =DX =SI =DI =DS =ES ='
008     opcode:     db 0
009     opcodepos:  dw 0
010
011-028 ;;;;; COPY LINES 008-025 FROM EXAMPLE 6.2 (clrscr) ;;;;;
029-072 ;;;;; COPY LINES 028-071 FROM EXAMPLE 10.1 (printnum) ;;;;;
073-114 ;;;;; COPY LINES 073-114 FROM EXAMPLE 10.1 (printstr) ;;;;;
115-127 ;;;;; COPY LINES 116-128 FROM EXAMPLE 10.1 (kbisr) ;;;;;
128
129     ; single step interrupt service routine
130     trapisr:    push bp
131                 mov  bp, sp
132                 push ax
133                 push di
134                 push ds
135                 push es
136
137                 push cs
138                 pop  ds                 ; initialize ds to data segment
```

```
139
140                 mov  ax, [bp+4]
141                 mov  es, ax             ; load interrupted segment in es
142                 mov  di, [opcodepos]    ; load saved opcode position
143                 mov  byte [es:di], 0xCC ; reset the opcode to INT3
144                 and  word [bp+6], 0xFEFF; clear TF in flags on stack
145
146                 pop  es
147                 pop  ds
148                 pop  di
149                 pop  ax
150                 pop  bp
151                 iret
152
153     ; breakpoint interrupt service routine
154     debugisr:   push bp
155                 mov  bp, sp             ; to read cs, ip and flags
156                 push ax
157                 push bx
158                 push cx
159                 push dx
160                 push si
161                 push di
162                 push ds
163                 push es
164
165                 sti                     ; waiting for keyboard interrupt
166                 push cs
167                 pop  ds                 ; initialize ds to data segment
168
169                 mov  ax, [bp+4]
170                 mov  es, ax             ; load interrupted segment in es
171                 dec  word [bp+2]        ; decrement the return address
172                 mov  di, [bp+2]         ; read the return address in di
173                 mov  word [opcodepos], di ; remember the return position
174                 mov  al, [opcode]       ; load the original opcode
175                 mov  [es:di], al        ; restore original opcode there
176
177                 mov  byte [flag], 0     ; set flag to wait for key
178                 call clrscr             ; clear the screen
179
180                 mov  si, 6              ; first register is at bp+6
181                 mov  cx, 12             ; total 12 registers to print
182                 mov  ax, 0              ; start from row 0
183                 mov  bx, 5              ; print at column 5
184
185     l3:         push ax                 ; row number
186                 push bx                 ; column number
187                 mov  dx, [bp+si]
188                 push dx                 ; number to be printed
189                 call printnum           ; print the number
190                 sub  si, 2              ; point to next register
191                 inc  ax                 ; next row number
192                 loop l3                 ; repeat for the 12 registers
193
194                 mov  ax, 0              ; start from row 0
195                 mov  bx, 0              ; start from column 0
196                 mov  cx, 12             ; total 12 register names
197                 mov  si, 4              ; each name length is 4 chars
198                 mov  dx, names          ; offset of first name in dx
199
200     l1:         push ax                 ; row number
201                 push bx                 ; column number
202                 push dx                 ; offset of string
203                 push si                 ; length of string
204                 call printstr           ; print the string
205                 add  dx, 4              ; point to start of next string
206                 inc  ax                 ; new row number
207                 loop l1                 ; repeat for 12 register names
208
209                 or word [bp+6], 0x0100  ; set TF in flags image on stack
210
211     keywait:    cmp  byte [flag], 0     ; has a key been pressed
212                 je   keywait            ; no, check again
213
214                 pop es
```

```
215                 pop ds
216                 pop di
217                 pop si
218                 pop dx
219                 pop cx
220                 pop bx
221                 pop ax
222                 pop bp
223                 iret
224
225     start:      xor  ax, ax
226                 mov  es, ax             ; point es to IVT base
227                 mov  word [es:1*4], trapisr ; store offset at n*4
228                 mov  [es:1*4+2], cs     ; store segment at n*4+2
229                 mov  word [es:3*4], debugisr ; store offset at n*4
230                 mov  [es:3*4+2], cs     ; store segment at n*4+2
231                 cli                     ; disable interrupts
232                 mov  word [es:9*4], kbisr ; store offset at n*4
233                 mov  [es:9*4+2], cs     ; store segment at n*4+2
234                 sti                     ; enable interrupts
235
236                 mov si, l2              ; load breakpoint position in si
237                 mov al, [cs:si]         ; read opcode at that position
238                 mov [opcode], al        ; save opcode for later use
239                 mov byte [cs:si], 0xCC  ; change opcode to INT3
240
241     ; breakpoint is set now, INT3 will come at l2 on every iteration
242     ; sample code to check the working of our elementary debugger
243                 mov ax, 0
244                 mov bx, 0x10
245                 mov cx, 0x20
246                 mov dx, 0x40
247
248     l2:         inc ax
249                 add bx, 2
250                 dec cx
251                 sub dx, 2
252                 jmp l2
```

11
Multitasking

11.1. CONCEPTS OF MULTITASKING

To experience the power of assembly language we introduce how to implement multitasking. We observed in the debugger that our thread of instructions was broken by the debugger; it got the control, used all registers, displayed an elaborate interface, waited for the key, and then restored processor state to what was immediately before interruption. Our program resumed as if nothing happened. The program execution was in the same logical flow.

If we have two different programs A and B. Program A is broken, its state saved, and returned to B instead of A. By looking at the instruction set, we can immediately say that nothing can stop us from doing that. IRET will return to whatever CS and IP it finds on the stack. Now B is interrupted somehow, its state saved, and we return back to A. A will have no way of knowing that it was interrupted as its entire environment has been restored. It never knew the debugger took control when it was debugged. It sill has no way of gaining this knowledge. If this work of breaking and restoring programs is done at high speed the user will feel that all the programs are running at the same time where actually they are being switched to and forth at high speed.

In essence multitasking is simple, even though we have to be extremely careful when implementing it. The environment of a program in the very simple case is all its registers and stack. We will deal with stack later. Now to get control from the program without the program knowing about it, we can use the IRQ 0 highest priority interrupt that is periodically coming to the processor.

Now we present a very basic example of multitasking. We have two subroutines written in assembly language. All the techniques discussed here are applicable to code written in higher level languages as well. However the code to control this multitasking cannot be easily written in a higher level language so we write it in assembly language. The two subroutines rotate bars by changing characters at the two corners of the screen and have infinite loops. By hooking the timer interrupt and saving and restoring the registers of the tasks one by one, it appears that both tasks are running simultaneously.

Example 11.1

```
001     ; elementary multitasking of two threads
002     [org 0x0100]
003                   jmp start
004
005                   ;   ax,bx,ip,cs,flags storage area
006     taskstates:   dw   0, 0, 0, 0, 0      ; task0 regs
007                   dw   0, 0, 0, 0, 0      ; task1 regs
008                   dw   0, 0, 0, 0, 0      ; task2 regs
009
010     current:      db   0                  ; index of current task
011     chars:        db   '\|/-'             ; shapes to form a bar
012
013     ; one task to be multitasked
014     taskone:      mov  al, [chars+bx]     ; read the next shape
015                   mov  [es:0], al         ; write at top left of screen
```

```
016                 inc  bx                ; increment to next shape
017                 and  bx, 3             ; taking modulus by 4
018                 jmp  taskone           ; infinite task
019
020     ; second task to be multitasked
021     tasktwo:    mov  al, [chars+bx]    ; read the next shape
022                 mov  [es:158], al      ; write at top right of screen
023                 inc  bx                ; increment to next shape
024                 and  bx, 3             ; taking modulus by 4
025                 jmp  tasktwo           ; infinite task
026
027     ; timer interrupt service routine
028     timer:      push ax
029                 push bx
030
031                 mov  bl, [cs:current]  ; read index of current task
032                 mov  ax, 10            ; space used by one task
033                 mul  bl                ; multiply to get start of task
034                 mov  bx, ax            ; load start of task in bx
035
036                 pop  ax                ; read original value of bx
037                 mov  [cs:taskstates+bx+2], ax ; space for current task
038                 pop  ax                ; read original value of ax
039                 mov  [cs:taskstates+bx+0], ax ; space for current task
040                 pop  ax                ; read original value of ip
041                 mov  [cs:taskstates+bx+4], ax ; space for current task
042                 pop  ax                ; read original value of cs
043                 mov  [cs:taskstates+bx+6], ax ; space for current task
044                 pop  ax                ; read original value of flags
045                 mov  [cs:taskstates+bx+8], ax ; space for current task
046
047                 inc  byte [cs:current]  ; update current task index
048                 cmp  byte [cs:current], 3 ; is task index out of range
049                 jne  skipreset         ; no, proceed
050                 mov  byte [cs:current], 0 ; yes, reset to task 0
051
052     skipreset:  mov  bl, [cs:current]  ; read index of current task
053                 mov  ax, 10            ; space used by one task
054                 mul  bl                ; multiply to get start of task
055                 mov  bx, ax            ; load start of task in bx
056
057                 mov  al, 0x20
058                 out  0x20, al          ; send EOI to PIC
059
060                 push word [cs:taskstates+bx+8] ; flags of new task
061                 push word [cs:taskstates+bx+6] ; cs of new task
062                 push word [cs:taskstates+bx+4] ; ip of new task
063                 mov  ax, [cs:taskstates+bx+0]  ; ax of new task
064                 mov  bx, [cs:taskstates+bx+2]  ; bx of new task
065                 iret                   ; return to new task
066
067     start:      mov  word [taskstates+10+4], taskone ; initialize ip
068                 mov  [taskstates+10+6], cs     ; initialize cs
069                 mov  word [taskstates+10+8], 0x0200 ; initialize flags
070                 mov  word [taskstates+20+4], tasktwo ; initialize ip
071                 mov  [taskstates+20+6], cs     ; initialize cs
072                 mov  word [taskstates+20+8], 0x0200 ; initialize flags
073                 mov  word [current], 0         ; set current task index
074
075                 xor  ax, ax
076                 mov  es, ax                ; point es to IVT base
077                 cli
078                 mov  word [es:8*4], timer
079                 mov  [es:8*4+2], cs        ; hook timer interrupt
080                 mov  ax, 0xb800
081                 mov  es, ax                ; point es to video base
082                 xor  bx, bx                ; initialize bx for tasks
083                 sti
084
085                 jmp $                      ; infinite loop
```

The space where all registers of a task are stored is called the process control block or PCB. Actual PCB contains a few more things that are not

relevant to us now. INT 08 that is saving and restoring the registers is called the scheduler and the whole event is called a context switch.

11.2. ELABORATE MULTITASKING

In our next example we will save all 14 registers and the stack as well. 28 bytes are needed by these registers in the PCB. We add some more space to make the size 32, a power of 2 for easy calculations. One of these words is used to form a linked list of the PCBs so that strict ordering of active PCBs is not necessary. Also in this example we have given every thread its own stack. Now threads can have function calls, parameters and local variables etc. Another important change in this example is that the creation of threads is now dynamic. The thread registration code initializes the PCB, and adds it to the linked list so that the scheduler will give it a turn.

Example 11.2

```
001     ; multitasking and dynamic thread registration
002     [org 0x0100]
003                 jmp start
004
005     ; PCB layout:
006     ; ax,bx,cx,dx,si,di,bp,sp,ip,cs,ds,ss,es,flags,next,dummy
007     ;  0, 2, 4, 6, 8,10,12,14,16,18,20,22,24,  26 , 28 ,  30
008
009     pcb:            times 32*16 dw 0        ; space for 32 PCBs
010     stack:          times 32*256 dw 0       ; space for 32 512 byte stacks
011     nextpcb:        dw   1                  ; index of next free pcb
012     current:        dw   0                  ; index of current pcb
013     lineno:         dw   0                  ; line number for next thread
014-057
058     ;;;;; COPY LINES 028-071 FROM EXAMPLE 10.1 (printnum) ;;;;;
059
060     ; mytask subroutine to be run as a thread
061     ; takes line number as parameter
062     mytask:         push bp
063                     mov  bp, sp
064                     sub  sp, 2              ; thread local variable
065                     push ax
066                     push bx
067
068                     mov  ax, [bp+4]         ; load line number parameter
069                     mov  bx, 70             ; use column number 70
070                     mov  word [bp-2], 0     ; initialize local variable
071
072     printagain:     push ax                 ; line number
073                     push bx                 ; column number
074                     push word [bp-2]        ; number to be printed
075                     call printnum           ; print the number
076                     inc  word [bp-2]        ; increment the local variable
077                     jmp  printagain         ; infinitely print
078
079                     pop  bx
080                     pop  ax
081                     mov  sp, bp
082                     pop  bp
083                     ret
084
085     ; subroutine to register a new thread
086     ; takes the segment, offset, of the thread routine and a parameter
087     ; for the target thread subroutine
088     initpcb:        push bp
089                     mov  bp, sp
090                     push ax
091                     push bx
092                     push cx
093                     push si
094
095                     mov  bx, [nextpcb]      ; read next available pcb index
096                     cmp  bx, 32             ; are all PCBs used
097                     je   exit               ; yes, exit
098
```

```
099                 mov  cl, 5
100                 shl  bx, cl             ; multiply by 32 for pcb start
101
102                 mov  ax, [bp+8]         ; read segment parameter
103                 mov  [pcb+bx+18], ax    ; save in pcb space for cs
104                 mov  ax, [bp+6]         ; read offset parameter
105                 mov  [pcb+bx+16], ax    ; save in pcb space for ip
106
107                 mov  [pcb+bx+22], ds    ; set stack to our segment
108                 mov  si, [nextpcb]      ; read this pcb index
109                 mov  cl, 9
110                 shl  si, cl             ; multiply by 512
111                 add  si, 256*2+stack    ; end of stack for this thread
112                 mov  ax, [bp+4]         ; read parameter for subroutine
113                 sub  si, 2              ; decrement thread stack pointer
114                 mov  [si], ax           ; pushing param on thread stack
115                 sub  si, 2              ; space for return address
116                 mov  [pcb+bx+14], si    ; save si in pcb space for sp
117
118                 mov  word [pcb+bx+26], 0x0200 ; initialize thread flags
119                 mov  ax, [pcb+28]       ; read next of 0th thread in ax
120                 mov  [pcb+bx+28], ax    ; set as next of new thread
121                 mov  ax, [nextpcb]      ; read new thread index
123                 mov  [pcb+28], ax       ; set as next of 0th thread
124                 inc  word [nextpcb]     ; this pcb is now used
125
126     exit:       pop  si
127                 pop  cx
128                 pop  bx
129                 pop  ax
130                 pop  bp
131                 ret  6
132
133     ; timer interrupt service routine
134     timer:      push ds
135                 push bx
136
137                 push cs
138                 pop  ds                 ; initialize ds to data segment
139
140                 mov  bx, [current]      ; read index of current in bx
141                 shl  bx, 1
142                 shl  bx, 1
143                 shl  bx, 1
144                 shl  bx, 1
145                 shl  bx, 1              ; multiply by 32 for pcb start
146                 mov  [pcb+bx+0], ax     ; save ax in current pcb
147                 mov  [pcb+bx+4], cx     ; save cx in current pcb
148                 mov  [pcb+bx+6], dx     ; save dx in current pcb
149                 mov  [pcb+bx+8], si     ; save si in current pcb
150                 mov  [pcb+bx+10], di    ; save di in current pcb
151                 mov  [pcb+bx+12], bp    ; save bp in current pcb
152                 mov  [pcb+bx+24], es    ; save es in current pcb
153
154                 pop  ax                 ; read original bx from stack
155                 mov  [pcb+bx+2], ax     ; save bx in current pcb
156                 pop  ax                 ; read original ds from stack
157                 mov  [pcb+bx+20], ax    ; save ds in current pcb
158                 pop  ax                 ; read original ip from stack
159                 mov  [pcb+bx+16], ax    ; save ip in current pcb
160                 pop  ax                 ; read original cs from stack
161                 mov  [pcb+bx+18], ax    ; save cs in current pcb
162                 pop  ax                 ; read original flags from stack
163                 mov  [pcb+bx+26], ax    ; save cs in current pcb
164                 mov  [pcb+bx+22], ss    ; save ss in current pcb
165                 mov  [pcb+bx+14], sp    ; save sp in current pcb
166
167                 mov  bx, [pcb+bx+28]    ; read next pcb of this pcb
168                 mov  [current], bx      ; update current to new pcb
169                 mov  cl, 5
170                 shl  bx, cl             ; multiply by 32 for pcb start
171
172                 mov  cx, [pcb+bx+4]     ; read cx of new process
173                 mov  dx, [pcb+bx+6]     ; read dx of new process
174                 mov  si, [pcb+bx+8]     ; read si of new process
175                 mov  di, [pcb+bx+10]    ; read diof new process
```

```
176                 mov  bp, [pcb+bx+12]    ; read bp of new process
177                 mov  es, [pcb+bx+24]    ; read es of new process
178                 mov  ss, [pcb+bx+22]    ; read ss of new process
179                 mov  sp, [pcb+bx+14]    ; read sp of new process
180
181                 push word [pcb+bx+26]   ; push flags of new process
182                 push word [pcb+bx+18]   ; push cs of new process
183                 push word [pcb+bx+16]   ; push ip of new process
184                 push word [pcb+bx+20]   ; push ds of new process
185
186                 mov  al, 0x20
187                 out  0x20, al           ; send EOI to PIC
188
189                 mov  ax, [pcb+bx+0]     ; read ax of new process
190                 mov  bx, [pcb+bx+2]     ; read bx of new process
191                 pop  ds                 ; read ds of new process
192                 iret                    ; return to new process
193
194     start:      xor  ax, ax
195                 mov  es, ax             ; point es to IVT base
196
197                 cli
198                 mov  word [es:8*4], timer
199                 mov  [es:8*4+2], cs     ; hook timer interrupt
200                 sti
201
202     nextkey:    xor ah, ah              ; service 0 – get keystroke
203                 int 0x16                ; bios keyboard services
204
205                 push cs                 ; use current code segment
206                 mov  ax, mytask
207                 push ax                 ; use mytask as offset
208                 push word [lineno]      ; thread parameter
209                 call initpcb            ; register the thread
210
211                 inc  word [lineno]      ; update line number
212                 jmp  nextkey            ; wait for next keypress
```

When the program is executed the threads display the numbers independently. However as keys are pressed and new threads are registered, there is an obvious slowdown in the speed of multitasking. To improve that, we can change the timer interrupt frequency. The following can be used to set to an approximately 1ms interval.

```
mov  ax, 1100
out  0x40, al
mov  al, ah
out  0x40, al
```

This makes the threads look faster. However the only real change is that the timer interrupt is now coming more frequently.

11.3. MULTITASKING KERNEL AS TSR

The above examples had the multitasking code and the multitasked code in one program. Now we separate the multitasking kernel into a TSR so that it becomes an operation system extension. We hook a software interrupt for the purpose of registering a new thread.

Example 11.3

```
001     ; multitasking kernel as a TSR
002     [org 0x0100]
003                 jmp start
004
005     ; PCB layout:
006     ; ax,bx,cx,dx,si,di,bp,sp,ip,cs,ds,ss,es,flags,next,dummy
007     ;  0, 2, 4, 6, 8,10,12,14,16,18,20,22,24,  26 , 28 ,  30
008
009     pcb:        times 32*16 dw 0        ; space for 32 PCBs
```

```
010     stack:        times 32*256 dw 0       ; space for 32 512 byte stacks
011     nextpcb:      dw   1                  ; index of next free pcb
012     current:      dw   0                  ; index of current pcb
013
014-073 ;;;;; COPY LINES 133-192 FROM EXAMPLE 11.2 (timer) ;;;;;
074
075     ; software interrupt to register a new thread
076     ; takes parameter block in ds:si
077     ; parameter block has cs, ip, ds, es, and param in this order
078     initpcb:      push ax
079                   push bx
080                   push cx
081                   push di
082
083                   mov  bx, [cs:nextpcb]   ; read next available pcb index
084                   cmp  bx, 32             ; are all PCBs used
085                   je   exit               ; yes, exit
086
087                   mov  cl, 5
088                   shl  bx, cl             ; multiply by 32 for pcb start
089
090                   mov  ax, [si+0]         ; read code segment parameter
091                   mov  [cs:pcb+bx+18], ax ; save in pcb space for cs
092                   mov  ax, [si+2]         ; read offset parameter
093                   mov  [cs:pcb+bx+16], ax ; save in pcb space for ip
094                   mov  ax, [si+4]         ; read data segment parameter
095                   mov  [cs:pcb+bx+20], ax ; save in pcb space for ds
096                   mov  ax, [si+6]         ; read extra segment parameter
097                   mov  [cs:pcb+bx+24], ax ; save in pcb space for es
098
099                   mov  [cs:pcb+bx+22], cs ; set stack to our segment
100                   mov  di, [cs:nextpcb]   ; read this pcb index
101                   mov  cl, 9
102                   shl  di, cl             ; multiply by 512
103                   add  di, 256*2+stack    ; end of stack for this thread
104                   mov  ax, [si+8]         ; read parameter for subroutine
105                   sub  di, 2              ; decrement thread stack pointer
106                   mov  [cs:di], ax        ; pushing param on thread stack
107                   sub  di, 4              ; space for far return address
108                   mov  [cs:pcb+bx+14], di ; save di in pcb space for sp
109
110                   mov  word [cs:pcb+bx+26], 0x0200 ; initialize flags
111                   mov  ax, [cs:pcb+28]    ; read next of 0th thread in ax
112                   mov  [cs:pcb+bx+28], ax ; set as next of new thread
113                   mov  ax, [cs:nextpcb]   ; read new thread index
114                   mov  [cs:pcb+28], ax    ; set as next of 0th thread
115                   inc  word [cs:nextpcb]  ; this pcb is now used
116
117     exit:         pop  di
118                   pop  cx
119                   pop  bx
120                   pop  ax
121                   iret
123
124     start:        xor ax, ax
125                   mov es, ax              ; point es to IVT base
126
127                   mov word [es:0x80*4], initpcb
128                   mov [es:0x80*4+2], cs   ; hook software int 80
129                   cli
130                   mov word [es:0x08*4], timer
131                   mov [es:0x08*4+2], cs   ; hook timer interrupt
132                   sti
133
134                   mov dx, start
135                   add dx, 15
136                   mov cl, 4
137                   shr dx, cl
138
139                   mov ax, 0x3100          ; terminate and stay resident
140                   int 0x21
```

The second part of our example is a simple program that has the threads to be registered with the multitasking kernel using its exported services.

Example 11.4

```
001      ; multitasking TSR caller
002      [org 0x0100]
003                  jmp start
004
005      ; parameter block layout:
006      ; cs,ip,ds,es,param
007      ;  0, 2, 4, 6,  8
008
009      paramblock:   times 5 dw 0            ; space for parameters
010      lineno:       dw   0                  ; line number for next thread
011
012-055  ;;;;; COPY LINES 028-071 FROM EXAMPLE 10.1 (printnum) ;;;;;
056
057      ; subroutine to be run as a thread
058      ; takes line number as parameter
059      mytask:       push bp
060                    mov  bp, sp
061                    sub  sp, 2             ; thread local variable
062                    push ax
063                    push bx
064
065                    mov  ax, [bp+4]        ; load line number parameter
066                    mov  bx, 70            ; use column number 70
067                    mov  word [bp-2], 0    ; initialize local variable
068
069      printagain:   push ax                ; line number
070                    push bx                ; column number
071                    push word [bp-2]       ; number to be printed
072                    call printnum          ; print the number
073                    inc  word [bp-2]       ; increment the local variable
074                    jmp  printagain        ; infinitely print
075
076                    pop  bx
077                    pop  ax
078                    mov  sp, bp
079                    pop  bp
080                    retf
081
082      start:        mov  ah, 0             ; service 0 – get keystroke
083                    int  0x16              ; bios keyboard services
084
085                    mov  [paramblock+0], cs ; code segment parameter
086                    mov  word [paramblock+2], mytask ; offset parameter
087                    mov  [paramblock+4], ds ; data segment parameter
088                    mov  [paramblock+6], es ; extra segment parameter
089                    mov  ax, [lineno]
090                    mov  [paramblock+8], ax ; parameter for thread
091                    mov  si, paramblock    ; address of param block in si
092                    int  0x80              ; multitasking kernel interrupt
093
094                    inc  word [lineno]     ; update line number
095                    jmp  start             ; wait for next key
```

We introduce yet another use of the multitasking kernel with this new example. In this example three different sort of routines are multitasked by the same kernel instead of repeatedly registering the same routine.

Example 11.5

```
001      ; another multitasking TSR caller
002      [org 0x0100]
003                  jmp start
004
005      ; parameter block layout:
006      ; cs,ip,ds,es,param
007      ;  0, 2, 4, 6,  8
008
009      paramblock:   times 5 dw 0            ; space for parameters
010      lineno:       dw   0                  ; line number for next thread
011      chars:        db '\|/-'               ; chracters for rotating bar
012      message:      db 'moving hello'       ; moving string
013      message2:     db '            '       ; to erase previous string
```

```
014     messagelen:   dw 12                   ; length of above strings
015
016-059 ;;;;; COPY LINES 028-071 FROM EXAMPLE 10.1 (printnum) ;;;;;
060-101 ;;;;; COPY LINES 073-114 FROM EXAMPLE 10.1 (printstr) ;;;;;
102
103     ; subroutine to run as first thread
104     mytask:       push bp
105                   mov  bp, sp
106                   sub  sp, 2              ; thread local variable
107                   push ax
108                   push bx
109
110                   xor  ax, ax             ; use line number 0
111                   mov  bx, 70             ; use column number 70
112                   mov  word [bp-2], 0     ; initialize local variable
113
114     printagain:   push ax                 ; line number
115                   push bx                 ; column number
116                   push word [bp-2]        ; number to be printed
117                   call printnum           ; print the number
118                   inc  word [bp-2]        ; increment the local variable
119                   jmp  printagain         ; infinitely print
120
121                   pop  bx
123                   pop  ax
124                   mov  sp, bp
125                   pop  bp
126                   retf
127
128     ; subroutine to run as second thread
129     mytask2:      push ax
130                   push bx
131                   push es
132
133                   mov  ax, 0xb800
134                   mov  es, ax             ; point es to video base
135                   xor  bx, bx             ; initialize to use first shape
136
137     rotateagain:  mov  al, [chars+bx]     ; read current shape
138                   mov  [es:40], al        ; print at specified place
139                   inc  bx                 ; update to next shape
140                   and  bx, 3              ; take modulus with 4
141                   jmp  rotateagain        ; repeat infinitely
142
143                   pop  es
144                   pop  bx
145                   pop  ax
146                   retf
147
148     ; subroutine to run as third thread
149     mytask3:      push bp
150                   mov  bp, sp
151                   sub  sp, 2              ; thread local variable
152                   push ax
153                   push bx
154                   push cx
155
156                   mov  word [bp-2], 0     ; initialize line number to 0
157
158     nextline:     push word [bp-2]        ; line number
159                   mov  bx, 50
160                   push bx                 ; column number 50
161                   mov  ax, message
162                   push ax                 ; offset of string
163                   push word [messagelen]  ; length of string
164                   call printstr           ; print the string
165
166                   mov  cx, 0x100
167     waithere:     push cx                 ; save outer loop counter
168                   mov  cx, 0xffff
169                   loop $                  ; repeat ffff times
170                   pop  cx                 ; restore outer loop counter
171                   loop waithere           ; repeat 0x100 times
172
173                   push word [bp-2]        ; line number
174                   mov  bx, 50             ; column number 50
```

```
175                 push bx
176                 mov  ax, message2
177                 push ax                 ; offset of blank string
178                 push word [messagelen]  ; length of string
179                 call printstr           ; print the string
180
181                 inc  word [bp-2]        ; update line number
182                 cmp  word [bp-2], 25    ; is this the last line
183                 jne  skipreset          ; no, proceed to draw
184                 mov  word [bp-2], 0     ; yes, reset line number to 0
185
186     skipreset:  jmp  nextline           ; proceed with next drawing
187
188                 pop  cx
189                 pop  bx
190                 pop  ax
191                 mov  sp, bp
192                 pop  bp
193                 retf
194
195     start:      mov  [paramblock+0], cs ; code segment parameter
196                 mov  word [paramblock+2], mytask ; offset parameter
197                 mov  [paramblock+4], ds ; data segment parameter
198                 mov  [paramblock+6], es ; extra segment parameter
199                 mov  word [paramblock+8], 0 ; parameter for thread
200                 mov  si, paramblock     ; address of param block in si
201                 int  0x80               ; multitasking kernel interrupt
202
203                 mov  [paramblock+0], cs ; code segment parameter
204                 mov  word [paramblock+2], mytask2 ; offset parameter
205                 mov  [paramblock+4], ds ; data segment parameter
206                 mov  [paramblock+6], es ; extra segment parameter
207                 mov  word [paramblock+8], 0 ; parameter for thread
208                 mov  si, paramblock     ; address of param block in si
209                 int  0x80               ; multitasking kernel interrupt
210
211                 mov  [paramblock+0], cs ; code segment parameter
212                 mov  word [paramblock+2], mytask3 ; offset parameter
213                 mov  [paramblock+4], ds ; data segment parameter
214                 mov  [paramblock+6], es ; extra segment parameter
215                 mov  word [paramblock+8], 0 ; parameter for thread
216                 mov  si, paramblock     ; address of param block in si
217                 int  0x80               ; multitasking kernel interrupt
218
219                 jmp $
```

EXERCISES

1. Change the multitasking kernel such that a new two byte variable is introduced in the PCB. This variable contains the number of turns this process should be given. For example if the first PCB contains 20 in this variable, the switch to second process should occur after 20 timer interrupts (approx one second at default speed) and similarly the switch from second to third process should occur after the number given in the second process's PCB.
2. Change the scheduler of the multitasking kernel to enque the current process index a ready queue, and dequeue the next process index from it, and assign it to current. Therefore the next field of the PCB is no longer used. Use queue functions from Exercise 5.XX.
3. Add a function in the multitasking kernel to fork the current process through a software interrupt. Fork should allocate a new PCB and copy values of all registers of the caller's PCB to the new PCB. It should allocate a stack and change SS, SP appropriately in the new PCB. It has to copy the caller's stack on the newly allocated stack. It will set AX in the new PCB to 0 and in the old PB to 1 so that both threads can identify which is the creator and which is the created process and can act accordingly.

4. Add a function in the multitasking kernel accessible via a software interrupt that allows the current process to terminate itself.
5. Create a queue in the multitasking kernel called kbQ. This queue initially empty will contain characters typed by the user. Hook the keyboard interrupt for getting user keys. Convert the scan code to ASCII if the key is from a-z or 0-9 and enque it in kbQ. Ignore all other scan codes. Write a function checkkey accessible via a software interrupt that returns the process in AX a value removed from the queue. It waits if there is no key in the queue. Be aware of enabling interrupts if you wait here.
6. Modify the multitasking kernel such that the initial process displays at the last line of the screen whatever is typed by the user and clears that line on enter. If the user types quit followed by enter restore everything to normal as it was before the multitasking kernel was there. If the user types start followed by enter, start one more rotating bar on the screen. The first rotating bar should appear in the upper left, the next in the second column, then third and so on. The bar color should be white. The user can type the commands ‘white’, ‘red’, and ‘green’ to change the color of new bars.

12
Video Services

12.1. BIOS VIDEO SERVICES

The Basic Input Output System (BIOS) provides services for video, keyboard, serial port, parallel port, time etc. The video services are exported via INT 10. We will discuss some very simple services. Video services are classified into two broad categories; graphics mode services and text mode services. In graphics mode a location in video memory corresponds to a dot on the screen. In text mode this relation is not straightforward. The video memory holds the ASCII of the character to be shown and the actual shape is read from a font definition stored elsewhere in memory. We first present a list of common video services used in text mode.

```
INT 10 - VIDEO - SET VIDEO MODE
AH = 00h
AL = desired video mode
```


Some common video modes include 40x25 text mode (mode 0), 80x25 text mode (mode 2), 80x50 text mode (mode 3), and 320x200 graphics mode (mode D).

```
INT 10 - VIDEO - SET TEXT-MODE CURSOR SHAPE
AH = 01h
CH = cursor start and options
CL = bottom scan line containing cursor (bits 0-4)
INT 10 - VIDEO - SET CURSOR POSITION
AH = 02h
BH = page number
    0-3 in modes 2&3
    0-7 in modes 0&1
    0 in graphics modes
DH = row (00h is top)
DL = column (00h is left)
INT 10 - VIDEO - SCROLL UP WINDOW
AH = 06h
AL = number of lines by which to scroll up (00h = clear entire window)
BH = attribute used to write blank lines at bottom of window
CH, CL = row, column of window's upper left corner
DH, DL = row, column of window's lower right corner
INT 10 - VIDEO - SCROLL DOWN WINDOW
AH = 07h
AL = number of lines by which to scroll down (00h=clear entire window)
BH = attribute used to write blank lines at top of window
CH, CL = row, column of window's upper left corner
DH, DL = row, column of window's lower right corner
INT 10 - VIDEO - WRITE CHARACTER AND ATTRIBUTE AT CURSOR POSITION
AH = 09h
AL = character to display
BH = page number
```

```
BL = attribute (text mode) or color (graphics mode)
CX = number of times to write character
INT 10 - VIDEO - WRITE CHARACTER ONLY AT CURSOR POSITION
AH = 0Ah
AL = character to display
BH = page number
BL = attribute (text mode) or color (graphics mode)
CX = number of times to write character
INT 10 - VIDEO - WRITE STRING
AH = 13h
AL = write mode
   bit 0: update cursor after writing
   bit 1: string contains alternating characters and attributes
   bits 2-7: reserved (0)
BH = page number
BL = attribute if string contains only characters
CX = number of characters in string
DH, DL = row, column at which to start writing
ES:BP -> string to write
```

Chargen Services

In our first example we will read the font definition in memory and change it to include a set of all on pixels in the last line showing an effect of underline on all character including space. An 8x16 font is stored in 16 bytes. A sample character and the corresponding 16 values stored in the font information are shown for the character 'A'. We start with two services from the chargen subset of video services that we are going to use.




```
INT 10 - VIDEO - GET FONT INFORMATION
AX = 1130h
BH = pointer specifier
Return:
ES:BP = specified pointer
CX = bytes/character of on-screen font
DL = highest character row on screen
INT 10 - TEXT-MODE CHARGEN
AX = 1110h
ES:BP -> user table
CX = count of patterns to store
DX = character offset into map 2 block
BL = block to load in map 2
BH = number of bytes per character pattern
```

We will use 6 as the pointer specifier which means the 8x16 font stored in ROM.

Example 12.1

```
001     ; put underlines on screen font
002     [org 0x0100]
003                 jmp  start
004
005     font:       times 256*16 db 0       ; space for font
006
007     start:      mov  ax, 0x1130         ; service 11/30 – get font info
008                 mov  bx, 0x0600         ; ROM 8x16 font
009                 int  0x10               ; bios video services
010
011                 mov  si, bp             ; point si to rom font data
012                 mov  di, font           ; point di to space for font
```

```
013                 mov  cx, 256*16         ; font size
014                 push ds
015                 push es
016                 pop  ds                 ; ds:si to rom font data
017                 pop  es                 ; es:di to space for font
018                 cld                     ; auto increment mode
019                 rep  movsb              ; copy font
020
021                 push cs
022                 pop  ds                 ; restore ds to data segment
023
024                 mov  si, font-1         ; point si before first char
025                 mov  cx, 0x100          ; total 256 characters
026     change:     add  si, 16             ; one character has 16 bytes
027                 mov  byte [si], 0xFF    ; change last line to all ones
028                 loop change             ; repeat for each character
029
030                 mov  bp, font           ; es:bp points to new font
031                 mov  bx, 0x1000         ; bytes per char & block number
032                 mov  cx, 0x100          ; number of characters to change
033                 xor  dx, dx             ; first character to change
034                 mov  ax, 0x1110         ; service 11/10 – load user font
035                 int  0x10               ; bios video services
036
037                 mov ax, 0x4c00          ; terminate program
038                 int 0x21
```

Our second example is similar to the last example however in this case we are doing something funny on the screen. We are reversing the shapes of all the characters on the screen.

Example 12.2

```
001     ; reverse each character of screen font
002     [org 0x0100]
003                 jmp  start
004
005     font:       times 256*16 db 0       ; space for font
006
007     start:      mov  ax, 0x1130         ; service 11/30 – get font info
008                 mov  bx, 0x0600         ; ROM 8x16 font
009                 int  0x10               ; bios video services
010
011                 mov  si, bp             ; point si to rom font data
012                 mov  di, font           ; point di to space for font
013                 mov  cx, 256*16         ; font size
014                 push ds
015                 push es
016                 pop  ds                 ; ds:si to rom font data
017                 pop  es                 ; es:di to space for font
018                 cld                     ; auto increment mode
019                 rep  movsb              ; copy font
020
021                 push cs
022                 pop  ds                 ; restore ds to data segment
023
024                 mov si, font            ; point si to start of font
025     change:     mov al, [si]            ; read one byte
026                 mov cx, 8
027     inner:      shl al, 1               ; shift left with MSB in carry
028                 rcr bl, 1               ; rotate right using carry
029                 loop inner              ; repeat eight times
030                 mov [si], bl            ; write back reversed byte
031                 inc si                  ; next byte of font
032                 cmp si, font+256*16     ; is whole font reversed
033                 jne change              ; no, reverse next byte
034
035                 mov  bp, font           ; es:bp points to new font
036                 mov  bx, 0x1000         ; bytes per char & block number
037                 mov  cx, 0x100          ; number of characters to change
038                 xor  dx, dx             ; first character to change
039                 mov  ax, 0x1110         ; service 11/10 – load user font
040                 int  0x10               ; bios video services
041
```

```
042                mov  ax, 0x4c00         ; terminate program
043                int  0x21
```

Graphics Mode Services

We will take an example of using graphics mode video services as well. We will draw a line across the screen using the following service.

INT 10 - VIDEO - WRITE GRAPHICS PIXEL
AH = 0Ch
BH = page number
AL = pixel color
CX = column
DX = row

Example 12.3

```
001      ; draw line in graphics mode
002      [org 0x0100]
003                mov  ax, 0x000D         ; set 320x200 graphics mode
004                int  0x10               ; bios video services
005
006                mov  ax, 0x0C07         ; put pixel in white color
007                xor  bx, bx             ; page number 0
008                mov  cx, 200            ; x position 200
009                mov  dx, 200            ; y position 200
010
011      l1:       int  0x10               ; bios video services
012                dec  dx                 ; decrease y position
013                loop l1                 ; decrease x position and repeat
014
015                mov  ah, 0              ; service 0 – get keystroke
016                int  0x16               ; bios keyboard services
017
018                mov  ax, 0x0003         ; 80x25 text mode
019                int  0x10               ; bios video services
020
021                mov  ax, 0x4c00         ; terminate program
022                int  0x21
```

12.2. DOS VIDEO SERVICES

Services of DOS are more cooked and at a higher level than BIOS. They provide less control but make routine tasks much easier. Some important DOS services are listed below.

INT 21 - READ CHARACTER FROM STANDARD INPUT, WITH ECHO
AH = 01h
Return: AL = character read
INT 21 - WRITE STRING TO STANDARD OUTPUT
AH = 09h
DS:DX -> $ terminated string
INT 21 - BUFFERED INPUT
AH = 0Ah
DS:DX -> dos input buffer

The DOS input buffer has a special format where the first byte stores the maximum characters buffer can hold, the second byte holds the number of characters actually read on return, and the following space is used for the actual characters read. We start will an example of reading a string with service 1 and displaying it with service 9.

Example 12.4

```
001     ; character input using dos services
002     [org 0x0100]
003                 jmp start
004
005     maxlength:    dw   80                ; maximum length of input
006     message:      db   10, 13, 'hello $' ; greetings message
007     buffer:       times 81 db 0          ; space for input string
008
009     start:        mov  cx, [maxlength]   ; load maximum length in cx
010                   mov  si, buffer        ; point si to start of buffer
011
012     nextchar:     mov  ah, 1             ; service 1 – read character
013                   int  0x21              ; dos services
014
015                   cmp  al, 13            ; is enter pressed
016                   je   exit              ; yes, leave input
017                   mov  [si], al          ; no, save this character
018                   inc  si                ; increment buffer pointer
019                   loop nextchar          ; repeat for next input char
020
021     exit:         mov  byte [si], '$'    ; append $ to user input
022
023                   mov  dx, message       ; greetings message
024                   mov  ah, 9             ; service 9 – write string
025                   int  0x21              ; dos services
026
027                   mov  dx, buffer        ; user input buffer
028                   mov  ah, 9             ; service 9 – write string
029                   int  0x21              ; dos services
030
031                   mov  ax, 0x4c00        ; terminate program
032                   int  0x21
```

Our next example uses the more cooked buffered input service of DOS and using the same service 9 to print the string.

Example 12.5

```
001     ; buffer input using dos services
002     [org 0x0100]
003                 jmp  start
004
005     message:      db   10,13,'hello ', 10, 13, '$'
006     buffer:       db   80                ; length of buffer
007                   db   0                 ; number of character on return
008                   times 80 db 0          ; actual buffer space
009
010     start:        mov  dx, buffer        ; input buffer
011                   mov  ah, 0x0A          ; service A – buffered input
012                   int  0x21              ; dos services
013
014                   mov  bh, 0
015                   mov  bl, [buffer+1]    ; read actual size in bx
016                   mov  byte [buffer+2+bx], '$' ; append $ to user input
017
018                   mov  dx, message       ; greetings message
019                   mov  ah, 9             ; service 9 – write string
020                   int  0x21              ; dos services
021
022                   mov  dx, buffer+2      ; user input buffer
023                   mov  ah, 9             ; service 9 – write string
024                   int  0x21              ; dos services
025
026                   mov  ax, 0x4c00        ; terminate program
027                   int  0x21
```


More detail of DOS and BIOS interrupts is available in the Ralf Brown Interrupt List.

13
Secondary Storage

13.1. PHYSICAL FORMATION

A floppy disk is a circular plate with a fine coating of magnetic material over it. The plate is enclosed in a plastic jacket which has a cover that can slide to expose the magnetic surface. The drive motor attaches itself to the central piece and rotates the plate. Two heads on both sides can read the magnetically encoded data on the disk.

If the head is fixed and the motor rotates the disk the readable area on the disk surface forms a circle called a track. Head moved to the next step forms another track and so on. In hard disks the same structure is extended to a larger number of tracks and plates. The tracks are further cut vertically into sectors. This is a logical division of the area on the tracks. Each sector holds 512 bytes of data. A standard floppy disk has 80 tracks and 18 sectors per track with two heads, one on each side totallying to 2880 sectors or 1440 KB of data. Hard disks have varying number of heads and tracks pertaining to their different capacities.



BIOS sees the disks as a combination of sectors, tracks, and heads, as a raw storage device without concern to whether it is reading a file or directory. BIOS provides the simplest and most powerful interface to the storage medium. However this raw storage is meaningless to the user who needs to store his files and organize them into directories. DOS builds a logical structure on this raw storage space to provide these abstractions. This logical formation is read and interpreted by DOS. If another file system is build on the same storage medium the interpretations change. Main units of the DOS structure are the boot sector in head 0, track 0, and sector 1, the first FAT starting from head 0, track 0, sector 2, the second copy of FAT starting from head 0, track 0, sector 11, and the root directory starting from head 1, track 0, sector 2. The area from head 0, track 1, sector 16 to head 1, track 79, sector 18 is used for storing the data of the files. Among this we will be exploring the directory structure further. The 32 sectors reserved for the root directory contain 512 directory entries. The format of a 32 byte directory entry is shown below.

```
+00 Filename (8 bytes)
+08 Extension (3 bytes)
+0B Flag Byte (1 byte)
+0C Reserved (1 byte)
+0D Creation Date/Time (5 bytes)
+12 Last Accessed Data (2 bytes)
+14 Starting Cluster High Word (2 bytes) for FAT32
+16 Time (2 bytes)
+18 Date (2 bytes)
+1A Starting Cluster Low Word (2 bytes)
+1C File Size (4 bytes)
```

13.2. STORAGE ACCESS USING BIOS

We will be using BIOS disk services to directly see the data stored in the directory entries by DOS. For this purpose we will be using the BIOS disk services.

```
INT 13 - DISK - RESET DISK SYSTEM
AH = 00h
DL = drive
Return:
CF = error flag
AH = error code
INT 13 - DISK - READ SECTOR(S) INTO MEMORY
AH = 02h
AL = number of sectors to read (must be nonzero)
CH = low eight bits of cylinder number
CL = sector number 1-63 (bits 0-5)
     high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)
ES:BX -> data buffer
Return:
CF = error flag
AH = error code
AL = number of sectors transferred
INT 13 - DISK - WRITE DISK SECTOR(S)
AH = 03h
AL = number of sectors to write (must be nonzero)
CH = low eight bits of cylinder number
CL = sector number 1-63 (bits 0-5)
     high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)
ES:BX -> data buffer
Return:
CF = error flag
AH = error code
AL = number of sectors transferred
INT 13 - DISK - GET DRIVE PARAMETERS
AH = 08h
DL = drive (bit 7 set for hard disk)
Return:
CF = error flag
AH = error code
CH = low eight bits of maximum cylinder number
CL = maximum sector number (bits 5-0)
```

```
     high two bits of maximum cylinder number (bits 7-6)
DH = maximum head number
DL = number of drives
ES:DI -> drive parameter table (floppies only)
```

Example 13.1

```
001     ; floppy directory using bios services
002     [org 0x0100]
003                 jmp  start
004
005     sector:     times 512 db 0          ; space for directory sector
006     entryname:  times 11 db 0           ; space for a file name
007                 db   10, 13, '$'        ; new line and terminating $
008
009     start:      mov  ah, 0              ; service 0 – reset disk system
010                 mov  dl, 0              ; drive A:
011                 int  0x13               ; bios disk services
012                 jc   error              ; if error, terminate program
013
014                 mov  ah, 2              ; service 2 – read sectors
015                 mov  al, 1              ; count of sectors
016                 mov  ch, 0              ; cyliner
017                 mov  cl, 2              ; sector
018                 mov  dh, 1              ; head
019                 mov  dl, 0              ; drive A:
020                 mov  bx, sector         ; buffer to read sector
021                 int  0x13               ; bios disk services
022                 jc   error              ; if error, terminate program
023
024                 mov  bx, 0              ; start from first entry
025     nextentry:  mov  di, entryname      ; point di to space for filename
026                 mov  si, sector         ; point si to sector
027                 add  si, bx             ; move ahead to desired entry
028                 mov  cx, 11             ; one filename is 11 bytes long
029                 cld                     ; auto increment mode
030                 rep  movsb              ; copy filename
031
032                 mov  ah, 9              ; service 9 – output string
033                 mov  dx, entryname      ; filename to be printed
034                 int  0x21               ; dos services
035
036                 add  bx, 32             ; point to next dir entry
037                 cmp  bx, 512            ; is last entry in this sector
038                 jne  nextentry          ; no, print next entry
039
040     error:      mov  ax, 0x4c00         ; terminate program
041                 int  0x21
```

With the given services and the bits allocated for heads, tracks, and sectors only 8GB disks can be accessed. This limitation can be overcome by using INT 13 extensions that take a linear 64bit sector number and handle all the head, track, sector conversion themselves. The important services in this category are listed below.

```
INT 13 - INT 13 Extensions - EXTENDED READ
AH = 42h
DL = drive number
DS:SI -> disk address packet
Return:
CF = error flag
AH = error code
     disk address packet's block count field set to number of blocks
     successfully transferred
INT 13 - INT 13 Extensions - EXTENDED WRITE
AH = 43h
AL = write flags
```

```
DL = drive number
DS:SI -> disk address packet
Return:
CF = error flag
AH = error code
     disk address packet's block count field set to number of blocks
     successfully transferred
```

The format of the disk address packet used above is as follows.

```
Offset  Size    Description
 00h    BYTE    size of packet = 10h
 01h    BYTE    reserved (0)
 02h    WORD    number of blocks to transfer
 04h    DWORD   -> transfer buffer
 08h    QWORD   starting absolute block number
```

Hard disks have a different formation from floppy disks in that there is a partition table at the start that allows several logical disks to be maintained within a single physical disk. The physical sector 0 holds the master boot record and a partition table towards the end. The first 446 bytes contain MBR, then there are 4 16 byte partition entries and then there is a 2 byte signature. A partition table entry has the following format.

```
Byte 0 – 0x80 for active 0x00 for inactive
Byte 1-3 – Starting CHS
Byte 4 – Partition Type
Byte 5-7 – Ending CHS
Byte 8-B – Starting LBA
Byte C-F – Size of Partition
```

Some important partition types are listed below.

```
00 Unused Entry
01 FAT12
05 Extended Partition
06 FAT16
0b FAT32
0c FAT32 LBA
0e FAT16 LBA
0f Extended LBA
07 NTFS
```

Extended partition type signals that the specified area is treated as a complete hard disk with its own partition table and partitions. Therefore extended partitions allow a recursion in partitioning and consequently an infinite number of partitions are possible. The following program reads the partition tables (primary and extended) using recursion and displays in an indented form all partitions present on the first hard disk in the system.

Example 13.2

```
001     ; a program to display the partition table
002     [org 0x0100]
003                 jmp  start
004
005     dap:        db   0x10, 0        ; disk address packet
006                 dw   1
007                 dd   0, 0, 0
```

```
008
009-026 msg:          times 17 db ' '
027                   db   10, 13, '$'
028     fat12:        db   'FAT12...$'
029     fat16:        db   'FAT16...$'
030     fat32:        db   'FAT32...$'
031     ntfs:         db   'NTFS....$'
032     extended:     db   'EXTEND..$'
033     unknown:      db   'UNKNOWN.$'
034
035     partypes:     dw   0x1, fat12     ; table of known partition types
036                   dw   0x5, extended
037                   dw   0x6, fat16
038                   dw   0xe, fat16
039                   dw   0xb, fat32
040                   dw   0xc, fat32
041                   dw   0x7, ntfs
042                   dw   0xf, extended
043                   dw   0x0, unknown
044
045     ; subroutine to print a number in a string as hex
046     ; takes address of string and a 16bit number as parameter
047     printnum:     push bp
048                   mov  bp, sp
049                   push ax
050                   push bx
051                   push cx
052                   push dx
053                   push di
054
055                   mov  di, [bp+6]          ; string to store the number
056                   add  di, 3
057
058                   mov  ax, [bp+4]          ; load number in ax
059                   mov  bx, 16              ; use base 16 for division
060                   mov  cx, 4
061
062     nextdigit:    mov  dx, 0
063                   div  bx                  ; divide by 16
064                   add  dl, 0x30            ; convert into ascii value
065                   cmp  dl, 0x39
066                   jbe  skipalpha
067
068                   add  dl, 7
069
070     skipalpha:    mov  [di], dl            ; update char in string
071                   dec  di
072                   loop nextdigit
073
074                   pop  di
075                   pop  dx
076                   pop  cx
077                   pop  bx
078                   pop  ax
079                   pop  bp
080                   ret  4
081
082     ; subroutine to print the start and end of a partition
083     ; takes the segment and offset of the partition table entry
084     printpart:    push bp
085                   mov  bp, sp
086                   push es
087                   push ax
088                   push di
089
090                   les  di, [bp+4]          ; point es:di to dap
091
092                   mov  ax, msg
093                   push ax
094                   push word [es:di+0xA]
095                   call printnum            ; print first half of start
096
097                   add  ax, 4
098                   push ax
099                   push word [es:di+0x8]
100                   call printnum            ; print second half of start
```

```
101
102                 add  ax, 5
103                 push ax
104                 push word [es:di+0xE]
105                 call printnum           ; print first half of end
106
107                 add  ax, 4
108                 push ax
109                 push word [es:di+0xC]
110                 call printnum           ; print second half of end
111
112                 mov  dx, msg
113                 mov  ah, 9
114                 int  0x21               ; print the whole on the screen
115
116                 pop  di
117                 pop  ax
118                 pop  es
119                 pop  bp
120                 ret  4
121
123     ; recursive subroutine to read the partition table
124     ; take indentation level and 32bit absolute block number as parameters
125     readpart:   push bp
126                 mov  bp, sp
127                 sub  sp, 512            ; local space to read sector
128                 push ax
129                 push bx
130                 push cx
131                 push dx
132                 push si
133
134                 mov  ax, bp
135                 sub  ax, 512
136                 mov  word [dap+4], ax   ; init dest offset in dap
137                 mov  [dap+6], ds        ; init dest segment in dap
138                 mov  ax, [bp+4]
139                 mov  [dap+0x8], ax      ; init sector no in dap
140                 mov  ax, [bp+6]
141                 mov  [dap+0xA], ax      ; init second half of sector no
142
143                 mov  ah, 0x42           ; read sector in LBA mode
144                 mov  dl, 0x80           ; first hard disk
145                 mov  si, dap            ; address of dap
146                 int  0x13               ; int 13
147
148                 jc   failed             ; if failed, leave
149
150                 mov  si, -66            ; start of partition info
151     nextpart:   mov  ax, [bp+4]         ; read relative sector number
152                 add  [bp+si+0x8], ax    ; make it absolute
153                 mov  ax, [bp+6]         ; read second half
154                 adc  [bp+si+0xA], ax    ; make seconf half absolute
155
156                 cmp  byte [bp+si+4], 0  ; is partition unused
157                 je   exit
158
159                 mov  bx, partypes       ; point to partition types
160                 mov  di, 0
161     nextmatch:  mov  ax, [bx+di]
162                 cmp  [bp+si+4], al      ; is this partition known
163                 je   found              ; yes, so print its name
164                 add  di, 4              ; no, try next entry in table
165                 cmp  di, 32             ; are all entries compared
166                 jne  nextmatch          ; no, try another
167
168     found:      mov  cx, [bp+8]         ; load indentation level
169                 jcxz noindent           ; skip if no indentation needed
170     indent:     mov  dl, ' '
171                 mov  ah, 2              ; display char service
172                 int  0x21               ; dos services
173                 loop indent             ; print required no of spaces
174
175     noindent:   add  di, 2
176                 mov  dx, [bx+di]        ; point to partition type name
177                 mov  ah, 9              ; print string service
```

```
178                 int  0x21               ; dos services
179
180                 push ss
181                 mov  ax, bp
182                 add  ax, si
183                 push ax                 ; pass partition entry address
184                 call printpart          ; print start and end from it
185
186                 cmp  byte [bp+si+4], 5  ; is it an extended partition
187                 je   recurse            ; yes, make a recursive call
188
189                 cmp  byte [bp+si+4], 0xf ; is it an extended partition
190                 jne  exit               ; yes, make a recursive call
191
192     recurse:    mov  ax, [bp+8]
193                 add  ax, 2              ; increase indentation level
194                 push ax
195                 push word [bp+si+0xA]   ; push partition type address
196                 push word [bp+si+0x8]
197                 call readpart           ; recursive call
198
199     exit:       add  si, 16             ; point to next partition entry
200                 cmp  si, -2             ; gone past last entry
201                 jne  nextpart           ; no, read this entry
202
203     failed:     pop  si
204                 pop  dx
205                 pop  bx
206                 pop  cx
207                 pop  ax
208                 mov  sp, bp
209                 pop  bp
210                 ret  6
211
212     start:      xor  ax, ax
213                 push ax                 ; start from zero indentation
214                 push ax                 ; main partition table at 0
215                 push ax
216                 call readpart           ; read and print it
217
218                 mov  ax, 0x4c00         ; terminate program
219                 int  0x21
```

13.3. STORAGE ACCESS USING DOS

BIOS provides raw access to the storage medium while DOS gives a more logical view and more cooked services. Everything is a file. A directory is a specially organized file that is interpreted by the operating system itself. A list of important DOS services for file manipulation is given below.

INT 21 - CREATE OR TRUNCATE FILE
AH = 3Ch
CX = file attributes
DS:DX -> ASCIZ filename
Return:
CF = error flag
AX = file handle or error code
INT 21 - OPEN EXISTING FILE
AH = 3Dh
AL = access and sharing modes
DS:DX -> ASCIZ filename
CL = attribute mask of files to look for (server call only)
Return:
CF = error flag
AX = file handle or error code
INT 21 - CLOSE FILE
AH = 3Eh

```
BX = file handle
Return:
CF = error flag
AX = error code
INT 21 - READ FROM FILE
AH = 3Fh
BX = file handle
CX = number of bytes to read
DS:DX -> buffer for data
Return:
CF = error flag
AX = number of bytes actually read or error code
INT 21 - WRITE TO FILE
AH = 40h
BX = file handle
CX = number of bytes to write
DS:DX -> data to write
Return:
CF = error flag
AX = number of bytes actually written or error code
INT 21 - DELETE FILE
AH = 41h
DS:DX -> ASCIZ filename (no wildcards, but see notes)
Return:
CF = error flag
AX = error code
INT 21 - SET CURRENT FILE POSITION
AH = 42h
AL = origin of move
BX = file handle
CX:DX = offset from origin of new file position
Return:
CF = error flag
DX:AX = new file position in bytes from start of file
AX = error code in case of error
INT 21 - GET FILE ATTRIBUTES
AX = 4300h
DS:DX -> ASCIZ filename
Return:
CF = error flag
CX = file attributes
AX = error code
INT 21 - SET FILE ATTRIBUTES
AX = 4301h
CX = new file attributes
DS:DX -> ASCIZ filename
Return:
CF = error flag
AX = error code
```

We will use some of these services to find that two files are same in contents or different. We will read the file names from the command prompt. The command string is passed to the program in the program segment prefix located at offset 0 in the current segment. The area from 0-7F contains information for DOS, while the command tail length is stored at 80. From 81 to FF, the actual command tail is stored terminated by a CR (Carriage Retrun).

Example 13.3

```
001     ; file comparison using dos services
002     [org 0x0100]
003                 jmp  start
004
005     filename1:    times 128 db 0          ; space for first filename
006     filename2:    times 128 db 0          ; space for second filename
007     handle1:      dw   0                  ; handle for first file
008     handle2:      dw   0                  ; handle for second file
009     buffer1:      times 4096 db 0         ; buffer for first file
010     buffer2:      times 4096 db 0         ; buffer for second file
011
012     format:       db   'Usage error: diff <filename1> <filename2>$'
013     openfailed:   db   'First file could not be opened$'
014     openfailed2:  db   'Second file could not be opened$'
015     readfailed:   db   'First file could not be read$'
016     readfailed2:  db   'Second file could not be read$'
017     different:    db   'Files are different$'
018     same:         db   'Files are same$'
019
020     start:        mov  ch, 0
021                   mov  cl, [0x80]         ; command tail length in cx
022                   dec  cx                 ; leave the first space
023                   mov  di, 0x82           ; start of command tail in di
024                   mov  al, 0x20           ; space for parameter separation
025                   cld                     ; auto increment mode
026                   repne scasb             ; search space
027                   je   param2             ; if found, proceed
028                   mov  dx, format         ; else, select error message
029                   jmp  error              ; proceed to error printing
030
031     param2:       push cx                 ; save original cx
032                   mov  si, 0x82           ; set si to start of param
033                   mov  cx, di             ; set di to end of param
034                   sub  cx, 0x82           ; find param size in cx
035                   dec  cx                 ; excluding the space
036                   mov  di, filename1      ; set di to space for filename 1
037                   rep  movsb              ; copy filename there
038                   mov  byte [di], 0       ; terminate filename with 0
039                   pop  cx                 ; restore original cx
040                   inc  si                 ; go to start of next filename
041                   mov  di, filename2      ; set di to space for filename 2
042                   rep  movsb              ; copy filename there
043                   mov  byte [di], 0       ; terminate filename with 0
044
045                   mov  ah, 0x3d           ; service 3d – open file
046                   mov  al, 0              ; readonly mode
047                   mov  dx, filename1      ; address of filename
048                   int  0x21               ; dos services
049                   jnc  open2              ; if no error, proceed
050                   mov  dx, openfailed     ; else, select error message
051                   jmp  error              ; proceed to error printing
052
053     open2:        mov [handle1], ax       ; save handle for first file
054                   mov  ah, 0x3d           ; service 3d – open file
055                   mov  al, 0              ; readonly mode
056                   mov  dx, filename2      ; address of filename
057                   int  0x21               ; dos services
058                   jnc  store2             ; if no error, proceed
059                   mov  dx, openfailed2    ; else, select error message
060                   jmp  error              ; proceed to error printing
061
062     store2:       mov  [handle2], ax      ; save handle for second file
063
064     readloop:     mov  ah, 0x3f           ; service 3f – read file
065                   mov  bx, [handle1]      ; handle for file to read
066                   mov  cx, 4096           ; number of bytes to read
067                   mov  dx, buffer1        ; buffer to read in
068                   int  0x21               ; dos services
069                   jnc  read2              ; if no error, proceed
070                   mov  dx, readfailed     ; else, select error message
071                   jmp  error              ; proceed to error printing
072
073     read2:        push ax                 ; save number of bytes read
074                   mov  ah, 0x3f           ; service 3f – read file
```

```
075                 mov  bx, [handle2]      ; handle for file to read
076                 mov  cx, 4096           ; number of bytes to read
077                 mov  dx, buffer2        ; buffer to read in
078                 int  0x21               ; dos services
079                 jnc  check              ; if no error, proceed
080                 mov  dx, readfailed2    ; else, select error message
081                 jmp  error              ; proceed to error printing
082
083     check:      pop  cx                 ; number of bytes read of file 1
084                 cmp  ax, cx             ; are number of byte same
085                 je   check2             ; yes, proceed to compare them
086                 mov  dx, different      ; no, files are different
087                 jmp  error              ; proceed to message printing
088
089     check2:     test ax, ax             ; are zero bytes read
090                 jnz  compare            ; no, compare them
091                 mov  dx, same           ; yes, files are same
092                 jmp  error              ; proceed to message printing
093
094     compare:    mov  si, buffer1        ; point si to file 1 buffer
095                 mov  di, buffer2        ; point di to file 2 buffer
096                 repe cmpsb              ; compare the two buffers
097                 je   check3             ; if equal, proceed
098                 mov  dx, different      ; else, files are different
099                 jmp  error              ; proceed to message printing
100
101     check3:     cmp  ax, 4096           ; were 4096 bytes read
102                 je   readloop           ; yes, try to read more
103                 mov  dx, same           ; no, files are same
104
105     error:      mov  ah, 9              ; service 9 – output message
106                 int  0x21               ; dos services
107
108                 mov  ah, 0x3e           ; service 3e – close file
109                 mov  bx, [handle1]      ; handle of file to close
110                 int  0x21               ; dos services
111
112                 mov  ah, 0x3e           ; service 3e – close file
113                 mov  bx, [handle2]      ; handle of file to close
114                 int  0x21               ; dos services
115
116                 mov  ax, 0x4c00         ; terminate program
117                 int  0x21
```

Another interesting service that DOS provides regarding files is executing them. An important point to understand here is that whenever a program is executed in DOS all available memory is allocated to it. No memory is available to execute any new programs. Therefore memory must be freed using explicit calls to DOS for this purpose before a program is executed. Important services in this regard are listed below.

INT 21 - ALLOCATE MEMORY

AH = 48h

BX = number of paragraphs to allocate

Return:

CF = error flag

AX = segment of allocated block or error code in case of error

BX = size of largest available block in case of error

INT 21 - FREE MEMORY

AH = 49h

ES = segment of block to free

Return:

CF = error flag

AX = error code

INT 21 - RESIZE MEMORY BLOCK

AH = 4Ah

BX = new size in paragraphs

ES = segment of block to resize

```
Return:
CF = error flag
AX = error code
BX = maximum paragraphs available for specified memory block
INT 21 - LOAD AND/OR EXECUTE PROGRAM
AH = 4Bh
AL = type of load (0 = load and execute)
DS:DX -> ASCIZ program name (must include extension)
ES:BX -> parameter block
Return:
CF = error flag
AX = error code
```

The format of parameter block is as follows.

```
Offset  Size    Description
 00h    WORD    segment of environment to copy for child process
                (copy caller's environment if 0000h)
 02h    DWORD   pointer to command tail to be copied into child's PSP
 06h    DWORD   pointer to first FCB to be copied into child's PSP
 0Ah    DWORD   pointer to second FCB to be copied into child's PSP
 0Eh    DWORD   (AL=01h) will hold subprogram's initial SS:SP on return
 12h    DWORD   (AL=01h) will hold entry point (CS:IP) on return
```

As an example we will use the multitasking kernel client from the multitasking chapter and modify it such that after running all three threads it executes a new instance of the command prompt instead of indefinitely hanging around.

Example 13.4

```
001     ; another multitasking TSR caller
002     [org 0x0100]
003                 jmp  start
004
005     ; parameter block layout:
006     ; cs,ip,ds,es,param
007     ;  0, 2, 4, 6,  8
008
009     paramblock:   times 5 dw 0            ; space for parameters
010     lineno:       dw   0                  ; line number for next thread
011     chars:        db '\|/-'               ; chracters for rotating bar
012     message:      db 'moving hello'       ; moving string
013     message2:     db '             '      ; to erase previous string
014     messagelen:   dw 12                   ; length of above strings
015     tail:         db ' ',13
016     command:      db 'COMMAND.COM', 0
017     execblock:    times 11 dw 0
018
019-062 ;;;;; COPY LINES 028-071 FROM EXAMPLE 10.1 (printnum) ;;;;;
063-104 ;;;;; COPY LINES 073-114 FROM EXAMPLE 10.1 (printstr) ;;;;;
104-127 ;;;;; COPY LINES 103-126 FROM EXAMPLE 11.5 (mytask) ;;;;;
128-146 ;;;;; COPY LINES 128-146 FROM EXAMPLE 11.5 (mytask2) ;;;;;
147-192 ;;;;; COPY LINES 148-193 FROM EXAMPLE 11.5 (mytask3) ;;;;;
193
194     start:        mov  [paramblock+0], cs ; code segment parameter
195                   mov  word [paramblock+2], mytask ; offset parameter
196                   mov  [paramblock+4], ds ; data segment parameter
197                   mov  [paramblock+6], es ; extra segment parameter
198                   mov  word [paramblock+8], 0 ; parameter for thread
199                   mov  si, paramblock     ; address of param block in si
200                   int  0x80               ; multitasking kernel interrupt
201
202                   mov  [paramblock+0], cs ; code segment parameter
203                   mov  word [paramblock+2], mytask2 ; offset parameter
204                   mov  [paramblock+4], ds ; data segment parameter
```

```
205                 mov  [paramblock+6], es ; extra segment parameter
206                 mov  word [paramblock+8], 0 ; parameter for thread
207                 mov  si, paramblock     ; address of param block in si
208                 int  0x80               ; multitasking kernel interrupt
209
210                 mov  [paramblock+0], cs ; code segment parameter
211                 mov  word [paramblock+2], mytask3 ; offset parameter
212                 mov  [paramblock+4], ds ; data segment parameter
213                 mov  [paramblock+6], es ; extra segment parameter
214                 mov  word [paramblock+8], 0 ; parameter for thread
215                 mov  si, paramblock     ; address of param block in si
216                 int  0x80               ; multitasking kernel interrupt
217
218                 mov  ah, 0x4a           ; service 4a – resize memory
219                 mov  bx, end            ; end of memory retained
220                 add  bx, 15             ; rounding up
221                 mov  cl, 4
222                 shr  bx, cl             ; converting into paras
223                 int  0x21               ; dos services
224
225                 mov  ah, 0x4b           ; service 4b - exec
226                 mov  al, 0              ; load and execute
227                 mov  dx, command        ; command to be executed
228                 mov  bx, execblock      ; address of execblock
229                 mov  word [bx+2], tail  ; offset of command tail
230                 mov  [bx+4], ds         ; segment of command tail
231                 int  0x21               ; dos services
232
233                 jmp $                   ; loop infinitely if returned
234 end:
```

13.4. DEVICE DRIVERS

Device drivers are operating system extensions that become part of the operating system and extend its services to new devices. Device drivers in DOS are very simple. They just have their services exposed through the file system interface.

Device driver file starts with a header containing a link to the next driver in the first four bytes followed by a device attribute word. The most important bit in the device attribute word is bit 15 which dictates if it is a character device or a block device. If the bit is zero the device is a character device and otherwise a block device. Next word in the header is the offset of a strategy routine, and then is the offset of the interrupt routine and then in one byte, the number of units supported is stored. This information is padded with seven zeroes.

Strategy routine is called whenever the device is needed and it is passed a request header. Request header stores the unit requested, the command code, space for return value and buffer pointers etc. Important command codes include 0 to initialize, 1 to check media, 2 to build a BIOS parameter block, 4 and 8 for read and write respectively. For every command the first 13 bytes of request header are same.

```
RH+0    BYTE            Length of request header
RH+1    BYTE            Unit requested
RH+2    BYTE            Command code
RH+3    BYTE            Driver's return code
RH+5    9 BYTES Reserved
```

The request header details for different commands is listed below.

0 – Driver Initialization

Passed to driver

```
RH+18   DWORD   Pointer to character after equal sign on CONFIG.SYS line
that loaded driver (read-only)
```

```
RH+22   BYTE    Drive number for first unit of this block driver
(0=A...)
Return from driver
RH+13   BYTE    Number of units (block devices only)
RH+14   DWORD   Address of first free memory above driver (break
address)
RH+18   DWORD   BPB pointer array (block devices only)
```

1 – Media Check

```
RH+13   BYTE    Media descriptor byte
Return
RH+14   BYTE    Media change code
                       -1 if disk changed
                       0 if dont know whether disk changed
                       1 if disk not changed
RH+15   DWORD   pointer to previous volume label if device attrib bit
11=1 (open/close/removable media supported)
```

2 – Build BPB

```
RH+13   BYTE    Media descriptor byte
RH+14   DWORD   buffer address (one sector)
Return
RH+18   DWORD   pointer to new BPB
if bit 13 (ibm format) is set buffer is first sector of fat, otherwise
scrach space
```

4 – Read / 8 – Write / 9 – Write with verify

```
RH+13   BYTE    Media descriptor byte
RH+14   DWORD   transfer address
RH+18   WORD    byte or sector count
RH+20   WORD    starting sector number (for block devices)
Return
RH+18   WORD    actual byte or sectors transferred
RH+22   DWORD   pointer to volume label if error 0Fh is returned
```

The BIOS parameter block discussed above is a structure that provides parameters about the storage medium. It is stored in the first sector or the boot sector of the device. Its contents are listed below.

```
00-01   bytes per sector
02      sectors per allocation unit
03-04   Number of reserved sectors ( 0 based)
05      number of file allocation tables
06-07   max number of root directory entries
08-09   total number of sectors in medium
0A      media descriptor byte
0B-0C   number of sectors occupied by a single FAT
0D-0E   sectors per track (3.0 or later)
0F-10   number of heads (3.0 or later)
11-12   number of hidden sectors (3.0 or later)
13-14   high-order word of number of hidden sectors (4.0)
15-18   IF bytes 8-9 are zero, total number of sectors in medium
19-1E   Reserved should be zero
```

We will be building an example device driver that takes some RAM and expresses it as a secondary storage device to the operating system. Therefore a new drive is added and that can be browsed to, filed copied to and from just like ordinary drives expect that this drive is very fast as it is located in the RAM. This program cannot be directly executed since it is not a user program. This must be loaded by adding the line “device=filename.sys” in the “config.sys” file in the root directory.

Example 13.5


```
001     ; ram disk dos block device driver
002     header:     dd   -1                  ; no next driver
003                 dw   0x2000              ; driver attributes: block device
004                 dw   strategy            ; offset of strategy routine
005                 dw   interrupt           ; offset of interrupt routine
006                 db   1                   ; no of units supported
007                 times 7 db 0             ; reserved
008
009     request:    dd   0                   ; space for request header
010
011     ramdisk:    times 11 db 0            ; initial part of boot sector
012     bpb:        dw   512                 ; bytes per sector
013                 db   1                   ; sectors per cluster
014                 dw   1                   ; reserved sectors
015                 db   1                   ; fat copies
016                 dw   48                  ; root dir entries
017                 dw   105                 ; total sectors
018                 db   0xf8                ; media desc byte: fixed disk
019                 dw   1                   ; sectors per fat
020                 times 482 db 0           ; remaining part of boot sector
021                 db   0xfe, 0xff, 0xff    ; special bytes at start of FAT
022                 times 509 db 0           ; remaining FAT entries unused
023                 times 103*512 db 0       ; 103 sectors for data
024     bpbptr:     dw   bpb                 ; array of bpb pointers
025
026     dispatch:   dw   init                ; command 0: init
027                 dw   mediacheck          ; command 1: media check
028                 dw   getbpb              ; command 2: get bpb
029                 dw   unknown             ; command 3: not handled
030                 dw   input               ; command 4: input
031                 dw   unknown             ; command 5: not handled
032                 dw   unknown             ; command 6: not handled
033                 dw   unknown             ; command 7: not handled
034                 dw   output              ; command 8: output
035                 dw   output              ; command 9: output with verify
036
037     ; device driver strategy routine
038     strategy:   mov  [cs:request], bx    ; save request header offset
039                 mov  [cs:request+2], es  ; save request header segment
040                 retf
041
042     ; device driver interrupt routine
043     interrupt:  push ax
044                 push bx
045                 push cx
046                 push dx
047                 push si
048                 push di
049                 push ds
050                 push es
051
052                 push cs
053                 pop  ds
054
055                 les  di, [request]
056                 mov  word [es:di+3], 0x0100
057                 mov  bl, [es:di+2]
058                 mov  bh, 0
059                 cmp  bx, 9
060                 ja   skip
061                 shl  bx, 1
062
063                 call [dispatch+bx]
064
065     skip:       pop  es
066                 pop  ds
067                 pop  di
068                 pop  si
069                 pop  dx
070                 pop  cx
071                 pop  bx
072                 pop  ax
073                 retf
074
```

```
075     mediacheck: mov  byte [es:di+14], 1
076                 ret
077
078     getbpb:     mov  word [es:di+18], bpb
079                 mov  [es:di+20], ds
080                 ret
081
082     input:      mov  ax, 512
083                 mul  word [es:di+18]
084                 mov  cx, ax
085
086                 mov  ax, 512
087                 mul  word [es:di+20]
088                 mov  si, ax
089                 add  si, ramdisk
090
091                 les  di, [es:di+14]
092                 cld
093                 rep  movsb
094                 ret
095
096     output:     mov  ax, 512
097                 mul  word [es:di+18]
098                 mov  cx, ax
099
100                 lds  si, [es:di+14]
101                 mov  ax, 512
102                 mul  word [es:di+20]
103                 mov  di, ax
104                 add  di, ramdisk
105
106                 push cs
107                 pop  es
108                 cld
109                 rep  movsb
110     unknown:    ret
111
112     init:       mov  ah, 9
113                 mov  dx, message
114                 int  0x21
115
116                 mov  byte [es:di+13], 1
117                 mov  word [es:di+14], init
118                 mov  [es:di+16], ds
119                 mov  word [es:di+18], bpbptr
120                 mov  [es:di+20], ds
121                 ret
122
123     message:    db   13, 10, 'RAM Disk Driver loaded',13,10,'$'
```

14
Serial Port Programming

14.1. INTRODUCTION

Serial port is a way of communication among two devices just like the parallel port. The basic difference is that whole bytes are sent from one place to another in case of parallel port while the bits are sent one by one on the serial port in a specially formatted fashion. The serial port connection is a 9pin DB-9 connector with pins assigned as shown below.




We have made a wire that connects signal ground of the two connectors, the TD of one to the RD of the other and the RD of one to the TD of the other. This three wire connection is sufficient for full duplex serial communication. The data on the serial port is sent in a standard format called RS232 communication. The data starts with a 1 bit called the start bit, then five to eight data bits, an optional parity bit, and one to two 0 bits called stop bits. The number of data bits, parity bits, and the number of stop bits have to be configured at both ends. Also the duration of a bit must be precisely known at both ends called the baud rate of the communication.

The BIOS INT 14 provides serial port services. We will use a mix of BIOS services and direct port access for our example. A major limitation in using BIOS is that it does not allows interrupt driven data transfer, i.e. we are interrupted whenever a byte is ready to be read or a byte can be transferred since the previous transmission has completed. To achieve this we have to resort to direct port access. Important BIOS services regarding the serial port are discussed below.

```
INT 14 - SERIAL - INITIALIZE PORT
AH = 00h
AL = port parameters
DX = port number (00h-03h)
Return:
AH = line status
AL = modem status
```

Every bit of line status conveys different information. From most significant to least significant, the meanings are timeout, transmitter shift register empty, transmitter holding register empty, break detect, receiver ready, overrun, parity error, and framing error. Modem status is not used in direct serial communication. The port parameters in AL consist of the baud

rate, parity scheme, number of stop bits, and number of data bits. The description of various bits is as under.




```
INT 14 - SERIAL - WRITE CHARACTER TO PORT
AH = 01h
AL = character to write
DX = port number (00h-03h)
Return:
AH bit 7 = error flag
AH bits 6-0 = port status
INT 14 - SERIAL - READ CHARACTER FROM PORT
AH = 02h
DX = port number (00h-03h)
Return:
AH = line status
AL = received character if AH bit 7 clear
INT 14 - SERIAL - GET PORT STATUS
AH = 03h
DX = port number (00h-03h)
Return:
AH = line status
AL = modem status
```

Serial port is also accessible via I/O ports. COM1 is accessible via ports 3F8-3FF while COM2 is accessible via 2F8-2FF. The first register at 3F8 (or 2F8 for the other port) is the transmitter holding register if written to and the receiver buffer register if read from. Other registers of our interest include 3F9 whose bit 0 must be set to enable received data available interrupt and bit 1 must be set to enable transmitter holding register empty interrupt. Bit 0 of 3FA is set if an interrupt is pending and its bits 1-3 identify the cause of the interrupt. The three bit causes are as follows.

```
110    (16550, 82510) timeout interrupt pending
101    (82510) timer interrupt
100    (82510) transmit machine
011    receiver line status interrupt. priority=highest
010    received data available register interrupt. priority=second
001    transmitter holding register empty interrupt. priority=third
000    modem status interrupt. priority=fourth
```

The register at 3FB is line control register while the one at 3FD is line status register. The line status register has the same bits as returned in line status by the get port status BIOS interrupt however the most significant bit

is reserved in this case instead of signaling a timeout. The register at 3FC is the modem control register. Bit 3 of this register must be set to enable interrupt generation by the serial port.

14.2. SERIAL COMMUNICATION

We give an example where two computers are connected using a serial cable made just as described above. The program is to be run on both computers. After that whatever is typed on one computer appears on the screen of the other.

Example 14.1

```
001     ; a program using serial port to transfer data back and forth
002     [org 0x0100]
003                 jmp  start
004
005     screenpos:    dw   0              ; where to display next character
006
007     ; subroutine to clear the screen
008     clrscr:       push es
009                   push ax
010                   push cx
011                   push di
012
013                   mov  ax, 0xb800
014                   mov  es, ax         ; point es to video base
015                   xor  di, di         ; point di to top left column
016                   mov  ax, 0x0720     ; space char in normal attribute
017                   mov  cx, 2000       ; number of screen locations
018
019                   cld                 ; auto increment mode
020                   rep  stosw          ; clear the whole screen
021
022                   pop  di
023                   pop  cx
024                   pop  ax
025                   pop  es
026                   ret
027
028     serial:       push ax
029                   push bx
030                   push dx
031                   push es
032
033                   mov  dx, 0x3FA      ; interrupt identification register
034                   in   al, dx         ; read register
035                   and  al, 0x0F       ; leave lowerniblle only
036                   cmp  al, 4          ; is receiver data available
037                   jne  skipall        ; no, leave interrupt handler
038
039                   mov  dx, 0x3F8      ; data register
040                   in   al, dx         ; read character
041
042                   mov  dx, 0xB800
043                   mov  es, dx         ; point es to video memory
044                   mov  bx, [cs:screenpos] ; get current screen position
045                   mov  [es:bx], al    ; write character on screen
046                   add  word [cs:screenpos], 2 ; update screen position
047                   cmp  word [cs:screenpos], 4000 ; is the screen full
048                   jne  skipall        ; no, leave interrupt handler
049
050                   call clrscr         ; clear the screen
051                   mov  word [cs:screenpos], 0 ; reset screen position
052
053     skipall:      mov  al, 0x20
054                   out  0x20, al       ; end of interrupt
055
056                   pop  es
057                   pop  dx
058                   pop  bx
059                   pop  ax
060                   iret
```

```
061
062     start:        call clrscr         ; clear the screen
063
064                   mov  ah, 0          ; initialize port service
065                   mov  al, 0xE3       ; line settings = 9600, 8, N, 1
066                   xor  dx, dx         ; port = COM1
067                   int  0x14           ; BIOS serial port services
068
069                   xor  ax, ax
070                   mov  es, ax         ; point es to IVT base
071                   mov  word [es:0x0C*4], serial
072                   mov  [es:0x0C*4+2], cs ; hook serial port interrupt
073
074                   mov  dx, 0x3FC      ; modem control register
075                   in   al, dx         ; read register
076                   or   al, 8          ; enable bit 3 (OUT2)
077                   out  dx, al         ; write back to register
078
079                   mov  dx, 0x3F9      ; interrupt enable register
080                   in   al, dx         ; read register
081                   or   al, 1          ; receiver data interrupt enable
082                   out  dx, al         ; write back to register
083
084                   in   al, 0x21       ; read interrupt mask register
085                   and  al, 0xEF       ; enable IRQ 4
086                   out  0x21, al       ; write back to register
087
088     main:         mov  ah, 0          ; read key service
089                   int  0x16           ; BIOS keybaord services
090                   push ax             ; save key for later use
091
092     retest:       mov  ah, 3          ; get line status
093                   xor  dx, dx         ; port = COM1
094                   int  0x14           ; BIOS keyboard services
095                   and  ah, 32         ; trasmitter holding register empty
096                   jz   retest         ; no, test again
097
098                   pop  ax             ; load saved key
099                   mov  dx, 0x3F8      ; data port
100                   out  dx, al         ; send on serial port
101
102                   jmp  main
```

15
Protected Mode Programming


15.1. INTRODUCTION

Till now we have been discussing the 8088 architecture which was a 16bit processor. Newer processors of the Intel series provide 32bit architecture. Till now we were in real mode of a newer processor which is basically a compatibility mode making the newer processor just a faster version of the original 8088. Switching processor in the newer 32bit mode is a very easy task. Just turn on the least significant bit of a new register called CR0 (Control Register 0) and the processor switches into 32bit mode called protected mode. However manipulations in the protected mode are very different from those in the read mode.

All registers in 386 have been extended to 32bits. The new names are EAX, EBX, ECX, EDX, ESI, EDI, ESP, EBP, EIP, and EFLAGS. The original names refer to the lower 16bits of these registers. A 32bit address register can access upto 4GB of memory so memory access has increased a lot.

As regards segment registers the scheme is not so simple. First of all we call them segment selectors instead of segment registers and they are still 16bits wide. We are also given two other segment selectors FS and GS for no specific purpose just like ES.


The working of segment registers as being multiplied by 10 and added into the offset for obtaining the physical address is totally changed. Now the selector is just an index into an array of segment descriptors where each descriptor describes the base, limit, and attributes of a segment. Role of selector is to select on descriptor from the table of descriptors and the role of descriptor is to define the actual base address. This decouples the selection and actual definition which is needed in certain protection mechanisms introduced into this processor. For example an operating system can define the possible descriptors for a program and the program is bound to select one of them and nothing else. This sentence also hints that the processor has some sense of programs that can or cannot do certain things like change this table of descriptors. This is called the privilege level of the program and varies for 0 (highest privilege) to 3 (lowest privilege). The format of a selector is shown below.




The table index (TI) is set to 0 to access the global table of descriptors called the GDT (Global Descriptor Table). It is set to 1 to access another table, the local descriptor table (LDT) that we will not be using. RPL is the requested privilege level that ranges from 0-3 and informs what privilege level

the program wants when using this descriptor. The 13bit index is the actual index into the GDT to select the appropriate descriptor. 13 bits mean that a maximum of 8192 descriptors are possible in the GDT.

The GDT itself is an array of descriptors where each descriptor is an 8byte entry. The base and limit of GDT is stored in a 48bit register called the GDTR. This register is loaded with a special instruction LGDT and is given a memory address from where the 48bits are fetched. The first entry of the GDT must always be zero. It is called the null descriptor. After that any number of entries upto a maximum of 8191 can follow. The format of a code and data descriptor is shown below.





The 32bit base in both descriptors is scattered into different places because of compatibility reasons. The limit is stored in 20 bits but the G bit defines that the limit is in terms of bytes of 4K pages therefore a maximum of 4GB size is possible. The P bit must be set to signal that this segment is present in memory. DPL is the descriptor privilege level again related to the protection levels in 386. D bit defines that this segment is to execute code is 16bit mode or 32bit mode. C is conforming bit that we will not be using. R signals that the segment is readable. A bit is automatically set whenever the segment is accessed. The combination of S (system) and X (executable) tell that the descriptors is a code or a data descriptor. B (big) bit tells that if this data segment is used as stack SP is used or ESP is used.

Our first example is a very rudimentary one that just goes into protected mode and prints an A on the screen by directly accessing 000B8000.

Example 15.1

```
001     [org 0x0100]
002                 jmp  start
003
004     gdt:        dd   0x00000000, 0x00000000   ; null descriptor
005                 dd   0x0000FFFF, 0x00CF9A00   ; 32bit code
006                 ;      \--/\--/    \/||||\/
007                 ;        |   |      | ||||+--- Base (16..23)=0 fill later
008                 ;        |   |      | |||+--- X=1 C=0 R=1 A=0
009                 ;        |   |      | ||+--- P=1 DPL=00 S=1
010                 ;        |   |      | |+--- Limit (16..19) = F
011                 ;        |   |      | +--- G=1 D=1 r=0 AVL=0
```

```
012                 ;       |   |      +--- Base (24..31) = 0
013                 ;       |   +--- Limit (0..15) = FFFF
014                 ;       +--- Base (0..15)=0 fill later
015                 dd   0x0000FFFF, 0x00CF9200   ; data
016                 ;      \--/\--/    \/||||\/
017                 ;       |   |      | ||||+--- Base (16..23) = 0
018                 ;       |   |      | |||+--- X=0 E=0 W=1 A=0
019                 ;       |   |      | ||+--- P=1 DPL=00 S=1
020                 ;       |   |      | |+--- Limit (16..19) = F
021                 ;       |   |      | +--- G=1 B=1 r=0 AVL=0
022                 ;       |   |      +--- Base (24..31) = 0
023                 ;       |   +--- Limit (0..15) = FFFF
024                 ;       +--- Base (0..15) = 0
025
026     gdtreg:     dw   0x17      ; 16bit limit
027                 dd   0         ; 32bit base (filled later)
028
029     stack:      times 256 dd 0 ; for use in p-mode
030     stacktop:
031
032     start:      mov  ax, 0x2401
033                 int  0x15           ; enable A20
034
035                 xor  eax, eax
036                 mov  ax, cs
037                 shl  eax, 4
038                 mov  [gdt+0x08+2], ax
039                 shr  eax, 16
040                 mov  [gdt+0x08+4], al         ; fill base of code desc
041
042                 xor  edx, edx
043                 mov  dx, cs
044                 shl  edx, 4
045                 add  edx, stacktop             ; edx = stack top for p-
046     mode
047
048                 xor  eax, eax
049                 mov  ax, cs
050                 shl  eax, 4
051                 add  eax, gdt
052                 mov  [gdtreg+2], eax          ; fill phy base of gdt
053                 lgdt [gdtreg]                 ; load gdtr
054
055                 mov  eax, cr0
056                 or   eax, 1
057
058                 cli                           ; MUST disable interrupts
059                 mov  cr0, eax                 ; P-MODE ON
060                 jmp  0x08:pstart              ; load cs
061
062     ;;;;; 32bit protected mode ;;;;;
063
064     [bits 32] ; ask assembler to generate 32bit code
065     pstart:     mov  eax, 0x10
066                 mov  ds, ax
067                 mov  es, ax                   ; load other seg regs
068                 mov  fs, ax                   ; flat memory model
069                 mov  gs, ax
070                 mov  ss, ax
071                 mov  esp, edx
072
073                 mov  byte [0x000b8000], 'A'   ; direct poke at video
074                 jmp  $                        ; hang around
075
```

Gate A20 is a workaround for a bug that is not detailed here. The BIOS call will simply enable it to open the whole memory for us. Another important thing is that the far jump we used loaded 8 into CS but CS is now a selector so it means Index=1, TI=0, and RPL=0 and therefore the actual descriptor loaded is the one at index 1 in the GDT.

15.2. 32BIT PROGRAMMING

Our next example is to give a falvour of 32bit programming. We have written the printstr function for read and for protected mode. The availability of larger registers and flexible addressing rules allows writing a much comprehensive version of the code. Also offsets to parameters and default widths change.

Example 15.2

```
001     [org 0x0100]
002                     jmp  start
003
004     gdt:            dd   0x00000000, 0x00000000   ; null descriptor
005                     dd   0x0000FFFF, 0x00CF9A00   ; 32bit code
006                     dd   0x0000FFFF, 0x00CF9200   ; data
007
008     gdtreg:         dw   0x17                     ; 16bit limit
009                     dd   0                        ; 32bit base
010
011     rstring:        db   'In Real Mode...', 0
012     pstring:        db   'In Protected Mode...', 0
013
014     stack:          times 256 dd 0                ; 1K stack
015     stacktop:
016
017     printstr:       push bp                       ; real mode print string
018                     mov  bp, sp
019                     push ax
020                     push cx
021                     push si
022                     push di
023                     push es
024
025                     mov  di,[bp+4]  ;load string address
026                     mov  cx,0xffff  ;load maximum possible size in cx
027                     xor  al,al      ;clear al reg
028                     repne scasb     ;repeat scan
029                     mov ax,0xffff   ;
030                     sub ax,cx       ;calculate length
031                     dec ax          ;off by one, as it includes zero
032                     mov cx,ax       ;move length to counter
033
034                     mov ax, 0xb800
035                     mov es, ax               ; point es to video base
036                     mov ax,80                ;its a word move, clears ah
037                     mul byte [bp+8]         ;its a byte mul to calc y offset
038                     add ax,[bp+10]           ;add x offset
039                     shl ax,1                 ;mul by 2 to get word offset
040                     mov di,ax                ;load pointer
041
042                     mov si, [bp+4]           ; string to be printed
043                     mov ah, [bp+6]           ; load attribute
044
045                     cld                      ; set auto increment mode
046     nextchar:       lodsb                    ;load next char and inc si by 1
047                     stosw                    ;store ax and inc di by 2
048                     loop nextchar
049
050                     pop es
051                     pop di
052                     pop si
053                     pop cx
054                     pop ax
055                     pop bp
056                     ret 8
057
058     start:            push byte 0                 ; 386 can directly push
059     immediates
060                     push byte 10
061                     push byte 7
062                     push word rstring
063                     call printstr
064
```

```
065                 mov  ax, 0x2401
066                 int  0x15               ; enable a20
067
068                 xor  eax, eax
069                 mov  ax, cs
070                 shl  eax, 4
071                 mov  [gdt+0x08+2], ax
072                 shr  eax, 16
073                 mov  [gdt+0x08+4], al         ; set base of code desc
074
075                 xor  edx, edx
076                 mov  dx, cs
077                 shl  edx, 4
078                 add  edx, stacktop       ; stacktop to be used in p-mode
079
080                 xor  ebx, ebx
081                 mov  bx, cs
082                 shl  ebx, 4
083                 add  ebx, pstring        ; pstring to be used in p-mode
084
085                 xor  eax, eax
086                 mov  ax, cs
087                 shl  eax, 4
088                 add  eax, gdt
089                 mov  [gdtreg+2], eax          ; set base of gdt
090                 lgdt [gdtreg]                 ; load gdtr
091
092                 mov  eax, cr0
093                 or   eax, 1
094
095                 cli                           ; disable interrupts
096                 mov  cr0, eax                 ; enable protected mode
097                 jmp  0x08:pstart              ; load cs
098
099     ;;;;; 32bit protected mode ;;;;;
100
101     [bits 32]
102     pprintstr:    push ebp                ; p-mode print string routine
103                 mov  ebp, esp
104                 push eax
105                 push ecx
106                 push esi
107                 push edi
108
109                 mov  edi, [ebp+8]  ;load string address
110                 mov  ecx, 0xffffffff  ;load maximum possible size in cx
111                 xor  al, al      ;clear al reg
112                 repne scasb     ;repeat scan
113                 mov  eax, 0xffffffff   ;
114                 sub  eax, ecx       ;calculate length
115                 dec  eax          ;off by one, as it includes zero
116                 mov  ecx, eax       ;move length to counter
117
118                 mov  eax, 80                ;its a word move, clears ah
119                 mul   byte [ebp+16]           ;its a byte mul to calc y
120     offset
121                 add  eax, [ebp+20]           ;add x offset
123                 shl  eax, 1                 ;mul by 2 to get word offset
124                 add  eax, 0xb8000
125                 mov  edi, eax                ;load pointer
126
127                 mov esi, [ebp+8]           ; string to be printed
128                 mov ah, [ebp+12]           ; load attribute
129
130                 cld                       ; set auto increment mode
131     pnextchar:    lodsb                   ;load next char and inc si by 1
132                 stosw                     ;store ax and inc di by 2
133                 loop pnextchar
134
135                 pop  edi
136                 pop  esi
137                 pop  ecx
138                 pop  eax
139                 pop  ebp
140                 ret  16                 ; 4 args now mean 16 bytes
141
```

```
142     pstart:       mov  ax, 0x10           ; load all seg regs to 0x10
143                   mov  ds, ax             ; flat memory model
144                   mov  es, ax
145                   mov  fs, ax
146                   mov  gs, ax
147                   mov  ss, ax
148                   mov  esp, edx           ; load saved esp on stack
149
150                   push byte 0
133                   push byte 11
134                   push byte 7
135                   push ebx
136                   call pprintstr              ; call p-mode print string
137     routine
138
139                   mov  eax, 0x000b8000
140                   mov  ebx, '/-\|'
141
142     nextsymbol:   mov  [eax], bl
143                   mov  ecx, 0x00FFFFFF
144                   loop $
145                   ror  ebx, 8
146                   jmp  nextsymbol
```

15.3. VESA LINEAR FRAME BUFFER

As an example of accessing a really large area of memory for which protected mode is a necessity, we will be accessing the video memory in high resolution and high color graphics mode where the necessary video memory is alone above a megabyte. We will be using the VESA VBE 2.0 for a standard for these high resolution modes.

VESA is the Video Electronics Standards Association and VBE is the set of Video BIOS Extensions proposed by them. The VESA VBE 2.0 standard includes a linear frame buffer mode that we will be using. This mode allows direct access to the whole video memory. Some important VESA services are listed below.

INT 10 – VESA – Get SuperVGA Infromation
AX = 4F00h
ES:DI -> buffer for SuperVGA information
Return:
AL = 4Fh if function supported
AH = status
INT 10 – VESA – Get SuperVGA Mode Information
AX = 4F01h
CX = SuperVGA video mode
ES:DI -> 256-byte buffer for mode information
Return:
AL = 4Fh if function supported
AH = status
ES:DI filled if no error
INT 10 – VESA – Set VESA Video Mode
AX = 4F02h
BX = new video mode
Return:
AL = 4Fh if function supported
AH = status

One of the VESA defined modes is 4117 which is a 1024x768 mode with 16bit color and a linear frame buffer. The 16 color bits for every pixel are organized in 5:6:5 format with 5 bits for red, 6 for green, and 5 for blue. This makes 32 shades of red and blue and 64 shades of green and 64K total

possible colors. The 32bit linear frame buffer base address is available at offset 28 in the mode information buffer. Our example will produces shades of green on the screen and clear them and again print them in an infinite loop with delays in between.


Example 15.3

```
001     [org 0x0100]
002                     jmp  start
003
004     modeblock:      times 256 db 0
005
006     gdt:            dd   0x00000000, 0x00000000   ; null descriptor
007                     dd   0x0000FFFF, 0x00CF9A00   ; 32bit code
008                     dd   0x0000FFFF, 0x00CF9200   ; data
009
010     gdtreg:         dw   0x17                     ; 16bit limit
011                     dd   0                        ; 32bit base
012
013     stack:          times 256 dd 0                ; 1K stack
014     stacktop:
015
016     start:          mov  ax, 0x4f01          ; get vesa mode information
017                     mov   cx, 0x4117             ; 1024*768*64K linear frame
018     buffer
019                     mov  di, modeblock
020                     int  0x10
021                     mov  esi, [modeblock+0x28]    ; save frame buffer base
022
023                     mov  ax, 0x4f02          ; set vesa mode
024                     mov  bx, 0x4117
025                     int  0x10
026
027                     mov  ax, 0x2401
028                     int  0x15                ; enable a20
029
030                     xor  eax, eax
031                     mov  ax, cs
032                     shl  eax, 4
033                     mov  [gdt+0x08+2], ax
034                     shr  eax, 16
035                     mov  [gdt+0x08+4], al         ; set base of code desc
036
037                     xor  edx, edx
038                     mov  dx, cs
039                     shl  edx, 4
040                     add  edx, stacktop       ; stacktop to be used in p-mode
041
042                     xor  eax, eax
043                     mov  ax, cs
044                     shl  eax, 4
045                     add  eax, gdt
046                     mov  [gdtreg+2], eax          ; set base of gdt
047                     lgdt [gdtreg]                 ; load gdtr
048
049                     mov  eax, cr0
050                     or   eax, 1
051
052                     cli                           ; disable interrupts
053                     mov  cr0, eax                 ; enable protected mode
054                     jmp  0x08:pstart              ; load cs
055
056     ;;;;; 32bit protected mode ;;;;;
057
058     [bits 32]
059     pstart:         mov  ax, 0x10            ; load all seg regs to 0x10
060                     mov  ds, ax              ; flat memory model
061                     mov  es, ax
062                     mov  fs, ax
063                     mov  gs, ax
064                     mov  ss, ax
065                     mov  esp, edx            ; load saved esp on stack
066
067     l1:             xor  eax, eax
```

```
068                 mov  edi, esi
069                 mov  ecx, 1024*768*2/4        ; divide by 4 as dwords
070                 cld
071                 rep  stosd
072
073                 mov  eax, 0x07FF07FF
074                 mov  ecx, 32                   ; no of bands
075                 mov  edi, esi
076
077     l2:         push ecx
078                 mov  ecx, 768*16                      ; band width = 32
079     lines
080                 cld
081                 rep stosd
082
083                 mov  ecx, 0x000FFFFF           ; small wait
084                 loop $
085                 pop  ecx
086
087                 sub  eax, 0x00410041
088                 loop l2
089
090                 mov  ecx, 0x0FFFFFFF           ; long wait
091                 loop $
092                 jmp  l1
093
```

15.4. INTERRUPT HANDLING

Handling interrupts in protected mode is also different. Instead of the IVT at physical address 0 there is the IDT (interrupt descriptor table) located at physical address stored in IDTR, a special purpose register. The IDTR is also a 48bit register similar in structure to the GDTR and loaded with another special instruction LGDT. The format of the interrupt descriptor is as shown below.



The P and DPL have the same meaning as in data and code descriptors. The S bit tells that this is a system descriptor while the 1110 following it tells that it is a 386 interrupt gate. Our example hooks the keyboard and timer interrupts and displays certain things on the screen to show that they are working.

Example 15.4

```
001     [org 0x0100]
002                 jmp  start
003
004     gdt:        dd   0x00000000, 0x00000000   ; null descriptor
005                 dd   0x0000FFFF, 0x00CF9A00   ; 32bit code
006                 dd   0x0000FFFF, 0x00CF9200   ; data
007
008     gdtreg:     dw   0x17                     ; 16bit limit
009                 dd   0                        ; 32bit base
```

```
010
011     idt:          times 8 dw unhandled, 0x0008, 0x8e00, 0x0000
012                   dw   timer, 0x0008, 0x8e00, 0x0000
013                        \---/  \----/    ||\/  \----/
014                          |      |       || |    +----- offset bits 16..32
015                          |      |       || +----- reserved
016                          |      |       |+------ Type=E 386 Interrupt Gate
017                          |      |       +--- P=1 DPL=00 S=0
018                          |      +------- selector
019                          +-------- offset bits 0..15
020                   dw   keyboard, 0x0008, 0x8e00, 0x0000
021                   times 246 dw unhandled, 0x0008, 0x8e00, 0x0000
022
023     idtreg:       dw   0x07FF
024                   dd   0
025
026     stack:        times 256 dd 0                ; 1K stack
027     stacktop:
028
029     start:        mov  ax, 0x2401
030                   int  0x15                ; enable a20
031
032                   xor  eax, eax
033                   mov  ax, cs
034                   shl  eax, 4
035                   mov  [gdt+0x08+2], ax
036                   shr  eax, 16
037                   mov  [gdt+0x08+4], al         ; set base of code desc
038
039                   xor  edx, edx
040                   mov  dx, cs
041                   shl  edx, 4
042                   add  edx, stacktop       ; stacktop to be used in p-mode
043
044                   xor  eax, eax
045                   mov  ax, cs
046                   shl  eax, 4
047                   add  eax, gdt
048                   mov  [gdtreg+2], eax          ; set base of gdt
049                   lgdt [gdtreg]                 ; load gdtr
050
051                   xor  eax, eax
052                   mov  ax, cs
053                   shl  eax, 4
054                   add  eax, idt
055                   mov  [idtreg+2], eax          ; set base of idt
056
057                   cli                           ; disable interrupts
058                   lidt [idtreg]                 ; load idtr
059
060                   mov  eax, cr0
061                   or   eax, 1
062                   mov  cr0, eax                 ; enable protected mode
063
064                   jmp  0x08:pstart              ; load cs
065
066     ;;;;; 32bit protected mode ;;;;;
067
068     [bits 32]
069     unhandled:    iret
070
071     timer:        push eax
072
073                   inc  byte [0x000b8000]
074
075                  mov  al, 0x20
076                   out  0x20, al
077                   pop  eax
078                   iret
079
080     keyboard:     push eax
081
082                   in   al, 0x60
083                   mov  ah, al
084                   and  al, 0x0F
085                   shr  ah, 4
```

```
086                 add  ax, 0x3030
087                 cmp  al, 0x39
088                 jbe  skip1
089                 add  al, 7
090     skip1:      cmp  ah, 0x39
091                 jbe  skip2
092                 add  ah, 7
093     skip2:      mov  [0x000b809C], ah
094                 mov  [0x000b809E], al
095
096     skipkb:     mov  al, 0x20
097                 out  0x20, al
098                 pop  eax
099                 iret
100
101     pstart:     mov  ax, 0x10           ; load all seg regs to 0x10
102                 mov  ds, ax             ; flat memory model
103                 mov  es, ax
104                 mov  fs, ax
105                 mov  gs, ax
106                 mov  ss, ax
107                 mov  esp, edx           ; load saved esp on stack
108
109                 mov  al, 0xFC
110                 out  0x21, al           ; no unexpected int comes
111
112                 sti                     ; interrupts are okay now
113
114                 jmp  $
```

EXERCISES

1. Write very brief and to-the-point answers.
   a. Why loading idtr with a value appropriate for real mode is necessary while gdtr is not?
   b. What should we do in protected mode so that when we turn protection off, we are in unreal mode?
   c. If the line jmp code:next is replaced with call code:somefun, the prefetch queue is still emptied. What problem will occur when somefun will return?
   d. How much is ESP decremented when an interrupt arrives. This depends on weather we are in 16-bit mode or 32-bit. Does it depend on any other thing as well? If yes, what?
   e. Give two instructions that change the TR register.
2. Name the following descriptors like code descriptor, data descriptor, interrupt gate etc.

```
gdt:    dd 0x00000000, 0x00000000
        dd 0x00000000, 0x00000000
        dd 0x80000fA0, 0x0000820b
        dd 0x0000ffff, 0x00409a00
        dd 0x80000000, 0x0001d20b
```

3. Using the above GDT, which of the following values, when moved into DS will cause an exception and why.

```
0x00
0x08
0x10
0x18
0x28
0x23
```

4. Using the above GDT, if DS contains 0x20, which of the following offsets will cause an exception on read access?

```
0x0ffff
0x10000
0x10001
```

5. The following function is written in 32-bit code for a 16-bit stack. Against every instruction, write the prefixes generated before that instruction. Prefixes can be address size, operand size, repeat, or segment override. Then rewrite the code such that no prefixes are generated considering that this is assembled and executed in 32-bit mode. Don't care for retaining register values. The function copies specified number of DWORDs between two segments.

```
[bits 32]
memcpy:       mov  bp, sp
              lds  esi, [bp+4]        ; source address
              les  edi, [bp+10]       ; destination address
              mov  cx, [bp+16]        ; count of DWORDs to move
              shl  cx, 1              ; make into count of WORDs
L1:           mov  dx, [si]
              mov  [es:di], dx
              dec  cx
              jnz  L1
              ret
```

6. Rewrite the following scheduler so that it schedules processes stored in readyQ, where enque and deque functions are redefined and readyQ contains TSS selectors of processes to be multitasked. Remember you can't use a register as a segment in a jump (eg jmp ax:0) but you can jump to an indirect address (eg jmp far [eax]) where eax points to a six-byte address. Declare any variables you need.

```
              mov al, 0x20
scheduler:    jmp USERONESEL:0
              out  0x20, al
              mov  byte [USERONEDESC+5], 0x89
              jmp  USERTWOSEL:0
              out  0x20, al
              mov  byte [USERTWODESC+5], 0x89
              jmp  scheduler
```

7. Protected mode has specialized mechanism for multitasking using task state segments but the method used in real mode i.e. saving all registers in a PCB, selecting the next PCB and loading all registers from there is still applicable. Multitask two tasks in protected mode multitasking without TSS. Assume that all processes are at level zero so no protection issues arise. Be careful to save the complete state of the process.
8. Write the following descriptors.
    a. 32 bit, conforming, execute-only code segment at level 2, with base at 6MB and a size of 4MB.
    b. 16 bit, non-conforming, readable code segment at level 0, with base at 1MB and a size of 10 bytes.
    c. Read only data segment at level 3, with base at 0 and size of 1MB.
    d. Interrupt Gate with selector 180h and offset 11223344h.
9. Write physical addresses for the following accesses where CS points to the first descriptor above, DS to the second, ES to the third, EBX contains 00010000h, and ESI contains 00020000h
    a. [bx+si]
    b. [ebx+esi-2ffffh]
    c. [es:ebx-10h]
10. Which of the following will cause exceptions and why. The registers have the same values as the last question.
    a. mov eax, [cs:10000h]
    b. mov [es:esi:100h], ebx
    c. mov ax, [es:ebx]
11. Give short answers.
    a. How can a GPF (General protection fault) occur while running the following code

```
push es
pop  es
```

b. How can a GPF occur during the following instruction? Give any two reasons.

```
jmp  10h:100h
```

c. What will happen if we call interrupt 80h after loading out IDT and before switching to protected mode?

d. What will happen if we call interrupt 80h after switching into protected mode but before making a far jump?

12. Write the following descriptors. Assume values for attributes not specifically mentioned.
    a. Write able 32-bit data segment with 1 GB base and 1 GB limit and a privilege level of 2.
    b. Readable 16-bit code descriptor with 1 MB base and 1 MB limit and a privilege level of 1.
    c. Interrupt gate given that the handler is at 48h:12345678h and a privilege level of 0.
13. Describe the following descriptors. Give their type and the value of all their fields.

```
dd 01234567h, 789abcdeh
dd 30405060h, 70809010h
dd 00aabb00h, 00ffee00h
```

14. Make an EXE file, switch into protected mode, rotate an asterisk on the border of the screen, and return to real mode when the border is traversed.

16
Interfacing with High Level Languages

16.1. CALLING CONVENTIONS

To interface an assembly routine with a high level language program means to be able to call functions back and forth. And to be able to do so requires knowledge of certain behavior of the HLL when calling functions. This behavior of calling functions is called the calling conventions of the language. Two prevalent calling conventions are the C calling convention and the Pascal calling convention.

What is the naming convention

C prepends an underscore to every function or variable name while Pascal translates the name to all uppercase. C++ has a weird name mangling scheme that is compiler dependent. To avoid it C++ can be forced to use C style naming with extern “C” directive.

How are parameters passed to the routine

In C parameters are pushed in reverse order with the rightmost being pushed first. While in Pascal they are pushed in proper order with the leftmost being pushed first.

Which registers must be preserved

Both standards preserve EBX, ESI, EDI, EBP, ESP, DS, ES, and SS.

Which registers are used as scratch

Both standards do not preserve or guarantee the value of EAX, ECX, EDX, FS, GS, EFLAGS, and any other registers.

Which register holds the return value

Both C and Pascal return upto 32bit large values in EAX and upto 64bit large values in EDX:EAX.

Who is responsible for removing the parameters

In C the caller removes the parameter while in Pascal the callee removes them. The C scheme has reasons pertaining to its provision for variable number of arguments.

16.2. CALLING C FROM ASSEMBLY

For example we take a function divide declared in C as follows.

```
int divide( int dividend, int divisor );
```

To call this function from assembly we have to write.

```
push dword [mydivisor]
```

```
push dword [mydividend]
call _divide
add esp, 8
; EAX holds the answer
```

Observe the order of parameters according to the C calling conventions and observe that the caller cleared the stack. Now take another example of a function written in C as follows.

```
void swap( int* p1, int* p2 )
{
        int temp = *p1;
        *p1 = *p2;
        *p2 = temp;
}
```

To call it from assembly we have to write this.

```
[section .text]
extern _swap
x:              dd 4
y:              dd 7

push dword y
push dword x
call _swap      ; will only retain the specified registers
add esp, 8
```

Observe how pointers were initialized appropriately. The above function swap was converted into assembly by the gcc compiler as follows.

```
; swap generated by gcc with no optimizations (converted to Intel
syntax)
; 15 instructions AND 13 memory accesses
_swap:
        push ebp
        mov     ebp, esp
        sub     esp, 4                          ; space created for temp

        mov eax, [ebp+8]
        mov eax, [eax]
        mov     [ebp-4], eax                    ; temp = *p1

        mov edx, [ebp+8]
        mov eax, [ebp+12]
        mov eax, [eax]
        mov     [edx], eax                      ; *p1 = *p2

        mov edx, [ebp+12]
        mov eax, [ebp-4]
        mov [edx], eax                ; *p2 = temp

        leave  ;;;;; EQUIVALENT TO mov esp, ebp AND pop ebp ;;;;;
        ret
```

If we turn on optimizations the same function is compiled into the following code.

```
; generated with full optimization by gcc compiler
; 12 instructions AND 11 memory accesses
_swap:
        push    ebp
        mov     ebp, esp
        push    ebx

        mov     edx, [ebp+8]
        mov     ecx, [ebp+12]
        mov     ebx, [edx]
        mov     eax, [ecx]
        mov     [edx], eax
        mov     [ecx], ebx

        pop     ebx
        pop     ebp
        ret
```

16.3. CALLING ASSEMBLY FROM C

We now write a hand optimized version in assembly. Our version is only 6 instructions and 6 memory accesses.

Example 16.1

```
001     [section .text]
002     global        _swap
003     _swap:        mov  ecx,[esp+4]        ; copy parameter p1 to ecx
004                   mov  edx,[esp+8]        ; copy parameter p2 to edx
005                   mov  eax,[ecx]  ; copy *p1 into eax
006                   xchg eax,[edx]  ; exchange eax with *p2
007                   mov  [ecx],eax  ; copy eax into *p1
008                   ret                     ; return from this function
```

We assemble the above program with the following command.

- nasm –f win32 swap.asm

This produces a swap.obj file. The format directive told the assembler that it is to be linked with a 32bit Windows executable. The linking process involves resolving imported symbols of one object files with export symbols of another. In NASM an imported symbol is declared with the extern directive while and exported symbol is declared with the global directive.

We write the following program in C to call this assembly routine. We should have provided the swap.obj file to the C linker otherwise an unresolved external symbol error will come.

Example 16.1

```
001     #include <stdio.h>
002
003     void swap( int* p1, int* p2 );
004
005     int main()
006     {
007       int a = 10, b = 20;
008       printf( "a=%d b=%d\n", a, b );
009       swap(&a, &b );
010       printf( "a=%d b=%d\n", a, b );
011       system( "PAUSE" );
012       return 0;
013     }
```

EXERCISES

1. Write a traverse function in assembly, which takes an array, the number of elements in the array and the address of another function to be called for each member of the array. Call the function from a C program.
2. Make the linked list functions make in Exercise 5.XX available to C programs using the following declarations.

```
struct node {
        int data;
        struct node* next;
};
void init( void );
struct node* createlist( void );
void insertafter( struct node*, int );
void deleteafter( struct node* );
void deletelist( struct node* );
```

3. Add two functions to the above program implemented in C. The function “printnode” should print the data in the passed node using printf, while “countfree” should count the number of free nodes by traversing the free list starting from the node address stored in firstfree.

```
void printnode( struct node* );
void countfree( void );
```

4. Add the function “printlist” to the above program and implement in assembly. This function should traverse the list whose head is passed as parameter and for each node containing data (head is dummy and doesn’t contain data) calls the C function printnode to actually print the contained data.

```
void printlist( struct node* );
```

5. Modify the createlist and deletelist functions in the above program to increment and decrement an integer variable “listcount” declared in C to maintain a count of linked lists present.

17
Comparison with Other Processors

We emphasized that assembly language has to be learned once and every processor can be programmed by that person. To give a flavour of two different widely popular processors we introduce the Motorolla 68K series and the Sun SPARC processors. The Motorolla 68K processors are very popular in high performance embedded applications while the Sun SPARC processors are popular in very high end enterprise servers. We will compare them with the Intel x86 series which is known for its success in the desktop market.

17.1. MOTOROLLA 68K PROCESSORS

Motorolla 68K processors are very similar to Intel x86 series in their architecture and instruction set. The both are of the same era and added various features at the same time. The instructions are very similar however the difference in architecture evident from a programmer's point of view must be understood.

68K processors have 16 23bit general purpose registers named from A0-A7 and D0-D7. A0-A7 can hold addresses in indirect memory accesses. These can also be used as software stack pointers. Stack in 68K is not as rigit a structure as it is in x86. There is a 32bit program counter (PC) that holds the address of currently executing instruction. The 8bit condition code register (CCR) holds the X (Extend) N (Negative) Z (Zero) V (Overflow) C (Carry) flags. X is set to C for extended operations (addition, subtraction, or shifting).

Motrolla processors allow bit addressing, that is a specific bit in a byte or a bit field, i.e. a number of bits can be directly accessed. This is a very useful feature especially in control applications. Other data types include byte, word, long word, and quad word. A special MOVE16 instruction also accepts a 16byte block.

68K allows indirect memory access using any A register. A special memory access allows post increment or predecrement as part of memory access. These forms are written as (An), (An)+, and –(An). Other forms allow addressing with another regiser as index and with constant displacement. Using one of the A registers as the stack pointer and using the post increment and pre decrement forms of addressing, stack is implemented. Immediates can also be given as arguments and are preceded with a hash sign (#). Addressing is indicated with parenthesis instead of brackets.

68K has no segmentation; it however has a paged memory model. It used the big endian format in contrast to the little endian used by the Intel processors. It has varying instruction lengths from 1-11 words. It has a decrementing stack just like the Intel one. The format of instructions is "operation source, destination" which is different from the Intel order of operands. Some instructions from various instruction groups are given below.

```
Data Movement
EXG D0, D2
MOVE.B (A1), (A2)
```

```
MOVEA (2222).L, A4
MOVEQ #12, D7
Arithmetic
ADD D7, (A4)
CLR (A3)              (set to zero)
CMP (A2), D1
ASL, ASR, LSL, LSR, ROR, ROL, ROXL, ROXR (shift operations)
Program Control
BRA label
JMP (A3)
BSR label             (CALL)
JSR (A2)              (indirect call)
RTD #4                (RET N)
Conditional Branch
BCC                   (branch if carry clear)
BLS                   (branch if Lower or Same)
BLT                   (branch if Less Than)
BEQ                   (branch if Equal)
BVC                   (branch if Overflow clear)
```

17.2. SUN SPARC PROCESSOR

The Sun SPARC is a very popular processing belonging to the RISC (reduced instruction set computer) family of processors. RISC processors originally named because of the very few rudimentary instructions they provided, are now providing almost as many instruction as CISC (complex instruction set computer). However some properties like a fixed instruction size and single clock execution for most instructions are there.

SPARC stands for Scalable Processor ARChitecture. SPARC is a 64bit processor. It byte order is user settable and even on a per program basis. So one program may be using little endian byte order and another may be using big endian at the same time. Data types include byte, Halfword, Word (32bit), and Double Word (64bits) and Quadword. It has a fixed 32bit instruction size. It has a concept of ASI (Address Space Identifier); an 8bit number that works similar to a segment.

There are 8 global registers and 8 alternate global registers. One of them is active at a time and accessible as g0-g7. Apart from that it has 8 in registers (i0-i7), 8 local registers (l0-l7), and 8 out registers (o0-o7). All registers are 64bit in size. The global registers can also be called r0-r7, in registers as r8-r15, local registers as r16-r23, and out registers as r24-r31.

SPARC introduces a concept of register window. One window is 24 registers and the active window is pointed to by a special register called Current Window Pointer (CWP). The actual number of registers in the processor is in hundreds not restricted by the architecture definition. Two instruction SAVE and RESTORE move this register window forward and backward by 16 registers. Therefore one SAVE instruction makes the out register the in registers and brings in new local and out registers. A RESTORE instruction makes the in registers out registers and restores the old local and in registers. This way parameters passing and returning can be totally done in registers and there is no need to save and restore registers inside subroutines.

The register o6 is conventionally used as the stack pointer. Return address is stored in o7 by the CALL instruction. The register g0 (r0) is always 0 so loading 0 in a register is made easy. SPARC is a totally register based architecture, or it is called a load-store architecture where memory access is only allowed in data movement instruction. Rest of the operations must be done on registers.

SPARC instructions have two sources and a distinct destination. This allows more flexibility in writing programs. Some examples of instructions of this processor follow.

```
Data Movement
LDSB [rn], rn                (load signed byte)
LDUW [rn], rn                (load unsigned word)
STH [rn], rn                 (store half word)
Arithmetic
source1 = rn
source2 = rn or simm13
dest = rn
ADD r2, r3, r4
SUB r2, 4000, r5
SLL, SRA, SRL                (shifting)
AND, OR, XOR                 (logical)
Program Control
CALL                         (direct call)
JMPL                         (register indirect)
RET
SAVE
RESTORE
BA label                     (Branch Always)
BE label                     (branch if equal)
BCC label                    (branch if carry clear)
BLE label                    (branch if less or equal)
BVS label                    (branch if overflow set)
```

CS401

Computer Architecture and Assembly Language Programming

BSCS 4th semester

Final Term Short Notes + MCQS

1. Which One of the following instruction is used to return from an interrupts service routine? (page 104)

Iret

2. The fist parallel port LPTI has ports designed from____to_____ (page 125)

378,37A

3. _____is used for exporting keyboard services. (page 108)

INT 16

4. Which of the following in the priority of interrupt Request (IRQ) 0? (Page 114)

Highest

5. Each of Bits of Points_____corresponds to one of the interrupts Request (IRQ) lines. (page 115)

21

6. If the_____flag is set, then after every instruction a type 1 interrupt will be generated automatically. (page 133)

Trap OR Interrupt

7. _____is/are the point number(s) for parallel point. (page 115)

378

8. Which of the following stand for TSR? (page 121)

Terminate and Stay Resident

9. Which of the following is correct regarding the input frequency of programmable interval timer (PIT)? (Page 122)

It is Fixed

10. At the end of servicing an interrupt _____signal is used to inform the programmable interrupt controller (PIC) about it. (page 114)

EOI

11. In programmable interrupt controller which of the following ports is referred as interrupt mask register?
    a. 19
    b. 20
    c. 21
    d. 22
12. _____is the highest priority interrupt in interrupt controller
    a. IRQ 0
    b. IRQ 1
    c. IRQ 2
    d. IRQ 3
13. IRET returns on the basis of _____ and _____
    a. CS, IP
    b. DS, IP
    c. CS, SS

AL-JUNAID INSTITUTE

d. IP, SP

14. If _____ is set, the after every instruction a type 1 interrupt will be automatically generated.
    a. Parity flag
    b. Trap flag
    c. Carry flag
    d. Overflow flag
15. The interrupt handler uses _____instruction to return back to the caller.
    a. IRET
    b. RETI
    c. INTR
    d. RET
16. Which of the following interrupt is used for Arithmetic overflow?
    a. INT 1
    b. INT 2
    c. INT 3
    d. INT 4
17. During the execution of INT instruction , some contents are pushed on to the stack , the order of pushing then is
    a. CS , IP and then FLAGS register
    b. IP,CS and then FLAGS register
    c. FLAGS register, CS and then IP
    d. FLAGS register, IP and the CS
18. Each of the bits at port _____corresponding to one of the IRQ lines.
    a. 18
    b. 19
    c. 20
    d. 21
19. Which of the following pins of the parallel port connector are grounded?
    a. 10-18
    b. 18-25
    c. 25-32
    d. 32-39
20. Which of the following interrupts plays the most significant part during step debugging of a program?
    a. INT 0
    b. INT 1
    c. INT 2
    d. INT 3
21. Which of the following IRQs is connected to serial port COM 2?
    a. IRQ 0
    b. IRQ 1
    c. IRQ 2
    d. IRQ 3
22. Which of the following IRQs is connected to serial port COM 1?
    a. IRQ 4

AL-JUNAID INSTITUTE

b. IRQ 5
c. IRQ 6
d. IRQ 7

23. Which of the following IRQs is used by the parallel port?
    a. IRQ 4
    b. IRQ 5
    c. IRQ 6
    d. IRQ 7
24. In programmable interrupt controller which of the following ports is used to selectively enabling or disabling interrupts?
    a. 19
    b. 20
    c. 21
    d. 22
25. The space where all the registers of task are stored is called _____
    a. Control block
    b. Process control block
    c. Stack
    d. Memory
26. Which of the following is the destination register in IN instruction?
    a. AL or AX
    b. BL or BX
    c. CL or CX
    d. DL or DX
27. Which of the following interrupts is used for saving and restoring the registers
    a. INT 6
    b. INT 7
    c. INT 8
    d. INT 0
28. In multitasking environment, which of the following structure is used to maintain the ordering of active PCBs?
    a. Array
    b. Register
    c. Linked List
    d. Stack
29. In multitasking which of the following interrupts is used as scheduler during context switching?
    a. INT 21
    b. INT 16
    c. INT 13
    d. INT 8
30. Which of the following are required for thread entry?
    a. CS and DS
    b. CS and IP
    c. IP and general purpose registers
    d. SS and SP

AL JUNAID INSTITUTE

31. The time interval between two timer tick is?
    a. 40 ms
    b. 45 ms
    c. 50 ms
    d. 55 ms
32. Which of the following flag can be used for mathematical operations?
    a. Direction Flag
    b. Carry Flag
    c. Trap Flag
    d. Interrupt Flag
33. In multi tasking, the process of saving and restoring to values of registers from a process control block (PCB) is called _____
    a. Context switching
    b. Context saving
    c. Context restoring
    d. Code switching
34. When two devices in a system want to use the same IRQ line, is referred as:
    a. IRQ Collision
    b. IRQ Conflict
    c. IRQ Crash
    d. IRQ Blockage
35. An End of Interrupt (EOI) signal is sent by
    a. Handler
    b. Processor
    c. IRQ
    d. PIC
36. Which of the following is the BIOS interrupt providing keyboard service?
    a. INT 0x13
    b. INT 0x14
    c. INT 0x15
    d. INT 0x16
37. Threads can have function calls, parameters and _____ variables.
    a. Global
    b. Local
    c. Legal
    d. Illegal
38. Which of the following arranges jobs in a sequence in order to be executed?
    a. Process control block
    b. Arranger
    c. Control unit
    d. Scheduler
39. Which of the following flags cannot be cleared using an assembly instruction?
    a. Trap flag
    b. Interrupt flag
    c. Direction flag
    d. Carry flag

AL-JUNAID INSTITUTE

40. Which of the following is the highest priority interrupt?
    a. INT3
    b. INT2
    c. INT1
    d. INT0
41. At the end of servicing an interrupt, which of the following is used to inform tha PIC that it is completed?
    a. RET
    b. EOI
    c. IRET
    d. RET N
42. Which of the following interrupts is used for maintaining the system time?
    a. INT 0
    b. INT 1
    c. INT 8
    d. INT 10
43. Which of the following is used for exporting parallel port services?
    a. INT 17
    b. INT 16
    c. INT 15
    d. INT 8
44. In programmable interrupt controller which of the following ports is referred as a control port?
    a. 19
    b. 20
    c. 21
    d. 22
45. The first parallel port LPT1 has port number designated from _____.
    a. 178 to 17A
    b. 278 to 27A
    c. 378 to 37A
    d. 478 to 47A
46. _____ is/are the port number(s) for parallel port.
    a. 20 and 21
    b. 60 to 64
    c. 380
    d. 378
47. The number of pins in a parallel port connector are?
    a. 20
    b. 25
    c. 30
    d. 35
48. The offset address of an interrupt n will be at
    a. n
    b. nx2
    c. nx3

AL-JUNAID INSTITUTE

d. nx4

49. Programmable interrupt controller has two ports (20 and 21). Port 20 is the control port while port 21 is _____.
    a. The interrupt mask register
    b. Interrupt port
    c. Output port
    d. Input port
50. Which of the following instruction selects memory address space?
    a. MOV
    b. DEC
    c. IN
    d. ADD
51. The thread registration code initializes the PCB and adds it to the linked list so that the _____ will give it a turn.
    a. Assembler
    b. Scheduler
    c. Linker
    d. Debugger
52. Which of the following instruction is used for disabling all the interrupts during a program execution?
    a. Cli
    b. Sti
    c. Reti
    d. Iret
53. IBM AT has how many PICs (Programmable interrupt controller)
    a. 1
    b. 2
    c. 3
    d. 4
54. Programmable interrupt controller (PIC) has
    a. One input signals and eight output signals
    b. One input signal and one output signal
    c. Eight input signals and one output signals
    d. Eight input signals and eight output signals
55. In 8088 processor, there can be total _____ possible entries in an interrupt vector table.
    a. 256
    b. 64
    c. 128
    d. 512
56. Each thread can have their own
    a. Execution area
    b. Stack
    c. Memory
    d. Array
57. The parallel port connector is called ?
    a. DB-25

AL JUNAID INSTITUTE

b. BD-25
c. DB-24
d. BD-24

58. In 8088, the physical memory address for Interrupt Vector Table is fixed and the table occupies exactly _____ of memory.
a. 1 KB
b. 1 MB
c. 64 KB
d. 4 Bytes

59. Which of the following interrupts is non maskable interrupt?
a. INT 0
b. INT 1
c. INT 2
d. INT 3

60. Using OUT instruction on parallel data port results into a signal of _____ for every 1 bit.
a. 0 V
b. 1 V
c. 5 V
d. 10 V

61. PCB stands for?
a. Process Control Block
b. Process Cleaning Block
c. Programmable Counter Block
d. Programs Control Block

62. Which of the following interrupts is used in debugging with the trap flag?
a. INT 0
b. INT 1
c. INT 2
d. INT 3

63. Which of the following port number is used to send an end of interrupt (EOI) signal to the PIC after an interrupt is ended?
a. 0x16
b. 0x20
c. 0x60
d. 0x378

64. Which of the following instruction is used for reading a char from keyboard?
a. out al, 0x60
b. in al, 0x60
c. out dx, al
d. out dx, 0x378

65. In PIC, which of the following port is used for selectively enabling or disabling interrupts?
a. 19
b. 20
c. 21
d. 22

AL JUNAID INSTITUTE

66. DOS has single entry point to access all its services through interrupt_____
    a. INT 21
    b. INT 16
    c. INT 2
    d. INT 10
67. Which of the following pins of parallel port are used to carry the data from processor to the device connected through parallel port?
    a. Pin 2 to pin 9
    b. Pin 10
    c. Pin 4
    d. Pin 18 to pin 25
68. The input frequency of the programmable interval timer(PIT) is
    a. Fixed
    b. Depends on processor block
    c. Variable
    d. Depends on hardware attached
69. All registers of task are stored in space called _____
    a. Process storage block
    b. Process control block
    c. Process terminal
    d. Swapping space
70. Which of the following IRQ`s is derived by a key board
    a. IRQ 0
    b. IRQ 1
    c. IRQ 2
    d. IRQ 3
71. The programmable interval timer (PIT) has input frequency of
    a. 1.193MHz
    b. 2.193MHz
    c. 3.193MHz
    d. 4.193MHz
72. Changing and restoring the state of Control processing unit (CPU) is referred as
    a. Thrashing
    b. Multitasking
    c. Context Switching
    d. Multithreading
73. For the external hardware to generate an interrupt there are how many pins outside the processor?
    a. 1
    b. 2
    c. 3
    d. 4
74. Which of the following instruction selects peripheral address space?
    a. MOV
    b. DEC
    c. IN

ALJUNAID INSTITUTE

d. ADD

75. Which of the following is the most commonly used port with printer?
    a. Serial Port
    b. USB port
    c. Parallel Port
    d. DVI Port
76. _____allows us to execute one instruction at a time rather than the whole program at once
    a. INT 0
    b. INT 1
    c. INT 2
    d. INT 3
77. Which of the following is used for exporting keyboard services?
    a. INT 16
    b. INT 11
    c. INT 12
    d. INT 8
78. TSR stands for
    a. Terminate and store routines
    b. Transmits and save resources
    c. Terminate and Stay resident
    d. Truncate and start recursively
79. Which of the following interrupts is of highest priority interrupt?
    a. Key Board Interrupt
    b. Timer Interrupt
    c. INT 2
    d. INT 3
80. In older computers, the port number designed for parallel pert LPT2 are_____
    a. 078-07A
    b. 178-17A
    c. 278-27A
    d. 378-37A
81. Which of the following is the ACK pin in DB-25 Connector
    a. 10
    b. 11
    c. 12
    d. 13
82. Which of the following IRQs is a cascading interrupt?
    a. IRQ 0
    b. IRQ 1
    c. IRQ 2
    d. IRQ 3
83. In interrupt masking, we use _____ to get control from the program without letting the program know about it.
    a. IRQ 0
    b. IRQ 1

AL JUNAID INSTITUTE

c. IRQ 5
d. IRQ 7

84. The output of programmable timer interval is connected to which line of the PIC?
a. IRQ 0
b. IRQ 1
c. IRQ 2
d. IRQ 3

85. Which of the following IRQs is used for Floppy disk drive?
a. IRQ 4
b. IRQ 5
c. IRQ 6
d. IRQ 7

86. In multitasking, each PCB requires _____ bytes to store the values of registers.
a. 14
b. 28
c. 32
d. 16

87. Which of the following IRQs is used for sound card or network card?
a. IRQ 4
b. IRQ 5
c. IRQ 6
d. IRQ 7

88. Programmable interrupt controller has _____ ports.
a. 1
b. 2
c. 3
d. 4

89. Which of the following bits of parallel control port enables the IRQ 7 triggering by the ACK pin?
a. Bit 1
b. Bit 2
c. Bit 3
d. Bit 4

90. Which of the following IRQs is derived by a timer device?
a. IRQ 0
b. IRQ 1
c. IRQ 2
d. IRQ 3

91. _____is a special type of interrupt that returns to the same instruction instead f the next instruction
a. Divide overflow
b. Debug interrupt
c. Arithmetic overflow interrupt
d. Change the sign interrupt

92. All the registers & stack are saved in
a. Multitasking

AL JUNAID INSTITUTE

b. Multi-Processing
c. Function call
d. BIOS

93. Which of the following is the source register in OUT instruction?
a. AL or AX
b. BL or BX
c. CL or CX
d. DL or DX

94. Which of the following is the destination register in IN instruction?
a. AL or AX
b. BL or BX
c. CL or CX
d. DL or DX

95. In the context of video service, if we want to set the cursor at top left corner, which of the values will be stored in DH and DL respectively?
a. 00.00 page 141
a. 00.80
b. 25.80
c. 0.01

96. Which of the following INT 21 service is used to read character from standard input?
a. 00
b. 01 page 144
b. 02
c. 03

97. "INT13-BIOS disk service" generally uses which register to return the "error flag"?
a. CF page 148
a. DL
b. AH
c. AL

98. Which of the following service of INT 10 is used to get the video font information?
a. 1129h
b. 1130h page 142
b. 1128h
c. 1127h

99. Which of the following service of INT 10 is used to write graphic pixel on the screen?
a. 0x0A
b. 0x0B
c. 0x0C page 144
c. 0x0D

100. On executing INT 0x21-service 0x3D, if file is successfully opened then
a. CF will contain 1

ALUNAID INSTITUTE

b. CF will contain 0
c. ZF will contain 1
d. ZF will contain 0

101. On executing INT 0x21-service 0x3D, if file can't be opened then
a. CF will contain 1
b. CF will contain 0
c. ZF will contain 1
d. ZF will contain 0

102. Device drivers can be divided into _____ major categories
a. 5
b. 4
c. 3
d. 2

103. We can set the current file position in DOS using service number _____
a. 0x38
b. 0x40
c. 0x42 page 154
e. 0x43

104. COM1 is accessible via ports _____ while COM2 is accessible via _____
a. 3FD, 3F9
b. 2F8-2FF, 3F8-3FF
c. 3F9, 3FD
d. 3F8-3FF, 2F8-2FF page 164

105. In the context of vides services, if we want to write string then which of the value will be placed in AH?
a. 10h
b. 12h
c. 11h
d. 13h page 142

106. In the context of video service, if we want to scroll the window up which of the following will be value of AH?
a. AH = 05h
b. AH = 06h page 141
a. AH = 07h
b. AH = 08h

107. In the context of video services, if we want to set cursor position which of the following will be the value of AH?
a. AH = 01h
b. AH = 02h page 139

ALJUNAID INSTITUTE

c. AH = 03h
d. AH = 04h

108. Which standard format is used for sending data on the serial port?
a. Full duplex
b. BIOS INT 14
c. RS232 page 163
d. COM1

109. INT 0x13 service 0x08 is use to _____
a. Read disk sector
b. Write disk sector
c. Reset disk sector
d. Get drive parameter page 148

110. Parameters pushed to the routine in _____ order with the rightmost being pushed first using language
a. Reverse page 179
b. Proper
c. Forward
d. Same

111. Parameters pushed to the routine in _____ order with the left most being pushed first using Pascal language
a. Proper page 179
b. Same
c. Reverse
d. Forward

112. _____ symbol is added to any function or variable using the C language naming convention
a. Underscore page 177
b. #
c. &
d. @

113. Which of the following BIOS INT provides serial port services
a. INT 21
b. INT 14 page 163
c. INT 10
d. INT 08

114. A 32-bit address register can access up to _____ of memory
a. 2 MB
b. 2 GB
c. 4 MB
d. 4 GB page 167

AL JUNAID INSTITUTE

115. . BIOS video services are exported via interrupt
   a. INT 10 page 139
   b. INT 9
   c. INT 8
   d. INT 7

116. Which of the following is used to terminate a string in assembly language?
   a. !
   b. #
   c. $
   d. ;

117. The bits are sent one by one in specially formatted fashion on the_____
   a. Half duplex
   b. Parallel port
   c. Full duplex
   d. Serial port page 163

118. In VESA defined modes _____bits for every pixel are organized
   a. 8 color
   b. 16 color page 172
   c. 32 color
   d. 64 color

119. What is the abbreviation VESA _____ and VBE _____
   a. Video Electrical System Association, VGA BIOS Extensions
   b. Video Electronics Standards Administration , Video Bus Extensions
   c. Video Electronics Standard Association, Video BIOS Extensions page 172
   d. VGA Electronics Standard Association, Video BIOS External

120. Which of the following services of INT 21 is used to write a string on standard output?
   a. 00h
   b. 02h
   c. 09h page 144
   d. 10h

121. In 9pin DB 9 connector, which pin is assigned to RD (Received Data)?
   a. 1
   b. 2 page 163
   c. 3
   d. 4

122. The maximum length of DOS command line parameters is
   a. 64 bit

AL-JUNAID INSTITUTE

b. 127 bits
c. 256 bits
d. 512 bits

123. In C _____ is responsible for removing the parameters.
a. Clear
b. Callee
c. Caller page 179
d. Stack

124. While using INT 10 for writing graphic pixel on screen, which of the following registers hold the information about pixel color?
a. DH
b. DL
c. AH
d. AL page 144

125. . As compared to _____ , _____ provides more cooked services.
a. BIOS, DOS page 144
b. DOS, OS
c. DOS, BIOS
d. OS, DOS

126. _____ Register is used for storing the base and limit of GDT.
a. LGDT
b. GDTR page 168
c. Null Descriptor
d. LDT

127. INT13-BIOS disk service" generally uses which register to return the "error code"?
a. CF
b. DL
c. AH page 148
d. AL

128. In case of COM File, first command line parameter is stored at _____ offset of 'Program segment prefix'
a. 0x80
b. 0x82
c. 0x84
d. 0x86

129. New devices are allowed to work with the existing operating system with the help of
_____.
a. Sockets

AL JUNAID INSTITUTE

b. Port addresses
c. BIOS
d. Device drivers page 158

130. _____ byte of DOS data buffer stores the maximum characters buffer can hold.

a. First page 144
b. Second
c. Third
d. Last

131. The register size of 386 architecture is _____

a. 16 bit
b. 32 bit page 167
c. 20 bit
d. 4 GB

132. Com 1 is connected with

a. IRQ 2
b. IRQ 3
c. IRQ 4 page 106
d. IRQ 5

133. Which of the following services of INT 10 is used for writing the string?

a. 0x12
b. 0x13 page 142
c. 0x11
d. 0x10

134. The first entry of the GDT must always be zero, it is called the _____

a. Null Descriptor page 168
b. Data Descriptor
c. Code Descriptor
d. Global Descriptor Table

135. The first sector on hard disk contains the

a. Hard disk
b. Partition table page 150
c. Data size
d. Sector size

136. BIOS video services are broadly classified into _____categories

a. 1
b. 2 page 140
c. 3
d. 4

AL-JUNAID INSTITUTE

137. In case of COM file, maximum length of parameters passed through command line can be _____
   a. 63 bytes
   b. 127 bytes
   c. 255 bytes
   d. 511 bytes

138. In Pascal _____ is responsibility for removing the parameters
   a. Stack
   b. Clear
   c. Caller
   d. Callee page 179

139. Hard disk MBR (Master Boot record) is of size
   a. 446 bytes page 150
   b. 350 bytes
   c. 512 bytes
   d. 256 bytes

140. In 9pin DB 9 connector , which pin is assigned to Signal Ground
   a. 3
   b. 4
   c. 5 page 163
   d. 6

141. Two prevalent calling conventions are the _____ and _____
   a. C# calling convention, Java calling convention
   b. C calling convention, Pascal Calling convention page 179
   c. C++ calling convention, Java calling convention
   d. C++ calling Convention, Python calling Convention

142. Com2 is connected with
   a. IRQ 2
   b. IRQ 3 page 106
   c. IRQ 4
   d. IRQ 5

143. BPB stands for
   a. Basic Parameter Block
   b. BIOS Precise Block
   c. Basic Precise Block
   d. Bios Parameter Block page 159

144. While writing graphic pixel on the screen, which registers hold the value for setting cursor position?
   a. AX, BX
   b. AX, CX

ALHAMD INSTITUTE

c. BX, CX
d. CX, DX

145. The VESA VBE 2.0 standard include a _____ mode which allows direct access to the whole video memory.
a. Parallel frame buffer
b. Liner frame buffer page 172
c. Real
d. Protected

146. In 9pin DB 9 connector, which pin is assignment to TD (Transmitted Data)?
a. 1
b. 2
c. 3
d. 4

147. INT 0x13 service 0x03 is used to _____
a. Read disk sector
b. Write disk sector page 148
c. Reset disk sector
d. Get drive parameter

148. Serial port services are provided by the _____
a. BIOS INT 11
b. BIOS INT 14 page 163
c. BIOS INT 13
d. RS232

149. Which of the following register hold the page number for using the write string service of INT 10?
a. AH
b. BL
c. CL
d. BH page 144

150. The "program segment prefix" for com file is of _____size
a. 64bytes
b. 128 bytes
c. 256 bytes
d. 512 bytes

151. Which of the following registers are used as DOS input buffer
a. DS, AX
b. SS, SP
c. DS, DX page 144
d. CS:BX

ALJUNAID INSTITUTE

152. Which register is generally used to specify the service number of an interrupt
   a. DX
   b. AX page 100
   c. BX
   d. CX

153. The root directory of floppy contains _____fixed entries
   a. 64
   b. 256
   c. 128
   d. 512 page 156

154. In FAT32 file system directory entry in DOS consist of how many bytes?
   a. 16
   b. 24
   c. 32 page 147
   d. 64

155. _____ is the highest priority interrupt in interrupt controller
   a. IRQ 0 page 106
   b. IRQ 1
   c. IRQ 2
   d. IRQ 3

156. Operating system organize data in form of
   a. Folder
   b. Batch file
   c. File page 153
   d. None of given

157. The higher 16 bit of EAX register are labeled as
   a. AX
   b. EAH
   c. AH
   d. None of given

158. _____is special type of interrupt that returns to the same instruction instead of the next instruction. (page 107)

Divide overflow interrupt

159. In Intel 8088, there are total of____possible interrupt vectors in an interrupt vector table. (page 105)

256

160. Which of the following pins of DB-256 connector are ground? (page 125)

18-25

161. Which of the following interrupts is used for saving and restoring the register? (page141)

AL-JUNAID INSTITUTE

INT 08

162. Which of the following instructions is used to read a character from the keyboard port? (page

INT al, Ox60

163. In Intel 8088, the interrupt vector Table occupies ____ of memory.

1 KB NOT Sure (GOOGLE)

164. Which of the following interrupt request is used for a floppy disk drive? (Page 114)

IRQ 6

165. Which of the following interrupt request is used for a parallel ports? (page 114)

IRQ 7

166. Which of the following is the order of pushing the contents on stack during the execution of INT instruction?

Flags, CS and Then IP

167. Which of the following interrupt request (IRQ) is connected to the serial Ports COM2? (Page 114)

IRQ 3

168. Which of the following interrupt request (IRQ) is connected to the sound card or the network card or the modem? (Page 114)

IRQ 5

169. Which of the following interrupt request (IRQ) is connected to the serial Ports COM1? (Page 114)

IRQ 4

170. Which of the following Interrupts play the most significance part during single step debugging of a program? (Page 105)

INT 1

171. Which of the following is the highest priority interrupt? (Page 114)

INT 08

172. An end of interrupt (EOI) signal is sent by the _____ (Page 114)

Interrupt Handler

173. Which of the following flags can be used in mathematical operation? (Page 133)

Carry flag

174. The thread registration code initializes the process control block (PCB) and adds it to the linked list. The_____ then gives it a turn. (Page 141)

Scheduler

175. Which of the following IRQs is derived by a keyboard? (Page 114)

IRQ 1

176. Which of the following IRQs is the cascading interrupt connected to the output of the second 8451? (Page 114)

IRQ 2

177. The space where all the registers of task are stored is called _____ (page 140)

AL JUNAID INSTITUTE

Process Control Block OR PCB

178. Which of the following is the destination register in IN instruction? (Page 115)

AL OR AX

179. Which of the following interrupt is used for Arithmetic overflow? (page 106)

INT 4

180. Which of the following interrupt is used for NMI-Non Mask Able? (Page 105)

INT 2

181. Which of the following interrupt Trap, Single step? (Page 105)

INT 1

182. Which of the following interrupt Division by zero? (Page 105)

INT 0

183. IRET returns on the basis of _____ and _____ (Page 104)

CS and IP

184. Which of the following interrupts is used for saving and restoring the registers? (Page 141)

INT 08 OR INT 8

185. The time interval between two timer tick is. (Page 122)

55ms

186. When two devices in a system want to use the same IRQ line, is referred as. (Page 114)

IRQ Conflict

187. Which of the following is the BIOS interrupt providing keyboard service? (Page 110)

INT 0x16

188. Threads can have function calls, parameters and _____ variables. (Page 141)

LOCAL

189. Which of the following flags cannot be cleared using an assembly instruction?

Trap Flag

190. In older computers, the port number designed for parallel pert LPT2 are_____ (Page 125)

278-27A

191. Which of the following instruction selects memory address space? (Page 115)

MOV

192. Which of the following port number is used to send an end of interrupt (EOI) signal to the PIC after an interrupt is ended? (Page 124)

0x20

193. The parallel port connector is called? (Page 125)

DB-25

194. The interrupt mask register which can be used for enabling or disabling interrupts is associated with. (Page 115)

21

Short Notes:

Leacture 10

The three flags not used for mathematical operations are:

1. the direction flag,
2. the interrupt flag and
3. the trap flags

If the **trap flag is set**, the after every instruction a type 1 interrupt will be automatically generated. This is named as the single step interrupt. This is like the divide by zero interrupt which was never explicitly invoked but it came itself. The debugger is made using this interrupt.

INT 1 function: It allows one instruction to be executed and then return control to us. It has its display code and its code to wait for the key in the INT 1 handler. Therefore, after every instruction the values of all registers are shown and the debugger waits for a key.

Another interrupt used by the debugger is **the break point interrupt INT 3**.

INT 3 has a single byte opcode so it can replace any instruction. To put a breakpoint, the instruction is replaced with INT 3 opcode and restored in the INT 3 handler. The INT 3 opcode is placed again by a single step interrupt that is set up for this purpose after the replaced instruction has been executed.

Note: There is no instruction to set or clear the trap flag like there are instructions for the interrupt and direction flags.

PUSHF and POPF:

We use two special instructions PUSHF and POPF to push and pop the flag from the stack.

We use PUSHF to place flags on the stack, change TF in this image on the stack and then reload into the flags register with POPF. The single step interrupt will come after the first instruction after POPF.

The interrupt mechanism automatically clears IF and TF otherwise there would an infinite recursion of the single step interrupt.

The TF is set in the flags on the stack so another interrupt will come after one more instruction is executed after the return of the interrupt.

Leacture 11:

AL-JUNAID INSTITUTE

To get control from the program without the program knowing about it, we can use the **IRQ 0** highest priority interrupt that is periodically coming to the processor.

PCB:

The space where all registers of a task are stored is called the process control block or PCB.

INT 08 that is saving and restoring the registers is called the scheduler and the whole event is called a context switch.

Threads can have function calls, parameters and local variables etc.

How to improve the slowdown in the speed of multitasking:

As keys are pressed and new threads are registered, there is an obvious slowdown in the speed of multitasking. To improve that, we can change the timer interrupt frequency. The following can be used to set to an approximately 1ms interval:

```
mov ax, 1100
out 0x40, al
mov al, ah
out 0x40, al
```

This makes the threads look faster.

Leacture 12:

The **video services** are exported via **INT 10.**

Classification of Video services:

1. graphics mode services and
2. text mode services.

In graphics mode a location in video memory corresponds to a dot on the screen.

In text mode, the video memory holds the ASCII of the character to be shown and the actual shape is read from a font definition stored elsewhere in memory.

A list of common **video services** used in text mode.

INT 10 - VIDEO - SET VIDEO MODE

AH = 00h

AL = desired video mode

Some **common video modes** include 40x25 text mode (mode 0), 80x25 text mode (mode 2), 80x50 text mode (mode 3), and 320x200 graphics mode (mode D).

INT 10 - VIDEO - SET TEXT-MODE CURSOR SHAPE

AH = 01h

CH = cursor start and options

AL-JUNAID INSTITUTE

CL = bottom scan line containing cursor (bits 0-4)

INT 10 - VIDEO - SET CURSOR POSITION

AH = 02h
BH = page number
0-3 in modes 2&3
0-7 in modes 0&1
0 in graphics modes
DH = row (00h is top)
DL = column (00h is left)

INT 10 - VIDEO - SCROLL UP WINDOW

AH = 06h
AL = number of lines by which to scroll up (00h = clear entire window)
BH = attribute used to write blank lines at bottom of window
CH, CL = row, column of window's upper left corner DH,
DL = row, column of window's lower right corner

Leacture 14:


Serial port:

Serial port is a way of communication among two devices just like the parallel port.

Difference b/w parallel and serial ports:

The basic difference is that whole bytes are sent from one place to another in case of parallel port while the bits are sent one by one on the serial port in a specially formatted fashion.

The serial port connection is a 9pin DB-9 connector with pins assigned as shown below.



The data on the serial port is sent in a standard format called **RS232 communication**.

Start bit, data bit, parity bit and stop bit:

JUNAID INSTITUTE

The data starts with a 1 bit called the start bit, then five to eight data bits, an optional parity bit, and one to two 0 bits called stop bits.

The number of data bits, parity bits, and the number of stop bits have to be configured at both ends. Also, the duration of a bit must be precisely known at both ends called the baud rate of the communication.

The **BIOS INT 14** provides serial port services.

Limitation in using BIOS:

A major limitation in using BIOS is that it does not allows interrupt driven data transfer, i.e. we are interrupted whenever a byte is ready to be read or a byte can be transferred since the previous transmission has completed. To achieve this, we have to resort to direct port access.

Important BIOS services regarding the serial port are discussed below:

INT 14 - SERIAL - INITIALIZE PORT

AH = 00h
AL = port parameters
DX = port number (00h-03h)
Return:
AH = line status
AL = modem status

Modem status is not used in direct serial communication.

The port parameters in AL consist of the baud rate, parity scheme, number of stop bits, and number of data bits.

INT 14 - SERIAL - WRITE CHARACTER TO PORT

AH = 01h
AL = character to write
DX = port number (00h-03h)
Return:
AH bit 7 = error flag
AH bits 6-0 = port status

INT 14 - SERIAL - READ CHARACTER FROM PORT

AH = 02h
DX = port number (00h-03h)
Return:
AH = line status
AL = received character if AH bit 7 clear

AL-JUNAID INSTITUTE

INT 14 - SERIAL - GET PORT STATUS
AH = 03h
DX = port number (00h-03h)
Return:
AH = line status
AL = modem status
Serial port access:

Serial port is also accessible via I/O ports.

COM1 is accessible via ports 3F8-3FF while **COM2** is accessible via 2F8-2FF.

The first register at **3F8** (or 2F8 for the other port) is the transmitter holding register if written to and the receiver buffer register if read from.

3F9 whose bit 0 must be set to enable received data available interrupt and bit 1 must be set to enable transmitter holding register empty interrupt.

Bit-0 of **3FA** is set if an interrupt is pending and its bits 1-3 identify the cause of the interrupt.

The three-bit causes are as follows:
110 (16550, 82510) timeout interrupt pending
101 (82510) timer interrupt
100 (82510) transmit machine
011 receiver line status interrupt. priority=highest
010 received data available register interrupt. priority=second
001 transmitter holding register empty interrupt. priority=third
000 modem status interrupt. priority=fourth

The register at **3FB** is line control register while the one at **3FD** is line status register.

The register at **3FC** is the modem control register. Bit-3 of this register must be set to enable interrupt generation by the serial port.

Leacture 15:

Protected Mode:

Switching processor in the newer 32-bit mode is a very easy task. Just turn on the least significant bit of a new register called CR0 (Control Register 0) and the processor switches into 32-bit mode called protected mode. However, manipulations in the protected mode are very different from those in the read mode.

Extended registers:

All registers in 386 have been extended to 32-bits. The new names are EAX, EBX, ECX, EDX, ESI, EDI, ESP, EBP, EIP, and EFLAGS. The original names refer to the lower 16-bits of these registers.

AL-JUNAID INSTITUTE

A 32-bit address register can access up to 4GB of memory so memory access has increased a lot.

Segment selectors:

We call segment registers as segment selectors and they are still 16-bits wide. We are also given two other segment selectors FS and GS for no specific purpose just like ES.

The working of segment registers as being multiplied by 10 and added into the offset for obtaining the physical address is totally changed.

Working of segment selector:


Now the selector is just an index into an array of segment descriptors where each descriptor describes the base, limit, and attributes of a segment.

Role of selector is to select on descriptor from the table of descriptors and the role of descriptor is to define the actual base address.

For example, an operating system can define the possible descriptors for a program and the program is bound to select one of them and nothing else. This sentence also hints that the processor has some sense of programs that can or cannot do certain things like change this table of descriptors. This is called the privilege level of the program and varies for 0 (highest privilege) to 3 (lowest privilege).

Format of a selector:

The format of a selector is shown below.



The table index (TI):

TI is set to 0 to access the global table of descriptors called the GDT (Global Descriptor Table).

It is set to 1 to access another table, the local descriptor table (LDT).

RPL:

AL-JUNAID INSTITUTE

RPL is the requested privilege level that ranges from 0-3 and informs what privilege level the program wants when using this descriptor.

Index:

The 13-bit index is the actual index into the GDT to select the appropriate descriptor. 13 bits mean that a maximum of 8192 descriptors are possible in the GDT.

GDT:

The GDT itself is an array of descriptors where each descriptor is an 8-byte entry. The base and limit of GDT is stored in a 48-bit register called the **GDTR.**

This register is loaded with a special instruction LGDT and is given a memory address from where the 48-bits are fetched.

The first entry of the GDT must always be zero. It is called the null descriptor. After that any number of entries up to a maximum of 8191 can follow.

Format of code & data descriptor:

The format of a code and data descriptor is shown below.

code (application) segment descriptor

offset	31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
+4	BASE (bit31..24)								G	D	r.	AVL	LIMIT (bit19..16)				P	DPL		S=1	X=1	C	R	A	BASE (bit23..16)							
+0	BASE (bit15..0)																LIMIT (bit15..0)															

data (application) segment descriptor

offset	31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
+4	BASE (bit31..24)								G	B	r.	AVL	LIMIT (bit19..16)				P	DPL		S=1	X=0	E	W	A	BASE (bit23..16)							
+0	BASE (bit15..0)																LIMIT (bit15..0)															

The **32-bit base** in both descriptors is scattered into different places because of compatibility reasons.

The **limit** is stored in 20 bits but the **G bit** defines that the limit is in terms of bytes of 4K pages therefore a maximum of 4GB size is possible.

The **P bit** must be set to signal that this segment is present in memory.

DPL is the descriptor privilege level again related to the protection levels in 386.

D bit defines that this segment is to execute code is 16-bit mode or 32bit mode.

195. is conforming bit.

R signals that the segment is readable.

A bit is automatically set whenever the segment is accessed.

The combination of **S** (system) and **X** (executable) tell that the descriptor is a code or a data descriptor.
B (big) bit tells that if this data segment is used as stack SP or ESP is used.

VESA and VBE:

VESA is the Video Electronics Standards Association and VBE is the set of Video BIOS Extensions proposed by them. The VESA VBE 2.0 standard includes a linear frame buffer mode. This mode allows direct access to the whole video memory.

Some important VESA services are listed below:

INT 10 – VESA – Get SuperVGA Information
AX = 4F00h
ES:DI -> buffer for SuperVGA information
Return:
AL = 4Fh if function supported
AH = status
INT 10 – VESA – Get SuperVGA Mode Information
AX = 4F01h
CX = SuperVGA video mode
ES:DI -> 256-byte buffer for mode information
Return:
AL = 4Fh if function supported
AH = status
ES:DI filled if no error
INT 10 – VESA – Set VESA Video Mode
AX = 4F02h
BX = new video mode

AL-JUNAID INSTITUTE

Return:
AL = 4Fh if function supported
AH = status

VESA mode 4117:

One of the VESA defined modes is 4117 which is a 1024x768 mode with 16-bit color and a linear frame buffer. The 16 color bits for every pixel are organized in 5:6:5 format with 5 bits for red, 6 for green, and 5 for blue. This makes 32 shades of red and blue and 64 shades of green and 64K total possible colors. The 32-bit linear frame buffer base address is available at offset 28 in the mode information buffer.


INTERRUPT HANDLING

Handling interrupts in protected mode is also different. Instead of the IVT at physical address 0 there is the IDT (interrupt descriptor table) located at physical address stored in IDTR, a special purpose register.

IDTR:

The IDTR is also a 48-bit register similar in structure to the GDTR and loaded with another special instruction LGDT.

The format of the interrupt descriptor is as shown below:



The **P** and **DPL** have the same meaning as in data and code descriptors.

The **S bit** tells that this is a system descriptor while the 1110 following it tells that it is a 386-interrupt gate.

Past PAPERS

41.Why memory to memory move is not allow in 8088 processor architecture?

42.following are three INT 13 Disk of Bios write services number against each service?

1 .get drive perameter

.read disk sector

.write disk sector

43. Difference between the order of parameter passing in pascal and C?

44.In multitasking environment,which process is used to store and restore states of process

45.which basic system programs are used to stard the computer

46.explain following four lines

1 mov si,l2

```
mov al,[cs:si]
mov [opcode],al
mov byte [cs:si],0xCC
```

47.which instructions are used to call subordinate and then get back to the same point where the function was called? explain these intstruction with help of example

48.what are the important " command codes" in real header of device drivers?

49. How interrupt handling in protected mode is different than the interrupt handling in real mode

50. Suppose you desire to work on computer system and you switch on the computer, identify which service is executed to boot the computer system and also explain the main responsibilities of the services?

In truncated file service which register read service and file attributes

2.SACS instruction works?

3.which interrupt is called scheduler.which main purpose of that.

4.which interrupt interrupt and control back to dos.write name of interrupt and service number.

5.serial port intiziltaion service number and also write attributes of it with service number those initialize them.

6.physical address btna tha

7.data movment instruction de v thi un ka btna tha k kon sy processor me use hoti hain.
8.code dia hua tha btna tha k instruction kya kam kr rhi us me.
9.code likhna tha apna name on top of screen show krny ka.
10.code likhna tha aik array ka jis me 128 elements ho har element 4 byte ka ho or har element ki value 0 ho.
Overall paper bhut easy tha..

AL-JUNAID INSTITUTE

Virtual University	CS401-ASSEMBLY LANGUAGE (Solved Macq's) LECTURE FROM (22 to 45)	VU LMS HELP vulmshelp.com
Junaidfazal08@gmail.com Bc190202640@vu.edu.pk	FOR MORE VISIT VULMSHELP.COME	JUNAID MALIK 0304-1659294

AL-JUNAID TECH INSTITUTE



For CS619 Project Feel Free To Contact With Me

Ph# 0304-1659294
Email: junaidfazal08@gmail.com

AL-JUNAIDN TECH INSTITUTE

1. Suppose AL contains 5 decimals then after two left shifts produces the value as

- 5
- 10
- 15
- 20 (Page 52)

2. In graphics mode a location in video memory corresponds to a_____on the screen.

- Line
- Dot (Page 149)
- Circle
- Rectangle

3. Creation of threads can be

- Static
- Dynamic (Page 141)
- Easy
- Difficult

4. The thread registration code initializes the PCB and adds it to the linked list so that the _____will give it a turn.

- Assembler
- Scheduler (Page 141)
- linked
- Debugger

5. VESA VBE 2.0 is a standard for

- High resolution Mode (Page 180)
- Low resolution Mode
- Medium resolution Mode
- Very High Resolution Mode

6. Which of the following gives the more logical view of the storage medium

- BIOS
- DOS (Page 155)
- Both
- None

7. Which of the following IRQs is derived by a key board?

- IRQ 0
- IRQ 1 (Page 114)
- IRQ 2

- IRQ 3

8. Which of the following IRQs is used for Floppy disk drive?

- IRQ 4
- IRQ 5
- IRQ 6 (Page 114)
- IRQ 7

9. Which of the following pins of a parallel port connector are grounded?

- 10-18
- 18-25 (Page 125)
- 25-32
- 32-39

10. The physical address of IDT (Interrupt Descriptor Table) is stored in _____

- GDTR
- IDTR (Page 182)
- IVT
- IDTT

11. In NASM an imported symbol is declared with the.....while and exported symbol is declared
With the.....

- Global directive, External directive
- External directive, Global directive (Page 189)
- Home Directive, Foreign Directive
- Foreign Directive, Home Directive

12. In 68K processors there is a..... program counter (PC) that holds the address of currently executing
Instruction

- 8bit
- 16bit
- 32bit (Page 191)
- 64bit

13. To reserve 8-bits in memory ___directive is used.

- db. (Page 25)
- dw
- dn
- dd

14. In the "mov ax, 5" 5 is the_____operand.

- Source (Page 18)
- Destination
- Memory

0304-1659294
www.vulmshelp.com

- Register

15. RETF will pop the segment address in the

- CS register (Page 72)
- DS register
- SS register
- ES register

16. For the execution of the instruction "DIV BL", the implied dividend will be stored in

- AX (Page 85)
- BX
- CX
- DX

17. When a number is divided by zero "A Division by 0" interrupt is generated. Which instruction is used for this?

Purpose

- INT 0
- INT 1
- INT 2
- This interrupt is generated automatically (Page 107)

18. INT 21 service 01H is used to read character from standard input with echo. It returns the result in _____

Register.

- AL (Page 152)
- BL
- CL
- BH

19. BIOS sees the disks as

- Logical storage
- Raw storage (Page 155)
- In the form of sectors only
- In the form of tracks only

20. In 9pin DB 9, which pin number is assigned to CD (Carrier Detect)?

- 1 (Page 171)
- 2
- 3
- 4

21. In 9pin DB 9, Signal ground is assigned on pin number

- 4
- 5 (Page 171)
- 6
- 3

22. In 9pin DB 9, RI (Ring Indicator) is assigned on pin number

- ► 6
- ► 7

AL JUNAID TECH INSTITUTE 0304-1659294 www.vulmshelp.com

- ► 8
- ► 9 (Page 171)

23. Motorola 68K processors have .....23bit general purpose registers.

- ► 4
- ► 8
- ► 16 (Page 191)
- ► 32

24. When two devices in the system want to use the same IRQ line then what will happen?

- ► An IRQ Collision
- ► An IRQ Conflict (Page 114)
- ► An IRQ Crash
- ► An IRQ Blockage

25. in the instruction MOV AX, 5 the number of operands are

- ► 1
- ► 2 (Page 25)
- ► 3
- ► 4

26. Which flags are NOT used for mathematical operations?

- ► Carry, Interrupt and Trap flag.
- ► Direction, Interrupt and Trap flag. (Page 133)
- ► Direction, Overflow and Trap flag.
- ► Direction, Interrupt and Sign flag

27. The physical address of the stack is obtained by

- ► SS: SI combination
- ► SS: SP combination (Page 68)
- ► ES: BP combination
- ► ES: SP combination

28. Value of AH in the write Graphics pixel service is

- ► 0Ch (Page 152)
- ► 0Bh
- ► 1Ch
- ► 2Ch

29. Threads can have function calls, parameters and _____variables.

- ► Global
- ► Local (Page 141)
- ► Legal
- ► Illegal

30. Creation of threads can be

- ► Static
- ► Dynamic (Page 141) rep
- ► Easy

0304 1659294 www.vulmshelp.com

- ► Difficult

31. How many prevalent calling conventions do exist?

- ► 1
- ► 2 (Page 187)
- ► 3
- ► 4

32. VESA VBE 2.0 is a standard for

- ► High resolution Mode (Page 180) rep
- ► Low resolution Mode
- ► Medium resolution Mode
- ► Very High resolution Mode

33. The serial port connection is a ----------connector

- ► 9pin DB 9 (Page 171)
- ► 8pin DB 9
- ► 3pin DB 9
- ► 9pin DB 5

34. Which of the following gives the more logical view of the storage medium

- ► BIOS
- ► DOS (Page 55) rep
- ► Both
- ► None

35. In STOSB instruction, when DF is clear, SI is

- ► Incremented by 1 (Page 92)
- ► Incremented by 2
- ► Decremented by 1
- ► Decremented by 2

36. After the execution of STOSW the CX will be

- ► Decremented by 1 (Page 92)
- ► Decremented by 2
- ► Incremented by 1
- ► Incremented by 2

37. IRQ is referred to

- ► Eight input signals
- ► One output signal
- ► One input signals
- ► Eight output signals

38. Which of the following IRQs is derived by a key board?

- ► IRQ 0
- ► IRQ 1 (Page 113) rep
- ► IRQ 2
- ► IRQ 3

39. Which of the following IRQs is connected to serial port COM 1?

- ► IRQ 4 (page 114)
- ► IRQ 5
- ► IRQ 6

0304-1659294
www.vulmshelp.com

- ► IRQ 7

40. The physical address of IDT (Interrupt Descriptor Table) is stored in _____

- ► GDTR
- ► IDTR (Page 182) rep
- ► IVT
- ► IDTT

41. Assembly language is:

- ► Low-level programming language (Page 3)
- ► High-level programming language
- ► Also known as machine language
- ► not considered closer to the computer

42. The number of bits required to access 1MB of memory are

- ► 16 bits
- ► 32 bits
- ► depends on the processor architecture (Page 20)
- ► 20 bits

43. In STOSB instruction, SI is decremented or incremented by

- ► 3
- ► 2
- ► 1 (Page 92)
- ► 4

44. In programmable interrupt controller, which of the following ports is referred as a control port.

- ► 19
- ► 20 (Page 115)
- ► 21
- ► 22

45. INT 21 service 01H is used to read character from standard input with echo. It returns the result In_____register.

- ► AL (Page 152) rep
- ► BL
- ► CL
- ► BH

46. In device attribute word, which of the following bit decides whether it is a character device or a block device

- ► Bit 12
- ► Bit 13
- ► Bit 14
- ► Bit 15 (Page 116)

47. In 9pin DB 9, which pin number is assigned to CTS (Clear to send)?

- ► 6
- ► 7
- ► 8 (Page 171)
- ► 9

48. In 9pin DB 9, which pin number is assigned to RD (Received Data)?

- ► 1
- ► 2 (Page 171)

0304-1659294 www.vulmshelp.com

- ► 3
- ► 4

49. VESA (Video Electronics Standards Association) organizes 16 color bits for every pixel in

- 5:5:5 format
- ► 5:6:5 format (Page 180)
- ► 6:5:6 format
- ► 5:6:7 format

50. Motorola 68K processors have .....23bit general purpose registers.

- ► 4
- ► 8
- ► 16 (Page 191) rep
- ► 32

51. Programmable Interrupt Controller (PIC) has

- ► One input signals and eight output signals
- ► One input signal and one output signal
- ► Eight input signals and one output signals (Page 113)
- ► Eight input signals and eight output signals

52. Video services are classified into .....broad categories.

- ► 5
- ► 4
- ► 3
- ► 2 (Page 149

53. BL contains 5 decimal then after right shift, BL will become

- ➢ 3
- ➢ 2.5 (Page 52)
- ➢ 5
- ➢ 10

54. 8 * 16 font is stored in_____bytes.

- ➢ 3
- ➢ 4
- ➢ 8
- ➢ 16 (Page 150)

55. In DOS input buffer, number of characters actually read on return is stored in

- ➢ First byte
- ➢ Second byte (Page 152)
- ➢ Third byte
- ➢ Fourth byte

56. IRQ 0 has priority

- ➢ Low
- ➢ High
- ➢ Highest (Page 114)
- ➢ Medium

57. Thread registration code initialize PCB and add to linked list so that_____will give it turn.

- ➢ Assembler
- ➢ Linker

0304-1659294
www.vulmshelp.com

- Scheduler (Page 141) rep
- Debugger

58... Traditional calling conventions are in_____number

- 1
- 2 (Page 187)
- 3
- 4

59. VESA VEB 2.0 is standard for

- High Resolution Mode (Page 180) rep
- Low Resolution Mode
- Very High Resolution Mode
- Medium Resolution Mode

60. to clear direction flag which instruction is used?

- Cld (Page 92)
- Clrd
- Cl df
- Clr df

61. In STOSW instruction, When DI is cleared, SI is

- Incremented by 1
- Incremented by 2 (Page 92)
- Decremented by 1
- Decremented by 2

62 Interrupt that is used in debugging with help of trap flag is

- INT 0
- INT 1 (Page 105)
- INT 2
- INT 3

63. INT for arithmetic overflow is

- INT 1
- INT 2
- INT 3
- INT 4 (Page 106)

64. IRQ referred as

- Eight Input signals (Page 113) rep
- One Input signal
- Eight Output signals
- One output signal

65. IRQ for keyboard is

____1_____(Page 114)

66. IRQ for sound card is

_____5_____(Page 114)

67. IRQ for floppy disk is

_____6_____(Page 114)

68. IRQ with highest priority is

- Keyboard IRQ

0304-1659294
www.vulmshelp.com

- Timer IRQ (Page 114)
- Sound Card
- Floppy Disk

69. Pin for parallel port ground is

- 10-18
- 18-25 (Page 125) rep
- 25-32
- 32-39

70. The physical address of Interrupt Descriptor Table (IDT) is stored in

- GDTR
- IDTR (Page 182) rep
- IVT
- IDTT

71. CX register is

- Count register (Page 15)
- Data register
- Index register
- Base register

72. OUT instruction uses

__AX or AL_____as source register. (Page 115)

73. IN DB-9 connector the Data Set ready pin is at

- 5
- 6 (Page 171)
- 7
- 8

74. If two devices uses same IRQ then there is

- IRQ collision
- IRQ conflict (Page 114) rep
- IRQ drop

75. VESA organizes 16 bit color for every pixel in ratio

- 5:5:5
- 5:6:5 (Page 180) rep
- 6:5:6
- 5:6:

76. SP is associated with ..... By default

- SS (Page 34)
- DS
- CS
- ES

77. Which bit of the attributes byte represents the red component of foreground color?

- 5
- 4
- 3
- 2 (Page 81)

78. An 8 x 16 font is stored in_____bytes.

0304-1659294 www.vulmshelp.com

- ► 2
- ► 4
- ► 8
- ► 16 (Page 150) rep

79. In DOS input buffer, the number of characters actually read on return is stored in___byte.

- ► Third
- ► Fourth
- ► First
- ► Second (Page 152) rep

80. Which of the following gives the more logical view of the storage medium

- ► BIOS
- ► DOS
- ► Both
- ► None

81. In STOSW instruction, when DF is clear, SI is

- ► Incremented by 1
- ► Incremented by 2 (Page 92)
- ► Decremented by 1
- ► Decremented by 2

82. Which of the following interrupts is Non mask able interrupt

- ► INT 2 (Page 105)
- ► INT 3
- ► INT 0
- ► INT 1

83. Which of the following IRQs is connected to serial port COM 2?

- ► IRQ 0
- ► IRQ 1
- ► IRQ 2
- ► IRQ 3 (Page 114)

84. The time interval between two timer ticks is?

- ► 40ms
- ► 45ms
- ► 50ms
- ► 55ms (Page 122)

85. The physical address of IDT (Interrupt Descriptor Table) is stored in _____

- ► GDTR
- ► IDTR (Page 182) rep
- ► IVT
- ► IDTT

86. In NASM an imported symbol is declared with the.....while and exported symbol is declared With the.....

- ► Global directive, External directive
- ► External directive, Global directive (Page 189) rep
- ► Home Directive, Foreign Directive
- ► Foreign Directive, Home Directive

0304-1659294 www.vulmshelp.com

87. In 68K processors there is a 32bit .....that holds the address of currently executing instruction

- ► Program counter (Page 191)
- ► Stack pointer
- ► Register
- ► Stack

88. Single step interrupt is

- ► Hardware interrupt
- ► like divide by zero interrupt (Page 133)
- ► like divide by 1 interrupt
- ► Software interrupt

89. Which of the following is NOT true about registers:

- ► their operation is very much like memory
- ► Intermediate results may also be stored in registers
- ► They are also called scratch pad ram
- ► None of given options

90. Types of jump are:

- ► Short, near
- ► Short, near, far (Page 45)
- ► near, far
- ► short, far

91. MS DOS uses_____display mode.

- ► Character based (Page 79)
- ► Graphics based
- ► Numeric based
- ► Console based

92. Which of the following IRQs is derived by a timer device?

- ► IRQ 0 (Page 114)
- ► IRQ 1
- ► IRQ 2
- ► IRQ 3

93. In programmable interrupt controller, which of the following ports is referred as a control port?

- ► 19
- ► 20 (Page 115) rep
- ► 21
- ► 22

94. INT 21 service 01H is used to read character from standard input with echo. It returns the result in_____register.

- ► AL (Page 152) rep
- ► BL
- ► CL
- ► BH

95. In 9pin DB 9, which pin number is assigned to DSR (Dataset Ready)?

- ► 4
- ► 5
- ► 6 (Page 171)

0304-1659294
www.vulmshelp.com

► 7

96. In 9pin DB 9, which pin number is assigned to TD (Transmitted Data)?

► 1
► 2
► 3 (Page 171)
► 4

97. In 9pin DB 9, Signal ground is assigned on pin number

► 4
► 5 (Page 171)
► 6
► 3

98.8088 is a.....

► 16 bit processor (Page 14)
► 32 bit processor
► 64 bit processor
► 128 bit processor

99. The table index (TI) is set to_____to access the GDT (Global Descriptor Table).

► 1
► 0 (Page 175)
► -1
► -2

100. VESA (Video Electronics Standards Association) organizes 16 color bits for every pixel in

► 5:5:5 format
► 5:6:5 format (Page 180) rep
► 6:5:6 format
► 5:6:7 format

101. Which flags are NOT used for mathematical operations?

► Carry, Interrupt and Trap flag.
► Direction, Interrupt and Trap flag. (Page 133) rep
► Direction, Overflow and Trap flag.
► Direction, Interrupt and Sign flag

102. When a 32 bit number is divided by a 16 bit number, the quotient is of

➢ 32 bits
➢ 16 bits (Page 85)
➢ 8 bits
➢ 4 bits

103. in the instruction MOV AX, 5 the number of operands are

➢ 1
➢ 2 (Page 25) rep
➢ 3
➢ 4

104. In DOS input buffer, number of characters actually read on return is stored in

➢ First byte
➢ Second byte (Page 152) rep
➢ Third byte
➢ Fourth byte

AL-JUNAID TECH INSTITUTE ©0304-1659294 www.vulmshelp.com

105. VESA VEB 2.0 is standard for

- High Resolution Mode (Page 180) rep
- Low Resolution Mode
- Very High Resolution Mode
- Medium Resolution Mode

106. IN DB-9 connector the Data Set ready pin is at

- 5
- 6 (Page 171) rep
- 7
- 8

107. Threads can have function calls, parameters and variables.

- Global
- Local (Page 141)
- Legal
- Illegal

108. How many prevalent calling conventions do exist?

- 1
- 2 (Page 187) rep
- 3
- 4

109. In 9pin DB 9 DSR is assigned on pin number

- 4
- 5
- 6 (Page 171)
- 7

110. In 9pin DB 9 CTS is assigned on pin number

- 6
- 7
- 8 (Page 171)
- 9

112. In 9pin DB 9 CD is assigned on pin number

- 1 (Page 171)
- 2
- 3
- 4

113. A 32bit address register can access up to ...access has .of memory so memory increased a lot.

- 2GB
- 4GB (Page 175)
- 6GB
- 8GB

114. In device attribute word which of the following bit decides whether it is a character device or a block device

- Bit 12
- Bit 13
- Bit 14
- Bit 15 (Page 166) rep

0304-1659294
www.vulmshelp.com

115.Which of the following IRQ is cascading interrupt

- IRQ 0
- IRQ 1
- IRQ 2 (Page 114)
- IRQ 3

116. Which of the following interrupts is used for Arithmetic overflow

- INT 1
- INT 2
- INT 3
- INT 4 (Page 106) rep

117. An End of Interrupt (EOI) signal is sent by

- Handler (Page 114)
- Processor
- IRQ
- PIC

118. The number of pins in a parallel port connector are?

- 20
- 25 (Page 125)
- 30
- 35

119. Which of the following pins of a parallel port connector are grounded?

- 10-18
- 18-25 (Page 125) rep
- 25-32
- 32-39

120. In NASM an imported symbol is declared with the .....while and exported symbol is declared With the.....

- Global directive, External directive
- External directive, Global directive (Page 189) rep
- Home Directive, Foreign Directive
- Foreign Directive, Home Directive

121. Sun SPARC Processor has a fixed_____instruction size.

- 16bit
- 32bit (Page 192) rep
- 64bit
- 20bit

122. When the subprogram finishes, the_____retrieves the return address from the stack and transfers control to that location.

- RET instruction Click here for detail
- CALL instruction
- POP instruction
- Jump instruction

123. A 32 bit address register can access up to_____of memory.

- 1 GB
- 6 GB
- 4 GB (Page 175) rep
- 2 GB

0304-1659294
www.vulmshelp.com

AL-JUNAIDN TECH INSTITUTE

124. The value of a segment register when the processor is running under protected mode is called _____

- segment descriptor
- segment selector
- global descriptor table
- protected register

125. FS and FS and GS are two_____in protected mode.

- segment registers
- segment selectors (Page 175)
- stack pointers
- register pointers

126. IRQ 0 interrupt have_____priority

- low
- medium
- highest (Page 114) rep
- lowest

127. IDT stands for_____.

- interrupt descriptor table (Page 182)
- individual descriptor table
- inline data table
- interrupt descriptor table

128. Every bit of line status in serial port conveys_____information.

- different (Page 171)
- same
- partial
- full

129. There are total_____bytes in a standard floppy disk.

- 1444k
- 1440k (Page 155)
- 1280k
- 2480k

130. An 8x16 font is stored in_____bytes.

- 8
- 16 (Page 150) rep
- 4
- 20

131. Memory address space is selected when which of the following instructions is given to the processors Select correct option:

- MOV (page 115)
- DEC
- IN
- ADD

132. PCB stands for?

- Select correct option:
- Process Control Block (Page 140)
- Process Clearing Block
- Programmable Counter Block

0304-1659294
www.vulmshelp.com

- Programs Control Block

132. The input frequency of the programmable interval timer (PIT) is

- Fixed (Page 122)
- Depends on processor clock
- Variable
- Depends on hardware attached

133. Programmable interrupt controller has two ports 20 and 21. Port 20 is the control port while port 21 is.....

- The Interrupt mask register (Page 115)
- Interrupt port
- Output port
- Input port

134. The time interval between two timer ticks is?

- 40ms
- 45ms
- 50ms
- 55ms (Page 122)

135. Which of the following interrupts is used for saving and restoring the registers

- INT6
- Int7
- Int8 (Page 141)
- Int0

136. In programmable interrupt controller which of the following ports is referred as an interrupt mask register?

- 19
- 20
- 21 (Page 115)
- 22

137. The programmable interval timer (PIT) has input frequency of

- 193MHZ (Page 122)
- 192MHZ
- 196MHZ
- 198MHZ

138. Peripheral address space is selected when which of the following instructions is given to the processor?

- MOV
- IN (Page 155)
- Add
- Out

139. Direction flag, the interrupt flag, and the trap flag are

- used for mathematical operations
- not used for mathematical operations (Page 133)
- status flags
- not status flags

140. The space where all the registers of a task are stored is called the

AL-JUNAID TECH INSTITUTE 0304-1659294 www.vulmshelp.com

- control block (Page 140)
- process control block
- stack
- memory

141. Which of the following interrupt is of highest priority interrupt?

- Key board interrupt
- Timer interrupt (Page 122)
- INT 2
- INT 3

142. The instruction used to read a character from the keyboard port is

- in al, 0x60 (Page 125)
- out al, 0x60
- in al, 0x80
- out al, 0x80

143. Each thread can have their own

- execution area
- stack (Page 141)
- memory
- array

144. All the registers & stack are saved in

- Multitasking
- multi-processing
- function call
- BIOS

145. There is no instruction to clear the

- Trap flag (Page 133)
- Interrupt flag
- Direction flag
- None of the above

146. The interrupt mask register which can be used for selectively enabling or disabling interrupts is associated with

- Port 19
- Port 20
- Port 21 (Page 115)
- Port 22

147. The parallel port connector is called?

0304-1659294
www.vulmshelp.com

- DB-25 (Page 125)
- BD-25
- DB-24
- BD-24

148. Which of the following is not true about registers:

- Their operation is very much like memory
- Intermediate results may also be stored in registers.
- They are also called scratch pad ram
- None of given options.

149. move [bop], al moves the one byte content of the AL register to the address contained in

- BP register in the current
- Stack segment (Page 35)
- Code segment
- Data segment
- Extra segment

150. In a rotate through carry right (RCR) instruction applied on a 16 bit word effectively there is

- 16 bits rotation
- 1 bit rotation
- 17 bits rotation (Page 53)
- 8 bits rotation

151. The 8088 stack works on

- Word sized elements (Page 68)
- Byte sized elements
- Double sized element
- Nibble sized element

152. An 8 x 16 font is stored in_____bytes.

- 4
- 8
- 16 (Page 150) rep

153. INT 10 is used for_____services.

- RAM
- Disk
- BIOS video (Page 149)
- DOS video

154. Priority of IRQ 0 interrupt is

- medium
- high

0304-1659294
www.vulmshelp.com

- highest (Page 114) rep
- low

155. Threads can have function calls, parameters and _____variables.

- global
- local (Page 141) rep
- legal
- illegal

156. How many prevalent calling conventions do exist?

- 1
- 2 (Page 187) rep
- 3
- 4

157. In 9pin DB 9 DSR is assigned on pin number

- 4
- 5
- 6 (Page 171) rep
- 7

158. In 9pin DB 9 CTS is assigned on pin number

- 6
- 7
- 8 (Page 171) rep
- 9

159. In 9pin DB 9 CD is assigned on pin number

- 1 (Page 171) rep
- 2
- 3
- 4

160. In 9pin DB 9 RD is assigned on pin number

- 1
- 2 (Page 171)
- 3
- 4

161. In device attribute word which of the following bit decides whether it is a character device or a block device

- Bit 12
- Bit 13

AL JUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

- Bit 14
- Bit 15 (Page 166)

162. Video services are classified into_____broad categories

- 2 (Page 149)
- 3
- 4
- 5

163. In STOSB instruction, when DF is clear, SI is

- Incremented by 1 (Page 92) rep
- Incremented by 2
- Decremented by 1
- Decremented by 2

164. The process of sending signals back and forth is called

- Activity
- Hand-shaking
- Interruption
- Time clicking

165. Which of the following interrupts is used for Arithmetic Overflow?

- INT 1
- INT 2
- INT 3
- INT 4 (Page 106) rep

166. Which of the following is a special type of interrupt that returns to the same instruction instead of the next Instruction?

- Divide overflow interrupt (Page 107)
- Debug interrupt
- Arithmetic overflow interrupt
- Change of sign interrupt

167. Which of the following IRQs is derived by a timer device?

- IRQ 0 (Page 114) rep
- IRQ 1
- IRQ 2
- IRQ 3

168. Which of the following IRQs is connected to serial port COM 2?

- IRQ 0
- IRQ 1

0304-1659294 www.vulmshelp.com

- IRQ 2
- IRQ 3 (Page 114) rep

169. An End of Interrupt (EOI) signal is sent by

- Handler (Page 114) rep
- Processor
- IRQ
- PIC

170. The source registers in OUT is

- AL or AX (Page 115) rep
- BL or BX
- CL or CX
- DL or DX

171. In programmable interrupt controller which of the following ports is used for selectively enabling or disabling interrupts

- 19
- 20
- 21 (Page 115)
- 22

172. The number of pins in a parallel port connector are?

- 20
- 25 (Page 125) rep
- 30
- 35

173. Which of the following pins of a parallel port connector are grounded?

- 10-18
- 18-25 (Page 125) rep
- 25-32
- 32-39

174. If the decimal number "35" is shifted by two bit to left, the new value will be

- 35
- 70
- 140 (00100011 = 35, 10001100=140)
- 17

175. A 32bit address register can access unto .....Of memory so memory access has increased a lot.

AL JUNAID TECH INSTITUTE 0304 1659294 www.vulmshelp.com

- 2GB
- 4GB (Page 175) rep
- 6GB
- 8GB

176. In NASM an imported symbol is declared with the .....while and exported symbol is declared With the.....

- Global directive, External directive
- External directive, Global directive (Page 189) rep
- Home Directive, Foreign Directive
- Foreign Directive, Home Directive

177. Single step interrupt is

- Hardware interrupt
- Like divide by zero interrupt (Page 133) rep
- Like divide by 1 interrupt
- Software interrupt

176. In programmable interrupt controller which of the following ports is referred as interrupt mask register?

a. 19
b. 20
c. 21
d. 22

177. _____is the highest priority interrupt in interrupt controller?

a. IRQ 0
b. IRQ 1
c. IRQ 2
d. IRQ 3

178. IRET returns on the basis of___and _____

a. CS, IP
b. DS, IP
c. CS, SS
d. IP,SP

170. If_is set, the after every instruction a type 1 interrupt will be automaticallygenerated.

e. Parity flag
b. Trap flag
c. Carry flag
d. Overflow flag

180.The interrupt handler uses_____instruction to return back to the caller.

a. IRET
b. RETI

0304-1659294 www.vulmshelp.com

c. INTR
d. RET

179. Which of the following interrupt is used for Arithmetic overflow?

a. INT 1
b. INT 2
c. INT 3
d. INT 4

180. During the execution of INT instruction , some contents are pushed on to the stack , the orderof pushing then is

a. CS , IP and then FLAGS register
b. IP,CS and then FLAGS register
c. c. FLAGS register, CS and then IP
d. FLAGS register, IP and the CS

181. Each of the bits at port_____corresponding to one of the IRQ lines.

d. 18
e. 19
f. 20
d. 21

181. Which of the following pins of the parallel port connector are grounded?

a. 10-18
b. 18-25
c. 25-32
d. 32-39

182. Which of the following interrupts plays the most significant part during step debugging of a program?

a. INT 0
b. INT 1
c. INT 2
d. INT 3

183. Which of the following IRQs is connected to serial port COM 2?

a. IRQ 0
b. IRQ 1
c. IRQ 2
d. IRQ 3

184. Which of the following IRQs is connected to serial port COM 1?

- IRQ 4
- IRQ 5
- IRQ 6
- IRQ 7

185. Which of the following IRQs is used by the parallel port?

a. IRQ 4
b. IRQ 5
c. IRQ 6
d. IRQ 7

0304-1659294
www.vulmshelp.com

186. **In programmable interrupt controller which of the following ports is used to selectivelyenabling or disabling interrupts?**

a. 19
b. 20
c. 21
d. 22

187.

The space where all the registers of task are stored is called _____

a. Control block
b. Process control block
c. Stack
d. Memory

188. **Which of the following is the destination register in IN instruction?**

a. AL or AX
b. BL or BX
c. CL or CX
d. DL or DX

189. **Which of the following interrupts is used for saving and restoring the registers**

a. INT 6
b. INT 7
c. INT 8
d. INT 0

190. **In multitasking environment, which of the following structure is used to maintain theordering of active PCBs?**

a. Array
b. Register
c. Linked List
d. Stack

191. **In multitasking which of the following interrupts is used as scheduler during contextswitching?**

a. INT 21
b. INT 16
c. INT 13
d. INT 8

192. **Which of the following are required for thread entry?**

a. CS and DS
b. CS and IP
c. IP and general purpose registers
d. SS and SP

193. **Which of the following flag can be used for mathematical operations?**

a. Direction Flag
b. Carry Flag
c. Trap Flag
d. Interrupt Flag

194.

In multi- tasking, the process of saving and restoring to values of registers from a

0304-1659294
www.vulmshelp.com

processcontrol block (PCB) is called _

a. Context switching
b. Context saving
c. Context restoring
d. Code switching

195. When two devices in a system want to use the same IRQ line, is referred as:

a. IRQ Collision
b. IRQ Conflict
c. IRQ Crash
d. IRQ Blockage

196. An End of Interrupt (EOI) signal is sent by

a. Handler
b. Processor
c. IRQ
d. PIC

197. Which of the following is the BIOS interrupt providing keyboard service?

a. INT 0x13
b. INT 0x14
c. INT 0x15
d. INT 0x16

198.

Threads can have function calls, parameters and_____variables.

a. Global
b. Local
c. Legal
d. Illegal

199. Which of the following arranges jobs in a sequence in order to be executed?

a. Process control block
b. Arranger
c. Control unit
d. Scheduler

200. Which of the following flags cannot be cleared using an assembly instruction?

a. Trap flag
b. Interrupt flag
c. Direction flag
d. Carry flag

201. Which of the following is the highest priority interrupt?

a. INT3
b. INT2
c. INT1
d. INT0

202. At the end of servicing an interrupt, which of the following is used to inform tha PIC that it is completed?

a. RET
b. EOI
c. IRET
d. RET N

AL-JUNAID TECH INSTITUTE 0304-1639294 www.vulmshelp.com

203. **Which of the following interrupts is used for maintaining the system time?**

a. INT 0
b. INT 1
c. INT 8
d. INT 10

204. **Which of the following is used for exporting parallel port services?**

a. INT 17
b. INT 16
c. INT 15
d. INT 8

205. **In programmable interrupt controller which of the following ports is referred as a controlport?**

a. 19
b. 20
c. 21
d. 22

206.

The first parallel port LPT1 has port number designated from_____.

a. 178 to 17A
b. 278 to 27A
c. 378 to 37A
d. 478 to 47A

207. **___is/are the port number(s) for parallel port.**

a. 20 and 21
b. 60 to 64
c. 380
d. 378

208. **The number of pins in a parallel port connector are?**

a. 20
b. 25
c. 30
d. 35

209. **The offset address of an interrupt n will be at**

a. n
b. nx2
c. nx3
d. nx4

210.

Programmable interrupt controller has two ports (20 and 21). Port 20 is the control port whileport 21 is.

a. The interrupt mask register
b. Interrupt port
c. Output port
d. Input port

211. **Which of the following instruction selects memory address space?**

a. MOV

0304-1659294
www.vulmshelp.com

b. DEC
c. IN
d. ADD

212. The thread registration code initializes the PCB and adds it to the linked list so that the _____will give it a turn.

a. Assembler
b. Scheduler
c. Linker
d. Debugger

213. Which of the following instruction is used for disabling all the interrupts during a programexecution?

a. Cli
b. Sti
c. Reti
d. Iret

214. IBM AT has how many PICs (Programmable interrupt controller)

a. 1
b. 2
c. 3
d. 4

215. Programmable interrupt controller (PIC) has

a. One input signals and eight output signals
b. One input signal and one output signal
c. Eight input signals and one output signals
d. Eight input signals and eight output signals

216. In 8088 processor, there can be total possible entries in an interrupt vector table.

a. 256
b. 64
c. 128
d. 512

217. Each thread can have their own

a. Execution area
b. Stack
c. Memory
d. Array

218. The parallel port connector is called?

a. DB-25
b. BD-25
c. DB-24
d. BD-24

219. In 8088, the physical memory address for Interrupt Vector Table is fixed and the tableoccupies exactly_____of memory.

0304-1659294
www.vulmshelp.com

a. 1 KB
b. 1 MB
c. 64 KB
d. 4 Bytes

220. Which of the following interrupts is non maskable interrupt?

a. INT 0
b. INT 1
c. INT 2
d. INT 3

222.

Using OUT instruction on parallel data port results into a signal of_____for every 1 bit.

e. 0 V
f. 1 V
g. 5 V
h. 10 V

221. PCB stands for?

a. Process Control Block
b. Process Cleaning Block
c. Programmable Counter Block
d. Programs Control Block

222. Which of the following interrupts is used in debugging with the trap flag?

a. INT 0
b. INT 1
c. INT 2
d. INT 3

223. Which of the following port number is used to send an end of interrupt (EOI) signal to thePIC after an interrupt is ended?

a. 0x16
b. 0x20
c. 0x60
d. 0x378

224. Which of the following instruction is used for reading a char from keyboard?

a. out al, 0x60
b. in al , 0x60
c. out dx, al
d. out dx, 0x378

225. In PIC, which of the following port is used for selectively enabling or disabling interrupts?

a. 19
b. 20
c. 21
d. 22

226. DOS has single entry point to access all its services through interrupt__

a. INT 21
b. INT 16

AL-JUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

c. INT 2
d. INT 10

227. Which of the following pins of parallel port are used to carry the data from processor to thedevice connected through parallel port?

a. Pin 2 to pin 9
b. Pin 10
c. Pin 4
d. Pin 18 to pin 25

228. The input frequency of the programmable interval timer(PIT) is

a. Fixed
b. Depends on processor block
c. Variable
d. Depends on hardware attached

229.

All registers of task are stored in space called _____

a. Process storage block
b. Process control block
c. Process terminal
d. Swapping space

230. Which of the following IRQ`s is derived by a key board

a. IRQ 0
b. IRQ 1
c. IRQ 2
d. IRQ 3

231. The programmable interval timer (PIT) has input frequency of

a. 1.193MHz
b. 2.193MHz
c. 3.193MHz
d. 4.193MHz

232. Changing and restoring the state of Control processing unit (CPU) is referred as

a. Thrashing
b. Multitasking
c. Context Switching
d. Multithreading

233. For the external hardware to generate an interrupt there are how many pins outside theprocessor?

a. 1
b. 2
c. 3
d. 4

234. Which of the following instruction selects peripheral address space?

a. MOV
b. DEC
c. IN
d. ADD

235. Which of the following is the most commonly used port with printer?

0304-1659294
www.vulmshelp.com

a. Serial Port
b. USB port
c. Parallel Port
d. DVI Port

236. _____**allows us to execute one instruction at a time rather than the whole program atonce**

a. INT 0
b. INT 1
c. INT 2
d. INT 3

237. Which of the following is used for exporting keyboard services?

a. INT 16
b. INT 11
c. INT 12
d. INT 8

238. TSR stands for

a. Terminate and store routines
b. Transmits and save resources
c. Terminate and Stay resident
d. Truncate and start recursively

239. In older computers, the port number designed for parallel pert LPT2 area.

- 078-07A
- 178-17A
- 378-37A
- 278-27A

240. Which of the following is the ACK pin in DB-25 Connector

a. 10
b. 11
c. 12
d. 13

241. Which of the following IRQs is a cascading interrupt?

- IRQ 0
- IRQ 1
- IRQ 2
- IRQ 3

242.

In interrupt masking, we use_____to get control from the program without letting theprogram know about it.

a. IRQ 0
b. IRQ 1
c. IRQ 5
d. IRQ 7

243. The output of programmable timer interval is connected to which line

0304-1659294
www.vulmshelp.com

of the PIC?

a. IRQ 0
b. IRQ 1
c. IRQ 2
d. IRQ 3

244.

In multitasking, each PCB requires_____bytes to store the values of registers.

a. 14
b. 28
c. 32
d. 16

245. Which of the following IRQs is used for sound card or network card?

a. IRQ 4
b. IRQ 5
c. IRQ 6
d. IRQ 7

246.

Programmable interrupt controller has_____ports.

a. 1
b. 2
c. 3
d. 4

247. Which of the following bits of parallel control port enables the IRQ 7 triggering by the ACKpin?

a. Bit 1
b. Bit 2
c. Bit 3
d. Bit 4

248.

All the registers & stack are saved in

- Multitasking
- Multi-Processing
- Function call
- BIOS

249.

Which of the following is the source register in OUT instruction?

a. AL or AX
b. BL or BX
c. CL or CX
d. DL or DX

250. Which of the following is the destination register in IN instruction?

a. AL or AX
b. BL or BX

0304-1659294
www.vulmshelp.com

c. CL or CX
d. DL or DX

AL-JUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

AL-JUNAID INSTITUTE GROUP



CS401- Computer Architecture and Assembly Language Programming

FINALTERM EXAMINATION

Spring 2010

Question No: 1 (Marks: 1) - Please choose one

Suppose AL contains 5 decimal then after two left shifts produces the value as

- ► 5
- ► 10
- ► 15
- ► **20 (Page 52)**

Question No: 2 (Marks: 1) - Please choose one

In graphics mode a location in video memory corresponds to a _____ on the screen.

- ► line
- ► **dot (Page 149)**
- ► circle
- ► rectangle

Question No: 3 (Marks: 1) - Please choose one

Creation of threads can be

- ► static
- ► **dynamic (Page 141)**
- ► easy
- ► difficult

Question No: 4 (Marks: 1) - Please choose one

The thread registration code initializes the PCB and adds it to the linked list so that the _____ will give it a turn.

- ► assembler
- ► **scheduler (Page 141)**
- ► linker
- ► debugger

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 5 (Marks: 1) - Please choose one
VESA VBE 2.0 is a standard for
- ► **High resolution Mode (Page 180)**
- ► Low resolution Mode
- ► Medium resolution Mode
- ► Very High resolution Mode

Question No: 6 (Marks: 1) - Please choose one
Which of the following gives the more logical view of the storage medium
- ► BIOS
- ► **DOS (Page 155)**
- ► Both
- ► None

Question No: 7 (Marks: 1) - Please choose one
Which of the following IRQs is derived by a key board?
- ► IRQ 0
- ► **IRQ 1 (Page 114)**
- ► IRQ 2
- ► IRQ 3

Question No: 8 (Marks: 1) - Please choose one
Which of the following IRQs is used for Floppy disk derive?
- ► IRQ 4
- ► IRQ 5
- ► **IRQ 6 (Page 114)**
- ► IRQ 7

Question No: 9 (Marks: 1) - Please choose one
Which of the following pins of a parallel port connector are grounded?
- ► 10-18
- ► **18-25 (Page 125)**
- ► 25-32
- ► 32-39

Question No: 10 (Marks: 1) - Please choose one
The physical address of IDT(Interrupt Descriptor Table) is stored in _____
- ► GDTR
- ► **IDTR (Page 182)**
- ► IVT
- ► IDTT

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 11 (Marks: 1) - Please choose one
In NASM an imported symbol is declared with the ..... while and exported symbol is declared with the.....

- ► Global directive, External directive
- ► **External directive, Global directive (Page 189)**
- ► Home Directive, Foreign Directive
- ► Foreign Directive, Home Directive

Question No: 12 (Marks: 1) - Please choose one
In 68K processors there is a ..... program counter (PC) that holds the address of currently executing instruction

- ► 8bit
- ► 16bit
- ► **32bit (Page 191)**
- ► 64bit

Question No: 13 (Marks: 1) - Please choose one
To reserve 8-bits in memory ___ directive is used.

- ► **db (Page 25)**
- ► dw
- ► dn
- ► dd

Question No: 14 (Marks: 1) - Please choose one
In the "mov ax, 5" 5 is the _____ operand.

- ► **source (Page 18)**
- ► destination
- ► memory
- ► register

Question No: 15 (Marks: 1) - Please choose one
RETF will pop the segment address in the

- ► **CS register (Page 72)**
- ► DS register
- ► SS register
- ► ES register

Question No: 16 (Marks: 1) - Please choose one
For the execution of the instruction "DIV BL", the implied dividend will be stored in

- ► **AX (Page 85)**
- ► BX
- ► CX
- ► DX

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 17 (Marks: 1) - Please choose one
When a number is divided by zero ”A Division by 0” interrupt is generated. Which instruction is used for this purpose

- ► INT 0
- ► INT 1
- ► INT 2
- ► **This interrupt is generated automatically (Page 107)**

Question No: 18 (Marks: 1) - Please choose one
INT 21 service 01H is used to read character from standard input with echo. It returns the result in _____ register.

- ► **AL (Page 152)**
- ► BL
- ► CL
- ► BH

Question No: 19 (Marks: 1) - Please choose one
BIOS sees the disks as

- ► logical storage
- ► **raw storage (Page 155)**
- ► in the form of sectors only
- ► in the form of tracks only

Question No: 20 (Marks: 1) - Please choose one
In 9pin DB 9, which pin number is assigned to CD (Carrier Detect)?

- ► **1 (Page 171)**
- ► 2
- ► 3
- ► 4

Question No: 21 (Marks: 1) - Please choose one
In 9pin DB 9, Signal ground is assigned on pin number

- ► 4
- ► **5 (Page 171)**
- ► 6
- ► 3

Question No: 22 (Marks: 1) - Please choose one
In 9pin DB 9, RI (Ring Indicator) is assigned on pin number

- ► 6
- ► 7
- ► 8
- ► **9 (Page 171)**

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 23 (Marks: 1) - Please choose one
Motorola 68K processors have..... 23bit general purpose registers.

- ► 4
- ► 8
- ► **16 (Page 191)**
- ► 32

Question No: 24 (Marks: 1) - Please choose one
When two devices in the system want to use the same IRQ line then what will happen?

- ► An IRQ Collision
- ► **An IRQ Conflict (Page 114)**
- ► An IRQ Crash
- ► An IRQ Blockage

Question No: 25 (Marks: 1) - Please choose one
In the instruction **MOV AX, 5** the number of operands are

- ► 1
- ► **2 (Page 25)**
- ► 3
- ► 4

Question No: 26 (Marks: 1) - Please choose one
Which flags are NOT used for mathematical operations ?

- ► Carry, Interrupt and Trap flag.
- ► **Direction, Interrupt and Trap flag. (Page 133)**
- ► Direction, Overflow and Trap flag.
- ► Direction, Interrupt and Sign flag.

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

Question No: 1 (Marks: 1) - Please choose one
The physical address of the stack is obtained by

- ► SS:SI combination
- ► **SS:SP combination (Page 68)**
- ► ES:BP combination
- ► ES:SP combination

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 2 (Marks: 1) - Please choose one
Value of AH in the write Graphics pixel service is
- ► **0Ch (Page 152)**
- ► 0Bh
- ► 1Ch
- ► 2Ch

Question No: 3 (Marks: 1) - Please choose one
Threads can have function calls, parameters and _____ variables.
- ► global
- ► **local (Page 141)**
- ► legal
- ► illegal

Question No: 4 (Marks: 1) - Please choose one
Creation of threads can be
- ► static
- ► **dynamic (Page 141) rep**
- ► easy
- ► difficult

Question No: 5 (Marks: 1) - Please choose one
How many prevalent calling conventions do exist
- ► 1
- ► **2 (Page 187)**
- ► 3
- ► 4

Question No: 6 (Marks: 1) - Please choose one
VESA VBE 2.0 is a standard for
- ► **High resolution Mode (Page 180) rep**
- ► Low resolution Mode
- ► Medium resolution Mode
- ► Very High resolution Mode

Question No: 7 (Marks: 1) - Please choose one
The serial port connection is a ---------- connector
- ► **9pin DB 9 (Page 171)**
- ► 8pin DB 9
- ► 3pin DB 9
- ► 9pin DB 5

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 8 (Marks: 1) - Please choose one
Which of the following gives the more logical view of the storage medium
- ► BIOS
- ► **DOS (Page 55) rep**
- ► Both
- ► None

Question No: 9 (Marks: 1) - Please choose one
In STOSB instruction, when DF is clear, SI is
- ► **Incremented by 1 (Page 92)**
- ► Incremented by 2
- ► Decremented by 1
- ► Decremented by 2

Question No: 10 (Marks: 1) - Please choose one
After the execution of STOSW the CX will be
- ► **Decremented by 1 (Page 92)**
- ► Decremented by 2
- ► Incremented by 1
- ► Incremented by 2

Question No: 11 (Marks: 1) - Please choose one
IRQ is referred to
- ► **Eight input signals**
- ► One output signal
- ► One input signals
- ► Eight output signals

Question No: 12 (Marks: 1) - Please choose one
Which of the following IRQs is derived by a key board?
- ► IRQ 0
- ► **IRQ 1 (Page 113) rep**
- ► IRQ 2
- ► IRQ 3

Question No: 13 (Marks: 1) - Please choose one
Which of the following IRQs is connected to serial port COM 1?
- ► **IRQ 4 (page 114)**
- ► IRQ 5
- ► IRQ 6
- ► IRQ 7

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 14 (Marks: 1) - Please choose one
The physical address of IDT(Interrupt Descriptor Table) is stored in _____

- ► GDTR
- ► **IDTR (Page 182) rep**
- ► IVT
- ► IDTT

Question No: 15 (Marks: 1) - Please choose one
Assembly language is:

- ► **Low-level programming language (Page 3)**
- ► High-level programming language
- ► Also known as machine language
- ► Not considered closer to the computer

Question No: 16 (Marks: 1) - Please choose one
The number of bits required to access 1MB of memory are

- ► 16 bits
- ► 32 bits
- ► **Depends on the processor architecture (Page 20)**
- ► 20 bits

Question No: 17 (Marks: 1) - Please choose one
In STOSB instruction, SI is decremented or incremented by

- ► 3
- ► 2
- ► **1 (Page 92)**
- ► 4

Question No: 18 (Marks: 1) - Please choose one
In programmable interrupt controller, which of the following ports is referred as a *control port*.

- ► 19
- ► **20 (Page 115)**
- ► 21
- ► 22

Question No: 19 (Marks: 1) - Please choose one
INT 21 service 01H is used to read character from standard input with echo. It returns the result in _____ register.

- ► **AL (Page 152) rep**
- ► BL
- ► CL
- ► BH

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 20 (Marks: 1) - Please choose one

In device attribute word, which of the following bit decides whether it is a *character device* or a *block device*

- ► Bit 12
- ► Bit 13
- ► Bit 14
- ► **Bit 15 (Page 116)**

Question No: 21 (Marks: 1) - Please choose one

In 9pin DB 9, which pin number is assigned to CTS (Clear To Send) ?

- ► 6
- ► 7
- ► **8 (Page 171)**
- ► 9

Question No: 22 (Marks: 1) - Please choose one

In 9pin DB 9, which pin number is assigned to RD (Received Data) ?

- ► 1
- ► **2 (Page 171)**
- ► 3
- ► 4

Question No: 23 (Marks: 1) - Please choose one

VESA(Video Electronics Standards Association) organizes 16 color bits for every pixel in

- ► 5:5:5 format
- ► **5:6:5 format (Page 180)**
- ► 6:5:6 format
- ► 5:6:7 format

Question No: 24 (Marks: 1) - Please choose one

Motorola 68K processors have ..... 23bit general purpose registers.

- ► 4
- ► 8
- ► **16 (Page 191) rep**
- ► 32

Question No: 25 (Marks: 1) - Please choose one

Programmable Interrupt Controller (PIC) has

- ► One input signals and eight output signals
- ► One input signal and one output signal
- ► **Eight input signals and one output signals (Page 113)**
- ► Eight input signals and eight output signals

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 26 (Marks: 1) - Please choose one

Video services are classified into..... broad categories.

► 5
► 4
► 3
► **2 (Page 149)**

CS401- Computer Architecture and Assembly Language Programming

FINALTERM EXAMINATION

Spring 2010

1. BL contains 5 decimal then after right shift , BL will become
   - 3
   - **2.5 (Page 52)**
   - 5
   - 10

2. 8 * 16 font is stored in _____ bytes.
   - 3
   - 4
   - 8
   - **16 (Page 150)**

3. In DOS input buffer , number of characters actually read on return is stored in
   - First byte
   - **Second byte (Page 152)**
   - Third byte
   - Fourth byte

4. IRQ 0 has priority
   - Low
   - High
   - **Highest (Page 114)**
   - Medium

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

5. Thread registration code initialize PCB and add to linked list so that _____ will give it turn.

- Assembler
- Linker
- **Scheduler (Page 141) rep**
- Debugger

6. Traditional calling conventions are in _____ number

- 1
- **2 (Page 187)**
- 3
- 4

7. VESA VEB 2.0 is standard for

- **High Resolution Mode (Page 180) rep**
- Low Resolution Mode
- Very High Resolution Mode
- Medium Resolution Mode

8. To clear direction flag which instruction is used

- **Cld (Page 92)**
- Clrd
- Cl df
- Clr df

9. In STOSW instruction , When DI is cleared , SI is

- Incremented by 1
- **Incremented by 2 (Page 92)**
- Decremented by 1
- Decremented by 2

10. Interrupt that is used in debugging with help of trap flag is

- INT 0
- **INT 1 (Page 105)**
- INT 2
- INT 3

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

11. INT for arithmetic overflow is
    - INT 1
    - INT 2
    - INT 3
    - **INT 4 (Page 106)**

12. IRQ referred as
    - **Eight Input signals (Page 113) rep**
    - One Input signal
    - Eight Output signals
    - One output signal

13. IRQ for keyboard is ____**1**_____ (Page 114)

14. IRQ for sound card is _____**5**_____ (Page 114)

15. IRQ for floppy disk is _____**6**_____ (Page 114)

16. IRQ with highest priority is
    - Keyboard IRQ
    - **Timer IRQ (Page 114)**
    - Sound Card
    - Floppy Disk

17. Pin for parallel port ground is
    - 10-18
    - **18-25 (Page 125) rep**
    - 25-32
    - 32-39

18. The physical address of Interrupt Descriptor Table (IDT) is stored in
    - GDTR
    - **IDTR (Page 182) rep**
    - IVT
    - IDTT

20. CX register is
    - **Count register (Page 15)**
    - Data register
    - Index register
    - Base register

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

21. OUT instruction uses **AX or AL** as source register. (Page 115)

22. IN DB-9 connector the Data Set ready pin is at
- 5
- **6 (Page 171)**
- 7
- 8

23. If two devices uses same IRQ then there is
- IRQ collision
- **IRQ conflict (Page 114) rep**
- IRQ drop

24. VESA organizes 16 bit color for every pixel in ratio
- 5:5:5
- **5:6:5 (Page 180) rep**
- 6:5:6
- 5:6:7

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

Question No: 1 (Marks: 1) - Please choose one
SP is associated with……. By default
- ► **SS (Page 34)**
- ► DS
- ► CS
- ► ES

Question No: 2 (Marks: 1) - Please choose one
Which bit of the attributes byte represents the red component of foreground color
- ► 5
- ► 4
- ► 3
- ► **2 (Page 81)**

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 3 (Marks: 1) - Please choose one
An 8 x 16 font is stored in _____ bytes.

► 2
► 4
► 8
► **16 (Page 150) rep**

Question No: 4 (Marks: 1) - Please choose one
In DOS input buffer, the number of characters actually read on return is stored in _____ byte.

► third
► fourth
► first
► **second (Page 152) rep**

Question No: 5 (Marks: 1) - Please choose one
Which of the following gives the more logical view of the storage medium

► BIOS
► **DOS**
► Both
► None

Question No: 6 (Marks: 1) - Please choose one
In STOSW instruction, when DF is clear, SI is

► Incremented by 1
► **Incremented by 2 (Page 92)**
► Decremented by 1
► Decremented by 2

Question No: 7 (Marks: 1) - Please choose one
Which of the following interrupts is Non maskable interrupt

► **INT 2 (Page 105)**
► INT 3
► INT 0
► INT 1

Question No: 8 (Marks: 1) - Please choose one
Which of the following IRQs is connected to serial port COM 2?

► IRQ 0
► IRQ 1
► IRQ 2
► **IRQ 3 (Page 114)**

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 9 (Marks: 1) - Please choose one
The time interval between two timer ticks is?

- ► 40ms
- ► 45ms
- ► 50ms
- ► **55ms (Page 122)**

Question No: 10 (Marks: 1) - Please choose one
The physical address of IDT(Interrupt Descriptor Table) is stored in _____

- ► GDTR
- ► **IDTR (Page 182) rep**
- ► IVT
- ► IDTT

Question No: 11 (Marks: 1) - Please choose one
In NASM an imported symbol is declared with the ..... while and exported symbol is declared with the.....

- ► Global directive, External directive
- ► **External directive, Global directive (Page 189) rep**
- ► Home Directive, Foreign Directive
- ► Foreign Directive, Home Directive

Question No: 12 (Marks: 1) - Please choose one
In 68K processors there is a 32bit ..... that holds the address of currently executing instruction

- ► **Program counter (Page 191)**
- ► Stack pointer
- ► Register
- ► Stack

Question No: 13 (Marks: 1) - Please choose one
Single step interrupt is

- ► Hardware interrupt
- ► **Like divide by zero interrupt (Page 133)**
- ► Like divide by 1 interrupt
- ► Software interrupt

Question No: 14 (Marks: 1) - Please choose one
Which of the following is NOT true about registers:

- ► Their operation is very much like memory
- ► Intermediate results may also be stored in registers
- ► They are also called scratch pad ram
- ► **None of given options**

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 15 (Marks: 1) - Please choose one
Types of jump are:
- ► short, near
- ► **short, near, far (Page 45)**
- ► near, far
- ► short, far

Question No: 16 (Marks: 1) - Please choose one
MS DOS uses ____ display mode.
- ► **Character based (Page 79)**
- ► Graphics based
- ► Numeric based
- ► Console based

Question No: 17 (Marks: 1) - Please choose one
Which of the following IRQs is derived by a timer device?

- ► **IRQ 0 (Page 114)**
- ► IRQ 1
- ► IRQ 2
- ► IRQ 3

Question No: 18 (Marks: 1) - Please choose one
In programmable interrupt controller, which of the following ports is referred as a *control port*?
- ► 19
- ► **20 (Page 115) rep**
- ► 21
- ► 22

Question No: 19 (Marks: 1) - Please choose one
INT 21 service 01H is used to read character from standard input with echo. It returns the result in _____ register.
- ► **AL (Page 152) rep**
- ► BL
- ► CL
- ► BH

Question No: 20 (Marks: 1) - Please choose one
In 9pin DB 9, which pin number is assigned to DSR (DataSet Ready) ?
- ► 4
- ► 5
- ► **6 (Page 171)**
- ► 7

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 21 (Marks: 1) - Please choose one
In 9pin DB 9, which pin number is assigned to TD (Transmitted Data) ?
- ► 1
- ► 2
- ► **3 (Page 171)**
- ► 4

Question No: 22 (Marks: 1) - Please choose one
In 9pin DB 9, Signal ground is assigned on pin number
- ► 4
- ► **5 (Page 171)**
- ► 6
- ► 3

Question No: 23 (Marks: 1) - Please choose one
8088 is a .....
- ► **16 bit processor (Page 14)**
- ► 32 bit processor
- ► 64 bit processor
- ► 128 bit processor

Question No: 24 (Marks: 1) - Please choose one
The table index (TI) is set to _____ to access the GDT (Global Descriptor Table).
- ► 1
- ► **0 (Page 175)**
- ► -1
- ► -2

Question No: 25 (Marks: 1) - Please choose one
VESA(Video Electronics Standards Association) organizes 16 color bits for every pixel in
- ► 5:5:5 format
- ► **5:6:5 format (Page 180) rep**
- ► 6:5:6 format
- ► 5:6:7 format

Question No: 26 (Marks: 1) - Please choose one
Which flags are NOT used for mathematical operations?
- ► Carry, Interrupt and Trap flag.
- ► **Direction, Interrupt and Trap flag. (Page 133) rep**
- ► Direction, Overflow and Trap flag.
- ► Direction, Interrupt and Sign flag.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2009

Question No: 1 (Marks: 1) - Please choose one
When a 32 bit number is divided by a 16 bit number, the quotient is of
- $ 32 bits
- **$ 16 bits (Page 85)**
- $ 8 bits
- $ 4 bits

Question No: 2 (Marks: 1) - Please choose one
In the instruction MOV AX, 5 the number of operands are
- $ 1
- **$ 2 (Page 25) rep**
- $ 3
- $ 4

Question No: 3 (Marks: 1) - Please choose one
3. In DOS input buffer , number of characters actually read on return is stored in
- $ First byte
- **$ Second byte (Page 152) rep**
- $ Third byte
- $ Fourth byte

Question No: 4 (Marks: 1) - Please choose one
7. VESA VEB 2.0 is standard for
- **$ High Resolution Mode (Page 180) rep**
- $ Low Resolution Mode
- $ Very High Resolution Mode
- $ Medium Resolution Mode

Question No: 5 (Marks: 1) - Please choose one
22. IN DB-9 connector the Data Set ready pin is at
- $ 5
- **$ 6 (Page 171) rep**
- $ 7
- $ 8

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 6 (Marks: 1) - Please choose one

Threads can have function calls, parameters and _____variables.

$ global

$ local (Page 141)

$ legal

$ illegal

Question No: 7 (Marks: 1) - Please choose one

How many prevalent calling conventions do exist

$ 1

$ 2 (Page 187) rep

$ 3

$ 4

Question No: 8 (Marks: 1) - Please choose one

In 9pin DB 9 DSR is assigned on pin number

$ 4

$ 5

$ 6 (Page 171)

$ 7

Question No: 9 (Marks: 1) - Please choose one

In 9pin DB 9 CTS is assigned on pin number

$ 6

$ 7

$ 8 (Page 171)

$ 9

Question No: 10 (Marks: 1) - Please choose one

In 9pin DB 9 CD is assigned on pin number

$ 1 (Page 171)

$ 2

$ 3

$ 4

Question No: 11 (Marks: 1) - Please choose one

A 32bit address register can access upto ...access has .of memory so memory increased a lot.

$2GB

$4GB (Page 175)

$6GB

$8GB

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 12 (Marks: 1) - Please choose one
in device attribute word which of the following bit decides whether it is a charater device or a block device

$ Bit 12
$ Bit 13
$ Bit 14
$ Bit 15 (Page 166) rep

Question No: 13 (Marks: 1) - Please choose one
9. Which of the following IRQ is cascading interrupt

$ IRQ 0
$ IRQ 1
$ IRQ 2 (Page 114)
$ IRQ 3

Question No: 14 (Marks: 1) - Please choose one
Which of the following interrupts is used for Arithmetic overflow

$ INT 1
$ INT 2
$ INT 3
$ INT 4 (Page 106) rep

Question No: 15 (Marks: 1) - Please choose one
An End of Interrupt (EOI) signal is sent by

$ Handler (Page 114)
$ Processor
$ IRQ
$ PIC

Question No: 16 (Marks: 1) - Please choose one
The number of pins in a parallel port connector are?

$ 20
$ 25 (Page 125)
$ 30
$ 35

Question No: 17 (Marks: 1) - Please choose one
Which of the following pins of a parallel port connector are grounded?

$ 10-18
$ 18-25 (Page 125) rep
$ 25-32
$ 32-39

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 18 (Marks: 1) - Please choose one
In NASM an imported symbol is declared with the ..... while and exported symbol is declared with the.....

$ Global directive, External directive
$ External directive, Global directive (Page 189) rep
$ Home Directive, Foreign Directive
$ Foreign Directive, Home Directive

FINALTERM EXAMINATION
Fall 2008
CS401- Computer Architecture and Assembly Language Programming (Session - 1)

Question No: 1 (Marks: 1) - Please choose one
Which of the following is not true about registers:

Their operation is very much like memory
Intermediate results may also be stored in registers.
They are also called scratch pad ram
None of given options.

Question No: 2 (Marks: 1) - Please choose one
move [bp], al moves the one byte content of the AL register to the address contained in BP register in the current

Stack segment (Page 35)
Code segment
Data segment
Extra segment

Question No: 3 (Marks: 1) - Please choose one
In a rotate through carry right (RCR) instruction applied on a 16 bit word effectively there is

16 bits rotation
1 bit rotation
17 bits rotation (Page 53)
8 bits rotation

Question No: 4 (Marks: 1) - Please choose one
The 8088 stack works on

Word sized elements (Page 68)
Byte sized elements

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Double sized element
Nible sized element

Question No: 5 (Marks: 1) - Please choose one
An 8 x 16 font is stored in _____ bytes.
2
4
8
16 (Page 150) rep

Question No: 6 (Marks: 1) - Please choose one
INT 10 is used for _____ services.
RAM
Disk
BIOS video (Page 149)
DOS video

Question No: 7 (Marks: 1) - Please choose one
Priority of IRQ 0 interrupt is
medium
high
highest (Page 114) rep
low

Question No: 8 (Marks: 1) - Please choose one
Threads can have function calls, parameters and _____ variables.
global
local (Page 141) rep
legal
illegal

Question No: 9 (Marks: 1) - Please choose one
How many prevalent calling conventions do exist
1
2 (Page 187) rep
3
4

Question No: 10 (Marks: 1) - Please choose one
In 9pin DB 9 DSR is assigned on pin number
4
5
6 (Page 171) rep
7

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 11 (Marks: 1) - Please choose one
In 9pin DB 9 CTS is assigned on pin number
6
7
8 (Page 171) rep
9

Question No: 12 (Marks: 1) - Please choose one
In 9pin DB 9 CD is assigned on pin number
1 (Page 171) rep
2
3
4

Question No: 13 (Marks: 1) - Please choose one
In 9pin DB 9 RD is assigned on pin number
1
2 (Page 171)
3
4

Question No: 14 (Marks: 1) - Please choose one
in device attribute word which of the following bit decides whether it is a character device or a block device
Bit 12
Bit 13
Bit 14
Bit 15 (Page 166)

Question No: 15 (Marks: 1) - Please choose one
Video services are classified into _____ broad categories
2 (Page 149)
3
4
5

Question No: 16 (Marks: 1) - Please choose one
In STOSB instruction, when DF is clear, SI is
Incremented by 1 (Page 92) rep
Incremented by 2
Decremented by 1
Decremented by 2

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 17 (Marks: 1) - Please choose one
The process of sending signals back and forth is called
Activity
Hand-shaking
Interruption
Time clicking

Question No: 18 (Marks: 1) - Please choose one
Which of the following interrupts is used for Arithmetic Overflow?
INT 1
INT 2
INT 3
INT 4 (Page 106) rep

Question No: 19 (Marks: 1) - Please choose one
Which of the following is a special type of interrupt that returns to the same instruction instead of the next instruction?
Divide overflow interrupt (Page 107)
Debug interrupt
Arithmetic overflow interrupt
Change of sign interrupt

Question No: 20 (Marks: 1) - Please choose one
Which of the following IRQs is derived by a timer device?
IRQ 0 (Page 114) rep
IRQ 1
IRQ 2
IRQ 3

Question No: 21 (Marks: 1) - Please choose one
Which of the following IRQs is connected to serial port COM 2?
IRQ 0
IRQ 1
IRQ 2
IRQ 3 (Page 114) rep

Question No: 22 (Marks: 1) - Please choose one
An End of Interrupt (EOI) signal is sent by
Handler (Page 114) rep
Processor
IRQ
PIC

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 23 (Marks: 1) - Please choose one
The source registers in OUT is

AL or AX (Page 115) rep
BL or BX
CL or CX
DL or DX

Question No: 24 (Marks: 1) - Please choose one
In programmable interrupt controller which of the following ports is used for selectively enabling or disabling interrupts

19
20
21 (Page 115)
22

Question No: 25 (Marks: 1) - Please choose one
The number of pins in a parallel port connector are?

20
25 (Page 125) rep
30
35

Question No: 26 (Marks: 1) - Please choose one
Which of the following pins of a parallel port connector are grounded?

10-18
18-25 (Page 125) rep
25-32
32-39

Question No: 27 (Marks: 1) - Please choose one
If the decimal number "35" is shifted by two bit to left, the new value will be

35
70
140 (00100011 = 35 , 10001100=140)
17

Question No: 28 (Marks: 1) - Please choose one
A 32bit address register can access upto..... of memory so memory access has increased a lot.

2GB
4GB (Page 175) rep
6GB
8GB

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 29 (Marks: 1) - Please choose one
In NASM an imported symbol is declared with the ..... while and exported symbol is declared with the.....

Global directive, External directive
External directive, Global directive (Page 189) rep
Home Directive, Foreign Directive
Foreign Directive, Home Directive

Question No: 30 (Marks: 1) - Please choose one
Single step interrupt is

Hardware interrupt
Like divide by zero interrupt (Page 133) rep
Like divide by 1 interrupt
Software interrupt

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2007

Question No: 1 (Marks: 1) - Please choose one
Sun SPARC Processor has a fixed _____ instruction size.
? 16bit
? 32bit (Page 192) rep
? 64bit
? 20bit

Question No: 2 (Marks: 1) - Please choose one
When the subprogram finishes, the _____ retrieves the return address from the stack and transfers control to that location.
? RET instruction **Click here for detail**
? CALL instruction
? POP instruction
? Jump instruction

Question No: 3 (Marks: 1) - Please choose one
A 32 bit address register can access upto _____ of memory.
? 1 GB
? 6 GB
? 4 GB (Page 175) rep
? 2 GB

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 4 (Marks: 1) - Please choose one
The value of a segment register when the processor is running under protected mode is called _____
? segment descriptor
? segment selector
? global descriptor table
? protected register

Question No: 5 (Marks: 1) - Please choose one
FS and FS and GS are two _____ in protected mode.
? segment registers
? segment selectors (Page 175)
? stack pointers
? register pointers

Question No: 6 (Marks: 1) - Please choose one
IRQ 0 interrupt have _____ priority
? low
? medium
? highest (Page 114) rep
? lowest

Question No: 7 (Marks: 1) - Please choose one
IDT stands for _____.
? interrupt descriptor table (Page 182)
? individual descriptor table
? inline data table
? interrupt descriptor table

Question No: 8 (Marks: 1) - Please choose one
Every bit of line status in serial port conveys _____ information.
? different (Page 171)
? same
? partial
? full

Question No: 9 (Marks: 1) - Please choose one
There are total _____ bytes in a standard floppy disk.
? 1444k
? 1440k (Page 155)
? 1280k
? 2480k

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 10 (Marks: 1) - Please choose one
An 8x16 font is stored in _____ bytes.
? 8
? 16 (Page 150) rep
? 4
? 20

Cs401 – Quiz No.3 (June 2012)

Question No: 1(Marks: 1)
Memory address space is selected when which of the following instructions is given to the processor?s
Select correct option:
MOV (page 115)
DEC
IN
ADD

Question No: 2(Marks: 1)
PCB stands for?
Select correct option:
Process Control Block (Page 140)
Process Clearing Block
Programmable Counter Block
Programs Control Block

Question No: 3(Marks: 1)
The input frequency of the programmable interval timer (PIT) is
Fixed (Page 122)
Depends on processor clock
Variable
Depends on hardware attached

Question No: 4(Marks: 1)
Programmable interrupt controller has two ports 20 and 21. Port 20 is the control port while port 21 is.....
The Interrupt mask register (Page 115)
Interrupt port
Output port
Input port

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 5(Marks: 1)
The time interval between two timer ticks is ?
40ms
45ms
50ms
55ms (Page 122)

Question No: 6(Marks: 1)
Which of the following interrupts is used for saving and restoring the registers
INT6
Int7
Int8 (Page 141)
Int0
.

Question No: 7(Marks: 1)
In programmable interrupt controller which of the following ports is referred as a interrupt mask register?
19
20
21 (Page 115)
22

Question No: 8(Marks: 1)
The programmable interval timer (PIT) has input frequency of
1.193MHZ (Page 122)
2.192MHZ
3.196MHZ
4.198MHZ

Question No: 9(Marks: 1)
Peripheral address space is selected when which of the following instructions is given to the processor?
MOV
IN (Page 155)
Add
Out

Question No: 10(Marks: 1)
Direction flag, the interrupt flag, and the trap flag are
used for mathematical operations
not used for mathematical operations (Page 133)
status flags
not status flags

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Cs401 – Quiz No.3 (June 2012)

Question No: 1(Marks: 1)
The space where all the registers of a task are stored is called the
control block (Page 140)
process control block
stack
memory

Question No: 2(Marks: 1)
Which of the following interrupt is of highest priority interrupt?
Select correct option:
Key board interrupt
Timer interrupt (Page 122)
INT 2
INT 3

Question No: 3(Marks: 1)
The instruction used to read a character from the keyboard port is
in al, 0x60 (Page 125)
out al, 0x60
in al, 0x80
out al, 0x80

Question No: 4(Marks: 1)
Each thread can have their own
execution area
stack (Page 141)
memory
array

Question No: 5(Marks: 1)
All the registers & stack are saved in
Multitasking
multi-processing
function call
BIOS

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 6(Marks: 1)
There is no instruction to clear the
Select correct option:
Trap flag (Page 133)
Interrupt flag
Direction flag
None of the above

Question No: 7(Marks: 1)
The interrupt mask register which can be used for selectively enabling or disabling interrupts is associated with
Select correct option:
Port 19
Port 20
Port 21 (Page 115)
Port 22

Question No: 8(Marks: 1)
The parallel port connector is called?
Select correct option:
DB-25 (Page 125)
BD-25
DB-24
BD-24

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401-Assembly Language

(Solved Subjective)

LECTURE FROM (23 to 45)

Junaidfazal08@gmail.com
Bc190202640@vu.edu.pk

FOR MORE VISIT VULMSHELP.COME

JUNAID MALIK
0304-1659294

AL-JUNAID TECH INSTITUTE

www.vulmshelp.com





Language Courses Training Available

I'm providing paid courses in different languages within 3 Months,Certificate will be awarded after completion.

- HTML
- CSS
- JAVASCRIPT
- BOOTSTRAPS
- JQUERY
- PHP MYSQL
- NODES.JS
- REACT JS

LMS Handling Services

LMS Activities Paid Task

Assignments 95% Results

Quizes 95% Results

GDB 95% Results

For CS619 Project Feel Free To Contact With Me

Ph# 0304-1659294
Email: junaidfazal08@gmail.com

Question No.1

Define Stack Data Structure? 2 marks

Answer:- (Page 67)

Stack is a data structure that behaves in a first in last out manner. It can contain many elements and there is only one way in and out of the container. When an element is inserted it sits on top of all other elements and when an element is removed the one sitting at top of all others is removed first

Question No.2

How many broad categories video services are classified? 2 marks

Answer:- (Page 149)

Video services are classified into two broad categories; graphics mode services and text mode services.

Question No.3

What is programmer view of processor? 2 marks

Answer:- (Page 32)

The processor will blindly go there, where we mention even if it contains data and not code

Question No.4

INT-14-Serial-READ CHARACTER FORM PORT uses which two 8-bit registers to return to result? 2 marks

Answer:- (Page 172)

Return:
AH = line status
AL = received character if AH bit 7 clear

Question No.5

Difference between two instructions? 3 marks
mov byte [num1],5
mov word [num1],5

Answer:-

In first instruction, The variable num1 is treated as a byte and similarly 5 is also treated as byte.
In 2nd instruction, The variable num1 is treated as a word and similarly 5 is also treated as word.

Question No.6

Write two different modes of video services of BIOS? Differentiate between both modes? 3 Marks

Answer:- (Page 149)

Video services are classified into two broad categories; graphics mode services and text mode services. In graphics mode a location in video memory corresponds to a dot on the screen. In text mode this relation is not straightforward. The video memory holds the ASCII of the character to be shown and the actual shape is read from a font definition stored elsewhere in memory

Question No.7

Define Triple Fault? 3 Marks

Question No.8

Difference between roles of segment-selector and segment-descriptor? 3 Marks

Answer:- (Page 175)

Role of selector is to select on descriptor from the table of descriptors and the role of descriptor is to define the actual base address.

Question No.9

How value of Stack pointer (SP) changes after every PUSH or POP instructions? 5 Marks

Answer:- (Page 68)

Whenever an element is pushed on the stack SP is decremented by two and when we pop from it, it increments by 2 as in case of decrementing stack. A decrementing stack moves from higher addresses to lower addresses as elements are added in it

Question No.10 5 Marks

How to write disk sector using INT 13 service?

Answer:- (Page 156)

INT 13 - DISK - WRITE DISK SECTOR(S)
AH = 03h
AL = number of sectors to write (must be nonzero)
CH = low eight bits of cylinder number
CL = sector number 1-63 (bits 0-5)
high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)
ES:BX -> data buffer
Return:
CF = error flag
AH = error code
AL = number of sectors transferred

Question No.11

Write down instructions for data movement and arithmetic operations in Motorola 68K Processor? 5 Marks

Answer:- (Page 191)

Data Movement
EXG D0, D2
MOVE.B (A1), (A2)
MOVEA (2222).L, A4
MOVEQ #12, D7
Arithmetic
ADD D7, (A4)
CLR (A3) (set to zero)
CMP (A2), D1
ASL, ASR, LSL, LSR, ROR, ROL, ROXL, ROXR (shift operations)

0304-1659294
www.vulmshelp.com

Question No.12 5 Marks

How to load program using INT21 service?

Answer:- (Page 165)

INT 21 - LOAD AND/OR EXECUTE PROGRAM
AH = 4Bh
AL = type of load (0 = load and execute)
DS:DX -> ASCIZ program name (must include extension)
ES:BX -> parameter block
Return:
CF = error flag
AX = error code

Question No.13

Difference between serial and parallel communication.

Answer:- (Page 171)

Serial port is a way of communication among two devices just like the parallel port. The basic difference is that whole bytes are sent from one place to another in case of parallel port while the bits are sent one by one on the serial port in a specially formatted fashion.

Question No.14

Write brief about INT 13 – Extended READ SERVICES

Answer:-(Page 157)

INT 13 - INT 13 Extensions - EXTENDED READ
AH = 42h
DL = drive number
DS:SI -> disk address packet
Return:
CF = error flag
AH = error code

Question No.15

Describe briefly INT 3 functionality.

Answer:- (Page 133)

INT 3 is a Debug Interrupt. INT 3 has a single byte opcode so it can replace any instruction. This allows it to replace any instruction whatsoever. This is also called break point interrupt.

Question No.16

How to create or Truncate File using INT 21 Service?

Answer:- (Page 161)

INT 21 - CREATE OR TRUNCATE FILE
AH = 3Ch
CX = file attributes
DS:DX -> ASCIZ filename
Return:
CF = error flag
AX = file handle or error code

NAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

Question No.17

Define condition when ZF is set or clear? 2 marks

Answer:- (Page 41)

When the source is subtracted from the destination and both are equal the result is zero and therefore the zero flag is set.

Question No.18

Types of User descriptor?

Question No.19

System descriptor?

Answer:-(Page 182)

The S bit tells that this is a system descriptor

Question No.20

Define interrupt INT 0*80


Answer:- (Page 145)

int 0x80 ; multitasking kernel interrupt

Question No.21

Draw serial port connector? 5marks

Answer:-(Page 171)



Question No.22

Define extended ADD with carry? 5 marks

Answer:- (Page 57)

The instruction is ADC or "add with carry." Normal addition has two operands and the second operand is added to the firstoperand. However ADC has three operands. The third implied operand is the carry flag. The ADC instruction is specifically placed for extending the capability of ADD. Numbers of any size can be added using a proper combination of ADD and ADC. ADC first adds the carry flag to AX and then adds BX to AX. Therefore the last carry is also included in the result.

Question No.23

Data movement? 5 marks

Answer:- (Page 13)

These instructions are used to move data from one place to another. These places can be registers, memory, or
even inside peripheral devices. Some
examples are:
mov ax, bx
lad 1234

Question No.24

What is speed of multitasking?

Answer:- (Page 143)

When new threads are added, there is an obvious slowdown in the speed of multitasking. To improve that, We can change the timer interrupt frequency. The following can be used to set to an approximately 1ms interval.
mov ax, 1100
out 0x40, al
mov al, ah
out 0x40, al
This makes the threads look faster. However the only real change is that the timer interrupt is now coming more frequently

Question No.25

What is the function of ES and DS in video mode?

Answer:- (Page 81)

Both DS and ES can be used to access the video memory. However we commonly keep DS for accessing our data, and load ES with the segment of video memory.

Question No.26

Device drivers and its routine

Answer:- (Page 166)

Device drivers are operating system extensions that become part of the operating system and extend its services to new devices.

Question No.27

INT 13 Read sector into memory

Answer:- (Page 156)

INT 13 - DISK - READ SECTOR(S) INTO MEMORY
AH = 02h
AL = number of sectors to read (must be nonzero)
CH = low eight bits of cylinder number
CL = sector number 1-63 (bits 0-5)
high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)

ARSHAD TECH INSTITUTE
0304-1659294
www.vulmshelp.com

ES:BX -> data buffer
Return:
CF = error flag
AH = error code
AL = number of sectors transferred

Question No.28

SCAS instruction? How it checks null string?

Answer:- (Page 92,95)

SCAS compares a source byte or word in register AL or AX with the destination string element addressed by ES:DI and updates the flag. We use SCASB with REPNE and a zero in AL to find a zero byte in the string. In CX we load the maximum possible size, which are 64K bytes.

Question No.29

Function of 9 pin DB 9 Connectors?

Answer:- (Page 171)

1 – Carrier Detect
2 – Received Data
3 – Transmitted
4 – Data Terminal Ready
5 – Signal Ground
6 – Data Set Ready
7 – Request to Send
8 – Clear to Send
9 – Ring Indicator

Question No.30

What flags are used in AND operation

Answer:-

Affected Flag of AND are:
CF, OF, PF, SF, ZF and AC.

Question No.31

What do you mean by calling conventions?

Answer:- (Page 187)

To interface an assembly routine with a high level language program means to be able to call functions back and forth. And to be able to do so requires knowledge of certain behavior of the HLL when calling functions. This behavior of calling functions is called the calling conventions of the language. Two prevalent calling conventions are the C calling convention and the Pascal calling convention.

Question No.32

Why we say that stack behaves like LIFO? (Marks 2)

Answer:-

Because the structure of stack is based on first in last out. The value which we push last on the stack should be pop first.

0304-1659294

Question No.33

What are the services provided by INT 0x18? (Marks 2)

Question No.34

Which register's used by "INT 21-CREATE OR TRUNCATE FILE" to read service number and file attributes? (Marks 2)

Answer:-

AH = 3Ch
CX = file attributes
DS:DX -> ASCIZ filename

Question No.35

What do you mean by faulty instruction? (Marks 2)

Question No.36

Which instructions are to call a subroutine and to get back to the same point where the function was called? Explain these instruction with help of an Examples.(Marks 3)

Answer:- (Page 64)

CALL is used to call a subroutine and to get back RET is used. CALL takes a label as argument and execution
starts from that label, until the RET instruction is encountered and it takes execution back to the instruction following the CALL.
FOR EXAMPLE:

```
[org 0x0100]
jmp start
num: dw 1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,19,20
sum: add dx, [num+bx]
add bx,2
cmp bx,40
jne sum
ret
start: mov dx,0
mov bx,0
call sum
mov ax,0x4c00
int 0x21
```

Question No.37

With reference to the multitasking program" TSR Caller" writes against each instruction what they do. (Marks 3)

MOVE al, [chars+bx]
Move [es: 40], al
INC bx

Answer:- (Page 146)

MOVE al, [chars+bx]
It will read next character from the declared variable char.

Move [es: 40], al

AJ JUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

Answer: It will print the data at the specified place

INC bx
Answer: It will increment the register bx by 1

Question No.38
Consider the function "int divide (int divided, int divisor)" declared in C, write the code to call this function from assembly language? (Marks 3)
Answer:- (Page 187)
To call this function from assembly we have to write.

```
push dword [mydivisor]
push dword [mydividend]
call _divide
add esp, 8
; EAX holds the answer
```

Question No.39
How many type of Granularity are there? (Marks 3)
Answer:-
In particular two types of granularity have been delineated aggregation and abstraction.

Question No.40
Write an assembly language program that clears the computer screen? (marks 5)
Answer:- (Page 82)

```
; clear the
screen [org
0x0100]
mov ax, 0xb800; load video base in ax
mov es, ax              ; point es to video base
mov di, 0               ; point di to top left column
nextchar: mov word [es:di], 0x0720      ; clear next char on screen
add di, 2               ; move to next screen location
cmp di, 4000            ; has the whole screen cleared
jne nextchar            ; if no clear next position
mov ax, 0x4c00          ; terminate program
int 0x21
```

Question No.41
Write an assembly language program for drawing a line in graphic mode of video service? (Marks 5)
Answer:- (Page 152)

```
; draw line in graphics
mode [org 0x0100]
mov ax, 0x000D ; set 320x200 graphics
mode int 0x10 ; bios video services
```

VU JUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

```
mov ax, 0x0C07 ; put pixel in white
color xor bx, bx ; page number 0
mov cx, 200 ; x position 200
mov dx, 200 ; y position 200
l1: int 0x10 ; bios video
services dec dx ; decrease y
position
loop l1 ; decrease x position and
repeat mov ah, 0 ; service 0 – get
keystroke int 0x16 ; bios keyboard
services mov ax, 0x0003 ; 80x25 text
mode int 0x10 ; bios video services
mov ax, 0x4c00 ; terminate
program int 0x21
```

Question No.42

Write down the movement instruction for SUN SPARK processor? Provide at least two examples? (Marks 5)

Answer:- (Page 193)

Data Movement
LDSB [rn], rn (load signed byte)
LDUW [rn], rn (load unsigned word)
STH [rn], rn (store half word)

Question No.43

How many calling conversion also tell the names? (2)

Answer:- (Page 187)

Two prevalent calling conventions are the C calling convention and the Pascal calling convention.

Question No.44

Sun Spark Properties? 5

Answer:- (Page 192)

SPARC stands for Scalable Processor Architecture. SPARC is a 64bit processor. It byte order is user settable and even on a per program basis. There are 8 global registers and 8 alternate global registers. One of them is active at a time and accessible as g0-g7.SPARC introduces a concept of register window.One window is 24 registers and the active window is pointed to by a special register called Current Window Pointer (CWP).

Question No.45

How many bytes floppy root directory entry has? (2)

Answer:

224 bytes for a 3 1/2 inch floppy

Question No.46

Base Register Function?5

Answer:- (Page 35)

A base register is used in brackets and the actual address accessed depends on the value contained in that register. For example “mov [bx], ax” moves the two byte contents of the AX register to the address contained in the BX register in the current data segment. The instruction “mov [bp], al” moves the one byte content of the AL register to the address contained in the BP register in the current stack segment.

Question No.47

Chargen Services Attributes? 5

Answer:- (Page 150)

INT 10 - VIDEO - GET FONT INFORMATION
AX = 1130h
BH = pointer specifier
Return:
ES:BP = specified pointer
CX = bytes/character of on-screen font
DL = highest character row on screen

Question No.48

Difference SHR&SAR? 2

Answer:- (Page 150)

The sign bit is NOT retained in SHR operation while in SAR The sign bit is retained.

Question No.49

Imported and exported symbols in NASM? 2

Answer:- (Page 189)

In NASM an imported symbol is declared with the extern directive while and exported symbol is declared with the global directive.

Question No: 50 (Marks: 5)

In the context of **" INT 13 - DISK - WRITE DISK SECTOR(S)"** fill the blanks by choosing the correct answer against each blank space from the list given at the bottom.

Answer:- (Page 156)

AH = 03h
AL = number of sectors to write (must be nonzero)
CH = bits of low eight cylinder number
CL = sector number 1-63 (bits 0-5)

high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)
ES:BX -> data buffer
(Number of sectors to write, head number , 03h, data buffer , low eight bits of cylinder number)

Question No.51

What is CALL instruction work?

Answer:- (Page 64)

AL-NAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

CALL takes a label as argument and execution starts from that label, until the RET instruction is encountered and it takes execution back to the instruction following the CALL. The RET works regardless of the CALL and the CALL works regardless of the RET.

Question No: 52 (Marks: 2)

Write instructions to do the following. Copy contents of memory location with offset 0025 in the current data segment into AX.

Answer:-

Mov ax , [0025]

Question No.53

Define the multitasking (2)

Answer:-

Multitasking is processing multiple tasks at one time

Question No.54

Define the protected mode (3)

Answer:- (Page 175)

Switching processor in the newer 32bit mode is a very easy task. Just turn on the least significant bit of a new register called CR0 (Control Register 0) and the processor switches into 32bit mode called protected mode.

Question No.55

What is disk driver and why disk driver are necessary in BIOS (5)

Answer:- (Page 156)

BIOS disk services used to directly see the data stored in the directory entries by DOS. For this purpose we will be using the BIOS disk services.

Question No.56

Writ the code of break point interrupt routine (5)

Answer: Page 136 (Example 10.2)

0304-1659294
www.vulmshelp.com

Question No.57

Define the trap flag (3)

Answer:- (Page 133)

If the trap flag is set, the after every instruction a type 1 interrupt will be automatically generated. This is like the divide by zero interrupt which was never explicitly invoked but it came itself.

Question No.58

From what purpose INT 1 is reserved (2)

Answer:- (Page 105)

This interrupt is used in debugging with the trap flag. If the trap flag is set the Single Step Interrupt is generated after every instruction. By hooking this interrupt a debugger can get control after every instruction and display the registers etc.

Question No: 59 (Marks: 5)

Write assembly language instructions to set the timer interrupt frequency at 1 ms.

Answer: (Page 143)

```
mov    ax, 1100
out    0x40, al
mov    al, ah
out    0x40, al
```

Question No.60

When we multiply two 8 bit numbers, in how many bits there answer will be? (2 Marks)

Answer:-

16 bit

Question No: 61 (Marks: 5

Write down the operations of CMP instruction? (2)

Answer:- (Page 39)

The operation of CMP is to subtract the source operand from the destination operand, updating the flags without changing either the source or the destination.

Question No.62

Define serial port? (2 Marks)

Question No.63

Difference between serial and parallel communication.

Answer:- (Page 171)

Serial port is a way of communication among two devices just like the parallel port

Question No.64

How to reset disk file system using INT 13 Disk Rest services? (3 Marks)

Answer:- (Page 156)

INT 13 - DISK - RESET DISK SYSTEM
AH = 00h
DL = drive
Return:
CF = error flag
AH = error code

Question No.65

Why IF & TF are cleared? (3 Marks)

Answer:- (Page 133)

The interrupt mechanism automatically clears IF and TF otherwise there would an infinite recursion of the single step interrupt. The TF is set in the flags on the stack so another interrupt will comes after one more instruction is executed after the return of the interrupt.

Question No.66

Describe "Indexed Register Indirect + offset" addressing mode with example? (3 Marks)

Answer:- (Page 136)

ALNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

An index register is used with a constant offset in this addressing mode. The value contained in the index register is added with the constant offset to get the effective address. For example “mov [si+300], ax” moves the word contained in AX to the offset attained by adding 300 to SI in the current data segment and the instruction “mov [di+300], al” moves the byte contained in AL to the offset attained by adding 300 to DI in the current data segment.

Question No.67

Write the algorithm of bubble sort in your words? (5 Marks)

Answer:- (Page 46)

In this algorithm we compare consecutive numbers. If they are in required order e.g. if it is a descending sort and the first is larger then the second, then we leave them as it is and if they are not in order, we swap them. Then we do the same process for the next two numbers and so on till the last two are compared and possibly swapped.

Question No.68

List only five BIOS video services used in text mode? (5 Marks)

Answer:- (Page 149)

INT 10 - VIDEO - SET TEXT-MODE CURSOR
SHAPE INT 10 - VIDEO - SET CURSOR
POSITION INT 10 - VIDEO - SCROLL UP
WINDOW INT 10 - VIDEO - SCROLL DOWN
WINDOW INT 10 - VIDEO - WRITE STRING

Question No: 69 (Marks: 3)

Write the name three flags which are not used for mathematical operations.

Answer:- (Page 133)

The three flags not used for mathematical operations are the direction flag, the interrupt flag and the trap flag.

Question No: 70 (Marks: 3)

"INT 13 - DISK - GET DRIVE PARAMETERS” uses which registers to return *error flag* and *error number*.

Answer:- (Page 156)

CF = error flag
AH = error code

Question No: 71 (Marks: 3)

Who is responsible for removing the parameter from the stack when we call a function in C and Pascal?

Answer:- (Page 187)

In C the caller removes the parameter while in Pascal the callee removes them. The C scheme has reasons pertaining to its provision for variable number of arguments.

Question No.72

Which register is used as thread local variable? (2)

Answer:- (Page 141)

SP (stack pointer) register used as thread local variable

0304-1659294
www.vulmshelp.com

Question No.73

what is the difference in Motorola 64 k and x86 processors? 5 marks

Answer:- (Page 191)

The instructions are very similar however the difference in architecture evident. 68K processors have 16 23bit general purpose registers named from A0-A7 and D0-D7. A0-A7 can hold addresses in indirect memory accesses. These can also be used as software stack pointers. Stack in 68K is not as rigit a structure as it is in x86.

Question No.74

Which register is called a scratch register? 2 marks

Answer:- (Page 187)

EAX, ECX, EDX, FS, GS, EFLAGS, and any other registers.

Question No.75

What is scheduler

Answer:- (Page 141)

INT 08 that is saving and restoring the registers is called the scheduler.

Question No.76

VESA INT 10 service

Answer:- (Page 180)

INT 10 – VESA – Get SuperVGA Infromation
INT 10 – VESA – Get SuperVGA Mode Information
INT 10 – VESA – Set VESA Video Mode

Question No: 77 (Marks: 3)

VESA service **"INT 10 – VESA – Get SuperVGA Information"** uses which registers to return the result?

Answer:- (Page 180)

To return the result, "INT 10 – VESA – Get SuperVGA Information" uses:
Return:
AL = 4Fh if function supported
AH = status

Question No.78

What is Stack overflow

Answer:- (Page 187)

The strong argument in favour of callee cleared stacks is that the arguments were placed on the stack for the subroutine, the caller did not needed them for itself, so the subroutine is responsible for removing them. Removing the arguments is important as if the stack is not cleared or is partially cleared the stack will eventually become full, SP will reach 0, and thereafter wraparound producing unexpected results. This is called stack overflow.

Question No.79

Difference between naming conversion of C language & Pascal (5).

Answer:- (Page 187)

C pretends an underscore to every function or variable name while Pascal translates the name to all uppercase. C++ has a weird name mangling scheme that is compiler dependent. To avoid it C++ can be forced to use C style naming with extern "C" directive.

JUNAID TECH INSTITUTE
0304-1659294
www.vumaid.com

Question No.80

Difference between Data Bus & Control bus (5).

Answer:- (Page 9)

Data bus is used to move the data from the memory to the processor in a read operation and from the processor to the memory in a write operation. While one line of the bus is used to inform the memory about whether to do the read operation or the write operation. These lines are collectively known as the control bus

Question No: 81 (Marks: 2)

Define short jump

Answer:- (Page 46)

If the offset is stored in a single byte as in 75F2 with the opcode 75 and operand F2, the jump is called a short jump.

Question No.82

In what order C & Pascal instruction are passed to routines. (3).

Answer:- (Page 187)

In C parameters are pushed in reverse order with the rightmost being pushed first. While in Pascal they are pushed in proper order with the leftmost being pushed first.

Question No.83

Describe Debugger in the term of Trap Flag (5).

Answer:- (Page 133)

If the trap flag is set, the after every instruction a type 1 interrupt will be automatically generated. The debugger is made using this interrupt. It allows one instruction to be executed and then return control to us. It has its display code and its code to wait for the key in the INT 1 handler. Therefore after every instruction the values of all registers are shown and the debugger waits for a key.

Question No: 84 (Marks: 2)

Write instruction to allocate space for 32 PCBs.

Answer:- (Page 141)

pcb: times 32*16 dw 0 ; space for 32 PCBs

Question No.85

What the processor vision about video devices. (3).

Answer:- (Page 80)

The video device is seen by the computer as a memory area containing the ASCII codes that are currently displayed on the screen and a set of I/O ports controlling things like the resolution, the cursor height, and the cursor position.

Question No.86

lds si, [bp+4] from DS and SI will load? (2)

Answer:- (Page 97)

lds si, [bp+4]" will load SI from BP+4 and DS from BP+6.

FAHUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

Question No.87

What is processor control block answer in one line (2).

Answer:- (Page 140)

The space where all registers of a task are stored is called the process control block or PCB.

Question No.88

Define the debugger. How to run the debugger tell the command, and all its parts? (5)

Answer:-

A debugger is a computer program that lets you run your program, line by line and examine the values of variables or look at values passed into functions and let you figure out why it isn't running the way you expected it to.

We can run debugger by pressing F1 and F2.The debugger shows the values of registers, flags, stack, our code, and one or two areas of the system memory as data. Debugger allows us to step our program one instruction at a time and observe its effect on the registers and program data.

Question No.89

Define context switching 2 marks

Answer:- (Page 141)

INT 08 that is saving and restoring the registers is called the scheduler and the whole event is called a context switch.

Question No.90

Write the algorithm of multiplication of two 4 bits number? (3)

Answer:- (Page 51)

We take the first digit of the multiplier and multiply it with the multiplicand. As the digit is one the answer is the multiplicand itself. So we place the multiplicand below the bar. Before multiplying with the next digit a cross is placed at the right most place on the next line and the result is placed shifted one digit left.


Question No.91

How threads are register in the scheduler? (3)

Question No.92

Format of the interrupt descriptor

Answer:- (Page 182)



Question No.93

Define Faulty Instructions [3maks]

Question No.94

Write down purpose of JNZ instruction? (2)

Answer:- (Page 32)

The JNZ instruction is from the program control group and is a conditional jump, meaning that if the condition NZ is true (ZF=0) it will jump to the address mentioned and otherwise it will progress to the next instruction.

Question No.95

What are the ranges of addressable memory in protected mode?

Question No.96

Define Device drivers. Why device drivers are used when BIOS already have all available codes. write its need[5marks]

Answer:- (Page 166)

Device drivers are operating system extensions that become part of the operating system and extend its services to new devices. Device drivers in DOS are very simple. They just have their services exposed through the file system interface.

Question No.97

There was fill in blanks question with 10 marks. The choice was given at bottom.

Serial Port is also accessible via_____ports , _____is accessible via ports 3F8-3FF while _____is accessible via 2F8 -2FF.
The first register at 3F8 is the_____holding register if written to and the receiver _____ register if read from.
Other register of our interest include 3F9 whose_____must be set to enable received data available interrupt and_____must be set to enable transmitter holding register empty interrupt.
(Transmitter , COM 1 , I/O ports , COM2. bit 0 , Buffer ,
3FA)

Answer:- (Page 172)

Serial port is also accessible via **I/O** ports. **COM1** is accessible via ports 3F8-3FF while **COM2** is accessible via 2F8-2FF. The first register at 3F8 (or 2F8 for the other port) is the **transmitter** holding register if written to and the receiver **buffer** register if read from. Other registers of our interest include 3F9 whose **bit 0** must be set to enable received data available interrupt and **bit 1** must be set to enable transmitter holding register empty interrupt.

Question No.98

Fill in the blanks with proper words[solved] [5 marks]

Answer:- (Page 150)

AH = -09h --
AL = -- character to
display –
BH = - page number ---
BL = --- attribute ---
CX =--- number of times to write character –
(09h, page number, number of times to write character, attribute ,character to display,)

Question No.99

Define Hardware Interrupt & I/O ports (5 marks)

Answer:- (Page 113-114)

Hardware interrupts

Hardware interrupts are the real interrupts generated by the external world. there are many devices generating interrupts and there is only one pin going inside the processor and one pin cannot be technically derived by more than one source a controller is used in between called the Programmable Interrupt Controller (PIC).

I/O ports

For communicating with peripheral devices the processor uses I/O ports. There are only two operations with the external world possible, read or write. Similarly with I/O ports the processor can read or write an I/O port. When an I/O port is read or written to, the operation is not as simple as it happens in memory.

Question No.100

DOS allocate memory for program execution and then de-allocate , explain memory management in DOS (10 marks)

Answer:- (Page 121)

At physical address zero is the interrupt vector table. Then are the BIOS data area, DOS data area, IO.SYS, MSDOS.SYS and other device drivers. In the end there is COMMAND.COM command interpreter. The remaining space is called the transient program area as programs are loaded and executed in this area and the space reclaimed on their exit. A freemem pointer in DOS points where the free memory begins. When DOS loads a program the freemem pointer is moved to the end of memory, all the available space is allocated to it, and when it exits the freemem pointer comes back to its original place thereby reclaiming all space. This action is initiated by the DOS service 4C. The second method to legally terminate a program and give control back to DOS is using the service 31. Control is still taken back but the memory releasing part is modified. A portion of the allocated memory can be retained. So the difference in the two methods is that the freemem pointer goes back to the original place or a designated number of bytes ahead of that old position.

Question No.101

What do you mean by data label and code label? (2)

Answer:- (Page 32)

Labels can be used on code as well. Just like data labels they remember the address at which they are used. The assembler does not differentiate between code labels and data labels. The programmer is responsible for using a data label as data and a code label as code.

Question No.102

List some architecture? (3)

Answer:-

iAPX88 architecture

Motorolla 68K
x86 series architecture
SPARC stands for Scalable Processor ARChitecture

Question No.103

What information is required to be provided for the service "INT14-SERIAL WRITE CHARACTER TO PORT" in the following registers? (5 marks)

AH=_____
AL=_____
DX=_____

Answer:- (Page 172)

AH = 01h
AL = character to write
DX = port number (00h-03h)

Question No.104

Which instruction makes trap flag zero? If there is not any then how we make it zero? (5 marks)

Answer:- (Page 133)

There is no instruction to set or clear the trap flag like there are instructions for the interrupt and direction flags. We use two special instructions PUSHF and POPF to push and pop the flag from the stack. We use PUSHF to place flags on the stack, change TF in this image on the stack and then reload into the flags register with POPF.

Question No.105

Division by zero is done by which interrupt.

Answer:- (Page 105)

Division by zero is done by INT 0 interrupt.

Question No.106

Difference between wraparound and physical wraparound and physical wraparounds

Question No.107

How to load AND/ OR execute program using INT 21 services (5)

Answer:- (Page 165)

INT 21 - LOAD AND/OR EXECUTE PROGRAM
AH = 4Bh
AL = type of load (0 = load and execute)
DS:DX -> ASCIZ program name (must include extension)
ES:BX -> parameter block
Return:
CF = error flag
AX = error code

VU NAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

Question No.108

Differentiate synchronous transmission and asynchronous transmission? (3)

Answer:- (Page 103)

Asynchronous means that the interrupts occur, independent of the working of the processor, i.e. independent of the instruction currently executing. Synchronous events are those that occur side by side with another activity.

Question No.109

Following piece of code is taken from the program of scrolling up the screen write against each instruction what it does (5)

```
Mov ax 80
Mu byte [bp+4]
Mov si,  ax
Push si
Shl si1
```

Answer:- (Page 150)

```
mov ax, 80 ; load chars per row in ax
mul byte [bp+4] ; calculate source position
mov si, ax ; load source position in si
push si ; save position for later use
shl si, 1 ; convert to byte offset
```

Question No: 110 (Marks: 2)

Which bit of acknowledge is used to generate IRQ7

Answer:- (Page 125)

Bit "4" of acknowledge is used to generate IRQ7

Question No.111 (Marks: 2) -

INT 14 - SERIAL - READ CHARACTER 8 bit register return result in?

Answer:- (Page 172)

Return:
AH = line status
AL = received character if AH bit 7 clear

Question No: 112 (Marks: 2)

Write types of Devices?

Answer:-

The four types of computer devices are:-

1. input devices
2. output devices
3. storage devices and
4. The central processing unit i.e. C.P.U.

AL-JUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

Question No: 113 (Marks: 2)

Explain Divide overflow

Answer:- (Page 85)

If a large number is divided by a very small number it is possible that the quotient is larger than the space provided for it in the implied destination. In this case an interrupt is automatically generated and the program is usually terminated as a result. This is called a divide overflow error;

Question No: 114 (Marks: 5)

The program given below is written in assembly language. Write a program in C to call this assembly routine.

```
[section .text]
global      swap
swap:       mov ecx,[esp+4]       ; copy parameter p1 to ecx
            mov edx,[esp+8]       ; copy parameter p2 to edx
            mov eax,[ecx]         ; copy *p1 into eax
            xchg eax,[edx]        ; exchange eax with *p2
            mov [ecx],eax         ; copy eax into *p1
            ret                   ; return from this function
```

Answer:- (Page 189)

```
#include <stdio.h>
void swap( int* p1, int* p2 );
int main()
{
int a = 10, b = 20;
printf( "a=%d b=%d\n", a, b );
swap(&a, &b );
printf( "a=%d b=%d\n", a, b );
system( "PAUSE" );
return 0;
}
```

Question No: 115 (Marks: 2)

How interrupts are handled in protected mode.

Answer:- (Page 182)

Handling interrupts in protected mode is also different. Instead of the IVT at physical address 0 there is the IDT (interrupt descriptor table) located at physical address stored in IDTR, a special purpose register. The IDTR is also a 48bit register similar in structure to the GDTR and loaded with another special instruction LGDT.

AL-JUNAID TECH INSTITUTE
0304-1659294
www.vulmshelp.com

Question No: 116 (Marks:3)

Three basic steps B/w memory and processor to communicate.

Answer:- (Page 9)

The group of bits that the processor uses to inform the memory about which element to read or write is collectively known as the address bus. Another important bus called the data bus is used to move the data from the memory to the processor in a read operation and from the processor to the memory in a write operation. The third group consists of miscellaneous independent lines used for control purposes.

Question No: 117 (Marks:3)

What is baud rate, tell the parity bit function.

Answer:- (Page 171)

The data starts with a 1 bit called the start bit, then five to eight data bits, an optional parity bit, and one to two 0 bits called stop bits.

The number of data bits, parity bits, and the number of stop bits have to be configured at both ends. Also the duration of a bit must be precisely known at both ends called the baud rate of the communication.

Question No: 118 (Marks:5)

Write the instruction of following

Copy BL into CL

Answer: mov cl, bl

Question No.119

Copy DX into AX

Answer: mov ax, dx

Question No.120

Store 0x12 into AL

Answer: mov al, 0x12

Question No.121

Store 0x1234 into AX

Answer: mov ax, 0x1234

Question No.122

Store 0xFFFF into AX

Answer: mov ax, 0xFFFF

Question No: 123 (Marks: 2)

What dose descriptor 1st 16 bit tell?

Question No: 124 (Marks: 3)

How many Types of granularity also name them?

0304-1659294
www.vulmshelp.com

Answer:-

There are three types of granularity :

1. Data Granularity
2. Business Value Granularity
3. Functionality Granularity

Question No: 125 (Marks:5)

Fill in the blanks with proper words

The GDT itself is an array of descriptors where each descriptor is an 8byte entry.

The base and limit of GDT is stored in a 48bit register called the GDTR.

This register is loaded with a special instruction LGDT and is given a memory address from where the 48bits are fetched.

Read the passage carefully and choose proper word for each blank space from the list given below . In descriptors the 32bit base is scattered into different places because of compatibility reasons.

The limit is

stored in 20 bits but the ...**G .....** defines that the limit is in terms of bytes of 4K pages therefore a maximum of 4GB size is possible. The .....**P .....** must be set to signal that this segment is present in memory. DPL is the descriptor privilege level again related to the protection levels in 386. .....**D**..... defines that this segment is to execute code is 16bit mode or 32bit mode. .....**C.....** is conforming bit that we will not be using. .....**R.....** signals that the segment is readable. A bit is automatically set whenever the segment is accessed.

(A bit, C bit, G bit, D bit, P bit , R bit, B bit)

Answer: (Page 176)

The 32bit base in both descriptors is scattered into different places because of compatibility reasons. The limit is stored in 20 bits but the G bit defines that the limit is in terms of bytes of 4K pages therefore a maximum of 4GB size is possible. The P bit must be set to signal that this segment is present in memory. DPL is the descriptor privilege level again related to the protection levels in 386. D bit defines that this segment is to execute code is 16bit mode or 32bit mode. C is conforming bit that we will not be using. R signals that the segment is readable. A bit is automatically set whenever the segment is accessed.

0304-1639294
www.vulmshelp.com


AL-JUNAID TECH INSTITUTE
AJ
0304-1659294
www.vulmshelp.com

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2012

Q1. Define Stack Data Structure? 2 marks

Answer:- (Page 67)

Stack is a data structure that behaves in a first in last out manner. It can contain many elements and there is only one way in and out of the container. When an element is inserted it sits on top of all other elements and when an element is removed the one sitting at top of all others is removed first

Q2. How many broad categories video services are classified? 2 marks

Answer:- (Page 149)

Video services are classified into two broad categories; graphics mode services and text mode services.

Q3. What is programmer view of processor? 2 marks

Answer:- (Page 32)

The processor will blindly go there, where we mention even if it contains data and not code

Q4. INT-14-Serial-READ CHARACTER FORM PORT uses which two 8-bit registers to return to result? 2 marks

Answer:- (Page 172)

Return:
AH = line status
AL = received character if AH bit 7 clear

Q5. Difference between two instructions? 3 Marks

mov byte [num1],5
mov word [num1],5

Answer:-

In first instruction, The variable num1 is treated as a byte and similarly 5 is also treated as byte.
In 2nd instruction, The variable num1 is treated as a word and similarly 5 is also treated as word.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Q6. Write two different modes of video services of BIOS? Differentiate between both modes? 3 Marks

Answer:- (Page 149)

Video services are classified into two broad categories; graphics mode services and text mode services. In graphics mode a location in video memory corresponds to a dot on the screen. In text mode this relation is not straightforward. The video memory holds the ASCII of the character to be shown and the actual shape is read from a font definition stored elsewhere in memory

Q7. Define Triple Fault? 3 Marks

Q8. Difference between roles of segment-selector and segment-descriptor? 3 Marks

Answer:- (Page 175)

Role of selector is to select on descriptor from the table of descriptors and the role of descriptor is to define the actual base address.

Q9. How value of Stack pointer (SP) changes after every PUSH or POP instructions? 5 Marks

Answer:- (Page 68)

Whenever an element is pushed on the stack SP is decremented by two and when we pop from it, it increments by 2 as in case of decrementing stack. A decrementing stack moves from higher addresses to lower addresses as elements are added in it

Q10. How to write disk sector using INT 13 service? 5 Marks

Answer:- (Page 156)

INT 13 - DISK - WRITE DISK SECTOR(S)
AH = 03h
AL = number of sectors to write (must be nonzero)
CH = low eight bits of cylinder number
CL = sector number 1-63 (bits 0-5)
high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)
ES:BX -> data buffer
Return:
CF = error flag
AH = error code
AL = number of sectors transferred

Q11. Write down instructions for data movement and arithmetic operations in Motorola 68K Processor? 5 Marks

Answer:- (Page 191)

Data Movement
EXG D0, D2
MOVE.B (A1), (A2)
MOVEA (2222).L, A4

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

MOVEQ #12, D7
Arithmetic
ADD D7, (A4)
CLR (A3) (set to zero)
CMP (A2), D1
ASL, ASR, LSL, LSR, ROR, ROL, ROXL, ROXR (shift operations)

Q12. How to load program using INT21 service? 5 Marks
Answer:- (Page 165)
INT 21 - LOAD AND/OR EXECUTE PROGRAM
AH = 4Bh
AL = type of load (0 = load and execute)
DS:DX -> ASCIZ program name (must include extension)
ES:BX -> parameter block
Return:
CF = error flag
AX = error code

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2012

Difference between serial and parallel communication.
Answer:- (Page 171)
Serial port is a way of communication among two devices just like the parallel port. The basic difference is that whole bytes are sent from one place to another in case of parallel port while the bits are sent one by one on the serial port in a specially formatted fashion.

Write brief about INT 13 – Extended READ SERVICES
Answer:-(Page 157)
INT 13 - INT 13 Extensions - EXTENDED READ
AH = 42h
DL = drive number
DS:SI -> disk address packet
Return:
CF = error flag
AH = error code

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Describe briefly INT 3 functionality.
Answer:- (Page 133)
INT 3 is a Debug Interrupt. INT 3 has a single byte opcode so it can replace any instruction. This allows it to replace any instruction whatsoever. This is also called break point interrupt.

How to create or Truncate File using INT 21 Service?
Answer:- (Page 161)
INT 21 - CREATE OR TRUNCATE FILE
AH = 3Ch
CX = file attributes
DS:DX -> ASCIZ filename
Return:
CF = error flag
AX = file handle or error code

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2012

Q1) define condition when ZF is set or clear? 2 marks
Answer:- (Page 41)
When the source is subtracted from the destination and both are equal the result is zero and therefore the zero flag is set.


Q2) types of User descriptor?

Q3) system descriptor?
Answer:-(Page 182)
The S bit tells that this is a system descriptor

Q4) define interrupt INT 0*80
Answer:- (Page 145)
int 0x80 ; multitasking kernel interrupt

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Q5) draw serial port connector? 5marks
Answer:-(Page 171)



Q6) define extended ADD with carry? 5 marks
Answer:- (Page 57)
The instruction is ADC or "add with carry." Normal addition has two operands and the second operand is added to the firstoperand. However ADC has three operands. The third implied operand is the carry flag. The ADC instruction is specifically placed for extending the capability of ADD. Numbers of any size can be added using a proper combination of ADD and ADC. ADC first adds the carry flag to AX and then adds BX to AX. Therefore the last carry is also included in the result.

Q7) data movement? 5 marks
Answer:- (Page 13)
These instructions are used to move data from one place to another. These places can be registers, memory, or even inside peripheral devices. Some
examples are:
mov ax, bx
lad 1234

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2012

Q- What is speed of multitasking?
Answer:- (Page 143)
When new threads are added, there is an obvious slowdown in the speed of multitasking. To improve that, We can change the timer interrupt frequency. The following can be used to set to an approximately 1ms interval.

```
mov ax, 1100
out 0x40, al
mov al, ah
out 0x40, al
```

This makes the threads look faster. However the only real change is that the timer interrupt is now coming more frequently

Q- What is the function of ES and DS in video mode?
Answer:- (Page 81)
Both DS and ES can be used to access the video memory. However we commonly keep DS for accessing our data, and load ES with the segment of video memory.

Q-Device drivers and its routine
Answer:- (Page 166)
Device drivers are operating system extensions that become part of the operating system and extend its services to new devices.

Q-INT 13 Read sector into memory
Answer:- (Page 156)
INT 13 - DISK - READ SECTOR(S) INTO MEMORY
AH = 02h
AL = number of sectors to read (must be nonzero)
CH = low eight bits of cylinder number
CL = sector number 1-63 (bits 0-5)
high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)
ES:BX -> data buffer
Return:
CF = error flag
AH = error code
AL = number of sectors transferred

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Q-SCAS instruction? How it checks null string?
Answer:- (Page 92,95)
SCAS compares a source byte or word in register AL or AX with the destination string element addressed by ES:DI and updates the flag. We use SCASB with REPNE and a zero in AL to find a zero byte in the string. In CX we load the maximum possible size, which are 64K bytes.

Q-Function of 9 pin DB 9 Connectors?
Answer:- (Page 171)
1 – Carrier Detect
2 – Received Data
3 – Transmitted
4 – Data Terminal Ready
5 – Signal Ground
6 – Data Set Ready
7 – Request to Send
8 – Clear to Send
9 – Ring Indicator

Q-What flags are used in AND operation
Answer:-
Affected Flag of AND are:
CF, OF, PF, SF, ZF and AC.

Q-What do you mean by calling conventions?
Answer:- (Page 187)
To interface an assembly routine with a high level language program means to be able to call functions back and forth. And to be able to do so requires knowledge of certain behavior of the HLL when calling functions. This behavior of calling functions is called the calling conventions of the language. Two prevalent calling conventions are the C calling convention and the Pascal calling convention.

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2012

Q No 1: Why we say that stack behaves like LIFO? (Marks 2)
Answer:-
Because the structure of stack is based on first in last out. The value which we push last on the stack should be pop first.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Q No2: What are the services provided by INT 0x18? (Marks 2)

Q No3: Which register's used by "INT 21-CREATE OR TRUNCATE FILE" to read service number and file attributes? (Marks 2)

Answer:-

AH = 3Ch
CX = file attributes
DS:DX -> ASCIZ filename

Q No4: What do you mean by faulty instruction? (Marks 2)

Q No 5: Which instructions are to call a subroutine and to get back to the same point where the function was called? Explain these instruction with help of an Examples.(Marks 3)

Answer:- (Page 64)

CALL is used to call a subroutine and to get back RET is used. CALL takes a label as argument and execution starts from that label, until the RET instruction is encountered and it takes execution back to the instruction following the CALL.

FOR EXAMPLE:

```
[org 0x0100]
jmp start
num: dw 1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,19,20

sum: add dx, [num+bx]
add bx,2
cmp bx,40
jne sum
ret
start: mov dx,0
mov bx,0
call sum

mov ax,0x4c00
int 0x21
```

Q No6: With reference to the multitasking program" TSR Caller" writes against each instruction what they do. (Marks 3)

MOVE al, [chars+bx]
Move [es: 40], al
INC bx

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Answer:- (Page 146)
MOVE al, [chars+bx]
It will read next character from the declared variable char.

Move [es: 40], al
Answer: It will print the data at the specified place

INC bx
Answer: It will increment the register bx by 1

Q No7: Consider the function "int divide (int divided, int divisor)" declared in C, write the code to call this function from assembly language? (Marks 3)
Answer:- (Page 187)
To call this function from assembly we have to write.

```
push dword [mydivisor]
push dword [mydividend]
call _divide
add esp, 8
; EAX holds the answer
```

Q No 8: How many type of Granularity are there? (Marks 3)
Answer:- click here for detail
In particular two types of granularity have been delineated
aggregation and abstraction.

Q No 9: Write an assembly language program that clears the computer screen? (marks 5)
Answer:- (Page 82)

```
; clear the screen
[org 0x0100]
mov ax, 0xb800      ; load video base in ax
mov es, ax          ; point es to video base
mov di, 0           ; point di to top left column
nextchar: mov word [es:di], 0x0720      ; clear next char on screen
add di, 2           ; move to next screen location
cmp di, 4000        ; has the whole screen cleared
jne nextchar        ; if no clear next position
mov ax, 0x4c00      ; terminate program
int 0x21
```


Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Q No 10: Write an assembly language program for drawing a line in graphic mode of video service? (Marks 5)

Answer:- (Page 152)

```
; draw line in graphics mode
[org 0x0100]
mov ax, 0x000D ; set 320x200 graphics mode
int 0x10 ; bios video services
mov ax, 0x0C07 ; put pixel in white color
xor bx, bx ; page number 0
mov cx, 200 ; x position 200
mov dx, 200 ; y position 200
l1: int 0x10 ; bios video services
dec dx ; decrease y position
loop l1 ; decrease x position and repeat
mov ah, 0 ; service 0 – get keystroke
int 0x16 ; bios keyboard services
mov ax, 0x0003 ; 80x25 text mode
int 0x10 ; bios video services
mov ax, 0x4c00 ; terminate program
int 0x21
```

Q No 11: Write down the movement instruction for SUN SPARK processor? Provide at least two examples? (Marks 5)

Answer:- (Page 193)

Data Movement
LDSB [rn], rn (load signed byte)
LDUW [rn], rn (load unsigned word)
STH [rn], rn (store half word)

Q No12: What are the different registers setting values required to initialize the serial port? (Marks 5)

Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2012

Sun Spark Properties? 5
Answer:- (Page 192)
SPARC stands for Scalable Processor Architecture. SPARC is a 64bit processor. It byte order is user settable and even on a per program basis. There are 8 global registers and 8 alternate global registers. One of them is active at a time and accessible as g0-g7.SPARC introduces a concept of register window. One window is 24 registers and the active window is pointed to by a special register called Current Window Pointer (CWP).

DB 9 Connect Diagram? 5
Answer:- rep

Base Register Function?5
Answer:- (Page 35)
A base register is used in brackets and the actual address accessed depends on the value contained in that register. For example "mov [bx], ax" moves the two byte contents of the AX register to the address contained in the BX register in the current data segment. The instruction "mov [bp], al" moves the one byte content of the AL register to the address contained in the BP register in the current stack segment.

Chargen Services Attributes? 5
Answer:- (Page 150)
INT 10 - VIDEO - GET FONT INFORMATION
AX = 1130h
BH = pointer specifier
Return:
ES:BP = specified pointer
CX = bytes/character of on-screen font
DL = highest character row on screen

Difference SHR&SAR? 2
Answer:- (Page 150)
The sign bit is NOT retained in SHR operation while in SAR The sign bit is retained.

Imported and exported symbols in NASM? 2
Answer:- (Page 189)
In NASM an imported symbol is declared with the extern directive while and exported symbol is declared with the global directive.

Int 21 Create or Truncate File? 3
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2012

What is CALL instruction work?
Answer:- (Page 64)
CALL takes a label as argument and execution starts from that label, until the RET instruction is encountered and it takes execution back to the instruction following the CALL. The RET works regardless of the CALL and the CALL works regardless of the RET.

SUN SPARC processor.....three basic characteristics.
Answer:- rep

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011

Define the multitasking (2)
Answer:- Click here for detail
Multitasking is processing multiple tasks at one time

Define the protected mode (3)
Answer:- (Page 175)
Switching processor in the newer 32bit mode is a very easy task. Just turn on the least significant bit of a new register called CR0 (Control Register 0) and the processor switches into 32bit mode called protected mode.

What is disk driver and why disk driver are necessary in BIOS (5)
Answer:- (Page 156)
BIOS disk services used to directly see the data stored in the directory entries by DOS. For this purpose we will be using the BIOS disk services.

Writ the code of break point interrupt routine (5)
Answer: Page 136 (Example 10.2)

Define the trap flag (3)
Answer:- (Page 133)
If the trap flag is set, the after every instruction a type 1 interrupt will be automatically generated. This is like the divide by zero interrupt which was never explicitly invoked but it came itself.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

From what purpose INT 1 is reserved (2)
Answer:- (Page 105)
This interrupt is used in debugging with the trap flag. If the trap flag is set the Single Step Interrupt is generated after every instruction. By hooking this interrupt a debugger can get control after every instruction and display the registers etc.

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011

Write two examples of Instructions relating data movement used in "sun SPARK Processor". (2 Marks)
Answer:- rep

When we multiply two 8 bit numbers, in how many bits there answer will be? (2 Marks)
Answer:-
16 bit

What is trap flag? (2 Marks)
Answer:- rep

Define serial port? (2 Marks)
Difference between serial and parallel communication.
Answer:- (Page 171)
Serial port is a way of communication among two devices just like the parallel port

How to reset disk file system using INT 13 Disk Rest services? (3 Marks)
Answer:- (Page 156)
INT 13 - DISK - RESET DISK SYSTEM
AH = 00h
DL = drive
Return:
CF = error flag
AH = error code

Why IF & TF are cleared? (3 Marks)
Answer:- (Page 133)
The interrupt mechanism automatically clears IF and TF otherwise there would an infinite recursion of the single step interrupt. The TF is set in the flags on the stack so another interrupt will comes after one more instruction is executed after the return of the interrupt.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Describe "Indexed Register Indirect + offset" addressing mode with example? (3 Marks)
Answer:- (Page 136)
An index register is used with a constant offset in this addressing mode. The value contained in the index register is added with the constant offset to get the effective address. For example "mov [si+300], ax" moves the word contained in AX to the offset attained by adding 300 to SI in the current data segment and the instruction "mov [di+300], al" moves the byte contained in AL to the offset attained by adding 300 to DI in the current data segment.

Write the algorithm of bubble sort in your words? (5 Marks)
Answer:- (Page 46)
In this algorithm we compare consecutive numbers. If they are in required order e.g. if it is a descending sort and the first is larger then the second, then we leave them as it is and if they are not in order, we swap them. Then we do the same process for the next two numbers and so on till the last two are compared and possibly swapped.

List only five BIOS video services used in text mode? (5 Marks)
Answer:- (Page 149)
INT 10 - VIDEO - SET TEXT-MODE CURSOR SHAPE
INT 10 - VIDEO - SET CURSOR POSITION
INT 10 - VIDEO - SCROLL UP WINDOW
INT 10 - VIDEO - SCROLL DOWN WINDOW
INT 10 - VIDEO - WRITE STRING

Write main characteristic of SUN SPARK Processor? (5 Marks)
Answer:- rep

Write the code of "break point Interrupt routine". (5 Marks)
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011

1. Define multitasking? 3 marks
Answer:- rep

2. What is the function of selector and descriptor? 3 marks
Answer:- rep

4 what is the difference in Motorola 64 k and x86 processors? 5 marks
Answer:- (Page 191)
The instructions are very similar however the difference in architecture evident. 68K processors have 16 23bit general purpose registers named from A0-A7 and D0-D7. A0-A7 can hold addresses in indirect memory accesses. These can also be used as software stack pointers. Stack in 68K is not as rigit a structure as it is in x86.

5. Which register is called a scratch register? 2 marks
Answer:- (Page 187)
EAX, ECX, EDX, FS, GS, EFLAGS, and any other registers.

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011

What is scheduler
Answer:- (Page 141)
INT 08 that is saving and restoring the registers is called the scheduler.

VESA INT 10 service
Answer:- (Page 180)
INT 10 – VESA – Get SuperVGA Infromation
INT 10 – VESA – Get SuperVGA Mode Information
INT 10 – VESA – Set VESA Video Mode

Draw the DB-9 pin Connector and writ each PIN
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

What is Stack overflow

Answer:- (Page 187)

The strong argument in favour of callee cleared stacks is that the arguments were placed on the stack for the subroutine, the caller did not needed them for itself, so the subroutine is responsible for removing them. Removing the arguments is important as if the stack is not cleared or is partially cleared the stack will eventually become full, SP will reach 0, and thereafter wraparound producing unexpected results. This is called stack overflow.

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011

Difference between naming conversion of C language & Pascal (5).

Answer:- (Page 187)

C pretends an underscore to every function or variable name while Pascal translates the name to all uppercase. C++ has a weird name mangling scheme that is compiler dependent. To avoid it C++ can be forced to use C style naming with extern "C" directive.

Difference between Data Bus & Control bus (5).

Answer:- (Page 9)

Data bus is used to move the data from the memory to the processor in a read operation and from the processor to the memory in a write operation. While one line of the bus is used to inform the memory about whether to do the read operation or the write operation. These lines are collectively known as the control bus

Define protected mode (3)

Answer:- rep

In what order C & Pascal instruction are passed to routines. (3).

Answer:- (Page 187)

In C parameters are pushed in reverse order with the rightmost being pushed first. While in Pascal they are pushed in proper order with the leftmost being pushed first.

Describe Debugger in the term of Trap Flag (5).

Answer:- (Page 133)

If the trap flag is set, the after every instruction a type 1 interrupt will be automatically generated. The debugger is made using this interrupt. It allows one instruction to be executed and then return control to us. It has its display code and its code to wait for the key in the INT 1 handler. Therefore after every instruction the values of all registers are shown and the debugger waits for a key.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Define Multithreading (3).
Answer:- rep

What the processor vision about video devices. (3).
Answer:- (Page 80)
The video device is seen by the computer as a memory area containing the ASCII codes that are currently displayed on the screen and a set of I/O ports controlling things like the resolution, the cursor height, and the cursor position.
lds si, [bp+4] from DS and SI will load? (2)
Answer:- (Page 97)
lds si, [bp+4]" will load SI from BP+4 and DS from BP+6.

What is processor control block answer in one line (2).
Answer:- (Page 140)
The space where all registers of a task are stored is called the process control block or PCB.

Name the five video text mode of BIOS only list (5).
Answer:- rep

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011


Define context switching 2 marks
Answer:- (Page 141)
INT 08 that is saving and restoring the registers is called the scheduler and the whole event is called a context switch.

Make Diagram of Serial port and give pin names. 5 marks
Answer:- rep

3 common services given by video text mode. 2 marks
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Format of the interrupt descriptor
Answer:- (Page 182)



interrupt gate descriptor

offset	31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
+4	OFFSET (bit31..16)																P	DPL		S = 0	D		G = 1	10	reserved								
+0	CS selector																OFFSET (bit15..0)																

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011

1. Define Faulty Instructions [3maks]

2. Define Protected mode [3 marks]
Answer:- rep

3a. What are the ranges of addressable memory in protected mode?

5. Define Device drivers. Why device drivers are used when BIOS already have all available codes. write its need[5marks]
Answer:- (Page 166)
Device drivers are operating system extensions that become part of the operating system and extend its services to new devices. Device drivers in DOS are very simple. They just have their services exposed through the file system interface.

6. Write Bubble sort algorithm in your own words. [5 marks]
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

7. Fill in the blanks with proper words[solved] [5 marks]
Answer:- (Page 150)
AH = -09h --
AL = -- character to display --
BH = - page number ---
BL = --- attribute ---
CX =--- number of times to write character –
(09h, page number, number of times to write character, attribute ,character to display,)

8. How can we increase speed of multitasking process? [2marks]
Answer:- rep

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2011

Qno.41 How cam we improve the spec of the multitasking? (2)
Answer:- rep

Qno.42 What do you mean by data label and code label? (2)
Answer:- (Page 32)
Labels can be used on code as well. Just like data labels they remember the address at which they are used. The assembler does not differentiate between code labels and data labels. The programmer is responsible for using a data label as data and a code label as code.

Qno.43 What is system descriptor? (2)
Answer:- rep

Qno.44 What are device driver, Give your answer in two or three lines (2)
Answer:- rep

Qno.45 In what order the parameters are passed to routine in Pascal and C Language (3)
Answer:- rep

Qno.46 What is multitasking (3)
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Qno.47 Difference between wraparound and physical wraparound and physical wraparounds

Qno.49 How to load AND/ OR execute program using INT 21 services (5)
Answer:- (Page 165)
INT 21 - LOAD AND/OR EXECUTE PROGRAM
AH = 4Bh
AL = type of load (0 = load and execute)
DS:DX -> ASCIZ program name (must include extension)
ES:BX -> parameter block
Return:
CF = error flag
AX = error code

Qno.50 Describe the format of interrupt descriptor (5)
Answer:- rep

Qno.51 Following piece of code is taken from the program of scrolling up the screen write against each instruction what it does (5)

Mov ax 80
Mu byte [bp+4]
Mov si, ax
Push si
Shl si1

Answer:- (Page 150)
mov ax, 80 ; load chars per row in ax
mul byte [bp+4] ; calculate source position
mov si, ax ; load source position in si
push si ; save position for later use
shl si, 1 ; convert to byte offset

Qno.52 In context of video service write character and attribute at cursor position using INT 10 pick up correct statement given between and put it is proper blank spaces

AH…….
AL…….
BH…….
BL…….
CX…….
(5)
*
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Fall 2011

Question No: 42 (Marks: 2) -
INT 14 - SERIAL - READ CHARACTER 8 bit register return result in?
Answer:- (Page 172)
Return:
AH = line status
AL = received character if AH bit 7 clear

Question No: 43 (Marks: 2) -
What is the process control back answer in single line
Answer:- rep

Question No: 44 (Marks: 2) -
Explain Divide overflow
Answer:- (Page 85)
If a large number is divided by a very small number it is possible that the quotient is larger than the space provided for it in the implied destination. In this case an interrupt is automatically generated and the program is usually terminated as a result. This is called a divide overflow error;

Question No: 45 (Marks: 2)
What is the system descriptor?
Answer:- rep

Question No: 46 (Marks:3)
It is the part of Multitasking TSR caller, what will do these instructions
comment against them
Mov al, [chars+bx]
Mov [es:40],al
Inc bx
Answer:- rep

Question No: 48 (Marks:3)
Three basic steps B/w memory and processor to communicate.
Answer:- (Page 9)
The group of bits that the processor uses to inform the memory about which element to read or write is collectively known as the address bus. Another important bus called the data bus is used to move the data from the memory to the processor in a read operation and from the processor to the memory in a write operation. The third group consists of miscellaneous independent lines used for control purposes.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 49 (Marks:3)
What is baud rate, tell the parity bit function.
Answer:- (Page 171)
The data starts with a 1 bit called the start bit, then five to eight data bits, an optional parity bit, and one to two 0 bits called stop bits.
The number of data bits, parity bits, and the number of stop bits have to be configured at both ends. Also the duration of a bit must be precisely known at both ends called the baud rate of the communication.

Question No: 50 (Marks:5)
Write the instruction of following
Copy BL into CL
Answer: mov cl, bl

Copy DX into AX
Answer: mov ax, dx

Store 0x12 into AL
Answer: mov al, 0x12

Store 0x1234 into AX
Answer: mov ax, 0x1234

Store 0xFFFF into AX
Answer: mov ax, 0xFFFF

Question No: 51 (Marks:5)
9 pin DB9 connector , write function of any five
Answer:- rep

Question No: 52 (Marks:5)
Fill in the blanks with proper words
AH =
AL =
BH =
BL =
CX =
(09h, page number, number of times to write character, attribute ,character to display,)
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 52 (Marks:5)
Fill in the blanks with proper words
The GDT itself is an array of descriptors where each descriptor is an 8byte entry.
The base and limit of GDT is stored in a 48bit register called the GDTR.
This register is loaded with a special instruction LGDT and is given a memory address from where the 48bits are fetched.

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

Question No: 27 (Marks: 2)
How can we improve the speed of multitasking?
Answer:- rep

Question No: 28 (Marks: 2)
Write instructions to do the following. Copy contents of memory location with offset 0025 in the current data segment into AX.
Answer:-
Mov ax , [0025]

Question No: 29 (Marks: 2)
Write types of Devices?
Answer:- Click here for detail
The four types of computer devices are:-

1. input devices
2. output devices
3. storage devices and
4. The central processing unit i.e. C.P.U.
5.

Question No: 30 (Marks: 2)
What dose descriptor 1st 16 bit tell?

Question No: 31 (Marks: 3)
List down any three common video services for INT 10 used in text mode.
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 32 (Marks: 3)
How to create or Truncate File using INT 21 Service?
Answer:- rep

Question No: 33 (Marks: 3)
How many Types of granularity also name them?
Answer:- Click here for detail
There are three types of granularity :

1. Data Granularity
2. Business Value Granularity
3. Functionality Granularity

Question No: 34 (Marks: 5)
How to read disk sector into memory using INT 13 service?
Answer:- rep

Question No: 35 (Marks: 5)
The program given below is written in assembly language. Write a program in C to call this assembly routine.

```
[section .text]
global      swap
swap:       mov  ecx,[esp+4]     ; copy parameter p1 to ecx
            mov  edx,[esp+8]     ; copy parameter p2 to edx
            mov  eax,[ecx]       ; copy *p1 into eax
            xchg eax,[edx]       ; exchange eax with *p2
            mov  [ecx],eax       ; copy eax into *p1
            ret                  ; return from this function
```

Answer:- (Page 189)

```
#include <stdio.h>
void swap( int* p1, int* p2 );
int main()
{
int a = 10, b = 20;
printf( "a=%d b=%d\n", a, b );
swap(&a, &b );
printf( "a=%d b=%d\n", a, b );
system( "PAUSE" );
return 0;
}
```


Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 36 (Marks: 5)
Write the code of "break point interrupt routine".
Answer:- rep

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

Question No: 27 (Marks: 2)
What are device drivers? give your answer in two to three lines.
Answer:- rep

Question No: 28 (Marks: 2)
For what purpose "**INT 1**" is reserved ?
Answer:- rep

Question No: 29 (Marks: 2)
How interrupts are handled in protected mode.
Answer:- (Page 182)
Handling interrupts in protected mode is also different. Instead of the IVT at physical address 0 there is the IDT (interrupt descriptor table) located at physical address stored in IDTR, a special purpose register. The IDTR is also a 48bit register similar in structure to the GDTR and loaded with another special instruction LGDT.

Question No: 30 (Marks: 2)
Which bit of acknowledge is used to generate IRQ7
Answer:- (Page 125)
Bit "4" of acknowledge is used to generate IRQ7

Question No: 31 (Marks: 3)
Write the name three flags which are not used for mathematical operations.
Answer:- (Page 133)
The three flags not used for mathematical operations are the direction flag, the interrupt flag and the trap flag.

Question No: 32 (Marks: 3)
"INT 13 - DISK - GET DRIVE PARAMETERS" uses which registers to return *error flag* and *error number*.
Answer:- (Page 156)
CF = error flag
AH = error code

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 33 (Marks: 3)
Who is responsible for removing the parameter from the stack when we call a function in C and Pascal?
Answer:- (Page 187)
In C the caller removes the parameter while in Pascal the callee removes them. The C scheme has reasons pertaining to its provision for variable number of arguments.

Question No: 34 (Marks: 5)
Read the passage carefully and choose proper word for each blank space from the list given below .

In descriptors the 32bit base is scattered into different places because of compatibility reasons. The limit is stored in 20 bits but the ...**G**.....defines that the limit is in terms of bytes of 4K pages therefore a maximum of 4GB size is possible. The .....**P**..... must be set to signal that this segment is present in memory. DPL is the descriptor privilege level again related to the protection levels in 386. .....**D**..... defines that this segment is to execute code is 16bit mode or 32bit mode. .....**C**..... is conforming bit that we will not be using. .....**R**.....signals that the segment is readable. A bit is automatically set whenever the segment is accessed.

(A bit, C bit, G bit, D bit, P bit , R bit, B bit)
Answer: (Page 176)
The 32bit base in both descriptors is scattered into different places because of compatibility reasons. The limit is stored in 20 bits but the G bit defines that the limit is in terms of bytes of 4K pages therefore a maximum of 4GB size is possible. The P bit must be set to signal that this segment is present in memory. DPL is the descriptor privilege level again related to the protection levels in 386. D bit defines that this segment is to execute code is 16bit mode or 32bit mode. C is conforming bit that we will not be using. R signals that the segment is readable. A bit is automatically set whenever the segment is accessed.

Question No: 35 (Marks: 5)
Write assembly language instructions to set the timer interrupt frequency at 1 ms.
Answer: (Page 143)
```
mov   ax, 1100
out   0x40, al
mov   al, ah
out   0x40, al
```

Question No: 36 (Marks: 5)
In the context of **" INT 13 - DISK - WRITE DISK SECTOR(S)"** fill the blanks by choosing the correct answer against each blank space from the list given at the bottom.
Answer:- (Page 156)
AH = 03h
AL = number of sectors to write (must be nonzero)
CH = low eight bits of cylinder number
CL = sector number 1-63 (bits 0-5)

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

high two bits of cylinder (bits 6-7, hard disk only)
DH = head number
DL = drive number (bit 7 set for hard disk)
ES:BX -> data buffer
(Number of sectors to write, head number , 03h, data buffer , low eight bits of cylinder number)

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

How many bytes floppy root directory entry has? (2)
Answer: Click here for detail
224 bytes for a 3 1/2 inch floppy

How many calling conversion also tell the names? (2)
Answer:- (Page 187)
Two prevalent calling conventions are the C calling convention and the Pascal calling convention.

Which register is used as thread local variable? (2)
Answer:- (Page 141)
SP (stack pointer) register used as thread local variable

Write down the operations of CMP instruction? (2)
Answer:- (Page 39)
The operation of CMP is to subtract the source operand from the destination operand, updating the flags without changing either the source or the destination.

It is the part of Multitasking TSR caller, what will do these instructions comment against them (3)
Mov al, [chars+bx]
Mov [es:40],al
Inc bx
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Differentiate synchronous transmission and asynchronous transmission? (3)

Answer:- (Page 103)

Asynchronous means that the interrupts occur, independent of the working of the processor, i.e. independent of the instruction currently executing. Synchronous events are those that occur side by side with another activity.

List some architecture? (3)

Answer:-

iAPX88 architecture
Motorolla 68K
x86 series architecture
SPARC stands for Scalable Processor ARChitecture

1. What information is required to be provided for the service "INT14-SERIAL WRITE CHARACTER TO PORT" in the following registers? (5 marks)

AH=_____
AL=_____
DX=_____

Answer:- (Page 172)

AH = 01h
AL = character to write
DX = port number (00h-03h)

2. Write into C language (5 marks)

[section.txt]
Global swap

```
swap:  mov ecx,[esp+4]      copy parameters p1 to ecx
       mov edx[esp+8]       copy parameters p2 to edx
       mov eax,[ecx]        copy *p1 to eax
       xchg eax,[edx]             exchange eax to *p2
       mov [ecx],eax        copy eax to *p1
       ret                  return
```

Answer:- rep

3. Which instruction makes trap flag zero? If there is not any then how we make it zero? (5 marks)

Answer:- (Page 133)

There is no instruction to set or clear the trap flag like there are instructions for the interrupt and direction flags. We use two special instructions PUSHF and POPF to push and pop the flag from the stack. We use PUSHF to place flags on the stack, change TF in this image on the stack and then reload into the flags register with POPF.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

25. Division by zero is done by which interrupt.
Answer:- (Page 105)
Division by zero is done by INT 0 interrupt.

26. Define Hardware Interrupt & I/O ports (5 marks)
Answer:- (Page 113-114)
Hardware interrupts
Hardware interrupts are the real interrupts generated by the external world. there are many devices generating interrupts and there is only one pin going inside the processor and one pin cannot be technically derived by more than one source a controller is used in between called the Programmable Interrupt Controller (PIC).
I/O ports
For communicating with peripheral devices the processor uses I/O ports. There are only two operations with the external world possible, read or write. Similarly with I/O ports the processor can read or write an I/O port. When an I/O port is read or written to, the operation is not as simple as it happens in memory.

27. Five BIOS video services used in text mode (3 marks)
Answer:- rep

28. DOS allocate memory for program execution and then de-allocate , explain memory management in DOS (10 marks)
Answer:- (Page 121)
At physical address zero is the interrupt vector table. Then are the BIOS data area, DOS data area, IO.SYS, MSDOS.SYS and other device drivers. In the end there is COMMAND.COM command interpreter. The remaining space is called the transient program area as programs are loaded and executed in this area and the space reclaimed on their exit. A freemem pointer in DOS points where the free memory begins. When DOS loads a program the freemem pointer is moved to the end of memory, all the available space is allocated to it, and when it exits the freemem pointer comes back to its original place thereby reclaiming all space. This action is initiated by the DOS service 4C. The second method to legally terminate a program and give control back to DOS is using the service 31. Control is still taken back but the memory releasing part is modified. A portion of the allocated memory can be retained. So the difference in the two methods is that the freemem pointer goes back to the original place or a designated number of bytes ahead of that old position.

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

There was fill in blanks question with 10 marks. The choice was given at bottom.

29. Serial Port is also accessible via _____ ports , _____ is accessible via ports 3F8-3FF while _____ is accessible via 2F8 -2FF.
The first register at 3F8 is the _____ holding register if written to and the receiver _____ register if read from.
Other register of our interest include 3F9 whose _____ must be set to enable received data available interrupt and _____ must be set to enable transmitter holding register empty interrupt.
(Transmitter , COM 1 , I/O ports , COM2. bit 0 , Buffer , 3FA)
Answer:- (Page 172)
Serial port is also accessible via **I/O** ports. **COM1** is accessible via ports 3F8-3FF while **COM2** is accessible via 2F8-2FF. The first register at 3F8 (or 2F8 for the other port) is the **transmitter** holding register if written to and the receiver **buffer** register if read from. Other registers of our interest include 3F9 whose **bit 0** must be set to enable received data available interrupt and **bit 1** must be set to enable transmitter holding register empty interrupt.

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

Q no 41 Write down purpose of JNZ instruction? (2)
Answer:- (Page 32)
The JNZ instruction is from the program control group and is a conditional jump, meaning that if the condition NZ is true (ZF=0) it will jump to the address mentioned and otherwise it will progress to the next instruction.

Q no 42 How many bytes floppy root directory entry has? (2)
Answer:- rep

Q no 43 Write the programmer view of processor? (2)
Answer:- rep

Q no 44 What is scheduler? (2)
Answer:- rep

Q no 45 Write the names of any two descriptor? (3)
Answer:- rep

Q no 46 Define the protected mode? (3)
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Q no 47 Write the algorithm of multiplication of two 4 bits number? (3)
Answer:- (Page 51)
We take the first digit of the multiplier and multiply it with the multiplicand. As the digit is one the answer is the multiplicand itself. So we place the multiplicand below the bar. Before multiplying with the next digit a cross is placed at the right most place on the next line and the result is placed shifted one digit left.

Q no 48 How threads are register in the scheduler? (3)

Q no 49 INT 14 serial with character to port (5)
AH=……
AL=……..
AX=……
Answer:- rep

Q no 50 Define the debugger. How to run the debugger tell the command, and all its parts? (5)
Answer:-
A debugger is a computer program that lets you run your program, line by line and examine the values of variables or look at values passed into functions and let you figure out why it isn't running the way you expected it to.
We can run debugger by pressing F1 and F2.The debugger shows the values of registers, flags, stack, our code, and one or two areas of the system memory as data. Debugger allows us to step our program one instruction at a time and observe its effect on the registers and program data.

Q no 51 Write the code of "break point interrupt routine"? (5)
Answer:- rep

Q no 52 Describe the format of interrupt descriptor? (5)
Answer:- rep

CS401- Computer Architecture and Assembly Language Programming
FINALTERM EXAMINATION
Spring 2010

Question No: 27 (Marks: 2)
Write instruction to allocate space for 32 PCBs.
Answer:- (Page 141)
pcb: times 32*16 dw 0 ; space for 32 PCBs

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 28 (Marks: 2)
Define short jump
Answer:- (Page 46)
If the offset is stored in a single byte as in 75F2 with the opcode 75 and operand F2, the jump is called a short jump.

Question No: 29 (Marks: 2)
INT 14 - SERIAL - READ CHARACTER FROM PORT uses which two 8bit registers to return the results ?
Answer:- rep

Question No: 30 (Marks: 2)
Which registers are uses as scratch when we call a function?
Answer:- rep

Question No: 31 (Marks: 3)
VESA service **"INT 10 – VESA – Get SuperVGA Information"** uses which registers to return the result?
Answer:- (Page 180)
To return the result, "INT 10 – VESA – Get SuperVGA Information" uses:
Return:
AL = 4Fh if function supported
AH = status

Question No: 32 (Marks: 3)
Define the protected mode.
Answer:- rep

Question No: 33 (Marks: 3)
Describe briefly INT 3 functionality.
Answer:- rep

Question No: 34 (Marks: 5)
Read the passage carefully and choose proper word for each blank space from the list given below .

In descriptors the 32bit base is scattered into different places because of compatibility reasons. The limit is stored in 20 bits but the .....defines that the limit is in terms of bytes of 4K pages therefore a maximum of 4GB size is possible. The..... must be set to signal that this segment is present in memory. DPL is the descriptor privilege level again related to the protection levels in 386. ..... defines that this segment is to execute code is 16bit mode or 32bit mode. ..... is conforming bit that we will not be using. .....signals that the segment is readable. A bit is automatically set whenever the segment is accessed.

(A bit, C bit, G bit, D bit, P bit , R bit, B bit)
Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari

Question No: 35 (Marks: 5)

Answer the following:

- What is a device driver?

Answer:- rep

- Why are device drivers necessary, given that the BIOS already has code that communicates with the computer's hardware?

Answer:- rep

Question No: 36 (Marks: 5)

Write the code of "break point interrupt routine".

Answer:- rep

Muhammad Moaaz Siddiq MCS (3rd)
mc100401285@Gmail.com
Campus:- Institute of E-Learning & Modern Studies
(IEMS) Samundari