

Reading a Relative file directly or sequentially.

Example program

Click to view.

When viewing the program left click (or press the Page Up key) to see next comment and right click (or press Page Down) to see the previous comment.

\$ SET SOURCEFORMAT "FREE"

IDENTIFICATION DIVISION.

PROGRAM-ID. ReadRelative.

* Reads a Relative file directly or in s

ENVIRONMENT DIVISION.

INPUT-OUTPUT SECTION.

FILE-CONTROL.

SELECT SupplierFile ASSIGN TO "SUPP.DAT"

ORGANIZATION IS RELATIVE

ACCESS MODE IS DYNAMIC

RELATIVE KEY IS SupplierKey

FILE STATUS IS SupplierStatus.

DATA DIVISION.

FILE SECTION.

FD SupplierFile.

01 SupplierRecord.

88 EndOfFile VALUE HIGH-VALUES.

02 SupplierCode PIC 99.

02 SupplierName PIC X(20).

02 SupplierAddress PIC X(60).

WORKING-STORAGE SECTION.

01 SupplierStatus PIC X(2).

88 RecordFound VALUE "00".

01 SupplierKey PIC 99.

01 PrnSupplierRecord.

02 PrnSupplierCode PIC BB99.

02 PrnSupplierName PIC BBX(20).

02 PrnSupplierAddress PIC BBX(50).

01 ReadType PIC 9.

88 DirectRead VALUE 1.

88 SequentialRead VALUE 2.

First

ACCESS MODE IS
DYNAMIC means that
we expect to access this
file both directly and
sequentially.

Take note of the
condition name
monitoring the
SupplierStatus.
A code of 00 means
the operation was
successful.

PROCEDURE DIVISION.
BEGIN.

OPEN INPUT SupplierFile.

DISPLAY "Enter Read type (Direct=1, Seq=2)-> "
WITH NO ADVANCING.
ACCEPT ReadType.

IF DirectRead
DISPLAY "Enter supplier key (2 digits)-> "
WITH NO ADVANCING
ACCEPT SupplierKey
READ SupplierFile
INVALID KEY DISPLAY "SUPP STATUS :-",
SupplierStatus

END-READ
PERFORM DisplayRecord
END-IF

IF SequentialRead
READ SupplierFile NEXT RECORD
AT END SET EndOfFile TO TRUE
END-READ
PERFORM UNTIL EndOfFile
PERFORM DisplayRecord
READ SupplierFile NEXT RECORD
AT END SET EndOfFile TO TRUE
END-READ
END-PERFORM
END-IF

CLOSE SupplierFile.
STOP RUN.

DisplayRecord.

IF RecordFound
MOVE SupplierCode TO PrnSupplierCode
MOVE SupplierName TO PrnSupplierName
MOVE SupplierAddress TO PrnSupplierAddress
DISPLAY PrnSupplierRecord
END-IF.

First we find out how the user wants to read the file.

To read the file directly the user

To read the file sequentially we use a standard "Read Ahead" and loop

Note: The READ..NEXT RECORD is used when we want to read the file sequentially and the ACCESS MODE is DYNAMIC