

Open Watcom C++

Class Library Reference



Version 2.0

Open Watcom

Notice of Copyright

Copyright © 2002-2026 the Open Watcom Contributors. Portions Copyright © 1984-2002 Sybase, Inc. and its subsidiaries. All rights reserved.

Any part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of anyone.

For more information please visit <https://github.com/open-watcom/open-watcom-v2> .

Preface

Open Watcom C++ is an implementation of the C++ programming language. In addition to the C++ draft standard, the compiler supports numerous extensions for the PC environment.

This manual describes the Open Watcom C++ Class Libraries for DOS, Windows 3.x, Windows NT, Windows 95, 16-bit OS/2 1.x, 32-bit OS/2, and QNX. It includes a String Class, a Complex Class, Container Classes, and an I/O Stream hierarchy of classes. The Container classes include a set of intrusive, value and pointer list classes with their associated iterators.

This book was produced with the Open Watcom GML electronic publishing system, a software tool developed by WATCOM. In this system, writers use an ASCII text editor to create source files containing text annotated with tags. These tags label the structural elements of the document, such as chapters, sections, paragraphs, and lists. The Open Watcom GML software, which runs on a variety of operating systems, interprets the tags to format the text into a form such as you see here. Writers can produce output for a variety of printers, including laser printers, using separately specified layout directives for such things as font selection, column width and height, number of columns, etc. The result is type-set quality copy containing integrated text and graphics.

July, 1997.

Trademarks Used in this Manual

IBM is a registered trademark and OS/2 is a trademark of International Business Machines Corp.

Microsoft is a registered trademark of Microsoft Corp. Windows, Windows NT and Windows 95 are trademarks of Microsoft Corp.

QNX is a registered trademark of QNX Software Systems Ltd.

WATCOM is a trademark of Sybase, Inc. and its subsidiaries.

Table of Contents

Open Watcom C++ Class Library Reference	1
1 Header Files	3
2 Common Types	7
3 Predefined Objects	9
3.1 cin	9
3.2 cout	9
3.3 cerr	9
3.4 clog	10
4 istream Input	11
4.1 Formatted Input: Extractors	11
4.2 Unformatted Input	11
5 ostream Output	13
5.1 Formatted Output: Inserters	13
5.2 Unformatted Output	13
6 Library Functions and Types	15
7 Complex Class	17
Complex Class Description	18
Complex abs()	20
Complex acos()	21
Complex acosh()	22
Complex arg()	23
Complex asin()	24
Complex asinh()	25
Complex atan()	26
Complex atanh()	27
Complex()	28
Complex()	29
Complex()	30
~Complex()	31
Complex conj()	32
Complex cos()	33
Complex cosh()	34
Complex exp()	35
imag()	36
Complex imag()	37
Complex log()	38
Complex log10()	39
Complex norm()	40
Complex operator !=()	41
Complex operator *()	42
operator *=()	43
operator +()	44
Complex operator +()	45
operator +=()	46
operator -()	47

Table of Contents

Complex operator -()	48
operator ==()	49
Complex operator /()	50
operator /=()	51
Complex operator <<()	52
operator =()	53
Complex operator ==()	54
Complex operator >>()	55
Complex polar()	56
Complex pow()	57
real()	58
Complex real()	59
Complex sin()	60
Complex sinh()	61
Complex sqrt()	62
Complex tan()	63
Complex tanh()	64
 8 Container Exception Classes	65
WCExcept Class Description	66
WCExcept()	67
~WCExcept()	68
exceptions()	69
wc_state	70
WCIterExcept Class Description	71
WCIterExcept()	72
~WCIterExcept()	73
exceptions()	74
wciter_state	75
 9 Container Allocators and Deallocation	77
 10 Hash Containers	81
WCPtrHashDict<Key,Value> Class Description	82
WCPtrHashDict()	84
WCPtrHashDict()	85
WCPtrHashDict()	86
~WCPtrHashDict()	87
bitHash()	88
buckets()	89
clear()	90
clearAndDestroy()	91
contains()	92
entries()	93
find()	94
findKeyAndValue()	95
forAll()	96
insert()	97
isEmpty()	98
operator []()	99
operator []()	100
operator =()	101

Table of Contents

operator ==()	102
remove()	103
resize()	104
WCPtrHashTable<Type>, WCPtrHashSet<Type> Class Description	105
WCPtrHashSet()	107
WCPtrHashSet()	108
WCPtrHashSet()	109
~WCPtrHashSet()	110
WCPtrHashTable()	111
WCPtrHashTable()	112
WCPtrHashTable()	113
~WCPtrHashTable()	114
bitHash()	115
buckets()	116
clear()	117
clearAndDestroy()	118
contains()	119
entries()	120
find()	121
forAll()	122
insert()	123
isEmpty()	124
occurrencesOf()	125
operator =()	126
operator ==()	127
remove()	128
removeAll()	129
resize()	130
WCValHashDict<Key,Value> Class Description	131
WCValHashDict()	133
WCValHashDict()	134
WCValHashDict()	135
~WCValHashDict()	136
bitHash()	137
buckets()	138
clear()	139
contains()	140
entries()	141
find()	142
findKeyAndValue()	143
forAll()	144
insert()	145
isEmpty()	146
operator []()	147
operator []()	148
operator =()	149
operator ==()	150
remove()	151
resize()	152
WCValHashTable<Type>, WCValHashSet<Type> Class Description	153
WCValHashSet()	155
WCValHashSet()	156

Table of Contents

WCValHashSet()	157
~WCValHashSet()	158
WCValHashTable()	159
WCValHashTable()	160
WCValHashTable()	161
~WCValHashTable()	162
bitHash()	163
buckets()	164
clear()	165
contains()	166
entries()	167
find()	168
forAll()	169
insert()	170
isEmpty()	171
occurrencesOf()	172
operator =()	173
operator ==()	174
remove()	175
removeAll()	176
resize()	177
11 Hash Iterators	179
WCPtrHashDictIter<Key,Value> Class Description	180
WCPtrHashDictIter()	181
WCPtrHashDictIter()	182
~WCPtrHashDictIter()	183
container()	184
key()	185
operator ()()	186
operator ++()	187
reset()	188
reset()	189
value()	190
WCValHashDictIter<Key,Value> Class Description	191
WCValHashDictIter()	192
WCValHashDictIter()	193
~WCValHashDictIter()	194
container()	195
key()	196
operator ()()	197
operator ++()	198
reset()	199
reset()	200
value()	201
WCPtrHashSetIter<Type>, WCPtrHashTableIter<Type> Class Description	202
WCPtrHashSetIter()	203
WCPtrHashSetIter()	204
~WCPtrHashSetIter()	205
WCPtrHashTableIter()	206
WCPtrHashTableIter()	207
~WCPtrHashTableIter()	208

Table of Contents

container()	209
current()	210
operator ()()	211
operator ++()	212
reset()	213
reset()	214
WCValHashSetIter<Type>, WCValHashTableIter<Type> Class Description	215
WCValHashSetIter()	216
WCValHashSetIter()	217
~WCValHashSetIter()	218
WCValHashTableIter()	219
WCValHashTableIter()	220
~WCValHashTableIter()	221
container()	222
current()	223
operator ()()	224
operator ++()	225
reset()	226
reset()	227
12 List Containers	229
WCDLink Class Description	230
WCDLink()	231
~WCDLink()	232
WCIsvSList<Type>, WCIsvDList<Type> Class Description	233
WCIsvSList()	235
WCIsvSList()	236
~WCIsvSList()	237
WCIsvDList()	238
WCIsvDList()	239
~WCIsvDList()	240
append()	241
clear()	242
clearAndDestroy()	243
contains()	244
entries()	245
find()	246
findLast()	247
forAll()	248
get()	249
index()	250
index()	251
insert()	252
isEmpty()	253
operator =()	254
operator ==()	255
WCPtrSList<Type>, WCPtrDList<Type> Class Description	256
WCPtrSList()	258
WCPtrSList()	259
WCPtrSList()	260
~WCPtrSList()	261
WCPtrDList()	262

Table of Contents

WCPtrDList()	263
WCPtrDList()	264
~WCPtrDList()	265
append()	266
clear()	267
clearAndDestroy()	268
contains()	269
entries()	270
find()	271
findLast()	272
forAll()	273
get()	274
index()	275
insert()	276
isEmpty()	277
operator =()	278
operator ==()	279
WCSSLink Class Description	280
WCSSLink()	281
~WCSSLink()	282
WCValSList<Type>, WCValDList<Type> Class Description	283
WCValSList()	285
WCValSList()	286
WCValSList()	287
~WCValSList()	288
WCValDList()	289
WCValDList()	290
WCValDList()	291
~WCValDList()	292
append()	293
clear()	294
clearAndDestroy()	295
contains()	296
entries()	297
find()	298
findLast()	299
forAll()	300
get()	301
index()	302
insert()	303
isEmpty()	304
operator =()	305
operator ==()	306
13 List Iterators	307
WCIsvConstSListIter<Type>, WCIsvConstDListIter<Type> Class Description	308
WCIsvConstSListIter()	309
WCIsvConstSListIter()	310
~WCIsvConstSListIter()	311
WCIsvConstDListIter()	312
WCIsvConstDListIter()	313
~WCIsvConstDListIter()	314

Table of Contents

container()	315
current()	316
operator ()()	317
operator ++()	318
operator +=()	319
operator --()	320
operator ==()	321
reset()	322
reset()	323
WCIsvSListIter<Type>, WCIsvDListIter<Type> Class Description	324
WCIsvSListIter()	326
WCIsvSListIter()	327
~WCIsvSListIter()	328
WCIsvDListIter()	329
WCIsvDListIter()	330
~WCIsvDListIter()	331
append()	332
container()	333
current()	334
insert()	335
operator ()()	336
operator ++()	337
operator +=()	338
operator --()	339
operator ==()	340
reset()	341
reset()	342
WCPtrConstSListIter<Type>, WCPtrConstDListIter<Type> Class Description	343
WCPtrConstSListIter()	344
WCPtrConstSListIter()	345
~WCPtrConstSListIter()	346
WCPtrConstDListIter()	347
WCPtrConstDListIter()	348
~WCPtrConstDListIter()	349
container()	350
current()	351
operator ()()	352
operator ++()	353
operator +=()	354
operator --()	355
operator ==()	356
reset()	357
reset()	358
WCPtrSListIter<Type>, WCPtrDListIter<Type> Class Description	359
WCPtrSListIter()	361
WCPtrSListIter()	362
~WCPtrSListIter()	363
WCPtrDListIter()	364
WCPtrDListIter()	365
~WCPtrDListIter()	366
append()	367
container()	368

Table of Contents

current()	369
insert()	370
operator ()()	371
operator ++()	372
operator +=()	373
operator --()	374
operator -=()	375
reset()	376
reset()	377
WCValConstSListIter<Type>, WCValConstDListIter<Type> Class Description	378
WCValConstSListIter()	379
WCValConstSListIter()	380
~WCValConstSListIter()	381
WCValConstDListIter()	382
WCValConstDListIter()	383
~WCValConstDListIter()	384
container()	385
current()	386
operator ()()	387
operator ++()	388
operator +=()	389
operator --()	390
operator -=()	391
reset()	392
reset()	393
WCValSListIter<Type>, WCValDListIter<Type> Class Description	394
WCValSListIter()	396
WCValSListIter()	397
~WCValSListIter()	398
WCValDListIter()	399
WCValDListIter()	400
~WCValDListIter()	401
append()	402
container()	403
current()	404
insert()	405
operator ()()	406
operator ++()	407
operator +=()	408
operator --()	409
operator -=()	410
reset()	411
reset()	412
14 Queue Container	413
WCQueue<Type,FType> Class Description	414
WCQueue()	415
WCQueue()	416
~WCQueue()	417
clear()	418
entries()	419
first()	420

Table of Contents

get()	421
insert()	422
isEmpty()	423
last()	424
15 Skip List Containers	425
WCPtrSkipListDict<Key,Value> Class Description	426
WCPtrSkipListDict()	428
WCPtrSkipListDict()	429
WCPtrSkipListDict()	430
~WCPtrSkipListDict()	431
clear()	432
clearAndDestroy()	433
contains()	434
entries()	435
find()	436
findKeyAndValue()	437
forAll()	438
insert()	439
isEmpty()	440
operator []()	441
operator []()	442
operator =()	443
operator ==()	444
remove()	445
WCPtrSkipList<Type>, WCPtrSkipListSet<Type> Class Description	446
WCPtrSkipListSet()	448
WCPtrSkipListSet()	449
WCPtrSkipListSet()	450
~WCPtrSkipListSet()	451
WCPtrSkipList()	452
WCPtrSkipList()	453
WCPtrSkipList()	454
~WCPtrSkipList()	455
clear()	456
clearAndDestroy()	457
contains()	458
entries()	459
find()	460
forAll()	461
insert()	462
isEmpty()	463
occurrencesOf()	464
operator =()	465
operator ==()	466
remove()	467
removeAll()	468
WCValSkipListDict<Key,Value> Class Description	469
WCValSkipListDict()	471
WCValSkipListDict()	472
WCValSkipListDict()	473
~WCValSkipListDict()	474

Table of Contents

clear()	475
contains()	476
entries()	477
find()	478
findKeyAndValue()	479
forAll()	480
insert()	481
isEmpty()	482
operator []()	483
operator []()	484
operator ==()	485
operator ==()	486
remove()	487
WCValSkipList<Type>, WCValSkipListSet<Type> Class Description	488
WCValSkipListSet()	490
WCValSkipListSet()	491
WCValSkipListSet()	492
~WCValSkipListSet()	493
WCValSkipList()	494
WCValSkipList()	495
WCValSkipList()	496
~WCValSkipList()	497
clear()	498
contains()	499
entries()	500
find()	501
forAll()	502
insert()	503
isEmpty()	504
occurrencesOf()	505
operator ==()	506
operator ==()	507
remove()	508
removeAll()	509
16 Stack Container	511
WCStack<Type,FType> Class Description	512
WCStack()	513
WCStack()	514
~WCStack()	515
clear()	516
entries()	517
isEmpty()	518
pop()	519
push()	520
top()	521
17 Vector Containers	523
WCPtrSortedVector<Type>, WCPtrOrderedVector<Type> Class Description	524
WCPtrOrderedVector()	526
WCPtrOrderedVector()	527
~WCPtrOrderedVector()	528

Table of Contents

WCPtrSortedVector()	529
WCPtrSortedVector()	530
~WCPtrSortedVector()	531
append()	532
clear()	533
clearAndDestroy()	534
contains()	535
entries()	536
find()	537
first()	538
index()	539
insert()	540
insertAt()	541
isEmpty()	542
last()	543
occurrencesOf()	544
operator []()	545
operator =()	546
operator ==()	547
prepend()	548
remove()	549
removeAll()	550
removeAt()	551
removeFirst()	552
removeLast()	553
resize()	554
WCPtrVector<Type> Class Description	555
WCPtrVector()	556
WCPtrVector()	557
WCPtrVector()	558
~WCPtrVector()	559
clear()	560
clearAndDestroy()	561
length()	562
operator []()	563
operator =()	564
operator ==()	565
resize()	566
WCValSortedVector<Type>, WCValOrderedVector<Type> Class Description	567
WCValOrderedVector()	570
WCValOrderedVector()	571
~WCValOrderedVector()	572
WCValSortedVector()	573
WCValSortedVector()	574
~WCValSortedVector()	575
append()	576
clear()	577
contains()	578
entries()	579
find()	580
first()	581
index()	582

Table of Contents

insert()	583
insertAt()	584
isEmpty()	585
last()	586
occurrencesOf()	587
operator []()	588
operator =()	589
operator ==()	590
prepend()	591
remove()	592
removeAll()	593
removeAt()	594
removeFirst()	595
removeLast()	596
resize()	597
WCValVector<Type> Class Description	598
WCValVector()	599
WCValVector()	600
WCValVector()	601
~WCValVector()	602
clear()	603
length()	604
operator []()	605
operator =()	606
operator ==()	607
resize()	608
18 Input/Output Classes	609
filebuf Class Description	610
attach()	612
close()	613
fd()	614
filebuf()	615
filebuf()	616
filebuf()	617
~filebuf()	618
is_open()	619
open()	620
openprot	621
overflow()	622
pbackfail()	623
seekoff()	624
setbuf()	625
sync()	626
underflow()	627
fstream Class Description	628
fstream()	629
fstream()	630
fstream()	631
fstream()	632
~fstream()	633
open()	634

Table of Contents

fstreambase Class Description	635
attach()	636
close()	637
fstreambase()	638
fstreambase()	639
fstreambase()	640
fstreambase()	641
~fstreambase()	642
is_open()	643
fd()	644
open()	645
rdbuf()	646
setbuf()	647
ifstream Class Description	648
ifstream()	649
ifstream()	650
ifstream()	651
ifstream()	652
~ifstream()	653
open()	654
ios Class Description	655
bad()	657
bitalloc()	658
clear()	659
eof()	660
exceptions()	661
fail()	662
fill()	663
flags()	664
fmtflags	665
good()	668
init()	669
ios()	670
ios()	671
~ios()	672
iostate	673
iword()	674
openmode	675
operator !()	677
operator void *()	678
precision()	679
pword()	680
rdbuf()	681
rdstate()	682
seekdir	683
setf()	684
setstate()	685
sync_with_stdio()	686
tie()	687
unsetf()	688
width()	689
xalloc()	690

Table of Contents

iostream Class Description	691
iostream()	692
iostream()	693
iostream()	694
~iostream()	695
operator =()	696
operator =()	697
istream Class Description	698
eatwhite()	700
gcount()	701
get()	702
get()	703
get()	704
get()	705
getline()	706
ignore()	707
ipfx()	708
isfx()	709
istream()	710
istream()	711
istream()	712
~istream()	713
operator =()	714
operator =()	715
operator >>()	716
operator >>()	717
operator >>()	718
operator >>()	719
operator >>()	720
operator >>()	721
peek()	722
putback()	723
read()	724
seekg()	725
seekg()	726
sync()	727
tellg()	728
istrstream Class Description	729
istrstream()	730
istrstream()	731
~istrstream()	732
Manipulators	733
manipulator dec()	734
manipulator endl()	735
manipulator ends()	736
manipulator flush()	737
manipulator hex()	738
manipulator oct()	739
manipulator resetiosflags()	740
manipulator setbase()	741
manipulator setfill()	742
manipulator setiosflags()	743

Table of Contents

manipulator setprecision()	744
manipulator setw()	745
manipulator setwidth()	746
manipulator ws()	747
ofstream Class Description	748
ofstream()	749
ofstream()	750
ofstream()	751
ofstream()	752
~ofstream()	753
open()	754
ostream Class Description	755
flush()	757
operator <<()	758
operator <<()	759
operator <<()	760
operator <<()	761
operator <<()	762
operator <<()	763
operator <<()	764
operator =()	765
operator =()	766
opfx()	767
osfx()	768
ostream()	769
ostream()	770
ostream()	771
~ostream()	772
put()	773
seekp()	774
seekp()	775
tellp()	776
write()	777
ostrstream Class Description	778
ostrstream()	779
ostrstream()	780
~ostrstream()	781
pcount()	782
str()	783
stdiobuf Class Description	784
overflow()	785
stdiobuf()	786
stdiobuf()	787
~stdiobuf()	788
sync()	789
underflow()	790
streambuf Class Description	791
allocate()	794
base()	795
blen()	796
dbp()	797
do_sgetn()	798

Table of Contents

do_sputn()	799
doallocate()	800
eback()	801
ebuf()	802
egptr()	803
eptr()	804
gbump()	805
gptr()	806
in_avail()	807
out_waiting()	808
overflow()	809
pbackfail()	810
pbase()	811
pbump()	812
pptr()	813
sbumpc()	814
seekoff()	815
seekpos()	816
setb()	817
setbuf()	818
setg()	819
setp()	820
sgetc()	821
sgetchar()	822
sgetn()	823
snextc()	824
speekc()	825
sputbackc()	826
sputc()	827
sputn()	828
stossc()	829
streambuf()	830
streambuf()	831
~streambuf()	832
sync()	833
unbuffered()	834
underflow()	835
strstream Class Description	836
str()	837
strstream()	838
strstream()	839
~strstream()	840
strstreambase Class Description	841
rdbuf()	842
strstreambase()	843
strstreambase()	844
~strstreambase()	845
strstreambuf Class Description	846
alloc_size_increment()	847
doallocate()	848
freeze()	849
overflow()	850

Table of Contents

seekoff()	851
setbuf()	852
str()	853
strstreambuf()	854
strstreambuf()	855
strstreambuf()	856
strstreambuf()	857
~strstreambuf()	858
sync()	859
underflow()	860
19 String Class	861
String Class Description	862
alloc_mult_size()	864
get_at()	865
index()	866
length()	867
lower()	868
match()	869
operator !=()	870
String operator !=()	871
operator ()()	872
operator ()()	873
String operator +()	874
operator +=()	875
String operator <()	876
String operator <<()	877
String operator <=()	878
operator ==()	879
String operator ==()	880
String operator >()	881
String operator >=()	882
String operator >>()	883
operator []()	884
operator char()	885
operator char const *()	886
put_at()	887
String()	888
String()	889
String()	890
String()	891
String()	892
~String()	893
upper()	894
String valid()	895
valid()	896

Open Watcom C++ Class Library Reference

1 Header Files

The following header files are supplied with the Open Watcom C++ library. When a class or function from the library is used in a source file the related header file should be included in that source file. The header files can be included multiple times and in any order with no ill effect.

The facilities of the C standard library can be used in C++ programs by including the appropriate "cname" header. In that case all of the C standard library functions are in namespace `std`. For example, to use function `std::printf` one should include the header `cstdio`. Note that the cname headers declare in the global namespace any non-standard names they contain as extensions. It is also possible to include in a C++ program the same headers used by C programs. In that case, the standard functions are in both the global namespace as well as in namespace `std`.

Some of C++ standard library headers described below come in a form with a .h extension and in a form without an extension. The extensionless headers declare their library classes and functions in namespace `std`. The headers with a .h extension declare their library classes and functions in both the global namespace and in namespace `std`. Such headers are provided as a convenience and for compatibility with legacy code. Programs that intend to conform to Standard C++ should use the extensionless headers to access the facilities of the C++ standard library.

Certain headers defined by Standard C++ have names that are longer than the 8.3 limit imposed by the FAT16 filesystem. Such headers are provided with names that are truncated to eight characters so they can be used with the DOS host. However, one can still refer to them in #include directives using their full names as defined by the standard. If the Open Watcom C++ compiler is unable to open a header with the long name, it will truncate the name and try again.

The Open Watcom C++ library contains some components that were developed before C++ was standardized. These legacy components continue to be supported and are described in this documentation.

The header files are all located in the `\WATCOM\H` directory.

algorithm (algorith) This header file defines the standard algorithm templates.

complex This header file defines the `std::complex` class template and related function templates. This template can be instantiated for the three different floating point types. It can be used to represent complex numbers and to perform complex arithmetic.

complex.h This header file defines the legacy `Complex` class. This class is used to represent complex numbers and to perform complex arithmetic. The class defined in this header is not the Standard C++ `std::complex` class template.

exception/exception.h (exceptio/exceptio.h) This header file defines components to be used with the exception handling mechanism. It defines the base class of the standard exception hierarchy.

functional (function) This header file defines the standard functional templates. This includes the functors and binders described by Standard C++.

fstream/fstream.h This header file defines the `filebuf`, `fstreambase`, `ifstream`, `ofstream`, and `fstream` classes. These classes are used to perform C++ file input and output operations. The various class members are declared and inline member functions for the classes are defined.

generic.h This header file is part of the macro support required to implement generic containers prior to the introduction of templates in the C++ language. It is retained for backwards compatibility.

iomanip/iomanip.h This header file defines the parameterized manipulators.

ios/ios.h This header file defines the class `ios` that is used as a base of the other iostream classes.

iosfwd/iosfwd.h This header file provides forward declarations of the iostream classes. It should be used in cases where the full class definitions are not needed but where one still wants to declare pointers or references to iostream related objects. Typically this occurs in a header for another class that wants to provide overloaded inserter or extractor operators. By including `iosfwd` instead of `iostream` (for example), compilation speed can be improved because less material must be processed by the compiler.

Note that including `iosfwd` is the only appropriate way to forward declare the iostream classes. Manually writing forward declarations is not recommended.

iostream/iostream.h This header file (indirectly) defines the `ios`, `istream`, `ostream`, and `iostream` classes. These classes form the basis of the C++ formatted input and output support. The various class members are declared and inline member functions for the classes are defined. The `cin`, `cout`, `cerr`, and `clog` predefined objects are declared along with the non-parameterized manipulators.

istream/istream.h This header file defines class `istream` and class `iostream`. It also defines their associated parameterless manipulators.

iterator This header file defines several templates to facilitate the handling of iterators. In particular, it defines the `std::iterator_traits` template as well as several other supporting iterator related templates.

limits This header file defines the `std::numeric_limits` template and provides specializations of that template for each of the built-in types.

Note that this header is not directly related to the header `limits.h` from the C standard library (or to the C++ form of that header, `climits`).

list This header file defines the `std::list` class template. It provides a way to make a sequence of objects with efficient insert and erase operations.

map This header file defines the `std::map` and `std::multimap` class templates. They provide ways to associate keys to values.

memory This header file defines the default allocator template, `std::allocator`, as well as several function templates for manipulating raw (uninitialized) memory regions. In addition this header defines the `std::auto_ptr` template.

Note that the header `memory.h` is part of the Open Watcom C library and is unrelated to `memory`.

new/new.h	This header file provides declarations to be used with the intrinsic operator new and operator delete memory management functions.
numeric	This header file defines several standard algorithm templates pertaining to numerical computation.
ostream/ostream.h	This header file defines class ostream. It also defines its associated parameterless manipulators.
set	This header file defines the std::set and std::multiset class templates. They provide ways to make ordered collections of objects with efficient insert, erase, and find operations.
stdiobuf.h	This header file defines the stdiobuf class which provides the support for the C++ input and output operations to standard input, standard output, and standard error streams.
streambuf/streambuf.h (streambu/streambu.h)	This header file defines the streambuf class which provides the support for buffering of input and output operations. This header file is automatically included by the iostream.h header file.
string	This header file defines the std::basic_string class template. It also contains the type definitions for std::string and std::wstring. In addition, this header contains specializations of the std::char_traits template for both characters and wide characters.
string.hpp	This header file defines the legacy String class. The String class is used to manipulate character strings. Note that the.hpp extension is used to avoid colliding with the Standard C string.h header file. The class defined in this header is not the Standard C++ std::string class.
strstream.h (strstrea.h)	This header files defines the strstreambuf, strstreambase, istrstream, ostrstream, and strstream classes. These classes are used to perform C++ in-memory formatting. The various class members are declared and inline member functions for the classes are defined.
vector	This header contains the std::vector class template.
wcdefs.h	This header file contains definitions used by the Open Watcom legacy container libraries. If a container class needs any of these definitions, the file is automatically included. Note that all headers having names that start with "wc" are related to the legacy container libraries.
wclbase.h	This header file defines the base classes which are used by the list containers.
wclcom.h	This header file defines the classes which are common to the list containers.
wclibase.h	This header file defines the base classes which are used by the list iterators.
wclist.h	This header file defines the list container classes. The available list container classes are single and double linked versions of intrusive, value and pointer lists.
wclistit.h	This header file defines the iterator classes that correspond to the list containers.

wcqueue.h This header file defines the `queue` class. Entries in a queue class are accessed first in, first out.

westack.h This header file defines the `stack` class. Entries in a stack class are accessed last in, first out.

2 Common Types

The set of classes that make up the C++ class library use several common typedefs and macros. They are declared in `<iostream.h>` and `<fstream.h>`.

```
typedef long streampos;
typedef long streamoff;
typedef int filedesc;
#define __NOT_EOF 0
#define EOF -1
```

The `streampos` type represents an absolute position within the file. For Open Watcom C++, the file position can be represented by an integral type. For some file systems, or at a lower level within the file system, the stream position might be represented by an aggregate (structure) containing information such as cylinder, track, sector and offset.

The `streamoff` type represents a relative position within the file. The offset can always be represented as a signed integer quantity since it is a number of characters before or after an absolute position within the file.

The `filedesc` type represents the type of a C library file handle. It is used in places where the I/O stream library takes a C library file handle as an argument.

The `__NOT_EOF` macro is defined for cases where a function needs to return something other than `EOF` to indicate success.

The `EOF` macro is defined to be identical to the value provided by the `<stdio.h>` header file.

3 Predefined Objects

Most programs interact in some manner with the keyboard and screen. The C programming language provides three values, `stdin`, `stdout` and `stderr`, that are used for communicating with these "standard" devices, which are opened before the user program starts execution at `main()`. These three values are FILE pointers and can be used in virtually any file operation supported by the C library.

In a similar manner, C++ provides seven objects for communicating with the same "standard" devices. C++ provides the three C FILE pointers `stdin`, `stdout` and `stderr`, but they cannot be used with the extractors and inserters provided as part of the C++ library. C++ provides four new objects, called `cin`, `cout`, `cerr` and `clog`, which correspond to `stdin`, `stdout`, `stderr` and buffered `stderr`.

3.1 `cin`

`cin` is an `istream` object which is connected to "standard input" (usually the keyboard) prior to program execution. Values extracted using the `istream` operator `>>` class extractor operators are read from standard input and interpreted according to the type of the object being extracted.

Extractions from standard input via `cin` skip whitespace characters by default because the `ios::skipws` bit is on. The default behavior can be changed with the `ios::setf` public member function or with the `setiosflags` manipulator.

3.2 `cout`

`cout` is an `ostream` object which is connected to "standard output" (usually the screen) prior to program execution. Values inserted using the `ostream` operator `<<` class inserter operators are converted to characters and written to standard output according to the type of the object being inserted.

Insertions to standard output via `cout` are buffered by default because the `ios::unitbuf` bit is not on. The default behavior can be changed with the `ios::setf` public member function or with the `setiosflags` manipulator.

3.3 `cerr`

`cerr` is an `ostream` object which is connected to "standard error" (the screen) prior to program execution. Values inserted using the `ostream` operator `<<` class inserter operators are converted to characters and written to standard error according to the type of the object being inserted.

Insertions to standard error via `cerr` are not buffered by default because the `ios::unitbuf` bit is on. The default behavior can be changed with the `ios::setf` public member function or with the `setiosflags` manipulator.

3.4 *clog*

clog is an *ostream* object which is connected to "standard error" (the screen) prior to program execution. Values inserted using the *ostream* operator `<<` class inserter operators are converted to characters and written to standard error according to the type of the object being inserted.

Insertions to standard error via *clog* are buffered by default because the `ios::unitbuf` bit is not on. The default behavior can be changed with the `ios::setf` public member function or with the `setiosflags` manipulator.

4 *istream* Input

This chapter describes formatted and unformatted input.

4.1 Formatted Input: Extractors

The operator `>>` function is used to read formatted values from a stream. It is called an *extractor*. Characters are read and interpreted according to the type of object being extracted.

All operator `>>` functions perform the same basic sequence of operations. First, the input prefix function `ipfx` is called with a parameter of zero, causing leading whitespace characters to be discarded if `ios::skipws` is set in `ios::fmtflags`. If the input prefix function fails and returns zero, the operator `>>` function also fails and returns immediately. If the input prefix function succeeds, characters are read from the stream and interpreted in terms of the type of object being extracted and `ios::fmtflags`. Finally, the input suffix function `isfx` is called.

The operator `>>` functions return a reference to the specified stream so that multiple extractions can be done in one statement.

Errors are indicated via `ios::iostate`. `ios::failbit` is set if the characters read from the stream could not be interpreted for the required type. `ios::badbit` is set if the extraction of characters from the stream failed in such a way as to make subsequent extractions impossible. `ios::eofbit` is set if the stream was located at the end when the extraction was attempted.

4.2 Unformatted Input

The unformatted input functions are used to read characters from the stream without interpretation.

Like the extractors, the unformatted input functions follow a pattern. First, they call `ipfx`, the input prefix function, with a parameter of one, causing no leading whitespace characters to be discarded. If the input prefix function fails and returns zero, the unformatted input function also fails and returns immediately. If the input prefix function succeeds, characters are read from the stream without interpretation. Finally, `isfx`, the input suffix function, is called.

Errors are indicated via the iostate bits. `ios::failbit` is set if the extraction of characters from the stream failed. `ios::eofbit` is set if the stream was located at the end of input when the operation was attempted.

5 *ostream* Output

This chapter describes formatted and unformatted output.

5.1 Formatted Output: Inserters

The operator `<<` function is used to write formatted values to a stream. It is called an *inserter*. Values are formatted and written according to the type of object being inserted and `ios::fmtflags`.

All operator `<<` functions perform the same basic sequence of operations. First, the output prefix function `opfx` is called. If it fails and returns zero, the operator `<<` function also fails and returns immediately. If the output prefix function succeeds, the object is formatted according to its type and `ios::fmtflags`. The formatted sequence of characters is then written to the specified stream. Finally, the output suffix function `osfx` is called.

The operator `<<` functions return a reference to the specified stream so that multiple insertions can be done in one statement.

For details on the interpretation of `ios::fmtflags`, see the `ios::fmtflags` section of the Library Functions and Types Chapter.

Errors are indicated via `ios::iostate`. `ios::failbit` is set if the operator `<<` function fails while writing the characters to the stream.

5.2 Unformatted Output

The unformatted output functions are used to write characters to the stream without conversion.

Like the inserters, the unformatted output functions follow a pattern. First, they call the output prefix function `opfx` and fail if it fails. Then the characters are written without conversion. Finally, the output suffix function `osfx` is called.

Errors are indicated via `ios::iostate`. `ios::failbit` is set if the function fails while writing the characters to the stream.

6 Library Functions and Types

Each of the classes and functions in the Class Library is described in this chapter. Each description consists of a number of subsections:

Declared: This optional subsection specifies which header file contains the declaration for a class. It is only found in sections describing class declarations.

Derived From:

This optional subsection shows the inheritance for a class. It is only found in sections describing class declarations.

Derived By: This optional subsection shows which classes inherit from this class. It is only found in sections describing class declarations.

Synopsis: This subsection gives the name of the header file that contains the declaration of the function. This header file must be included in order to reference the function.

For class member functions, the protection associated with the function is indicated via the presence of one of the `private`, `protected`, or `public` keywords.

The full function prototype is specified. Virtual class member functions are indicated via the presence of the `virtual` keyword in the function prototype.

Semantics: This subsection is a description of the function.

Derived Implementation Protocol:

This optional subsection is present for virtual member functions. It describes how derived implementations of the virtual member function should behave.

Default Implementation:

This optional subsection is present for virtual member functions. It describes how the default implementation provided with the base class definition behaves.

Results: This optional subsection describes the function's return value, if any, and the impact of a member function on its object's state.

See Also: This optional subsection provides a list of related functions or classes.

7 Complex Class

This class is used for the storage and manipulation of complex numbers, which are often represented by *real* and *imaginary* components (Cartesian coordinates), or by *magnitude* and *angle* (polar coordinates). Each object stores exactly one complex number. An object may be used in expressions in the same manner as floating-point values.

The class documented here is the Open Watcom legacy complex class. It is not the `std::complex` class template specified by Standard C++.

Declared: complex.h

The `Complex` class is used for the storage and manipulation of complex numbers, which are often represented by *real* and *imaginary* components (Cartesian coordinates), or by *magnitude* and *angle* (polar coordinates). Each `Complex` object stores exactly one complex number. A `Complex` object may be used in expressions in the same manner as floating-point values.

Public Member Functions

The following constructors and destructors are declared:

```
Complex();
Complex( Complex const & );
Complex( double, double = 0.0 );
~Complex();
```

The following arithmetic member functions are declared:

```
Complex &operator =( Complex const & );
Complex &operator =( double );
Complex &operator +=( Complex const & );
Complex &operator +=( double );
Complex &operator -=( Complex const & );
Complex &operator -=( double );
Complex &operator *=( Complex const & );
Complex &operator *(= double );
Complex &operator /=( Complex const & );
Complex &operator /(= double );
Complex operator +() const;
Complex operator -() const;
double imag() const;
double real() const;
```

Friend Functions

The following I/O Stream inserter and extractor friend functions are declared:

```
friend istream &operator >>( istream &, Complex & );
friend ostream &operator <<( ostream &, Complex const & );
```

Related Operators

The following operators are declared:

```
Complex operator +( Complex const &, Complex const & );
Complex operator +( Complex const &, double );
Complex operator +( double , Complex const & );
Complex operator -( Complex const &, Complex const & );
Complex operator -( Complex const &, double );
Complex operator -( double , Complex const & );
Complex operator *( Complex const &, Complex const & );
Complex operator *( Complex const &, double );
Complex operator *( double , Complex const & );
Complex operator /( Complex const &, Complex const & );
Complex operator /( Complex const &, double );
Complex operator /( double , Complex const & );
int operator ==( Complex const &, Complex const & );
```

```
int      operator ==( Complex const &, double );
int      operator ==( double           , Complex const & );
int      operator !=( Complex const &, Complex const & );
int      operator !=( Complex const &, double );
int      operator !=( double           , Complex const & );
```

Related Functions

The following related functions are declared:

```
double abs  ( Complex const & );
Complex acos ( Complex const & );
Complex acosh( Complex const & );
double arg  ( Complex const & );
Complex asin ( Complex const & );
Complex asinh( Complex const & );
Complex atan ( Complex const & );
Complex atanh( Complex const & );
Complex conj ( Complex const & );
Complex cos  ( Complex const & );
Complex cosh ( Complex const & );
Complex exp  ( Complex const & );
double imag ( Complex const & );
Complex log  ( Complex const & );
Complex log10( Complex const & );
double norm ( Complex const & );
Complex polar( double       , double = 0 );
Complex pow  ( Complex const &, Complex const & );
Complex pow  ( Complex const &, double );
Complex pow  ( double       , Complex const & );
Complex pow  ( Complex const &, int );
double real ( Complex const & );
Complex sin  ( Complex const & );
Complex sinh ( Complex const & );
Complex sqrt ( Complex const & );
Complex tan  ( Complex const & );
Complex tanh ( Complex const & );
```

Complex abs()

Synopsis: `#include <complex.h>`
 `double abs(Complex const &num);`

Semantics: The `abs` function computes the magnitude of *num*, which is equivalent to the length (magnitude) of the vector when the *num* is represented in polar coordinates.

Results: The `abs` function returns the magnitude of *num*.

See Also: `arg`, `norm`, `polar`

Synopsis: `#include <complex.h>`
 `Complex acos(Complex const &num);`

Semantics: The `acos` function computes the arccosine of *num*.

Results: The `acos` function returns the arccosine of *num*.

See Also: `asin, atan, cos`

Complex acosh()

Synopsis: `#include <complex.h>`
 `Complex acosh(Complex const &num);`

Semantics: The `acosh` function computes the inverse hyperbolic cosine of *num*.

Results: The `acosh` function returns the inverse hyperbolic cosine of *num*.

See Also: `asinh`, `atanh`, `cosh`

Synopsis:

```
#include <complex.h>
double arg( Complex const &num );
```

Semantics: The `arg` function computes the angle of the vector when the *num* is represented in polar coordinates. The angle has the same sign as the real component of the *num*. It is positive in the 1st and 2nd quadrants, and negative in the 3rd and 4th quadrants.

Results: The `arg` function returns the angle of the vector when the *num* is represented in polar coordinates.

See Also: `abs`, `norm`, `polar`

Complex asin()

Synopsis: `#include <complex.h>`
 `Complex asin(Complex const &num);`

Semantics: The `asin` function computes the arcsine of *num*.

Results: The `asin` function returns the arcsine of *num*.

See Also: `acos, atan, sin`

Synopsis: `#include <complex.h>`
 `Complex asinh(Complex const &num);`

Semantics: The `asinh` function computes the inverse hyperbolic sine of *num*.

Results: The `asinh` function returns the inverse hyperbolic sine of *num*.

See Also: `acosh`, `atanh`, `sinh`

Complex atan()

Synopsis: `#include <complex.h>`
 `Complex atan(Complex const &num);`

Semantics: The atan function computes the arctangent of *num*.

Results: The atan function returns the arctangent of *num*.

See Also: acos, asin, tan

Synopsis: `#include <complex.h>`
 `Complex atanh(Complex const &num);`

Semantics: The `atanh` function computes the inverse hyperbolic tangent of *num*.

Results: The `atanh` function returns the inverse hyperbolic tangent of *num*.

See Also: `acosh`, `asinh`, `tanh`

Complex::Complex()

Synopsis:

```
#include <complex.h>
public:
Complex::Complex();
```

Semantics: This form of the public Complex constructor creates a default Complex object with value zero for both the real and imaginary components.

Results: This form of the public Complex constructor produces a default Complex object.

See Also: ~Complex, real, imag

Synopsis:

```
#include <complex.h>
public:
    Complex::Complex( Complex const &num );
```

Semantics: This form of the public Complex constructor creates a Complex object with the same value as *num*.

Results: This form of the public Complex constructor produces a Complex object.

See Also: ~Complex, real, imag

Complex::Complex()

Synopsis:

```
#include <complex.h>
public:
    Complex::Complex( double real, double imag = 0.0 );
```

Semantics: This form of the public Complex constructor creates a Complex object with the real component set to *real* and the imaginary component set to *imag*. If no imaginary component is specified, *imag* takes the default value of zero.

Results: This form of the public Complex constructor produces a Complex object.

See Also: ~Complex, real, imag

Synopsis:

```
#include <complex.h>
public:
Complex::~Complex();
```

Semantics: The public ~Complex destructor destroys the Complex object. The call to the public ~Complex destructor is inserted implicitly by the compiler at the point where the Complex object goes out of scope.

Results: The Complex object is destroyed.

See Also: Complex

Complex conj()

Synopsis: `#include <complex.h>`
 `Complex conj(Complex const &num);`

Semantics: The `conj` function computes the conjugate of *num*. The conjugate consists of the unchanged real component, and the negative of the imaginary component.

Results: The `conj` function returns the conjugate of *num*.

Synopsis: `#include <complex.h>`
 `Complex cos(Complex const &num);`

Semantics: The `cos` function computes the cosine of *num*.

Results: The `cos` function returns the cosine of *num*.

See Also: `acos, sin, tan`

Complex cosh()

Synopsis: `#include <complex.h>`
 `Complex cosh(Complex const &num);`

Semantics: The `cosh` function computes the hyperbolic cosine of *num*.

Results: The `cosh` function returns the hyperbolic cosine of *num*.

See Also: `acosh, sinh, tanh`

Synopsis: `#include <complex.h>`
 `Complex exp(Complex const &num);`

Semantics: The `exp` function computes the value of **e** raised to the power *num*.

Results: The `exp` function returns the value of **e** raised to the power *num*.

See Also: `log`, `log10`, `pow`, `sqrt`

Complex::imag()

Synopsis:

```
#include <complex.h>
public:
    double Complex::imag();
```

Semantics: The `imag` public member function extracts the imaginary component of the `Complex` object.

Results: The `imag` public member function returns the imaginary component of the `Complex` object.

See Also:

- `imag`, `real`
- `Complex::real`

Synopsis: `#include <complex.h>`
 `double imag(Complex const &num);`

Semantics: The `imag` function extracts the imaginary component of *num*.

Results: The `imag` function returns the imaginary component of *num*.

See Also: `real`
 `Complex::imag, real`

Complex log()

Synopsis: `#include <complex.h>`
 `Complex log(Complex const &num);`

Semantics: The `log` function computes the natural, or base **e**, logarithm of *num*.

Results: The `log` function returns the natural, or base **e**, logarithm of *num*.

See Also: `exp`, `log10`, `pow`, `sqrt`

Synopsis: `#include <complex.h>`
 `Complex log10(Complex const &num);`

Semantics: The `log10` function computes the base 10 logarithm of *num*.

Results: The `log10` function returns the base 10 logarithm of *num*.

See Also: `exp`, `log`, `pow`, `sqr`

Complex norm()

Synopsis: `#include <complex.h>`
 `double norm(Complex const &num);`

Semantics: The `norm` function computes the square of the magnitude of *num*, which is equivalent to the square of the length (magnitude) of the vector when *num* is represented in polar coordinates.

Results: The `norm` function returns the square of the magnitude of *num*.

See Also: `arg`, `polar`

Synopsis:

```
#include <complex.h>
int operator !=( Complex const &num1, Complex const &num2 );
int operator !=( Complex const &num1, double num2 );
int operator !=( double num1, Complex const &num2 );
```

Semantics:

The operator `!=` function compares *num1* and *num2* for inequality. At least one of the parameters must be a `Complex` object for this function to be called.

Two `Complex` objects are not equal if either of their corresponding real or imaginary components are not equal.

If the operator `!=` function is used with a `Complex` object and an object of any other built-in numeric type, the non-`Complex` object is converted to a `double` and the second or third form of the operator `!=` function is used.

Results:

The operator `!=` function returns a non-zero value if *num1* is not equal to *num2*, otherwise zero is returned.

See Also:

`operator ==`

Complex operator *()

Synopsis:

```
#include <complex.h>
Complex operator *( Complex const &num1, Complex const &num2 );
Complex operator *( Complex const &num1, double num2 );
Complex operator *( double num1, Complex const &num2 );
```

Semantics: The operator `*` function is used to multiply *num1* by *num2* yielding a `Complex` object.

The first operator `*` function multiplies two `Complex` objects.

The second operator `*` function multiplies a `Complex` object and a floating-point value. In effect, the real and imaginary components of the `Complex` object are multiplied by the floating-point value.

The third operator `*` function multiplies a floating-point value and a `Complex` object. In effect, the real and imaginary components of the `Complex` object are multiplied by the floating-point value.

If the operator `*` function is used with a `Complex` object and an object of any other built-in numeric type, the non-`Complex` object is converted to a `double` and the second or third form of the operator `*` function is used.

Results: The operator `*` function returns a `Complex` object that is the product of *num1* and *num2*.

See Also: `operator +, operator -, operator /`
`Complex::operator *=`

Synopsis:

```
#include <complex.h>
public:
Complex &Complex::operator *( Complex const &num );
Complex &Complex::operator *( double num );
```

Semantics: The operator `*=` public member function is used to multiply the *num* argument into the Complex object.

The first form of the operator `*=` public member function multiplies the Complex object by the Complex parameter.

The second form of the operator `*=` public member function multiplies the real and imaginary components of the Complex object by *num*.

A call to the operator `*=` public member function where *num* is any of the other built-in numeric types, causes *num* to be promoted to `double` and the second form of the operator `*=` public member function to be used.

Results: The operator `*=` public member function returns a reference to the target of the assignment.

See Also: `operator *`
`Complex::operator +=, operator -=, operator /=, operator =`

Complex::operator +()

Synopsis:

```
#include <complex.h>
public:
    Complex Complex::operator +();
```

Semantics: The unary operator `+ public member function` is provided for completeness. It performs no operation on the `Complex` object.

Results: The unary operator `+ public member function` returns a `Complex` object with the same value as the original `Complex` object.

See Also: `operator +`
`Complex::operator +=, operator -`

Synopsis:

```
#include <complex.h>
Complex operator +( Complex const &num1, Complex const &num2 );
Complex operator +( Complex const &num1, double num2 );
Complex operator +( double num1, Complex const &num2 );
```

Semantics: The `operator +` function is used to add *num1* to *num2* yielding a `Complex` object.

The first `operator +` function adds two `Complex` objects.

The second `operator +` function adds a `Complex` object and a floating-point value. In effect, the floating-point value is added to the real component of the `Complex` object.

The third `operator +` function adds a floating-point value and a `Complex` object. In effect, the floating-point value is added to the real component of the `Complex` object.

If the `operator +` function is used with a `Complex` object and an object of any other built-in numeric type, the non-`Complex` object is converted to a `double` and the second or third form of the `operator +` function is used.

Results: The `operator +` function returns a `Complex` object that is the sum of *num1* and *num2*.

See Also: `operator *, operator -, operator /`
`Complex::operator +, operator +=`

Complex::operator +=()

Synopsis:

```
#include <complex.h>
public:
    Complex &Complex::operator +=( Complex const &num );
    Complex &Complex::operator +=( double num );
```

Semantics: The operator `+=` public member function is used to add `num` to the value of the `Complex` object. The second form of the operator `+=` public member function adds `num` to the real component of the `Complex` object.

A call to the operator `+=` public member function where `num` is any of the other built-in numeric types, causes `num` to be promoted to `double` and the second form of the operator `+=` public member function to be used.

Results: The operator `+=` public member function returns a reference to the target of the assignment.

See Also: `operator +`
`Complex::operator *=`, `operator +`, `operator /=`, `operator -=`, `operator =`

Synopsis:

```
#include <complex.h>
public:
Complex Complex::operator -();
```

Semantics: The unary operator `-` public member function yields a `Complex` object with the real and imaginary components having the same magnitude as those of the original object, but with opposite sign.

Results: The unary operator `-` public member function returns a `Complex` object with the same magnitude as the original `Complex` object and with opposite sign.

See Also:

```
operator -
Complex::operator +, operator -=
```

Complex operator -()

Synopsis:

```
#include <complex.h>
Complex operator -( Complex const &num1, Complex const &num2 );
Complex operator -( Complex const &num1, double num2 );
Complex operator -( double num1, Complex const &num2 );
```

Semantics: The `operator -` function is used to subtract `num2` from `num1` yielding a `Complex` object.

The first `operator -` function computes the difference between two `Complex` objects.

The second `operator -` function computes the difference between a `Complex` object and a floating-point value. In effect, the floating-point value is subtracted from the real component of the `Complex` object.

The third `operator -` function computes the difference between a floating-point value and a `Complex` object. In effect, the real component of the result is `num1` minus the real component of `num2`

.

If the `operator -` function is used with a `Complex` object and an object of any other built-in numeric type, the non-`Complex` object is converted to a `double` and the second or third form of the `operator -` function is used.

Results: The `operator -` function returns a `Complex` object that is the difference between `num1` and `num2`.

See Also: `operator *, operator +, operator /`
`Complex::operator -, operator -=`

Synopsis:

```
#include <complex.h>
public:
Complex &Complex::operator -=( Complex const &num );
Complex &Complex::operator -(= double num );
```

Semantics:

The `operator -=` public member function is used to subtract `num` from the value of the `Complex` object. The second form of the `operator -=` public member function subtracts `num` from the real component of the `*obj..`

A call to the `operator -=` public member function where `num` is any of the other built-in numeric types, causes `num` to be promoted to `double` and the second form of the `operator -=` public member function to be used.

Results:

The `operator -=` public member function returns a reference to the target of the assignment.

See Also:

`operator -`
`Complex::operator *=, operator +=, operator -, operator /=, operator =`

Complex operator /()

Synopsis:

```
#include <complex.h>
Complex operator /( Complex const &num1, Complex const &num2 );
Complex operator /( Complex const &num1, double num2 );
Complex operator /( double num1, Complex const &num2 );
```

Semantics: The operator `/` function is used to divide *num1* by *num2* yielding a `Complex` object.

The first `operator /` function divides two `Complex` objects.

The second `operator /` function divides a `Complex` object by a floating-point value. In effect, the real and imaginary components of the complex number are divided by the floating-point value.

The third `operator /` function divides a floating-point value by a `Complex` object. Conceptually, the floating-point value is converted to a `Complex` object and then the division is done.

If the `operator /` function is used with a `Complex` object and an object of any other built-in numeric type, the non-`Complex` object is converted to a `double` and the second or third form of the `operator /` function is used.

Results: The `operator /` function returns a `Complex` object that is the quotient of *num1* divided by *num2*.

See Also: `operator *`, `operator +`, `operator -`
`Complex::operator /=`

Synopsis:

```
#include <complex.h>
public:
Complex &Complex::operator /=( Complex const &num );
Complex &Complex::operator /=( double num );
```

Semantics: The operator `/=` public member function is used to divide the `Complex` object by `num`. The second form of the operator `/=` public member function divides the real and imaginary components of the `Complex` object by `num`.

A call to the operator `/=` public member function where `num` is any of the other built-in numeric types, causes `num` to be promoted to `double` and the second form of the operator `/=` public member function to be used.

Results: The operator `/=` public member function returns a reference to the target of the assignment.

See Also: `operator /`
`Complex::operator *=, operator +=, operator -=, operator =`

Complex operator <<()

Synopsis: `#include <complex.h>`
 `friend ostream &operator <<(ostream &strm, Complex &num);`

Semantics: The operator `<<` function is used to write `Complex` objects to an I/O stream. The `Complex` object is always written in the form:

`(real,imag)`

The real and imaginary components are written using the normal rules for formatting floating-point numbers. Any formatting options specified prior to inserting the `num` apply to both the real and imaginary components. If the real and imaginary components are to be inserted using different formats, the `real` and `imag` member functions should be used to insert each component separately.

Results: The operator `<<` function returns a reference to the `strm` object.

See Also: `istream`

Synopsis:

```
#include <complex.h>
public:
Complex &Complex::operator =( Complex const &num );
Complex &Complex::operator =( double num );
```

Semantics: The `operator =` public member function is used to set the value of the `Complex` object to *num*. The first assignment operator copies the value of *num* into the `Complex` object.

The second assignment operator sets the real component of the `Complex` object to *num* and the imaginary component to zero.

A call to the `operator =` public member function where *num* is any of the other built-in numeric types, causes *num* to be promoted to `double` and the second form of the `operator =` public member function to be used.

Results: The `operator =` public member function returns a reference to the target of the assignment.

See Also: `Complex::operator *=`, `operator +=`, `operator -=`, `operator /=`

Complex operator ==()

Synopsis:

```
#include <complex.h>
int operator ==( Complex const &num1, Complex const &num2 );
int operator ==( Complex const &num1, double num2 );
int operator ==( double num1, Complex const &num2 );
```

Semantics:

The `operator ==` function compares *num1* and *num2* for equality. At least one of the arguments must be a `Complex` object for this function to be called.

Two `Complex` objects are equal if their corresponding real and imaginary components are equal.

If the `operator ==` function is used with a `Complex` object and an object of any other built-in numeric type, the non-`Complex` object is converted to a `double` and the second or third form of the `operator ==` function is used.

Results:

The `operator ==` function returns a non-zero value if *num1* is equal to *num2*, otherwise zero is returned.

See Also:

`operator !=`

Synopsis: #include <complex.h>
friend istream &operator >>(istream &strm, Complex &num);

Semantics: The operator `>>` function is used to read a `Complex` object from an I/O stream. A valid complex value is of one of the following forms:

```
(real,imag)  
real,imag  
(real)
```

If the imaginary portion is omitted, zero is assumed.

While reading a `Complex` object, whitespace is ignored before and between the various components of the number if the `ios::skipws` bit is set in `ios::fmtflags`.

Results: The operator `>>` function returns a reference to `strm`. `num` contains the value read from `strm` on success, otherwise it is unchanged.

See Also: `istream`

Complex polar()

Synopsis: `#include <complex.h>`
 `Complex polar(double mag, double angle = 0.0);`

Semantics: The `polar` function converts *mag* and *angle* (polar coordinates) into a complex number. The *angle* is optional and defaults to zero if it is unspecified.

Results: The `polar` function returns a `Complex` object that is *mag* and *angle* interpreted as polar coordinates.

See Also: `abs`, `arg`, `norm`

Synopsis:

```
#include <complex.h>
Complex pow( Complex const &num, Complex const &exp );
Complex pow( Complex const &num, double exp );
Complex pow( double num, Complex const &exp );
Complex pow( Complex const &num, int exp );
```

Semantics:

The `pow` function computes *num* raised to the power *exp*. The various forms are provided to minimize the amount of floating-point calculation performed.

Results:

The `pow` function returns a `Complex` object that is *num* raised to the power a `Complex` object that is *exp*.

See Also:

`exp`, `log`, `log10`, `sqrt`

Complex::real()

Synopsis:

```
#include <complex.h>
public:
    double Complex::real();
```

Semantics: The `real` public member function extracts the real component of the `Complex` object.

Results: The `real` public member function returns the real component of the `Complex` object.

See Also: `imag`, `real`
`Complex::imag`

Synopsis: `#include <complex.h>`
 `double real(Complex const &num);`

Semantics: The `real` function extracts the real component of *num*.

Results: The `real` function returns the real component of *num*.

See Also: `imag`
 `Complex::imag, real`

Complex sin()

Synopsis: `#include <complex.h>`
 `Complex sin(Complex const &num);`

Semantics: The `sin` function computes the sine of *num*.

Results: The `sin` function returns the sine of *num*.

See Also: `asin, cos, tan`

Synopsis: `#include <complex.h>`
 `Complex sinh(Complex const &num);`

Semantics: The `sinh` function computes the hyperbolic sine of *num*.

Results: The `sinh` function returns the hyperbolic sine of *num*.

See Also: `asinh, cosh, tanh`

Complex sqrt()

Synopsis: `#include <complex.h>`
 `Complex sqrt(Complex const &num);`

Semantics: The `sqrt` function computes the square root of *num*.

Results: The `sqrt` function returns the square root of *num*.

See Also: `exp`, `log`, `log10`, `pow`

Synopsis: `#include <complex.h>`
 `Complex tan(Complex const &num);`

Semantics: The `tan` function computes the tangent of *num*.

Results: The `tan` function returns the tangent of *num*.

See Also: `atan, cos, sin`

Complex tanh()

Synopsis: `#include <complex.h>`
 `Complex tanh(Complex const &num);`

Semantics: The `tanh` function computes the hyperbolic tangent of *num*.

Results: The `tanh` function returns the hyperbolic tangent of *num*.

See Also: `atanh`, `cosh`, `sinh`

8 Container Exception Classes

This chapter describes exception handling for the container classes.

Declared: wcexcept.h

The WCExcept class provides the exception handling for the container classes. If you have compiled your code with exception handling enabled, the C++ exception processing can be used to catch errors. Your source file must be compiled with the exception handling compile switch for C++ exception processing to occur. The container classes will attempt to set the container object into a reasonable state if there is an error and exception handling is not enabled, or if the trap for the specific error has not been enabled by your program.

By default, no exception traps are enabled and no exceptions will be thrown. Exception traps are enabled by setting the exception state with the exceptions member function.

The wcexcept.h header file is included by the header files for each of the container classes. There is normally no need to explicitly include the wcexcept.h header file, but no errors will result if it is included. This class is inherited as a base class for each of the containers. You do not need to derive from it directly.

The WCLListExcept class (formally used by the list container classes) has been replaced by the WCExcept class. A typedef of the WCLListExcept class to the WCExcept class and the wclist_state type to the wc_state type provide backward compatibility with previous versions of the list containers.

Public Enumerations

The following enumeration typedefs are declared in the public interface:

```
typedef int wc_state;
```

Public Member Functions

The following public member functions are declared:

```
WCExcept();
virtual ~WCExcept();
wc_state exceptions() const;
wc_state exceptions( wc_state );
```

Synopsis:

```
#include <wcexcept.h>
public:
WCExcept();
```

Semantics: This form of the public WCExcept constructor creates an WCExcept object.

The public WCExcept constructor is used implicitly by the compiler when it generates a constructor for a derived class. It is automatically used by the list container classes, and should not be required in any user derived classes.

Results: The public WCExcept constructor produces an initialized WCExcept object with no exception traps enabled.

See Also: ~WCExcept

WCExcept::~WCExcept()

Synopsis:

```
#include <wcexcept.h>
public:
    virtual ~WCExcept();
```

Semantics: The public ~WCExcept destructor does not do anything explicit. The call to the public ~WCExcept destructor is inserted implicitly by the compiler at the point where the object derived from WCExcept goes out of scope.

Results: The object derived from WCExcept is destroyed.

See Also: WCExcept

Synopsis:

```
#include <wcexcept.h>
public:
    wc_state exceptions() const;
    wc_state exceptions( wc_state set_flags );
```

Semantics: The `exceptions` public member function queries and/or sets the bits that control which exceptions are enabled for the list class. Each bit corresponds to an exception, and is set if the exception is enabled. The first form of the `exceptions` public member function returns the current settings of the exception bits. The second form of the function sets the exception bits to those specified by `set_flags`.

Results: The current exception bits are returned. If a new set of bits are being set, the returned value is the old set of exception bits.

Synopsis:

```
#include <wcexcept.h>
public:
enum wcstate {
    all_fine = 0x0000, // - no errors
    check_none = all_fine, // - throw no exceptions
    not_empty = 0x0001, // - container not empty
    index_range = 0x0002, // - index is out of range
    empty_container= 0x0004, // - empty container error
    out_of_memory = 0x0008, // - allocation failed
    resize_required= 0x0010, // - request needs resize
    not_unique = 0x0020, // - adding duplicate
    zero_buckets = 0x0040, // - resizing hash to zero
    // value to use to check for all errors
    check_all = (not_empty|index_range|empty_container
    |out_of_memory|resize_required
    |not_unique|zero_buckets)
};
typedef int wc_state;
```

Semantics:

The type `WCExcept::wcstate` is a set of bits representing the current state of the container object. The `WCExcept::wc_state` member `typedef` represents the same set of bits, but uses an `int` to represent the values, thereby avoiding problems made possible by the compiler's ability to use smaller types for enumerations. All uses of these bits should use the `WCExcept::wc_state` member `typedef`.

The bit values defined by the `WCExcept::wc_state` member `typedef` can be read and set by the `exceptions` member function, which is also used to control exception handling.

The `WCExcept::not_empty` bit setting traps the destruction of a container when the container has at one or more entries. If this error is not trapped, memory may not be properly released back to the system.

The `WCExcept::index_range` state setting traps an attempt to access a container item by an index value that is either not positive or is larger than the index of the last item in the container.

The `WCExcept::empty_container` bit setting traps an attempt to perform an invalid operation on a container with no entries.

The `WCExcept::out_of_memory` bit setting traps any container class allocation failures. If this exception is not enabled, the operation in which the allocation failed will return a FALSE (zero) value. Container class copy constructors and assignment operators can also throw this exception, and if not enabled incomplete copies may result.

The `WCExcept::resize_required` bit setting traps any vector operations which cannot be performed unless the vector is resized to a larger size. If this exception is not enabled, the vector class will attempt an appropriate resize when necessary for an operation.

The `WCExcept::not_unique` bit setting traps an attempt to add a duplicate value to a set container, or a duplicate key to a dictionary container. The duplicate value is not added to the container object regardless of the exception trap state.

The `WCExcept::zero_buckets` bit setting traps an attempt to resize of hash container to have zero buckets. No resize is performed whether or not the exception is enabled.

Declared: wcexcept.h

The WCIterExcept class provides the exception handling for the container iterators. If you have compiled your code with exception handling enabled, the C++ exception processing can be used to catch errors. Your source file must be compiled with the exception handling compile switch for C++ exception processing to occur. The iterators will attempt to set the class into a reasonable state if there is an error and exception handling is not enabled, or if the trap for the specific error has not been enabled by your program.

By default, no exception traps are enabled and no exceptions will be thrown. Exception traps are enabled by setting the exception state with the exceptions member function.

The wcexcept.h header file is included by the header files for each of the iterator classes. There is normally no need to explicitly include the wcexcept.h header file, but no errors will result if it is included. This class is inherited as part of the base construction for each of the iterators. You do not need to derive from it directly.

Public Enumerations

The following enumeration typedefs are declared in the public interface:

```
typedef int wciter_state;
```

Public Member Functions

The following public member functions are declared:

```
WCIterExcept();
virtual ~WCIterExcept();
wciter_state exceptions() const;
wciter_state exceptions( wciter_state );
```

WCIterExcept::WCIterExcept()

Synopsis:

```
#include <wcexcept.h>
public:
WCIterExcept();
```

Semantics: This form of the public WCIterExcept constructor creates an WCIterExcept object.

The public WCIterExcept constructor is used implicitly by the compiler when it generates a constructor for a derived class.

Results: The public WCIterExcept constructor produces an initialized WCIterExcept object with no exception traps enabled.

See Also: ~WCIterExcept

Synopsis:

```
#include <wcexcept.h>
public:
    virtual ~WCIterExcept();
```

Semantics: The public `~WCIterExcept` destructor does not do anything explicit. The call to the public `~WCIterExcept` destructor is inserted implicitly by the compiler at the point where the object derived from `WCIterExcept` goes out of scope.

Results: The object derived from `WCIterExcept` is destroyed.

See Also: `WCIterExcept`

WCIterExcept::exceptions()

Synopsis:

```
#include <wcexcept.h>
public:
    wciter_state exceptions() const;
    wciter_state exceptions( wciter_state set_flags );
```

Semantics: The `exceptions` public member function queries and/or sets the bits that control which exceptions are enabled for the iterator class. Each bit corresponds to an exception, and is set if the exception is enabled. The first form of the `exceptions` public member function returns the current settings of the exception bits. The second form of the function sets the exception bits to those specified by `set_flags`.

Results: The current exception bits are returned. If a new set of bits are being set, the returned value is the old set of exception bits.

Synopsis:

```
#include <wcexcept.h>
public:
enum wciterstate {
    all_fine = 0x0000, // - no errors
    check_none = all_fine, // - disable all exceptions
    undef_iter = 0x0001, // - position is undefined
    undef_item = 0x0002, // - iterator item is undefined
    iter_range = 0x0004, // - advance value is bad
    // value to use to check for all errors
    check_all= (undef_iter|undef_item|iter_range)
};
typedef int wciter_state;
```

Semantics: The type WCIterExcept::wciterstate is a set of bits representing the current state of the iterator. The WCIterExcept::wciter_state member typedef represents the same set of bits, but uses an int to represent the values, thereby avoiding problems made possible by the compiler's ability to use smaller types for enumerations. All uses of these bits should use the WCIterExcept::wciter_state member typedef.

The bit values defined by the WCIterExcept::wciter_state member typedef can be read and set by the member function exceptions, which is used to control exception handling.

The WCIterExcept::undef_iter bit setting traps the use of the iterator when the position within the container object is undefined. Trying to operate on an iterator with no associated container object, increment an iterator which is after the last element, or decrement an iterator positioned before the first element is an undefined operation.

The WCIterExcept::undef_item bit setting traps an attempt to obtain the current element of the iterator when the iterator has no associated container object, or is positioned either before or after the container elements. The undef_item exception can be thrown only by the key and value dictionary iterator member functions, and the current member function for non-dictionary iterators.

The WCIterExcept::iter_range bit setting traps an attempt to use a iteration count value that would place the iterator more than one element past the end or before the beginning of the container elements. The iter_range exception can be thrown only by the operator += and operator -= operators.

9 Container Allocators and Deallocation

Example

```
#include <iostream.h>
#include <wcclist.h>
#include <wcclistit.h>
#include <wcskip.h>
#include <wcskipit.h>
#include <stdlib.h>

#pragma warning 549 9

const int ElemsPerBlock = 50;

// Simple block allocation class. Allocate blocks for ElemsPerBlock
// elements, and use part of the block for each of the next ElemsPerBlock
// allocations, incrementing the number allocated elements. Repeat getting
// more blocks as needed.
//
// Store the blocks in an intrusive single linked list.
//
// On a element deallocation, assume we allocated the memory and just
// decrement the count of allocated elements. When the count gets to zero,
// free all allocated blocks
//
// This implementation assumes sizeof( char ) == 1
//

class BlockAlloc {
private:
    // the size of elements (in bytes)
    unsigned elem_size;

    // number of elements allocated
    unsigned num_allocated;

    // free space of this number of elements available in first block
    unsigned num_free_in_block;

    // list of blocks used to store elements (block are chunks of memory,
    // pointed by (char *) pointers.
    WCPtrSList<char> block_list;

    // pointer to the first block in the list
    char *curr_block;

public:
    inline BlockAlloc( unsigned size )
        : elem_size( size ), num_allocated( 0 )
        , num_free_in_block( 0 ) {};

    inline BlockAlloc() {
        block_list.clearAndDestroy();
    };

    // get memory for an element using block allocation
    void *allocator( size_t elem_size );

    // free memory for an element using block allocation and deallocation
    void deallocator( void *old_ptr, size_t elem_size );
};
```

```
void *BlockAlloc::allocator( size_t size ) {
    // need a new block to perform allocation
    if( num_free_in_block == 0 ) {
        // allocate memory for ElemsPerBlock elements
        curr_block = new char [size * ElemsPerBlock];
        if( curr_block == 0 ) {
            // allocation failed
            return( 0 );
        }
        // add new block to beginning of list
        if( !block_list.insert( curr_block ) ) {
            // allocation of list element failed
            delete[] curr_block;
            return( 0 );
        }
        num_free_in_block = ElemsPerBlock;
    }

    // curr block points to a block of memory with some free memory
    num_allocated++;
    num_free_in_block--;
    // return pointer to a free part of the block, starting at the end
    // of the block
    return( curr_block + num_free_in_block * size );
}

void BlockAlloc::deallocator( void *, size_t ) {
    // just decrement the count
    // don't free anything until all elements are deallocated
    num_allocated--;
    if( num_allocated == 0 ) {
        // all the elements allocated BlockAlloc object have now been
        // deallocated, free all the blocks
        block_list.clearAndDestroy();
        num_free_in_block = 0;
    }
}

const unsigned NumTestElems = 200;

// array with random elements
static unsigned test_elems[ NumTestElems ];

static void fill_test_elems() {
    for( int i = 0; i < NumTestElems; i++ ) {
        test_elems[ i ] = rand();
    }
}

void test_isv_list();
void test_val_list();
void test_val_skip_list();

void main() {
    fill_test_elems();

    test_isv_list();
    test_val_list();
    test_val_skip_list();
}

// An intrusive list class

class isvInt : public WCSLink {
public:
    static BlockAlloc memory_manage;
    int data;
```

```

isvInt( int datum ) : data( datum ) {};

void *operator new( size_t size ) {
    return( memory_manageallocator( size ) );
};

void operator delete( void *old, size_t size ) {
    memory_manage.deallocator( old, size );
};
};

// define static member data
BlockAlloc isvInt::memory_manage( sizeof( isvInt ) );

void test_isv_list() {
    WCIsvSList<isvInt> list;

    for( int i = 0; i < NumTestElems; i++ ) {
        list.insert( new isvInt( test_elems[ i ] ) );
    }

    WCIsvSListIter<isvInt> iter( list );
    while( ++iter ) {
        cout << iter.current()->data << " ";
    }
    cout << "\n\n\n";
    list.clearAndDestroy();
}

// WCValSList<int> memory allocator/dealloctor support
static BlockAlloc val_list_manager( WCValSListItemSize( int ) );

static void *val_list_alloc( size_t size ) {
    return( val_list_manager.allocator( size ) );
}

static void val_list_dealloc( void *old, size_t size ) {
    val_list_manager.deallocator( old, size );
}

// test WCValSList<int>
void test_val_list() {
    WCValSList<int> list( &val_list_alloc, &val_list_dealloc );

    for( int i = 0; i < NumTestElems; i++ ) {
        list.insert( test_elems[ i ] );
    }

    WCValSListIter<int> iter( list );
    while( ++iter ) {
        cout << iter.current() << " ";
    }
    cout << "\n\n\n";
    list.clear();
}

// skip list allocator deallocators: just use allocator and dealloctor
// functions on skip list elements with one and two pointers
// (this will handle 94% of the elements)
const int one_ptr_size = WCValSkipListItemSize( int, 1 );

```

```
const int two_ptr_size = WCValSkipList::itemSize( int, 2 );

static BlockAlloc one_ptr_manager( one_ptr_size );
static BlockAlloc two_ptr_manager( two_ptr_size );

static void *val_skip_list_alloc( size_t size ) {
    switch( size ) {
        case one_ptr_size:
            return( one_ptr_manager.allocator( size ) );
        case two_ptr_size:
            return( two_ptr_manager.allocator( size ) );
        default:
            return( new char[ size ] );
    }
}

static void val_skip_list_dealloc( void *old, size_t size ) {
    switch( size ) {
        case one_ptr_size:
            one_ptr_manager.deallocator( old, size );
            break;
        case two_ptr_size:
            two_ptr_manager.deallocator( old, size );
            break;
        default:
            delete old;
            break;
    }
}

// test WCValSkipList<int>
void test_val_skip_list() {
    WCValSkipList<int> skiplist( WCSKIPLIST_PROB_QUARTER
                                , WCDEFAULT_SKIPLIST_MAX_PTRS
                                , &val_skip_list_alloc
                                , &val_skip_list_dealloc );

    for( int i = 0; i < NumTestElems; i++ ) {
        skiplist.insert( test_elems[ i ] );
    }

    WCValSkipListIter<int> iter( skiplist );
    while( ++iter ) {
        cout << iter.current() << " ";
    }
    cout << "\n\n";
    skiplist.clear();
}
```

10 Hash Containers

This chapter describes hash containers.

WCPtrHashDict<Key,Value>

Declared: wchash.h

The WCPtrHashDict<Key,Value> class is a templated class used to store objects in a dictionary. Dictionaries store values with an associated key, which may be of any type. One example of a dictionary used in everyday life is the phone book. The phone numbers are the data values, and the customer name is the key. An example of a specialized dictionary is a vector, where the key value is the integer index.

As an element is looked up or inserted into the dictionary, the associated key is hashed. Hashing converts the key into a numeric index value which is used to locate the value. The storage area referenced by the hash value is usually called a bucket. If more than one key results in the same hash, the values associated with the keys are placed in a list stored in the bucket. The equality operator of the key's type is used to locate the key-value pairs.

In the description of each member function, the text `Key` is used to indicate the template parameter defining the type of the indices pointed to by the pointers stored in the dictionary. The text `Value` is used to indicate the template parameter defining the type of the data pointed to by the pointers stored in the dictionary.

The constructor for the WCPtrHashDict<Key,Value> class requires a hashing function, which given a reference to `Key`, returns an `unsigned` value. The returned value modulo the number of buckets determines the bucket into which the key-value pair will be located. The return values of the hash function can be spread over the entire range of `unsigned` numbers. The hash function return value must be the same for values which are equivalent by the equivalence operator for `Key`.

Note that pointers to the key values are stored in the dictionary. Destructors are not called on the keys pointed to. The key values pointed to in the dictionary should not be changed such that the equivalence to the old value is modified.

The WCExcept class is a base class of the WCPtrHashDict<Key,Value> class and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCPtrHashDict<Key,Value> object. No exceptions are enabled unless they are set by the exceptions member function.

Requirements of Key

The WCPtrHashDict<Key,Value> class requires `Key` to have:

A well defined equivalence operator with constant parameters
`(int operator ==(const Key &) const).`

Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrHashDict( unsigned (*hash_fn)( const Key & ), unsigned =
WC_DEFAULT_HASH_SIZE );
WCPtrHashDict( unsigned (*hash_fn)( const Key & ), unsigned =
WC_DEFAULT_HASH_SIZE, void * (*user_alloc)( size_t size ), void
(*user_dealloc)( void *old, size_t size ) );
WCPtrHashDict( const WCPtrHashDict & );
virtual ~WCPtrHashDict();
static unsigned bitHash( const void *, size_t );
unsigned buckets() const;
void clear();
```

```
void clearAndDestroy();
int contains( const Key * ) const;
unsigned entries() const;
Value * find( const Key * ) const;
Value * findKeyAndValue( const Key *, Key * & ) const;
void forAll( void (*user_fn)( Key *, Value *, void * ), void * );
int insert( Key *, Value * );
int isEmpty() const;
Value * remove( const Key * );
void resize( unsigned );
```

Public Member Operators

The following member operators are declared in the public interface:

```
Value * & operator []( const Key & );
const Value * & operator []( const Key & ) const;
WCPtrHashDict & operator =( const WCPtrHashDict & );
int operator ==( const WCPtrHashDict & ) const;
```

WCPtrHashDict<Key,Value>::WCPtrHashDict()

Synopsis:

```
#include <wchash.h>
public:
    WCPtrHashDict( unsigned (*hash_fn)( const Key & ) ,
    unsigned = WC_DEFAULT_HASH_SIZE );
```

Semantics: The public `WCPtrHashDict<Key,Value>` constructor creates an `WCPtrHashDict<Key,Value>` object with no entries and with the number of buckets in the second optional parameter, which defaults to the constant `WC_DEFAULT_HASH_SIZE` (currently defined as 101). The number of buckets specified must be greater than zero, and will be forced to at least one. If the hash dictionary object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If the `out_of_memory` exception is enabled, then attempting to insert into a hash table with zero buckets will throw an `out_of_memory` error.

The hash function `hash_fn` is used to determine which bucket each key-value pair will be assigned. If no hash function exists, the static member function `bitHash` is available to help create one.

Results: The public `WCPtrHashDict<Key,Value>` constructor creates an initialized `WCPtrHashDict<Key,Value>` object with the specified number of buckets and hash function.

See Also: `~WCPtrHashDict`, `bitHash`, `WCEexcept::out_of_memory`

Synopsis:

```
#include <wchash.h>
public:
    WCPtrHashDict( unsigned (*hash_fn)( const Key & ),
    unsigned = WC_DEFAULT_HASH_SIZE,
    void * (*user_alloc)( size_t ),
    void (*user_dealloc)( void *, size_t ) );
```

Semantics: Allocator and deallocator functions are specified for use when entries are inserted and removed from the hash dictionary. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a hash dictionary. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:
`WCPtrHashDictItemSize(Key, Value)`

Results: The public `WCPtrHashDict<Key,Value>` constructor creates an initialized `WCPtrHashDict<Key,Value>` object with the specified number of buckets and hash function.

See Also: `~WCPtrHashDict`, `bitHash`, `WCEexcept::out_of_memory`

WCPtrHashDict<Key,Value>::WCPtrHashDict()

Synopsis:

```
#include <wchash.h>
public:
    WCPtrHashDict( const WCPtrHashDict & );
```

Semantics: The public `WCPtrHashDict<Key, Value>` constructor is the copy constructor for the `WCPtrHashDict<Key, Value>` class. The new dictionary is created with the same number of buckets, hash function, all values or pointers stored in the dictionary, and the exception trap states. If the hash dictionary object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If there is not enough memory to copy all of the values in the dictionary, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

Results: The public `WCPtrHashDict<Key, Value>` constructor creates an `WCPtrHashDict<Key, Value>` object which is a copy of the passed dictionary.

See Also: `~WCPtrHashDict`, `operator =`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wchash.h>
public:
    virtual ~WCPtrHashDict();
```

Semantics: The public `~WCPtrHashDict<Key,Value>` destructor is the destructor for the `WCPtrHashDict<Key,Value>` class. If the number of dictionary elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the dictionary elements are cleared using the `clear` member function. The objects which the dictionary elements point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the public `~WCPtrHashDict<Key,Value>` destructor is inserted implicitly by the compiler at the point where the `WCPtrHashDict<Key,Value>` object goes out of scope.

Results: The public `~WCPtrHashDict<Key,Value>` destructor destroys an `WCPtrHashDict<Key,Value>` object.

See Also: `clear`, `clearAndDestroy`, `WCExcept::not_empty`

WCPtrHashDict<Key,Value>::bitHash()

Synopsis:

```
#include <wchash.h>
public:
    static unsigned bitHash( void *, size_t );
```

Semantics: The `bitHash` public member function can be used to implement a hashing function for any type. A hashing value is generated from the value stored for the number of specified bytes pointed to by the first parameter.

Results: The `bitHash` public member function returns an unsigned value which can be used as the basis of a user defined hash function.

See Also: `WCPtrHashDict`

Synopsis:

```
#include <wchash.h>
public:
    unsigned buckets const;
```

Semantics: The `buckets` public member function is used to find the number of buckets contained in the `WCPtrHashDict<Key, Value>` object.

Results: The `buckets` public member function returns the number of buckets in the dictionary.

See Also: `resize`

WCPtrHashDict<Key,Value>::clear()

Synopsis:

```
#include <wchash.h>
public:
void clear();
```

Semantics: The `clear` public member function is used to clear the dictionary so that it has no entries. The number of buckets remain unaffected. Objects pointed to by the dictionary elements are not deleted. The dictionary object is not destroyed and re-created by this function, so the object destructor is not invoked.

Results: The `clear` public member function clears the dictionary to have no elements.

See Also: `~WCPtrHashDict`, `clearAndDestroy`, `operator =`

Synopsis:

```
#include <wchash.h>
public:
void clearAndDestroy();
```

Semantics: The `clearAndDestroy` public member function is used to clear the dictionary and delete the objects pointed to by the dictionary elements. The dictionary object is not destroyed and re-created by this function, so the dictionary object destructor is not invoked.

Results: The `clearAndDestroy` public member function clears the dictionary by deleting the objects pointed to by the dictionary elements.

See Also: `clear`

WCPtrHashDict<Key,Value>::contains()

Synopsis:

```
#include <wchash.h>
public:
    int contains( const Key * ) const;
```

Semantics: The `contains` public member function returns non-zero if an element with the specified key is stored in the dictionary, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the `Key` type.

Results: The `contains` public member function returns a non-zero value if the `Key` is found in the dictionary.

See Also: `find`, `findKeyAndValue`

Synopsis:

```
#include <wchash.h>
public:
    unsigned entries() const;
```

Semantics: The `entries` public member function is used to return the current number of elements stored in the dictionary.

Results: The `entries` public member function returns the number of elements in the dictionary.

See Also: `buckets`, `isEmpty`

WCPtrHashDict<Key,Value>::find()

Synopsis:

```
#include <wchash.h>
public:
    Value * find( const Key * ) const;
```

Semantics: The `find` public member function is used to find an element with an equivalent key in the dictionary. If an equivalent element is found, a pointer to the element `Value` is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

Results: The element equivalent to the passed key is located in the dictionary.

See Also: `findKeyAndValue`

Synopsis:

```
#include <wchash.h>
public:
Value * findKeyAndValue( const Key *,
Key &, Value & ) const;
```

Semantics: The `findKeyAndValue` public member function is used to find an element in the dictionary with a key equivalent to the first parameter. If an equivalent element is found, a pointer to the element `Value` is returned. The reference to a `Key` passed as the second parameter is assigned the found element's key. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

Results: The element equivalent to the passed key is located in the dictionary.

See Also: `findKeyAndValue`

WCPtrHashDict<Key,Value>::forAll()

Synopsis:

```
#include <wchash.h>
public:
void forAll(
void (*user_fn)( Key *, Value *, void * ),
void * );
```

Semantics: The `forAll` public member function causes the user supplied function to be invoked for every key-value pair in the dictionary. The user function has the prototype

```
void user_func( Key * key, Value * value, void * data );
```

As the elements are visited, the user function is invoked with the `Key` and `Value` components of the element passed as the first two parameters. The second parameter of the `forAll` function is passed as the third parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

Results: The elements in the dictionary are all visited, with the user function being invoked for each one.

See Also: `find`, `findKeyAndValue`

Synopsis:

```
#include <wchash.h>
public:
    int insert( Key *, Value * );
```

Semantics: The `insert` public member function inserts a key and value into the dictionary, using the hash function on the key to determine to which bucket it should be stored. If allocation of the node to store the key-value pair fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

At some point, the number of buckets initially selected may be too small for the number of elements inserted. The resize of the dictionary can be controlled by the insertion mechanism by using `WCPtrHashDict` as a base class, and providing an `insert` member function to do a resize when appropriate. This `insert` could then call `WCPtrHashDict::insert` to insert the element. Note that copy constructors and assignment operators are not inherited in your class, but you can provide the following inline definitions (assuming that the class inherited from `WCPtrHashDict` is named `MyHashDict`):

```
inline MyHashDict( const MyHashDict &orig ) : WCPtrHashDict( orig ) {};
inline MyHashDict &operator=( const MyHashDict &orig ) {
    return( WCPtrHashDict::operator=( orig ) );
}
```

Results: The `insert` public member function inserts a key and value into the dictionary. If the insert is successful, a non-zero will be returned. A zero will be returned if the insert fails.

See Also: `operator =`, `WCExcept::out_of_memory`

WCPtrHashDict<Key,Value>::isEmpty()

Synopsis:

```
#include <wchash.h>
public:
    int isEmpty() const;
```

Semantics: The `isEmpty` public member function is used to determine if the dictionary is empty.

Results: The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the dictionary is empty.

See Also: `buckets`, `entries`

Synopsis:

```
#include <wchash.h>
public:
Value * & operator[]( const Key & );
```

Semantics: `operator []` is the dictionary index operator. A reference to the object stored in the dictionary with the given `Key` is returned. If no equivalent element is found, then a new key-value pair is created with the specified `Key` value, and initialized with the default constructor. The returned reference can then be assigned to, so that insertions can be made with the operator. If an allocation error occurs while inserting a new key-value pair, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

Results: The `operator []` public member function returns a reference to the element at the given key value. If the key does not exist, a reference to a created element is returned. The result of the operator may be assigned to.

See Also: `WCExcept::out_of_memory`

WCPtrHashDict<Key,Value>::operator []()

Synopsis:

```
#include <wchash.h>
public:
    Value * const & operator[]( const Key * ) const;
```

Semantics: `operator []` is the dictionary index operator. A constant reference to the object stored in the dictionary with the given `Key` is returned. If no equivalent element is found, then the `index_range` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

Results: The `operator []` public member function returns a constant reference to the element at the given key value. The result of the operator may not be assigned to.

See Also: `WCExcept::index_range`

Synopsis:

```
#include <wchash.h>
public:
    WCPtrHashDict & operator =( const WCPtrHashDict & );
```

Semantics: The `operator =` public member function is the assignment operator for the `WCPtrHashDict<Key,Value>` class. The left hand side dictionary is first cleared using the `clear` member function, and then the right hand side dictionary is copied. The hash function, exception trap states, and all of the dictionary elements are copied. If an allocation failure occurs when creating the buckets, the table will be created with zero buckets, and the `out_of_memory` exception is thrown if it is enabled. If there is not enough memory to copy all of the values or pointers in the dictionary, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

Results: The `operator =` public member function assigns the left hand side dictionary to be a copy of the right hand side.

See Also: `clear`, `WCExcept::out_of_memory`

WCPtrHashDict<Key,Value>::operator ==()

- Synopsis:**
- ```
#include <wchash.h>
public:
 int operator ==(const WCPtrHashDict &) const;
```
- Semantics:** The operator == public member function is the equivalence operator for the WCPtrHashDict<Key, Value> class. Two dictionary objects are equivalent if they are the same object and share the same address.
- Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side dictionary are the same object. A FALSE (zero) value is returned otherwise.

**Synopsis:**

```
#include <wchash.h>
public:
Value * remove(const Key *);
```

**Semantics:** The `remove` public member function is used to remove the specified element from the dictionary. If an equivalent element is found, the pointer value is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The element is removed from the dictionary if it found.

## *WCPtrHashDict<Key,Value>::resize()*

---

**Synopsis:**

```
#include <wchash.h>
public:
void resize(unsigned);
```

**Semantics:** The `resize` public member function is used to change the number of buckets contained in the dictionary. If the new number is larger than the previous dictionary size, then the hash function will be used on all of the stored elements to determine which bucket they should be stored into. Entries are not destroyed or created in the process of being moved. If there is not enough memory to resize the dictionary, the `out_of_memory` exception is thrown if it is enabled, and the dictionary will contain the number of buckets it contained before the resize. If the new number is zero, then the `zero_buckets` exception is thrown if it is enabled, and no resize will be performed. The dictionary is guaranteed to contain the same number of entries after the resize.

**Results:** The dictionary is resized to the new number of buckets.

**See Also:** `WCExcept::out_of_memory`, `WCExcept::zero_buckets`

**Declared:** wchash.h

WCPtrHashTable<Type> and WCPtrHashSet<Type> classes are templated classes used to store objects in a hash. A hash saves objects in such a way as to make it efficient to locate and retrieve an element. As an element is looked up or inserted into the hash, the value of the element is hashed. Hashing results in a numeric index which is used to locate the value. The storage area referenced by the hash value is usually called a bucket. If more than one element results in the same hash, the value associated with the hash is placed in a list stored in the bucket. A hash table allows more than one copy of an element that is equivalent, while the hash set allows only one copy. The equality operator of the element's type is used to locate the value.

In the description of each member function, the text Type is used to indicate the template parameter defining the type of the data pointed to by the pointers stored in the hash.

The constructor for the WCPtrHashTable<Type> and WCPtrHashSet<Type> classes requires a hashing function, which given a reference to Type, returns an unsigned value. The returned value modulo the number of buckets determines the bucket into which the element will be located. The return values of the hash function can be spread over the entire range of unsigned numbers. The hash function return value must be the same for values which are equivalent by the equivalence operator for Type.

Note that pointers to the elements are stored in the hash. Destructors are not called on the elements pointed to. The data values pointed to in the hash should not be changed such that the equivalence to the old value is modified.

The WCExcept class is a base class of the WCPtrHashTable<Type> and WCPtrHashSet<Type> classes and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCPtrHashTable<Type> and WCPtrHashSet<Type> objects. No exceptions are enabled unless they are set by the exceptions member function.

### Requirements of Type

The WCPtrHashTable<Type> and WCPtrHashSet<Type> classes requires Type to have:

A well defined equivalence operator with constant parameters  
( int operator ==( const Type & ) const ).

### Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrHashSet(unsigned (*hash_fn)(const Type &), unsigned =
WC_DEFAULT_HASH_SIZE);
WCPtrHashSet(unsigned (*hash_fn)(const Type &), unsigned =
WC_DEFAULT_HASH_SIZE, void * (*user_alloc)(size_t size), void
(*user_dealloc)(void *old, size_t size));
WCPtrHashSet(const WCPtrHashSet &);
virtual ~WCPtrHashSet();
WCPtrHashTable(unsigned (*hash_fn)(const Type &), unsigned =
WC_DEFAULT_HASH_SIZE);
WCPtrHashTable(unsigned (*hash_fn)(const Type &), unsigned =
WC_DEFAULT_HASH_SIZE, void * (*user_alloc)(size_t size), void
(*user_dealloc)(void *old, size_t size));
WCPtrHashTable(const WCPtrHashTable &);
virtual ~WCPtrHashTable();
```

## *WCPtrHashTable<Type>, WCPtrHashSet<Type>*

---

```
static unsigned bitHash(const void * , size_t);
unsigned buckets() const;
void clear();
void clearAndDestroy();
int contains(const Type *) const;
unsigned entries() const;
Type * find(const Type *) const;
void forAll(void (*user_fn)(Type * , void *) , void *);
int insert(Type *);
int isEmpty() const;
Type * remove(const Type *);
void resize(unsigned);
```

The following public member functions are available for the `WCPtrHashTable` class only:

```
unsigned occurrencesOf(const Type *) const;
unsigned removeAll(const Type *);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
WCPtrHashSet & operator =(const WCPtrHashSet &);
int operator ==(const WCPtrHashSet &) const;
WCPtrHashTable & operator =(const WCPtrHashTable &);
int operator ==(const WCPtrHashTable &) const;
```

**Synopsis:**

```
#include <wchash.h>
public:
WCPtrHashSet(unsigned (*hash_fn)(const Type &) ,
unsigned = WC_DEFAULT_HASH_SIZE);
```

**Semantics:** The `WCPtrHashSet<Type>` constructor creates a `WCPtrHashSet` object with no entries and with the number of buckets in the second optional parameter, which defaults to the constant `WC_DEFAULT_HASH_SIZE` (currently defined as 101). The number of buckets specified must be greater than zero, and will be forced to at least one. If the hash object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If the `out_of_memory` exception is enabled, then attempting to insert into a hash table with zero buckets will throw an `out_of_memory` error.

The hash function `hash_fn` is used to determine which bucket each value will be assigned to. If no hash function exists, the static member function `bitHash` is available to help create one.

**Results:** The `WCPtrHashSet<Type>` constructor creates an initialized `WCPtrHashSet` object with the specified number of buckets and hash function.

**See Also:** `~WCPtrHashSet`, `bitHash`, `WCExcept::out_of_memory`

## **WCPtrHashSet<Type>::WCPtrHashSet()**

---

**Synopsis:**

```
#include <wchash.h>
public:
 WCPtrHashSet(unsigned (*hash_fn)(const Type &),
 unsigned = WC_DEFAULT_HASH_SIZE,
 void * (*user_alloc)(size_t),
 void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the hash. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a hash. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
WCPtrHashSetItemSize( Type )

**Results:** The WCPtrHashSet<Type> constructor creates an initialized WCPtrHashSet object with the specified number of buckets and hash function.

**See Also:** ~WCPtrHashSet, bitHash, WCExcept::out\_of\_memory

**Synopsis:**

```
#include <wchash.h>
public:
WCPtrHashSet(const WCPtrHashSet &);
```

**Semantics:** The `WCPtrHashSet<Type>` is the copy constructor for the `WCPtrHashSet` class. The new hash is created with the same number of buckets, hash function, all values or pointers stored in the hash, and the exception trap states. If the hash object can be created, but an allocation failure occurs when creating the buckets, the hash will be created with zero buckets. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The `WCPtrHashSet<Type>` constructor creates a `WCPtrHashSet` object which is a copy of the passed hash.

**See Also:** `~WCPtrHashSet`, `operator =`, `WCExcept::out_of_memory`

## *WCPtrHashSet<Type>::~WCPtrHashSet()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 virtual ~WCPtrHashSet();
```

**Semantics:** The `WCPtrHashSet<Type>` destructor is the destructor for the `WCPtrHashSet` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the hash elements are cleared using the `clear` member function. The objects which the hash elements point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the `WCPtrHashSet<Type>` destructor is inserted implicitly by the compiler at the point where the `WCPtrHashSet` object goes out of scope.

**Results:** The call to the `WCPtrHashSet<Type>` destructor destroys a `WCPtrHashSet` object.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::not_empty`

**Synopsis:**

```
#include <wchash.h>
public:
WCPtrHashTable(unsigned (*hash_fn)(const Type &),
unsigned = WC_DEFAULT_HASH_SIZE);
```

**Semantics:** The `WCPtrHashTable<Type>` constructor creates a `WCPtrHashTable` object with no entries and with the number of buckets in the second optional parameter, which defaults to the constant `WC_DEFAULT_HASH_SIZE` (currently defined as 101). The number of buckets specified must be greater than zero, and will be forced to at least one. If the hash object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If the `out_of_memory` exception is enabled, then attempting to insert into a hash table with zero buckets will throw an `out_of_memory` error.

The hash function `hash_fn` is used to determine which bucket each value will be assigned to. If no hash function exists, the static member function `bitHash` is available to help create one.

**Results:** The `WCPtrHashTable<Type>` constructor creates an initialized `WCPtrHashTable` object with the specified number of buckets and hash function.

**See Also:** `~WCPtrHashTable`, `bitHash`, `WCEexcept::out_of_memory`

## *WCPtrHashTable<Type>::WCPtrHashTable()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 WCPtrHashTable(unsigned (*hash_fn)(const Type &),
 unsigned = WC_DEFAULT_HASH_SIZE,
 void * (*user_alloc)(size_t),
 void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the hash. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a hash. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
`WCPtrHashTableItemSize( Type )`

**Results:** The `WCPtrHashTable<Type>` constructor creates an initialized `WCPtrHashTable` object with the specified number of buckets and hash function.

**See Also:** `~WCPtrHashTable`, `bitHash`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wchash.h>
public:
WCPtrHashTable(const WCPtrHashTable &);
```

**Semantics:** The `WCPtrHashTable<Type>` is the copy constructor for the `WCPtrHashTable` class. The new hash is created with the same number of buckets, hash function, all values or pointers stored in the hash, and the exception trap states. If the hash object can be created, but an allocation failure occurs when creating the buckets, the hash will be created with zero buckets. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The `WCPtrHashTable<Type>` constructor creates a `WCPtrHashTable` object which is a copy of the passed hash.

**See Also:** `~WCPtrHashTable`, `operator =`, `WCExcept::out_of_memory`

## *WCPtrHashTable<Type>::~WCPtrHashTable()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 virtual ~WCPtrHashTable();
```

**Semantics:** The `WCPtrHashTable<Type>` destructor is the destructor for the `WCPtrHashTable` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the hash elements are cleared using the `clear` member function. The objects which the hash elements point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the `WCPtrHashTable<Type>` destructor is inserted implicitly by the compiler at the point where the `WCPtrHashTable` object goes out of scope.

**Results:** The call to the `WCPtrHashTable<Type>` destructor destroys a `WCPtrHashTable` object.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::not_empty`

**Synopsis:**

```
#include <wchash.h>
public:
 static unsigned bitHash(void *, size_t);
```

**Semantics:** The `bitHash` public member function can be used to implement a hashing function for any type. A hashing value is generated from the value stored for the number of specified bytes pointed to by the first parameter.

**Results:** The `bitHash` public member function returns an unsigned value which can be used as the basis of a user defined hash function.

**See Also:** `WCPtrHashSet`, `WCPtrHashTable`

## *WCPtrHashTable<Type>::buckets(), WCPtrHashSet<Type>::buckets()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 unsigned buckets() const;
```

**Semantics:** The `buckets` public member function is used to find the number of buckets contained in the hash object.

**Results:** The `buckets` public member function returns the number of buckets in the hash.

**See Also:** `resize`

**Synopsis:**

```
#include <wchash.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the hash so that it has no entries. The number of buckets remain unaffected. Objects pointed to by the hash elements are not deleted. The hash object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the hash to have no elements.

**See Also:** `~WCPtrHashSet`, `~WCPtrHashTable`, `clearAndDestroy`, `operator =`

## *WCPtrHashTable<Type>, WCPtrHashSet<Type>::clearAndDestroy()*

---

**Synopsis:**

```
#include <wchash.h>
public:
void clearAndDestroy();
```

**Semantics:** The `clearAndDestroy` public member function is used to clear the hash and delete the objects pointed to by the hash elements. The hash object is not destroyed and re-created by this function, so the hash object destructor is not invoked.

**Results:** The `clearAndDestroy` public member function clears the hash by deleting the objects pointed to by the hash elements.

**See Also:** `clear`

**Synopsis:**

```
#include <wchash.h>
public:
 int contains(const Type *) const;
```

**Semantics:** The `contains` public member function returns non-zero if the element is stored in the hash, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The `contains` public member function returns a non-zero value if the element is found in the hash.

**See Also:** `find`

## *WCPtrHashTable<Type>::entries(), WCPtrHashSet<Type>::entries()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 unsigned entries() const;
```

**Semantics:** The `entries` public member function is used to return the current number of elements stored in the hash.

**Results:** The `entries` public member function returns the number of elements in the hash.

**See Also:** `buckets`, `isEmpty`

**Synopsis:**

```
#include <wchash.h>
public:
 Type * find(const Type *) const;
```

**Semantics:** The `find` public member function is used to find an element with an equivalent key in the hash. If an equivalent element is found, a pointer to the element is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The element equivalent to the passed key is located in the hash.

## *WCPtrHashTable<Type>::forAll(), WCPtrHashSet<Type>::forAll()*

---

**Synopsis:**

```
#include <wchash.h>
public:
void forAll(
void (*user_fn)(Type *, void *),
void *);
```

**Semantics:** The `forAll` public member function causes the user supplied function to be invoked for every value in the hash. The user function has the prototype

```
void user_func(Type * value, void * data);
```

As the elements are visited, the user function is invoked with the element passed as the first. The second parameter of the `forAll` function is passed as the second parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

**Results:** The elements in the hash are all visited, with the user function being invoked for each one.

**See Also:** `find`

**Synopsis:**

```
#include <wchash.h>
public:
 int insert(Type *);
```

**Semantics:** The `insert` public member function inserts a value into the hash, using the `hash` function to determine to which bucket it should be stored. If allocation of the node to store the value fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

With a `WCPtrHashSet`, there must be only one equivalent element in the set. If an element equivalent to the inserted element is already in the hash set, the hash set will remain unchanged, and the `not_unique` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

At some point, the number of buckets initially selected may be too small for the number of elements inserted. The `resize` of the hash can be controlled by the insertion mechanism by using `WCPtrHashSet` (or `WCPtrHashTable`) as a base class, and providing an `insert` member function to do a `resize` when appropriate. This `insert` could then call `WCPtrHashSet::insert` (or `WCPtrHashTable::insert`) to insert the element. Note that copy constructors and assignment operators are not inherited in your class, but you can provide the following inline definitions (assuming that the class inherited from `WCPtrHashTable` is named `MyHashTable`):

```
inline MyHashTable(const MyHashTable &orig)
 : WCPtrHashTable(orig) {};
inline MyHashTable &operator=(const MyHashTable &orig) {
 return(WCPtrHashTable::operator=(orig));
}
```

**Results:** The `insert` public member function inserts a value into the hash. If the insert is successful, a non-zero will be returned. A zero will be returned if the insert fails.

**See Also:** `operator =`, `WCExcept::out_of_memory`

## *WCPtrHashTable<Type>::isEmpty(), WCPtrHashSet<Type>::isEmpty()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if the hash is empty.

**Results:** The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the hash is empty.

**See Also:** `buckets`, `entries`

**Synopsis:**

```
#include <wchash.h>
public:
 unsigned occurrencesOf(const Type *) const;
```

**Semantics:** The `occurrencesOf` public member function is used to return the current number of elements stored in the hash which are equivalent to the passed value. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The `occurrencesOf` public member function returns the number of elements in the hash.

**See Also:** `buckets`, `entries`, `find`, `isEmpty`

**Synopsis:**

```
#include <wchash.h>
public:
 WCPtrHashSet & operator =(const WCPtrHashSet &);
 WCPtrHashTable & operator =(const WCPtrHashTable &);
```

**Semantics:** The `operator =` public member function is the assignment operator for the `WCPtrHashTable<Type>` and `WCPtrHashSet<Type>` classes. The left hand side hash is first cleared using the `clear` member function, and then the right hand side hash is copied. The hash function, exception trap states, and all of the hash elements are copied. If an allocation failure occurs when creating the buckets, the table will be created with zero buckets, and the `out_of_memory` exception is thrown if it is enabled. If there is not enough memory to copy all of the values or pointers in the hash, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

**Results:** The `operator =` public member function assigns the left hand side hash to be a copy of the right hand side.

**See Also:** `clear`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wchash.h>
public:
 int operator ==(const WCPtrHashSet &) const;
 int operator ==(const WCPtrHashTable &) const;
```

**Semantics:** The `operator ==` public member function is the equivalence operator for the `WCPtrHashTable<Type>` and `WCPtrHashSet<Type>` classes. Two hash objects are equivalent if they are the same object and share the same address.

**Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side hash are the same object. A FALSE (zero) value is returned otherwise.

## *WCPtrHashTable<Type>::remove(), WCPtrHashSet<Type>::remove()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 Type * remove(const Type *);
```

**Semantics:** The `remove` public member function is used to remove the specified element from the hash. If an equivalent element is found, the pointer value is returned. Zero is returned if the element is not found. If the hash is a table and there is more than one element equivalent to the specified element, then the first equivalent element added to the table is removed. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The element is removed from the hash if it found.

**Synopsis:**

```
#include <wchash.h>
public:
 unsigned removeAll(const Type *);
```

**Semantics:** The `removeAll` public member function is used to remove all elements equivalent to the specified element from the hash. Zero is returned if no equivalent elements are found. Note that equivalence is based on the equivalence operator of the element type.

**Results:** All equivalent elements are removed from the hash.

## *WCPtrHashTable<Type>::resize(), WCPtrHashSet<Type>::resize()*

---

**Synopsis:**

```
#include <wchash.h>
public:
void resize(unsigned);
```

**Semantics:** The `resize` public member function is used to change the number of buckets contained in the hash. If the new number is larger than the previous hash size, then the hash function will be used on all of the stored elements to determine which bucket they should be stored into. Entries are not destroyed or created in the process of being moved. If there is not enough memory to resize the hash, the `out_of_memory` exception is thrown if it is enabled, and the hash will contain the number of buckets it contained before the resize. If the new number is zero, then the `zero_buckets` exception is thrown if it is enabled, and no resize will be performed. The hash is guaranteed to contain the same number of entries after the resize.

**Results:** The hash is resized to the new number of buckets.

**See Also:** `WCExcept::out_of_memory`, `WCExcept::zero_buckets`

**Declared:** wchash.h

The WCValHashDict<Key,Value> class is a templated class used to store objects in a dictionary. Dictionaries store values with an associated key, which may be of any type. One example of a dictionary used in everyday life is the phone book. The phone numbers are the data values, and the customer name is the key. An example of a specialized dictionary is a vector, where the key value is the integer index.

As an element is looked up or inserted into the dictionary, the associated key is hashed. Hashing converts the key into a numeric index value which is used to locate the value. The storage area referenced by the hash value is usually called a bucket. If more than one key results in the same hash, the values associated with the keys are placed in a list stored in the bucket. The equality operator of the key's type is used to locate the key-value pairs.

In the description of each member function, the text `Key` is used to indicate the template parameter defining the type of the indices used to store data in the dictionary. The text `Value` is used to indicate the template parameter defining the type of the data stored in the dictionary.

The constructor for the WCValHashDict<Key,Value> class requires a hashing function, which given a reference to `Key`, returns an `unsigned` value. The returned value modulo the number of buckets determines the bucket into which the key-value pair will be located. The return values of the hash function can be spread over the entire range of `unsigned` numbers. The hash function return value must be the same for values which are equivalent by the equivalence operator for `Key`.

Values are copied into the dictionary, which could be undesirable if the stored objects are complicated and copying is expensive. Value dictionaries should not be used to store objects of a base class if any derived types of different sizes would be stored in the dictionary, or if the destructor for a derived class must be called.

The WCExcept class is a base class of the WCValHashDict<Key,Value> class and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCValHashDict<Key,Value> object. No exceptions are enabled unless they are set by the exceptions member function.

### Requirements of Key and Value

The WCValHashDict<Key,Value> class requires `Key` to have:

A default constructor (`Key::Key()`).

A well defined copy constructor (`Key::Key( const Key & )`).

A well defined assignment operator (`Key & operator =( const Key & )`).

A well defined equivalence operator with constant parameters  
(`int operator ==( const Key & ) const`).

The WCValHashDict<Key,Value> class requires `Value` to have:

A default constructor (`Value::Value()`).

A well defined copy constructor (`Value::Value( const Value & )`).

A well defined assignment operator (`Value & operator =( const Value & )`).

### **Public Member Functions**

The following member functions are declared in the public interface:

```
WCValHashDict(unsigned (*hash_fn)(const Key &), unsigned =
WC_DEFAULT_HASH_SIZE);
WCValHashDict(unsigned (*hash_fn)(const Key &), unsigned =
WC_DEFAULT_HASH_SIZE, void * (*user_alloc)(size_t size), void
(*user_dealloc)(void *old, size_t size));
WCValHashDict(const WCValHashDict &);
virtual ~WCValHashDict();
static unsigned bitHash(const void *, size_t);
unsigned buckets() const;
void clear();
int contains(const Key &) const;
unsigned entries() const;
int find(const Key &, Value &) const;
int findKeyAndValue(const Key &, Key &, Value &) const;
void forAll(void (*user_fn)(Key, Value, void *), void *);
int insert(const Key &, const Value &);
int isEmpty() const;
int remove(const Key &);
void resize(unsigned);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
Value & operator [](const Key &);
const Value & operator [](const Key &) const;
WCValHashDict & operator =(const WCValHashDict &);
int operator ==(const WCValHashDict &) const;
```

**Synopsis:**

```
#include <wchash.h>
public:
WCValHashDict(unsigned (*hash_fn)(const Key &) ,
unsigned = WC_DEFAULT_HASH_SIZE);
```

**Semantics:** The public `WCValHashDict<Key, Value>` constructor creates an `WCValHashDict<Key, Value>` object with no entries and with the number of buckets in the second optional parameter, which defaults to the constant `WC_DEFAULT_HASH_SIZE` (currently defined as 101). The number of buckets specified must be greater than zero, and will be forced to at least one. If the hash dictionary object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If the `out_of_memory` exception is enabled, then attempting to insert into a hash table with zero buckets will throw an `out_of_memory` error.

The hash function `hash_fn` is used to determine which bucket each key-value pair will be assigned. If no hash function exists, the static member function `bitHash` is available to help create one.

**Results:** The public `WCValHashDict<Key, Value>` constructor creates an initialized `WCValHashDict<Key, Value>` object with the specified number of buckets and hash function.

**See Also:** `~WCValHashDict`, `bitHash`, `WCEexcept::out_of_memory`

## *WCValHashDict<Key,Value>::WCValHashDict()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 WCValHashDict(unsigned (*hash_fn)(const Key &),
 unsigned = WC_DEFAULT_HASH_SIZE,
 void * (*user_alloc)(size_t),
 void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the hash dictionary. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a hash dictionary. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
WCValHashDictItemSize( Key, Value )

**Results:** The public WCValHashDict<Key,Value> constructor creates an initialized WCValHashDict<Key,Value> object with the specified number of buckets and hash function.

**See Also:** ~WCValHashDict, bitHash, WCEexcept::out\_of\_memory

**Synopsis:**

```
#include <wchash.h>
public:
WCValHashDict(const WCValHashDict &);
```

**Semantics:** The public `WCValHashDict<Key, Value>` constructor is the copy constructor for the `WCValHashDict<Key, Value>` class. The new dictionary is created with the same number of buckets, hash function, all values or pointers stored in the dictionary, and the exception trap states. If the hash dictionary object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If there is not enough memory to copy all of the values in the dictionary, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The public `WCValHashDict<Key, Value>` constructor creates an `WCValHashDict<Key, Value>` object which is a copy of the passed dictionary.

**See Also:** `~WCValHashDict`, `operator =`, `WCExcept::out_of_memory`

## *WCValHashDict<Key,Value>::~WCValHashDict()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 virtual ~WCValHashDict();
```

**Semantics:** The public `~WCValHashDict<Key,Value>` destructor is the destructor for the `WCValHashDict<Key,Value>` class. If the number of dictionary elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the dictionary elements are cleared using the `clear` member function. The call to the public `~WCValHashDict<Key,Value>` destructor is inserted implicitly by the compiler at the point where the `WCValHashDict<Key,Value>` object goes out of scope.

**Results:** The public `~WCValHashDict<Key,Value>` destructor destroys an `WCValHashDict<Key,Value>` object.

**See Also:** `clear`, `WCExcept::not_empty`

**Synopsis:**

```
#include <wchash.h>
public:
 static unsigned bitHash(void *, size_t);
```

**Semantics:** The `bitHash` public member function can be used to implement a hashing function for any type. A hashing value is generated from the value stored for the number of specified bytes pointed to by the first parameter. For example:

```
unsigned my_hash_fn(const int & key) {
 return(WCValHashDict<int,String>::bitHash(&key, sizeof(int)));
}
WCValHashDict<int,String> data_object(&my_hash_fn);
```

**Results:** The `bitHash` public member function returns an unsigned value which can be used as the basis of a user defined hash function.

**See Also:** `WCValHashDict`

## *WCValHashDict<Key,Value>::buckets()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 unsigned buckets const;
```

**Semantics:** The *buckets* public member function is used to find the number of buckets contained in the *WCValHashDict<Key, Value>* object.

**Results:** The *buckets* public member function returns the number of buckets in the dictionary.

**See Also:** `resize`

**Synopsis:**

```
#include <wchash.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the dictionary so that it has no entries. The number of buckets remain unaffected. Elements stored in the dictionary are destroyed using the destructors of `Key` and of `Value`. The dictionary object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the dictionary to have no elements.

**See Also:** `~WCValHashDict`, `operator =`

## *WCValHashDict<Key,Value>::contains()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 int contains(const Key &) const;
```

**Semantics:** The `contains` public member function returns non-zero if an element with the specified key is stored in the dictionary, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The `contains` public member function returns a non-zero value if the `Key` is found in the dictionary.

**See Also:** `find`, `findKeyAndValue`

**Synopsis:**

```
#include <wchash.h>
public:
 unsigned entries() const;
```

**Semantics:** The `entries` public member function is used to return the current number of elements stored in the dictionary.

**Results:** The `entries` public member function returns the number of elements in the dictionary.

**See Also:** `buckets`, `isEmpty`

## *WCValHashDict<Key,Value>::find()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 int find(const Key &, Value &) const;
```

**Semantics:** The `find` public member function is used to find an element with an equivalent key in the dictionary. If an equivalent element is found, a non-zero value is returned. The reference to a `Value` passed as the second argument is assigned the found element's `Value`. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The element equivalent to the passed key is located in the dictionary.

**See Also:** `findKeyAndValue`

**Synopsis:**

```
#include <wchash.h>
public:
 int findKeyAndValue(const Key &, Key &, Value &) const;
```

**Semantics:** The `findKeyAndValue` public member function is used to find an element in the dictionary with a key equivalent to the first parameter. If an equivalent element is found, a non-zero value is returned. The reference to a `Key` passed as the second parameter is assigned the found element's `key`. The reference to a `Value` passed as the third argument is assigned the found element's `Value`. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The element equivalent to the passed key is located in the dictionary.

**See Also:** `findKeyAndValue`

## *WCValHashDict<Key,Value>::forAll()*

---

**Synopsis:**

```
#include <wchash.h>
public:
void forAll(
void (*user_fn)(Key, Value, void *),
void *);
```

**Semantics:** The `forAll` public member function causes the user supplied function to be invoked for every key-value pair in the dictionary. The user function has the prototype

```
void user_func(Key key, Value value, void * data);
```

As the elements are visited, the user function is invoked with the `Key` and `Value` components of the element passed as the first two parameters. The second parameter of the `forAll` function is passed as the third parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

**Results:** The elements in the dictionary are all visited, with the user function being invoked for each one.

**See Also:** `find`, `findKeyAndValue`

**Synopsis:**

```
#include <wchash.h>
public:
 int insert(const Key &, const Value &);
```

**Semantics:** The `insert` public member function inserts a key and value into the dictionary, using the hash function on the key to determine to which bucket it should be stored. If allocation of the node to store the key-value pair fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

At some point, the number of buckets initially selected may be too small for the number of elements inserted. The resize of the dictionary can be controlled by the insertion mechanism by using `WCValHashDict` as a base class, and providing an `insert` member function to do a resize when appropriate. This `insert` could then call `WCValHashDict::insert` to insert the element. Note that copy constructors and assignment operators are not inherited in your class, but you can provide the following inline definitions (assuming that the class inherited from `WCValHashDict` is named `MyHashDict`):

```
inline MyHashDict(const MyHashDict &orig) : WCValHashDict(orig) {};
inline MyHashDict &operator=(const MyHashDict &orig) {
 return(WCValHashDict::operator=(orig));
}
```

**Results:** The `insert` public member function inserts a key and value into the dictionary. If the insert is successful, a non-zero will be returned. A zero will be returned if the insert fails.

**See Also:** `operator =, WCExcept::out_of_memory`

## *WCValHashDict<Key,Value>::isEmpty()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if the dictionary is empty.

**Results:** The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the dictionary is empty.

**See Also:** `buckets`, `entries`

**Synopsis:**

```
#include <wchash.h>
public:
 Value & operator[](const Key &);
```

**Semantics:** operator [] is the dictionary index operator. A reference to the object stored in the dictionary with the given Key is returned. If no equivalent element is found, then a new key-value pair is created with the specified Key value, and initialized with the default constructor. The returned reference can then be assigned to, so that insertions can be made with the operator.

```
WCValHashDict<int, String> data_object(&my_hash_fn);
data_object[5] = "Hello";
```

If an allocation error occurs while inserting a new key-value pair, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

**Results:** The operator [] public member function returns a reference to the element at the given key value. If the key does not exist, a reference to a created element is returned. The result of the operator may be assigned to.

**See Also:** `WCExcept::out_of_memory`

## *WCValHashDict<Key,Value>::operator []()*

---

**Synopsis:**

```
#include <wchash.h>
public:
 const Value & operator[](const Key &) const;
```

**Semantics:** operator [] is the dictionary index operator. A constant reference to the object stored in the dictionary with the given Key is returned. If no equivalent element is found, then the `index_range` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

**Results:** The operator [] public member function returns a constant reference to the element at the given key value. The result of the operator may not be assigned to.

**See Also:** `WCExcept::index_range`

**Synopsis:**

```
#include <wchash.h>
public:
 WCValHashDict & operator =(const WCValHashDict &);
```

**Semantics:** The `operator =` public member function is the assignment operator for the `WCValHashDict<Key,Value>` class. The left hand side dictionary is first cleared using the `clear` member function, and then the right hand side dictionary is copied. The hash function, exception trap states, and all of the dictionary elements are copied. If an allocation failure occurs when creating the buckets, the table will be created with zero buckets, and the `out_of_memory` exception is thrown if it is enabled. If there is not enough memory to copy all of the values or pointers in the dictionary, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

**Results:** The `operator =` public member function assigns the left hand side dictionary to be a copy of the right hand side.

**See Also:** `clear`, `WCExcept::out_of_memory`

## *WCValHashDict<Key,Value>::operator ==()*

---

- Synopsis:**
- ```
#include <wchash.h>
public:
    int operator ==( const WCValHashDict & ) const;
```
- Semantics:** The operator == public member function is the equivalence operator for the WCValHashDict<Key, Value> class. Two dictionary objects are equivalent if they are the same object and share the same address.
- Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side dictionary are the same object. A FALSE (zero) value is returned otherwise.

Synopsis:

```
#include <wchash.h>
public:
    int remove( const Key & );
```

Semantics: The `remove` public member function is used to remove the specified element from the dictionary. If an equivalent element is found, a non-zero value is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

Results: The element is removed from the dictionary if it found.

WCValHashDict<Key,Value>::resize()

Synopsis:

```
#include <wchash.h>
public:
void resize( unsigned );
```

Semantics: The `resize` public member function is used to change the number of buckets contained in the dictionary. If the new number is larger than the previous dictionary size, then the hash function will be used on all of the stored elements to determine which bucket they should be stored into. Entries are not destroyed or created in the process of being moved. If there is not enough memory to resize the dictionary, the `out_of_memory` exception is thrown if it is enabled, and the dictionary will contain the number of buckets it contained before the resize. If the new number is zero, then the `zero_buckets` exception is thrown if it is enabled, and no resize will be performed. The dictionary is guaranteed to contain the same number of entries after the resize.

Results: The dictionary is resized to the new number of buckets.

See Also: `WCExcept::out_of_memory`, `WCExcept::zero_buckets`

Declared: wchash.h

WCValHashTable<Type> and WCValHashSet<Type> classes are templated classes used to store objects in a hash. A hash saves objects in such a way as to make it efficient to locate and retrieve an element. As an element is looked up or inserted into the hash, the value of the element is hashed. Hashing results in a numeric index which is used to locate the value. The storage area referenced by the hash value is usually called a bucket. If more than one element results in the same hash, the value associated with the hash is placed in a list stored in the bucket. A hash table allows more than one copy of an element that is equivalent, while the hash set allows only one copy. The equality operator of the element's type is used to locate the value.

In the description of each member function, the text Type is used to indicate the template parameter defining the type of the data to be stored in the hash.

The constructor for the WCValHashTable<Type> and WCValHashSet<Type> classes requires a hashing function, which given a reference to Type, returns an unsigned value. The returned value modulo the number of buckets determines the bucket into which the element will be located. The return values of the hash function can be spread over the entire range of unsigned numbers. The hash function return value must be the same for values which are equivalent by the equivalence operator for Type.

Values are copied into the hash, which could be undesirable if the stored objects are complicated and copying is expensive. Value hashes should not be used to store objects of a base class if any derived types of different sizes would be stored in the hash, or if the destructor for a derived class must be called.

The WCExcept class is a base class of the WCValHashTable<Type> and WCValHashSet<Type> classes and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCValHashTable<Type> and WCValHashSet<Type> objects. No exceptions are enabled unless they are set by the exceptions member function.

Requirements of Type

The WCValHashTable<Type> and WCValHashSet<Type> classes require Type to have:

A default constructor (Type::Type ()).

A well defined copy constructor (Type::Type(const Type &)).

A well defined assignment operator (Type & operator =(const Type &)).

A well defined equivalence operator with constant parameters
(int operator ==(const Type &) const).

Public Member Functions

The following member functions are declared in the public interface:

```
WCValHashSet( unsigned (*hash_fn)( const Type & ), unsigned =
WC_DEFAULT_HASH_SIZE );
WCValHashSet( unsigned (*hash_fn)( const Type & ), unsigned =
WC_DEFAULT_HASH_SIZE, void * (*user_alloc)( size_t size ), void
(*user_dealloc)( void *old, size_t size ) );
WCValHashSet( const WCValHashSet & );
virtual ~WCValHashSet();
```

```
WCValHashTable( unsigned (*hash_fn)( const Type & ), unsigned =
WC_DEFAULT_HASH_SIZE );
WCValHashTable( unsigned (*hash_fn)( const Type & ), unsigned =
WC_DEFAULT_HASH_SIZE, void * (*user_alloc)( size_t size ), void
(*user_dealloc)( void *old, size_t size ) );
WCValHashTable( const WCValHashTable & );
virtual ~WCValHashTable();
static unsigned bitHash( const void *, size_t );
unsigned buckets() const;
void clear();
int contains( const Type & ) const;
unsigned entries() const;
int find( const Type &, Type & ) const;
void forAll( void (*user_fn)( Type, void * ), void * );
int insert( const Type & );
int isEmpty() const;
int remove( const Type & );
void resize( unsigned );
```

The following public member functions are available for the WCValHashTable class only:

```
unsigned occurrencesOf( const Type & ) const;
unsigned removeAll( const Type & );
```

Public Member Operators

The following member operators are declared in the public interface:

```
WCValHashSet & operator =( const WCValHashSet & );
int operator ==( const WCValHashSet & ) const;
WCValHashTable & operator =( const WCValHashTable & );
int operator ==( const WCValHashTable & ) const;
```

Synopsis:

```
#include <wchash.h>
public:
WCValHashSet( unsigned (*hash_fn)( const Type & ) ,
unsigned = WC_DEFAULT_HASH_SIZE );
```

Semantics: The `WCValHashSet<Type>` constructor creates a `WCValHashSet` object with no entries and with the number of buckets in the second optional parameter, which defaults to the constant `WC_DEFAULT_HASH_SIZE` (currently defined as 101). The number of buckets specified must be greater than zero, and will be forced to at least one. If the hash object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If the `out_of_memory` exception is enabled, then attempting to insert into a hash table with zero buckets will throw an `out_of_memory` error.

The hash function `hash_fn` is used to determine which bucket each value will be assigned to. If no hash function exists, the static member function `bitHash` is available to help create one.

Results: The `WCValHashSet<Type>` constructor creates an initialized `WCValHashSet` object with the specified number of buckets and hash function.

See Also: `~WCValHashSet`, `bitHash`, `WCExcept::out_of_memory`

WCValHashSet<Type>::WCValHashSet()

Synopsis:

```
#include <wchash.h>
public:
    WCValHashSet( unsigned (*hash_fn)( const Type & ),
    unsigned = WC_DEFAULT_HASH_SIZE,
    void * (*user_alloc)( size_t ),
    void (*user_dealloc)( void *, size_t ) );
```

Semantics: Allocator and deallocator functions are specified for use when entries are inserted and removed from the hash. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a hash. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:
WCValHashSetItemSize(Type)

Results: The `WCValHashSet<Type>` constructor creates an initialized `WCValHashSet` object with the specified number of buckets and hash function.

See Also: ~`WCValHashSet`, `bitHash`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wchash.h>
public:
WCValHashSet( const WCValHashSet & );
```

Semantics: The `WCValHashSet<Type>` is the copy constructor for the `WCValHashSet` class. The new hash is created with the same number of buckets, hash function, all values or pointers stored in the hash, and the exception trap states. If the hash object can be created, but an allocation failure occurs when creating the buckets, the hash will be created with zero buckets. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

Results: The `WCValHashSet<Type>` constructor creates a `WCValHashSet` object which is a copy of the passed hash.

See Also: `~WCValHashSet`, `operator =`, `WCExcept::out_of_memory`

WCValHashSet<Type>::~WCValHashSet()

Synopsis:

```
#include <wchash.h>
public:
    virtual ~WCValHashSet();
```

Semantics: The `WCValHashSet<Type>` destructor is the destructor for the `WCValHashSet` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the hash elements are cleared using the `clear` member function. The call to the `WCValHashSet<Type>` destructor is inserted implicitly by the compiler at the point where the `WCValHashSet` object goes out of scope.

Results: The call to the `WCValHashSet<Type>` destructor destroys a `WCValHashSet` object.

See Also: `clear`, `WCExcept::not_empty`

Synopsis:

```
#include <wchash.h>
public:
WCValHashTable( unsigned (*hash_fn)( const Type & ),
unsigned = WC_DEFAULT_HASH_SIZE );
```

Semantics: The `WCValHashTable<Type>` constructor creates a `WCValHashTable` object with no entries and with the number of buckets in the second optional parameter, which defaults to the constant `WC_DEFAULT_HASH_SIZE` (currently defined as 101). The number of buckets specified must be greater than zero, and will be forced to at least one. If the hash object can be created, but an allocation failure occurs when creating the buckets, the table will be created with zero buckets. If the `out_of_memory` exception is enabled, then attempting to insert into a hash table with zero buckets will throw an `out_of_memory` error.

The hash function `hash_fn` is used to determine which bucket each value will be assigned to. If no hash function exists, the static member function `bitHash` is available to help create one.

Results: The `WCValHashTable<Type>` constructor creates an initialized `WCValHashTable` object with the specified number of buckets and hash function.

See Also: `~WCValHashTable`, `bitHash`, `WCEexcept::out_of_memory`

WCValHashTable<Type>::WCValHashTable()

Synopsis:

```
#include <wchash.h>
public:
    WCValHashTable( unsigned (*hash_fn)( const Type & ),
                    unsigned = WC_DEFAULT_HASH_SIZE,
                    void * (*user_alloc)( size_t ),
                    void (*user_dealloc)( void *, size_t ) );
```

Semantics: Allocator and deallocator functions are specified for use when entries are inserted and removed from the hash. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a hash. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:
`WCValHashTableItemSize(Type)`

Results: The `WCValHashTable<Type>` constructor creates an initialized `WCValHashTable` object with the specified number of buckets and hash function.

See Also: `~WCValHashTable`, `bitHash`, `WCEExcept::out_of_memory`

Synopsis:

```
#include <wchash.h>
public:
WCValHashTable( const WCValHashTable & );
```

Semantics: The `WCValHashTable<Type>` is the copy constructor for the `WCValHashTable` class. The new hash is created with the same number of buckets, hash function, all values or pointers stored in the hash, and the exception trap states. If the hash object can be created, but an allocation failure occurs when creating the buckets, the hash will be created with zero buckets. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

Results: The `WCValHashTable<Type>` constructor creates a `WCValHashTable` object which is a copy of the passed hash.

See Also: `~WCValHashTable`, `operator =`, `WCExcept::out_of_memory`

WCValHashTable<Type>::~WCValHashTable()

Synopsis:

```
#include <wchash.h>
public:
    virtual ~WCValHashTable();
```

Semantics: The `WCValHashTable<Type>` destructor is the destructor for the `WCValHashTable` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the hash elements are cleared using the `clear` member function. The call to the `WCValHashTable<Type>` destructor is inserted implicitly by the compiler at the point where the `WCValHashTable` object goes out of scope.

Results: The call to the `WCValHashTable<Type>` destructor destroys a `WCValHashTable` object.

See Also: `clear`, `WCExcept::not_empty`

Synopsis:

```
#include <wchash.h>
public:
    static unsigned bitHash( void *, size_t );
```

Semantics: The `bitHash` public member function can be used to implement a hashing function for any type. A hashing value is generated from the value stored for the number of specified bytes pointed to by the first parameter. For example:

```
unsigned my_hash_fn( const int & elem ) {
    return( WCValHashSet<int, String>::bitHash(&elem, sizeof(int));
```

```
    }
WCValHashSet<int> data_object( &my_hash_fn );
```

Results: The `bitHash` public member function returns an unsigned value which can be used as the basis of a user defined hash function.

See Also: `WCValHashSet`, `WCValHashTable`

WCValHashTable<Type>::buckets(), WCValHashSet<Type>::buckets()

Synopsis:

```
#include <wchash.h>
public:
    unsigned buckets() const;
```

Semantics: The `buckets` public member function is used to find the number of buckets contained in the hash object.

Results: The `buckets` public member function returns the number of buckets in the hash.

See Also: `resize`

Synopsis:

```
#include <wchash.h>
public:
void clear();
```

Semantics: The `clear` public member function is used to clear the hash so that it has no entries. The number of buckets remain unaffected. Elements stored in the hash are destroyed using the destructors of `Type`. The hash object is not destroyed and re-created by this function, so the object destructor is not invoked.

Results: The `clear` public member function clears the hash to have no elements.

See Also: `~WCValHashSet`, `~WCValHashTable`, `operator =`

WCValHashTable<Type>::contains(), WCValHashSet<Type>::contains()

Synopsis:

```
#include <wchash.h>
public:
    int contains( const Type & ) const;
```

Semantics: The `contains` public member function returns non-zero if the element is stored in the hash, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the element type.

Results: The `contains` public member function returns a non-zero value if the element is found in the hash.

See Also: `find`

Synopsis:

```
#include <wchash.h>
public:
    unsigned entries() const;
```

Semantics: The `entries` public member function is used to return the current number of elements stored in the hash.

Results: The `entries` public member function returns the number of elements in the hash.

See Also: `buckets`, `isEmpty`

WCValHashTable<Type>::find(), WCValHashSet<Type>::find()

Synopsis:

```
#include <wchash.h>
public:
    int find( const Type &, Type & ) const;
```

Semantics: The `find` public member function is used to find an element with an equivalent key in the hash. If an equivalent element is found, a non-zero value is returned. The reference to the element passed as the second argument is assigned the found element's value. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the element type.

Results: The element equivalent to the passed key is located in the hash.

Synopsis:

```
#include <wchash.h>
public:
void forAll(
void (*user_fn)( Type, void * ),
void * );
```

Semantics: The `forAll` public member function causes the user supplied function to be invoked for every value in the hash. The user function has the prototype

```
void user_func( Type & value, void * data );
```

As the elements are visited, the user function is invoked with the element passed as the first. The second parameter of the `forAll` function is passed as the second parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

Results: The elements in the hash are all visited, with the user function being invoked for each one.

See Also: `find`

WCValHashTable<Type>::insert(), WCValHashSet<Type>::insert()

Synopsis:

```
#include <wchash.h>
public:
    int insert( const Type & );
```

Semantics: The `insert` public member function inserts a value into the hash, using the `hash` function to determine to which bucket it should be stored. If allocation of the node to store the value fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

With a `WCValHashSet`, there must be only one equivalent element in the set. If an element equivalent to the inserted element is already in the hash set, the hash set will remain unchanged, and the `not_unique` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

At some point, the number of buckets initially selected may be too small for the number of elements inserted. The `resize` of the hash can be controlled by the insertion mechanism by using `WCValHashSet` (or `WCValHashTable`) as a base class, and providing an `insert` member function to do a `resize` when appropriate. This `insert` could then call `WCValHashSet::insert` (or `WCValHashTable::insert`) to insert the element. Note that copy constructors and assignment operators are not inherited in your class, but you can provide the following inline definitions (assuming that the class inherited from `WCValHashTable` is named `MyHashTable`):

```
inline MyHashTable( const MyHashTable &orig )
    : WCValHashTable( orig ) {};
inline MyHashTable &operator=( const MyHashTable &orig ) {
    return( WCValHashTable::operator=( orig ) );
}
```

Results: The `insert` public member function inserts a value into the hash. If the insert is successful, a non-zero will be returned. A zero will be returned if the insert fails.

See Also: `operator =`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wchash.h>
public:
    int isEmpty() const;
```

Semantics: The `isEmpty` public member function is used to determine if the hash is empty.

Results: The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the hash is empty.

See Also: `buckets`, `entries`

WCValHashTable<Type>::occurencesOf()

Synopsis:

```
#include <wchash.h>
public:
    unsigned occurrencesOf( const Type & ) const;
```

Semantics: The `occurencesOf` public member function is used to return the current number of elements stored in the hash which are equivalent to the passed value. Note that equivalence is based on the equivalence operator of the element type.

Results: The `occurencesOf` public member function returns the number of elements in the hash.

See Also: `buckets`, `entries`, `find`, `isEmpty`

Synopsis:

```
#include <wchash.h>
public:
WCValHashSet & operator =( const WCValHashSet & );
WCValHashTable & operator =( const WCValHashTable & );
```

Semantics: The `operator =` public member function is the assignment operator for the `WCValHashTable<Type>` and `WCValHashSet<Type>` classes. The left hand side hash is first cleared using the `clear` member function, and then the right hand side hash is copied. The hash function, exception trap states, and all of the hash elements are copied. If an allocation failure occurs when creating the buckets, the table will be created with zero buckets, and the `out_of_memory` exception is thrown if it is enabled. If there is not enough memory to copy all of the values or pointers in the hash, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

Results: The `operator =` public member function assigns the left hand side hash to be a copy of the right hand side.

See Also: `clear`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wchash.h>
public:
    int operator ==( const WCValHashSet & ) const;
    int operator ==( const WCValHashTable & ) const;
```

Semantics: The `operator ==` public member function is the equivalence operator for the `WCValHashTable<Type>` and `WCValHashSet<Type>` classes. Two hash objects are equivalent if they are the same object and share the same address.

Results: A TRUE (non-zero) value is returned if the left hand side and right hand side hash are the same object. A FALSE (zero) value is returned otherwise.

Synopsis:

```
#include <wchash.h>
public:
    int remove( const Type & );
```

Semantics: The `remove` public member function is used to remove the specified element from the hash. If an equivalent element is found, a non-zero value is returned. Zero is returned if the element is not found. If the hash is a table and there is more than one element equivalent to the specified element, then the first equivalent element added to the table is removed. Note that equivalence is based on the equivalence operator of the element type.

Results: The element is removed from the hash if it found.

WCValHashTable<Type>::removeAll()

Synopsis:

```
#include <wchash.h>
public:
    unsigned removeAll( const Type & );
```

Semantics: The `removeAll` public member function is used to remove all elements equivalent to the specified element from the hash. Zero is returned if no equivalent elements are found. Note that equivalence is based on the equivalence operator of the element type.

Results: All equivalent elements are removed from the hash.

Synopsis:

```
#include <wchash.h>
public:
void resize( unsigned );
```

Semantics: The `resize` public member function is used to change the number of buckets contained in the hash. If the new number is larger than the previous hash size, then the hash function will be used on all of the stored elements to determine which bucket they should be stored into. Entries are not destroyed or created in the process of being moved. If there is not enough memory to resize the hash, the `out_of_memory` exception is thrown if it is enabled, and the hash will contain the number of buckets it contained before the resize. If the new number is zero, then the `zero_buckets` exception is thrown if it is enabled, and no resize will be performed. The hash is guaranteed to contain the same number of entries after the resize.

Results: The hash is resized to the new number of buckets.

See Also: `WCExcept::out_of_memory`, `WCExcept::zero_buckets`

11 Hash Iterators

Hash iterators are used to step through a hash one or more elements at a time. Iterators which are newly constructed or reset are positioned before the first element in the hash. The hash may be traversed one element at a time using the pre-increment or call operator. An increment operation causing the iterator to be positioned after the end of the hash returns zero. Further increments will cause the `undef_iter` exception to be thrown, if it is enabled. The `WCIterExcept` class provides the common exception handling control interface for all of the iterators.

Since the iterator classes are all template classes, most of the functionality was derived from common base classes. In the listing of class member functions, those public member functions which appear to be in the iterator class but are actually defined in the common base class are identified as if they were explicitly specified in the iterator class.

WCPtrHashDictIter<Key,Value>

Declared: wchiter.h

The `WCPtrHashDictIter<Key,Value>` class is the templated class used to create iterator objects for `WCPtrHashDict<Key,Value>` objects. In the description of each member function, the text `Key` is used to indicate the template parameter defining the type of the indices pointed to by the pointers stored in the dictionary. The text `Value` is used to indicate the template parameter defining the type of the data pointed to by the pointers stored in the dictionary. The `WCIterExcept` class is a base class of the `WCPtrHashDictIter<Key,Value>` class and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCPtrHashDictIter<Key,Value>` object. No exceptions are enabled unless they are set by the `exceptions` member function.

Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrHashDictIter();
WCPtrHashDictIter( const WCPtrHashDict<Key,Value> & );
~WCPtrHashDictIter();
const WCPtrHashDict<Key,Value> *container() const;
Key *key();
void reset();
void reset( WCPtrHashDict<Key,Value> & );
Value * value();
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
```

Synopsis:

```
#include <wchiter.h>
public:
WCPtrHashDictIter();
```

Semantics: The public `WCPtrHashDictIter<Key,Value>` constructor is the default constructor for the class and initializes the iterator with no hash to operate on. The `reset` member function must be called to provide the iterator with a hash to iterate over.

Results: The public `WCPtrHashDictIter<Key,Value>` constructor creates an initialized `WCPtrHashDictIter` hash iterator object.

See Also: `~WCPtrHashDictIter`, `reset`

WCPtrHashDictIter<Key,Value>::WCPtrHashDictIter()

Synopsis:

```
#include <wchiter.h>
public:
WCPtrHashDictIter( WCPtrHashDict<Key,Value> & );
```

Semantics: The public `WCPtrHashDictIter<Key,Value>` constructor is a constructor for the class. The value passed as a parameter is a `WCPtrHashDict` hash object. The iterator will be initialized for that hash object and positioned before the first hash element. To position the iterator to a valid element within the hash, increment it using one of the `operator ++` or `operator ()` operators.

Results: The public `WCPtrHashDictIter<Key,Value>` constructor creates an initialized `WCPtrHashDictIter` hash iterator object positioned before the first element in the hash.

See Also: `~WCPtrHashDictIter`, `operator ()`, `operator ++`, `reset`

Synopsis:

```
#include <wchiter.h>
public:
~WCPtrHashDictIter();
```

Semantics: The public ~WCPtrHashDictIter<Key, Value> destructor is the destructor for the class. The call to the destructor is inserted implicitly by the compiler at the point where the WCPtrHashDictIter hash iterator object goes out of scope.

Results: The WCPtrHashDictIter hash iterator object is destroyed.

See Also: WCPtrHashDictIter

WCPtrHashDictIter<Key,Value>::container()

Synopsis:

```
#include <wchiter.h>
public:
    WCPtrHashDict<Key,Value> *container() const;
```

Semantics: The `container` public member function returns a pointer to the hash container object. If the iterator has not been initialized with a hash object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the hash object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a hash.

See Also: `WCPtrHashDictIter`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wchiter.h>
public:
Key *key();
```

Semantics: The key public member function returns a pointer to the Key value of the hash item at the current iterator position.

If the iterator is not associated with a hash, or the iterator position is either before the first element or past the last element in the hash, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: A pointer to Key at the current iterator element is returned. If the current element is undefined, an undefined pointer is returned.

See Also: `operator ()`, `operator ++`, `reset`, `WCIterExcept::undef_item`

WCPtrHashDictIter<Key,Value>::operator ()()

Synopsis:

```
#include <wchiter.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first hash element, the current item will be set to the first element. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `operator ++`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wchiter.h>
public:
    int operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

The current item will be set to the first hash element if the iterator was positioned before the first element in the hash. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `operator ()`, `reset`, `WCIterExcept::undef_iter`

WCPtrHashDictIter<Key,Value>::reset()

Synopsis:

```
#include <wchiter.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated hash.

Results: The iterator is positioned before the first hash element.

See Also: `WCPtrHashDictIter`, `container`

Synopsis:

```
#include <wchiter.h>
public:
void reset( WCPtrHashDict<Key,Value> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified hash. The iterator is positioned before the first element in the hash.

Results: The iterator is positioned before the first element of the specified hash.

See Also: `WCPtrHashDictIter`, `container`

WCPtrHashDictIter<Key,Value>::value()

Synopsis:

```
#include <wchiter.h>
public:
Value *value();
```

Semantics: The `value` public member function returns a pointer to the `Value` at the current iterator position.

If the iterator is not associated with a hash, or the iterator position is either before the first element or past the last element in the hash, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: A pointer to the `Value` at the current iterator element is returned. If the current element is undefined, an undefined pointer is returned.

See Also: `operator ()`, `operator ++`, `reset`, `WCIterExcept::undef_item`

Declared: wchiter.h

The `WCValHashDictIter<Key,Value>` class is the templated class used to create iterator objects for `WCValHashDict<Key,Value>` objects. In the description of each member function, the text `Key` is used to indicate the template parameter defining the type of the indices used to store data in the dictionary. The text `Value` is used to indicate the template parameter defining the type of the data stored in the dictionary. The `WCIterExcept` class is a base class of the `WCValHashDictIter<Key,Value>` class and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCValHashDictIter<Key,Value>` object. No exceptions are enabled unless they are set by the `exceptions` member function.

Public Member Functions

The following member functions are declared in the public interface:

```
WCValHashDictIter();
WCValHashDictIter( const WCValHashDict<Key,Value> & );
~WCValHashDictIter();
const WCValHashDict<Key,Value> *container() const;
Key key();
void reset();
void reset( WCValHashDict<Key,Value> & );
Value value();
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
```

WCValHashDictIter<Key,Value>::WCValHashDictIter()

Synopsis:

```
#include <wchiter.h>
public:
WCValHashDictIter();
```

Semantics: The public `WCValHashDictIter<Key,Value>` constructor is the default constructor for the class and initializes the iterator with no hash to operate on. The `reset` member function must be called to provide the iterator with a hash to iterate over.

Results: The public `WCValHashDictIter<Key,Value>` constructor creates an initialized `WCValHashDictIter` hash iterator object.

See Also: `~WCValHashDictIter`, `reset`

Synopsis:

```
#include <wchiter.h>
public:
WCValHashDictIter( WCValHashDict<Key,Value> & );
```

Semantics: The public `WCValHashDictIter<Key,Value>` constructor is a constructor for the class. The value passed as a parameter is a `WCValHashDict` hash object. The iterator will be initialized for that hash object and positioned before the first hash element. To position the iterator to a valid element within the hash, increment it using one of the `operator ++` or `operator ()` operators.

Results: The public `WCValHashDictIter<Key,Value>` constructor creates an initialized `WCValHashDictIter` hash iterator object positioned before the first element in the hash.

See Also: `~WCValHashDictIter`, `operator ()`, `operator ++`, `reset`

WCValHashDictIter<Key,Value>::~WCValHashDictIter()

Synopsis:

```
#include <wchiter.h>
public:
~WCValHashDictIter();
```

Semantics: The public ~WCValHashDictIter<Key, Value> destructor is the destructor for the class. The call to the destructor is inserted implicitly by the compiler at the point where the WCValHashDictIter hash iterator object goes out of scope.

Results: The WCValHashDictIter hash iterator object is destroyed.

See Also: WCValHashDictIter

Synopsis:

```
#include <wchiter.h>
public:
WCValHashDict<Key,Value> *container() const;
```

Semantics: The `container` public member function returns a pointer to the hash container object. If the iterator has not been initialized with a hash object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the hash object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a hash.

See Also: `WCValHashDictIter`, `reset`, `WCIterExcept::undef_iter`

WCValHashDictIter<Key,Value>::key()

Synopsis:

```
#include <wchiter.h>
public:
    Key key();
```

Semantics: The key public member function returns the value of Key at the current iterator position.

If the iterator is not associated with a hash, or the iterator position is either before the first element or past the last element in the hash, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: The value of Key at the current iterator element is returned. If the current element is undefined, a default initialized object is returned.

See Also: `operator ()`, `operator ++`, `reset`, `WCIterExcept::undef_item`

Synopsis:

```
#include <wchiter.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first hash element, the current item will be set to the first element. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `operator ++`, `reset`, `WCIterExcept::undef_iter`

WCValHashDictIter<Key,Value>::operator ++()

Synopsis:

```
#include <wchiter.h>
public:
    int operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

The current item will be set to the first hash element if the iterator was positioned before the first element in the hash. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `operator ()`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wchiter.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated hash.

Results: The iterator is positioned before the first hash element.

See Also: `WCValHashDictIter`, `container`

WCValHashDictIter<Key,Value>::reset()

Synopsis:

```
#include <wchiter.h>
public:
    void reset( WCValHashDict<Key,Value> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified hash. The iterator is positioned before the first element in the hash.

Results: The iterator is positioned before the first element of the specified hash.

See Also: `WCValHashDictIter`, `container`

Synopsis:

```
#include <wchiter.h>
public:
Value value();
```

Semantics: The `value` public member function returns the value of `Value` at the current iterator position.

If the iterator is not associated with a hash, or the iterator position is either before the first element or past the last element in the hash, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: The value of the `Value` at the current iterator element is returned. If the current element is undefined, a default initialized object is returned.

See Also: `operator ()`, `operator ++`, `reset`, `WCIterExcept::undef_item`

Declared: wchiter.h

The `WCPtrHashSetIter<Type>` and `WCPtrHashTableIter<Type>` classes are the templated classes used to create iterator objects for `WCPtrHashTable<Type>` and `WCPtrHashSet<Type>` objects. In the description of each member function, the text `Type` is used to indicate the hash element type specified as the template parameter. The `WCIterExcept` class is a base class of the `WCPtrHashSetIter<Type>` and `WCPtrHashTableIter<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCPtrHashSetIter<Type>` and `WCPtrHashTableIter<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrHashSetIter();
WCPtrHashSetIter( const WCPtrHashSet<Type> & );
~WCPtrHashSetIter();
WCPtrHashTableIter();
WCPtrHashTableIter( const WCPtrHashTable<Type> & );
~WCPtrHashTableIter();
const WCPtrHashTable<Type> *container() const;
const WCPtrHashSet<Type> *container() const;
Type *current() const;
void reset();
void WCPtrHashSetIter<Type>::reset( WCPtrHashSet<Type> & );
void WCPtrHashTableIter<Type>::reset( WCPtrHashTable<Type> & );
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
```

Synopsis:

```
#include <wchiter.h>
public:
WCPtrHashSetIter();
```

Semantics: The public `WCPtrHashSetIter<Type>` constructor is the default constructor for the class and initializes the iterator with no hash to operate on. The `reset` member function must be called to provide the iterator with a hash to iterate over.

Results: The public `WCPtrHashSetIter<Type>` constructor creates an initialized `WCPtrHashSetIter` hash iterator object.

See Also: `~WCPtrHashSetIter`, `WCPtrHashTableIter`, `reset`

WCPtrHashSetIter<Type>::WCPtrHashSetIter()

Synopsis:

```
#include <wchiter.h>
public:
WCPtrHashSetIter( WCPtrHashSet<Type> & );
```

Semantics: The public `WCPtrHashSetIter<Type>` constructor is a constructor for the class. The value passed as a parameter is a `WCPtrHashSet` hash object. The iterator will be initialized for that hash object and positioned before the first hash element. To position the iterator to a valid element within the hash, increment it using one of the operator `++` or operator `()` operators.

Results: The public `WCPtrHashSetIter<Type>` constructor creates an initialized `WCPtrHashSetIter` hash iterator object positioned before the first element in the hash.

See Also: `~WCPtrHashSetIter`, `operator ()`, `operator ++`, `reset`

Synopsis:

```
#include <wchiter.h>
public:
~WCPtrHashSetIter();
```

Semantics: The public ~WCPtrHashSetIter<Type> destructor is the destructor for the class. The call to the destructor is inserted implicitly by the compiler at the point where the WCPtrHashSetIter hash iterator object goes out of scope.

Results: The WCPtrHashSetIter hash iterator object is destroyed.

See Also: WCPtrHashSetIter, WCPtrHashTableIter

WCPtrHashTableIter<Type>::WCPtrHashTableIter()

Synopsis:

```
#include <wchiter.h>
public:
    WCPtrHashTableIter();
```

Semantics: The public `WCPtrHashTableIter<Type>` constructor is the default constructor for the class and initializes the iterator with no hash to operate on. The `reset` member function must be called to provide the iterator with a hash to iterate over.

Results: The public `WCPtrHashTableIter<Type>` constructor creates an initialized `WCPtrHashTableIter` hash iterator object.

See Also: `~WCPtrHashTableIter`, `WCPtrHashSetIter`, `reset`

Synopsis:

```
#include <wchiter.h>
public:
WCPtrHashTableIter( WCPtrHashTable<Type> & ) ;
```

Semantics: The public `WCPtrHashTableIter<Type>` constructor is a constructor for the class. The value passed as a parameter is a `WCPtrHashTable` hash object. The iterator will be initialized for that hash object and positioned before the first hash element. To position the iterator to a valid element within the hash, increment it using one of the `operator ++` or `operator ()` operators.

Results: The public `WCPtrHashTableIter<Type>` constructor creates an initialized `WCPtrHashTableIter` hash iterator object positioned before the first element in the hash.

See Also: `~WCPtrHashTableIter`, `operator ()`, `operator ++`, `reset`

WCPtrHashTableIter<Type>::~WCPtrHashTableIter()

Synopsis:

```
#include <wchiter.h>
public:
~WCPtrHashTableIter();
```

Semantics: The `WCPtrHashTableIter<Type>` destructor is the destructor for the class. The call to the destructor is inserted implicitly by the compiler at the point where the `WCPtrHashTableIter` hash iterator object goes out of scope.

Results: The `WCPtrHashTableIter` hash iterator object is destroyed.

See Also: `WCPtrHashSetIter`, `WCPtrHashTableIter`

Synopsis:

```
#include <wchiter.h>
public:
WCPtrHashTable<Type> *WCPtrHashTableIter<Type>::container() const;
WCPtrHashSet<Type> *WCPtrHashSetIter<Type>::container() const;
```

Semantics: The `container` public member function returns a pointer to the hash container object. If the iterator has not been initialized with a hash object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the hash object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a hash.

See Also: `WCPtrHashSetIter`, `WCPtrHashTableIter`, `reset`, `WCIterExcept::undef_iter`

WCPtrHashSetIter<Type>::current(), WCPtrHashTableIter<Type>::current()

Synopsis:

```
#include <wchiter.h>
public:
    Type *current();
```

Semantics: The `current` public member function returns a pointer to the hash item at the current iterator position.

If the iterator is not associated with a hash, or the iterator position is either before the first element or past the last element in the hash, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: A pointer to the current iterator element is returned. If the current element is undefined, `NULL(0)` is returned.

See Also: `operator ()`, `operator ++`, `reset`, `WCIterExcept::undef_item`

Synopsis:

```
#include <wchiter.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first hash element, the current item will be set to the first element. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `operator ++`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wchiter.h>
public:
    int operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

The current item will be set to the first hash element if the iterator was positioned before the first element in the hash. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `current`, `operator ()`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wchiter.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated hash.

Results: The iterator is positioned before the first hash element.

See Also: `WCPtrHashSetIter`, `WCPtrHashTableIter`, `container`

WCPtrHashSetIter<Type>::reset(), WCPtrHashTableIter<Type>::reset()

Synopsis:

```
#include <wchiter.h>
public:
void WCPtrHashSetIter<Type>::reset( WCPtrHashSet<Type> & );
void WCPtrHashTableIter<Type>::reset( WCPtrHashTable<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified hash. The iterator is positioned before the first element in the hash.

Results: The iterator is positioned before the first element of the specified hash.

See Also: `WCPtrHashSetIter`, `WCPtrHashTableIter`, `container`

Declared: wchiter.h

The WCValHashSetIter<Type> and WCValHashTableIter<Type> classes are the templated classes used to create iterator objects for WCValHashTable<Type> and WCValHashSet<Type> objects. In the description of each member function, the text Type is used to indicate the hash element type specified as the template parameter. The WCIterExcept class is a base class of the WCValHashSetIter<Type> and WCValHashTableIter<Type> classes and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCValHashSetIter<Type> and WCValHashTableIter<Type> objects. No exceptions are enabled unless they are set by the exceptions member function.

Public Member Functions

The following member functions are declared in the public interface:

```
WCValHashSetIter();
WCValHashSetIter( const WCValHashSet<Type> & );
~WCValHashSetIter();
WCValHashTableIter();
WCValHashTableIter( const WCValHashTable<Type> & );
~WCValHashTableIter();
const WCValHashTable<Type> *container() const;
const WCValHashSet<Type> *container() const;
Type current() const;
void reset();
void WCValHashSetIter<Type>::reset( WCValHashSet<Type> & );
void WCValHashTableIter<Type>::reset( WCValHashTable<Type> & );
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
```

WCValHashSetIter<Type>::WCValHashSetIter()

Synopsis:

```
#include <wchiter.h>
public:
    WCValHashSetIter();
```

Semantics: The public `WCValHashSetIter<Type>` constructor is the default constructor for the class and initializes the iterator with no hash to operate on. The `reset` member function must be called to provide the iterator with a hash to iterate over.

Results: The public `WCValHashSetIter<Type>` constructor creates an initialized `WCValHashSetIter` hash iterator object.

See Also: `~WCValHashSetIter`, `WCValHashTableIter`, `reset`

Synopsis:

```
#include <wchiter.h>
public:
WCValHashSetIter( WCValHashSet<Type> & );
```

Semantics: The public `WCValHashSetIter<Type>` constructor is a constructor for the class. The value passed as a parameter is a `WCValHashSet` hash object. The iterator will be initialized for that hash object and positioned before the first hash element. To position the iterator to a valid element within the hash, increment it using one of the operator `++` or operator `()` operators.

Results: The public `WCValHashSetIter<Type>` constructor creates an initialized `WCValHashSetIter` hash iterator object positioned before the first element in the hash.

See Also: `~WCValHashSetIter`, `operator ()`, `operator ++`, `reset`

WCValHashSetIter<Type>::~WCValHashSetIter()

Synopsis:

```
#include <wchiter.h>
public:
~WCValHashSetIter();
```

Semantics: The public ~WCValHashSetIter<Type> destructor is the destructor for the class. The call to the destructor is inserted implicitly by the compiler at the point where the WCValHashSetIter hash iterator object goes out of scope.

Results: The WCValHashSetIter hash iterator object is destroyed.

See Also: WCValHashSetIter, WCValHashTableIter

Synopsis:

```
#include <wchiter.h>
public:
WCValHashTableIter();
```

Semantics: The public `WCValHashTableIter<Type>` constructor is the default constructor for the class and initializes the iterator with no hash to operate on. The `reset` member function must be called to provide the iterator with a hash to iterate over.

Results: The public `WCValHashTableIter<Type>` constructor creates an initialized `WCValHashTableIter` hash iterator object.

See Also: `~WCValHashTableIter`, `WCValHashSetIter`, `reset`

WCValHashTableIter<Type>::WCValHashTableIter()

Synopsis:

```
#include <wchiter.h>
public:
    WCValHashTableIter( WCValHashTable<Type> & ) ;
```

Semantics: The public `WCValHashTableIter<Type>` constructor is a constructor for the class. The value passed as a parameter is a `WCValHashTable` hash object. The iterator will be initialized for that hash object and positioned before the first hash element. To position the iterator to a valid element within the hash, increment it using one of the `operator ++` or `operator ()` operators.

Results: The public `WCValHashTableIter<Type>` constructor creates an initialized `WCValHashTableIter` hash iterator object positioned before the first element in the hash.

See Also: `~WCValHashTableIter`, `operator ()`, `operator ++`, `reset`

Synopsis:

```
#include <wchiter.h>
public:
~WCValHashTableIter();
```

Semantics: The `WCValHashTableIter<Type>` destructor is the destructor for the class. The call to the destructor is inserted implicitly by the compiler at the point where the `WCValHashTableIter` hash iterator object goes out of scope.

Results: The `WCValHashTableIter` hash iterator object is destroyed.

See Also: `WCValHashSetIter`, `WCValHashTableIter`

WCValHashSetIter<Type>, WCValHashTableIter<Type>::container()

Synopsis:

```
#include <wchiter.h>
public:
    WCValHashTable<Type> *WCValHashTableIter<Type>::container() const;
    WCValHashSet<Type> *WCValHashSetIter<Type>::container() const;
```

Semantics: The `container` public member function returns a pointer to the hash container object. If the iterator has not been initialized with a hash object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the hash object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a hash.

See Also: `WCValHashSetIter`, `WCValHashTableIter`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wchiter.h>
public:
    Type current();
```

Semantics: The `current` public member function returns the value of the hash element at the current iterator position.

If the iterator is not associated with a hash, or the iterator position is either before the first element or past the last element in the hash, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: The value at the current iterator element is returned. If the current element is undefined, a default initialized object is returned.

See Also: `operator ()`, `operator ++`, `reset`, `WCIterExcept::undef_item`

Synopsis:

```
#include <wchiter.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first hash element, the current item will be set to the first element. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `operator ++`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wchiter.h>
public:
    int operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The hash element which follows the current item is set to be the new current item. If the previous current item was the last element in the hash, the iterator is positioned after the end of the hash.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

The current item will be set to the first hash element if the iterator was positioned before the first element in the hash. If the hash is empty, the iterator will be positioned after the end of the hash.

If the iterator is not associated with a hash or the iterator position before the increment was past the last element the hash, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a non-zero value if the iterator is positioned on a hash item. Zero(0) is returned when the iterator is incremented past the end of the hash.

See Also: `current`, `operator ()`, `reset`, `WCIterExcept::undef_iter`

WCValHashSetIter<Type>::reset(), WCValHashTableIter<Type>::reset()

Synopsis:

```
#include <wchiter.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated hash.

Results: The iterator is positioned before the first hash element.

See Also: `WCValHashSetIter`, `WCValHashTableIter`, `container`

Synopsis:

```
#include <wchiter.h>
public:
void WCValHashSetIter<Type>::reset( WCValHashSet<Type> & );
void WCValHashTableIter<Type>::reset( WCValHashTable<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified hash. The iterator is positioned before the first element in the hash.

Results: The iterator is positioned before the first element of the specified hash.

See Also: `WCValHashSetIter`, `WCValHashTableIter`, `container`

12 List Containers

List containers are single or double linked lists. The choice of which type of list to use is determined by the direction in which the list is traversed and by what is stored in the list. A list to which items are just added and removed may be most efficiently implemented as a single linked list. If frequent retrievals of items at given indexes within the list are made, double linked lists can offer some improved search performance.

There are three sets of list container classes: value, pointer and intrusive.

Value lists are the simplest to use but have the most requirements on the type stored in the lists. Copies are made of the values stored in the list, which could be undesirable if the stored objects are complicated and copying is expensive. Value lists should not be used to store objects of a base class if any derived types of different sizes would be stored in the list, or if the destructor for the derived class must be called. The `WCValSList<Type>` container class implements single linked value lists, and the `WCValDList<Type>` class double linked value lists.

Pointer list elements store pointers to objects. No creating, copying or destroying of objects stored in the list occurs. The only requirement of the type pointed to is that an equivalence operator is provided so that lookups can be performed. The `WCPtrSList<Type>` class implements single linked pointer lists, and the `WCPtrDList<Type>` class double linked pointer lists.

Intrusive lists require that the list elements are objects derived from the `WCSLink` or `WCDLink` class, depending on whether a single or double linked list is used. The list classes require nothing else from the list elements. No creating, destroying or copying of any object is performed by the intrusive list classes, and must be done by the user of the class. One advantage of an intrusive list is a list element can be removed from one list and inserted into another list without creating new list element objects or deleting old objects. The `WCIsvSList<Type>` class implements single linked intrusive lists, and the `WCIsvDList<Type>` class double linked intrusive lists.

A list may be traversed using the corresponding list iterator class. Iterators allow lists to be stepped through one or more elements at a time. The iterator classes which correspond to single linked list containers have some functionality inhibited. If backward traversal is required, the double linked containers and iterators must be used.

The classes are presented in alphabetical order. The `WCSLink` and `WCDLink` class provide a common control interface for the list elements for the intrusive classes.

Since the container classes are all template classes, deriving most of the functionality from common base classes was used. In the listing of class member functions, those public member functions which appear to be in the container class but are actually defined in the common base class are identified as if they were explicitly specified in the container class.

Declared: wclcom.h

Derived from: WCSLink

The WCDLink class is the building block for all of the double linked list classes. It is implemented in terms of the WCSLink base class. Since no user data is stored directly with it, the WCDLink class should only be used as a base class to derive a user defined class.

When creating a double linked intrusive list, the WCDLink class is used to derive the user defined class that holds the data to be inserted into the list.

The wclcom.h header file is included by the wclist.h header file. There is no need to explicitly include the wclcom.h header file unless the wclist.h header file is not included. No errors will result if it is included.

Note that the destructor is non-virtual so that list elements are of minimum size. Objects created as a class derived from the WCDLink class, but destroyed while typed as a WCDLink object will not invoke the destructor of the derived class..

Public Member Functions

The following public member functions are declared:

```
WCDLink();  
~WCDLink();
```

See Also: WCSLink

Synopsis:

```
#include <wclist.h>
public:
WCDLink();
```

Semantics: The public WCDLink constructor creates an WCDLink object. The public WCDLink constructor is used implicitly by the compiler when it generates a constructor for a derived class.

Results: The public WCDLink constructor produces an initialized WCDLink object.

See Also: ~WCDLink

WCDLink::~WCDLink()

Synopsis:

```
#include <wclist.h>
public:
~WCDLink();
```

Semantics: The public ~WCDLink destructor does not do anything explicit. The call to the public ~WCDLink destructor is inserted implicitly by the compiler at the point where the object derived from WCDLink goes out of scope.

Results: The object derived from WCDLink is destroyed.

See Also: WCDLink

Declared: wclist.h

The `WCIsvSList<Type>` and `WCIsvDList<Type>` classes are the templated classes used to create objects which are single or double linked lists. The created list is intrusive, which means that list elements which are inserted must be created with a library supplied base class. The class `WCSLink` provides the base class definition for single linked lists, and should be inherited by the definition of any list item for single linked lists. It provides the linkage that is used to traverse the list elements. Similarly, the class `WCDLink` provides the base class definition for double lists, and should be inherited by the definition of any list item for double lists.

In the description of each member function, the text `Type` is used to indicate the type value specified as the template parameter. `Type` is the type of the list elements, derived from `WCSLink` or `WCDLink`.

The `WCExcept` class is a base class of the `WCIsvSList<Type>` and `WCIsvDList<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCIsvSList<Type>` and `WCIsvDList<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

Requirements of Type

The `WCIsvSList<Type>` class requires only that `Type` is derived from `WCSLink`. The `WCIsvDList<Type>` class requires only that `Type` is derived from `WCDLink`.

Private Member Functions

In an intrusive list, copying a list is undefined. Setting the copy constructor and assignment operator as private is the standard mechanism to ensure a copy cannot be made. The following member functions are declared private:

```
void WCIsvSList( const WCIsvSList & );
void WCIsvDList( const WCIsvDList & );
WCIsvSList & WCIsvSList::operator =( const WCIsvSList & );
WCIsvDList & WCIsvDList::operator =( const WCIsvDList & );
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCIsvSList();
~WCIsvSList();
WCIsvDList();
~WCIsvDList();
int append( Type * );
void clear();
void clearAndDestroy();
int contains( const Type * ) const;
int entries() const;
Type * find( int = 0 ) const;
Type * findLast() const;
void forAll( void (*)( Type *, void * ), void * );
Type * get( int = 0 );
int index( const Type * ) const;
int index( int (*)( const Type *, void * ), void * ) const;
int insert( Type * );
int isEmpty() const;
```

Public Member Operators

The following member operators are declared in the public interface:

```
int WCIsvSList::operator ==( const WCIsvSList & ) const;
int WCIsvDList::operator ==( const WCIsvDList & ) const;
```

Sample Program Using an Intrusive List

```
#include <wclist.h>
#include <iostream.h>

class int_ddata : public WCDLink {
public:
    inline int_ddata() {};
    inline int_ddata() {};
    inline int_ddata( int datum ) : info( datum ) {};

    int      info;
};

static void test1( void );

void data_isv_prt( int_ddata * data, void * str ) {
    cout << (char *)str << "[" << data->info << "]\n";
}

void main() {
    try {
        test1();
    } catch( ... ) {
        cout << "we caught an unexpected exception\n";
    }
    cout.flush();
}

void test1 ( void ) {
    WCIsvDList<int_ddata>    list;
    int_ddata                  data1(1);
    int_ddata                  data2(2);
    int_ddata                  data3(3);
    int_ddata                  data4(4);
    int_ddata                  data5(5);

    list.exceptions( WCExcept::check_all );
    list.append( &data2 );
    list.append( &data3 );
    list.append( &data4 );

    list.insert( &data1 );
    list.append( &data5 );
    cout << "<intrusive double list for int_ddata>\n";
    list.forAll( data_isv_prt, "" );
    data_isv_prt( list.find( 3 ), "<the fourth element>" );
    data_isv_prt( list.get( 2 ), "<the third element>" );
    data_isv_prt( list.get(), "<the first element>" );
    list.clear();
    cout.flush();
}
```

Synopsis:

```
#include <wclist.h>
public:
WCIsvSList();
```

Semantics: The *WCIsvSList* public member function creates an empty *WCIsvSList* object.

Results: The *WCIsvSList* public member function produces an initialized *WCIsvSList* object.

See Also: ~*WCIsvSList*

WCIsvSList<Type>::WCIsvSList()

Synopsis:

```
#include <wclist.h>
private:
void WCIsvSList( const WCIsvSList & );
```

Semantics: The WCIsvSList private member function is the copy constructor for the single linked list class. Making a copy of the list object would result in a error condition, since intrusive lists cannot share data items with other lists.

Synopsis:

```
#include <wclist.h>
public:
~WCIsvSList();
```

Semantics: The ~WCIsvSList public member function destroys the WCIsvSList object. If the list is not empty and the not_empty exception is enabled, the exception is thrown. If the not_empty exception is not enabled and the list is not empty, the list is cleared using the clear member function. The call to the ~WCIsvSList public member function is inserted implicitly by the compiler at the point where the WCIsvSList object goes out of scope.

Results: The WCIsvSList object is destroyed.

See Also: WCIsvSList, clear, clearAndDestroy, WCExcept::not_empty

WCIsvDList<Type>::WCIsvDList()

Synopsis: `#include <wclist.h>`
 `public:`
 `WCIsvDList();`

Semantics: The WCIsvDList public member function creates an empty WCIsvDList object.

Results: The WCIsvDList public member function produces an initialized WCIsvDList object.

See Also: `~WCIsvDList`

Synopsis:

```
#include <wclist.h>
private:
WCIsvDList( const WCIsvDList & );
```

Semantics: The *WCIsvDList* private member function is the copy constructor for the double linked list class. Making a copy of the list object would result in a error condition, since intrusive lists cannot share data items with other lists.

WCIsvDList<Type>::~*WCIsvDList*()

Synopsis:

```
#include <wclist.h>
public:
~WCIsvDList();
```

Semantics: The ~WCIsvDList public member function destroys the WCIsvDList object. If the list is not empty and the not_empty exception is enabled, the exception is thrown. If the not_empty exception is not enabled and the list is not empty, the list is cleared using the clear member function. The call to the ~WCIsvDList public member function is inserted implicitly by the compiler at the point where the WCIsvDList object goes out of scope.

Results: The WCIsvDList object is destroyed.

See Also: WCIsvDList, clear, clearAndDestroy, WCExcept::not_empty

Synopsis:

```
#include <wclist.h>
public:
    int append( Type * );
```

Semantics: The append public member function is used to append the list element object to the end of the list. The address of (a pointer to) the list element object should be passed, not the value. Since the linkage information is stored in the list element, it is not possible for the element to be in more than one list, or in the same list more than once.

The passed list element should be constructed using the appropriate link class as a base. `WCSLink` must be used as a list element base class for single linked lists, and `WCDLink` must be used as a list element base class for double linked lists.

Results: The list element is appended to the end of the list and a TRUE value (non-zero) is returned.

See Also: `insert`

WCISvSList<Type>::clear(), WCISvDList<Type>::clear()

Synopsis:

```
#include <wclist.h>
public:
void clear();
```

Semantics: The `clear` public member function is used to clear the list object and set it to the state of the object just after the initial construction. The list object is not destroyed and re-created by this operator, so the object destructor is not invoked. The list elements are not cleared. Any list items still in the list are lost unless pointed to by some pointer object in the program code.

If any of the list elements are not allocated with `new` (local variable or global list elements), then the `clear` public member function must be used. When all list elements are allocated with `new`, the `clearAndDestroy` member function should be used.

Results: The `clear` public member function resets the list object to the state of the object immediately after the initial construction.

See Also: `~WCISvSList`, `~WCISvDList`, `clearAndDestroy`, `get`, `operator =`

Synopsis:

```
#include <wclist.h>
public:
void clearAndDestroy();
```

Semantics: The `clearAndDestroy` public member function is used to clear the list object and set it to the state of the object just after the initial construction. The list object is not destroyed and re-created by this operator, so the object destructor is not invoked. The link elements are deleted before the list is re-initialized.

If any elements in the list were not allocated by the `new` operator, the `clearAndDestroy` public member function must not be called. The `clearAndDestroy` public member function destroys each list element with the destructor for `Type` even if the list element was created as an object derived from `Type`, unless `Type` has a pure virtual destructor.

Results: The `clearAndDestroy` public member function resets the list object to the initial state of the object immediately after the initial construction and deletes the list elements.

See Also: `clear`, `get`

Synopsis:

```
#include <wclist.h>
public:
    int contains( const Type * ) const;
```

Semantics: The `contains` public member function is used to determine if a list element object is already contained in the list. The address of (a pointer to) the list element object should be passed, not the value. Each list element is compared to the passed element object to determine if it has the same address. Note that the comparison is of the addresses of the elements, not the contained values.

Results: Zero(0) is returned if the passed list element object is not found in the list. A non-zero result is returned if the element is found in the list.

See Also: `find`, `index`

Synopsis:

```
#include <wclist.h>
public:
    int entries() const;
```

Semantics: The `entries` public member function is used to determine the number of list elements contained in the list object.

Results: The number of entries stored in the list is returned, zero(0) is returned if there are no list elements.

See Also: `isEmpty`

WCIsvSList<Type>::find(), WCIsvDList<Type>::find()

Synopsis:

```
#include <wclist.h>
public:
    Type * find( int = 0 ) const;
```

Semantics: The `find` public member function returns a pointer to a list element in the list object. The list element is not removed from the list, so care must be taken not to delete the element returned to you. The optional parameter specifies which element to locate, and defaults to the first element. Since the first element of the list is the zero'th element, the last element will be the number of list entries minus one.

If the list is empty and the `empty_container` exception is enabled, the exception is thrown. If the `index_range` exception is enabled, the exception is thrown if the index value is negative or is greater than the number of list entries minus one.

Results: A pointer to the selected list element or the closest list element is returned. If the index value is negative, the closest list element is the first element. The last element is the closest element if the index value is greater than the number of list entries minus one. A value of `NULL(0)` is returned if there are no elements in the list.

See Also: `findLast`, `get`, `index`, `isEmpty`, `WCEExcept::empty_container`, `WCEExcept::index_range`

Synopsis:

```
#include <wclist.h>
public:
    Type * findLast() const;
```

Semantics: The `findLast` public member function returns a pointer to the last list element in the list object. The list element is not removed from the list, so care must be taken not to delete the element returned to you.

If the list is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, it is thrown. The `index_range` exception is thrown if it is enabled and the `empty_container` exception is not enabled.

Results: A pointer to the last list element is returned. A value of `NULL(0)` is returned if there are no elements in the list.

See Also: `find`, `get`, `isEmpty`, `WCExcept::empty_container`, `WCExcept::index_range`

WCIsvSList<Type>::forAll(), WCIsvDList<Type>::forAll()

Synopsis:

```
#include <wclist.h>
public:
    void forAll( void (*fn)( Type *, void * ), void * );
```

Semantics: The `forAll` public member function is used to cause the function *fn* to be invoked for each list element. The *fn* function should have the prototype

```
void (*fn)( Type *, void * )
```

The first parameter of *fn* shall accept a pointer to the list element currently active. The second argument passed to *fn* is the second argument of the `forAll` function. This allows a callback function to be defined which can accept data appropriate for the point at which the `forAll` function is invoked.

See Also: `WCIsvConstSListIter`, `WCIsvConstDListIter`, `WCIsvSListIter`, `WCIsvDListIter`

Synopsis:

```
#include <wclist.h>
public:
    Type * get( int = 0 );
```

Semantics: The `get` public member function returns a pointer to a list element in the list object. The list element is also removed from the list. The optional parameter specifies which element to remove, and defaults to the first element. Since the first element of the list is the zero'th element, the last element will be the number of list entries minus one.

If the list is empty and the `empty_container` exception is enabled, the exception is thrown. If the `index_range` exception trap is enabled, the exception is thrown if the index value is negative or is greater than the number of list entries minus one.

Results: A pointer to the selected list element or the closest list element is removed and returned. If the index value is negative, the closest list element is the first element. The last element is the closest element if the index value is greater than the number of list entries minus one. A value of `NULL(0)` is returned if there are no elements in the list.

See Also: `clear`, `clearAndDestroy`, `find`, `index`, `WCEexcept::empty_container`, `WCEexcept::index_range`

WCIsvSList<Type>::index(), WCIsvDList<Type>::index()

Synopsis:

```
#include <wclist.h>
public:
    int index( const Type * ) const;
```

Semantics: The `index` public member function is used to determine the index of the first list element equivalent to the passed element. The address of (a pointer to) the list element object should be passed, not the value. Each list element is compared to the passed element object to determine if it has the same address. Note that the comparison is of the addresses of the elements, not the contained values.

Results: The index of the first element equivalent to the passed element is returned. If the passed element is not in the list, negative one (-1) is returned.

See Also: `contains`, `find`, `get`

Synopsis:

```
#include <wclist.h>
public:
    int index( int (*test_fn)( const Type *, void * ),
               void * ) const;
```

Semantics: The `index` public member function is used to determine the index of the first list element for which the supplied `test_fn` function returns true. The `test_fn` function must have the prototype:

```
int (*test_fn)( const Type *, void * );
```

Each list element is passed in turn to the `test_fn` function as the first argument. The second parameter passed is the second argument of the `index` function. This allows the `test_fn` callback function to accept data appropriate for the point at which the `index` function is invoked. The supplied `test_fn` shall return a TRUE (non-zero) value when the index of the passed element is desired. Otherwise, a FALSE (zero) value shall be returned.

Results: The index of the first list element for which the `test_fn` function returns non-zero is returned. If the `test_fn` function returns zero for all list elements, negative one (-1) is returned.

See Also: `contains`, `find`, `get`

WCIsvSList<Type>::insert(), WCIsvDList<Type>::insert()

Synopsis:

```
#include <wcclist.h>
public:
    int insert( Type * );
```

Semantics: The *insert* public member function is used to insert the list element object to the beginning of the list. The address of (a pointer to) the list element object should be passed, not the value. Since the linkage information is stored in the list element, it is not possible for the element to be in more than one list, or in the same list more than once.

The passed list element should be constructed using the appropriate link class as a base. *WCSLink* must be used as a list element base class for single linked lists, and *WCDLink* must be used as a list element base class for double linked lists.

Results: The list element is inserted as the first element of the list and a TRUE value (non-zero) is returned.

See Also: *append*

Synopsis:

```
#include <wclist.h>
public:
    int isEmpty() const;
```

Semantics: The `isEmpty` public member function is used to determine if a list object has any list elements contained in it.

Results: A TRUE value (non-zero) is returned if the list object does not have any list elements contained within it. A FALSE (zero) result is returned if the list contains at least one element.

See Also: `entries`

WCIsvSList<Type>::operator =(), WCIsvDList<Type>::operator =()

Synopsis:

```
#include <wclist.h>
private:
WCIsvSList & WCIsvSList::operator =( const WCIsvSList & );
WCIsvDList & WCIsvDList::operator =( const WCIsvDList & );
```

Semantics:

The `operator =` private member function is the assignment operator for the class. Since making a copy of the list object would result in a error condition, it is made inaccessible by making it a private operator.

Synopsis:

```
#include <wclist.h>
public:
    int WCIsvSList::operator ==( const WCIsvSList & ) const;
    int WCIsvDList::operator ==( const WCIsvDList & ) const;
```

Semantics: The operator == public member function is the equivalence operator for the WCIsvSList<Type> and WCIsvDList<Type> classes. Two list objects are equivalent if they are the same object and share the same address.

Results: A TRUE (non-zero) value is returned if the left hand side object and the right hand side objects are the same object. A FALSE (zero) value is returned otherwise.

WCPtrSList<Type>, WCPtrDList<Type>

Declared: wclist.h

The `WCPtrSList<Type>` and `WCPtrDList<Type>` classes are the templated classes used to create objects which are single or double linked lists.

In the description of each member function, the text `Type` is used to indicate the type value specified as the template parameter. The pointers stored in the list point to values of type `Type`.

The `WCExcept` class is a base class of the `WCPtrSList<Type>` and `WCPtrDList<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCPtrSList<Type>` and `WCPtrDList<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

Requirements of Type

The `WCPtrSList<Type>` and `WCPtrDList<Type>` classes require `Type` to have:

(1) an equivalence operator with constant parameters

```
Type::operator ==( const Type & ) const
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrSList();
WCPtrSList( void * (*)( size_t ), void (*)( void *, size_t ) );
WCPtrSList( const WCPtrSList & );
~WCPtrSList();
WCPtrDList();
WCPtrDList( void * (*)( size_t ), void (*)( void *, size_t ) );
WCPtrDList( const WCPtrDList & );
~WCPtrDList();
int append( Type * );
void clear();
void clearAndDestroy();
int contains( const Type * ) const;
int entries() const;
Type * find( int = 0 ) const;
Type * findLast() const;
void forAll( void (*)( Type *, void * ), void * ) const;
Type * get( int = 0 );
int index( const Type * ) const;
int insert( Type * );
int isEmpty() const;
```

Public Member Operators

The following member operators are declared in the public interface:

```
WCPtrSList & WCPtrSList::operator =( const WCPtrSList & );
WCPtrDList & WCPtrDList::operator =( const WCPtrDList & );
int WCPtrSList::operator ==( const WCPtrSList & ) const;
int WCPtrDList::operator ==( const WCPtrDList & ) const;
```

Sample Program Using a Pointer List

```
#include <wclist.h>
#include <iostream.h>

static void test1( void );

void data_ptr_prt( int * data, void * str ) {
    cout << (char *)str << "[" << *data << "]`n";
}

void main() {
    try {
        test1();
    } catch( ... ) {
        cout << "we caught an unexpected exception`n";
    }
    cout.flush();
}

void test1 ( void ) {
    WCPtrDList<int>           list;
    int                         data1(1);
    int                         data2(2);
    int                         data3(3);
    int                         data4(4);
    int                         data5(5);

    list.append( &data2 );
    list.append( &data3 );
    list.append( &data4 );

    list.insert( &data1 );
    list.append( &data5 );
    cout << "<pointer double list for int>`n";
    list.forAll( data_ptr_prt, "" );
    data_ptr_prt( list.find( 3 ), "<the fourth element>" );
    data_ptr_prt( list.get( 2 ), "<the third element>" );
    data_ptr_prt( list.get(), "<the first element>" );
    list.clear();
    cout.flush();
}
```

WCPtrSList<Type>::WCPtrSList()

Synopsis: `#include <wclist.h>`
 `public:`
 `WCPtrSList();`

Semantics: The WCPtrSList public member function creates an empty WCPtrSList object.

Results: The WCPtrSList public member function produces an initialized WCPtrSList object.

See Also: WCPtrSList, ~WCPtrSList

Synopsis:

```
#include <wclist.h>
public:
WCPtrSList( void *(*allocator)( size_t ),  
void (*deallocator)( void *, size_t ) );
```

Semantics: The WCPtrSList public member function creates an empty WCPtrSList<Type> object. The *allocator* function is registered to perform all memory allocations of the list elements, and the *deallocator* function to perform all freeing of the list elements' memory. These functions provide the ability to control how the allocation and freeing of memory is performed, allowing for more efficient memory handling than the general purpose global operator new() and operator delete() can provide. Memory management optimizations may potentially be made through the *allocator* and *deallocator* functions, but are not recommended before managing memory is understood and determined to be worth while.

The *allocator* function shall return a pointer to allocated memory of size at least the argument, or zero(0) if the allocation cannot be performed. Initialization of the memory returned is performed by the WCPtrSList<Type> class.

The WCPtrSList<Type> class calls the *deallocator* function only on memory allocated by the *allocator* function. The *deallocator* shall free the memory pointed to by the first argument which is of size the second argument. The size passed to the *deallocator* function is guaranteed to be the same size passed to the *allocator* function when the memory was allocated.

The *allocator* and *deallocator* functions may assume that for a list object instance, the *allocator* is always called with the same first argument (the size of the memory to be allocated). The WCValSListItemSize(Type) macro returns the size of the elements which are allocated by the *allocator* function.

Results: The WCPtrSList public member function creates an initialized WCPtrSList<Type> object and registers the *allocator* and *deallocator* functions.

See Also: WCPtrSList, ~WCPtrSList

WCPtrSList<Type>::WCPtrSList()

Synopsis:

```
#include <wclist.h>
public:
void WCPtrSList( const WCPtrSList & );
```

Semantics: The `WCPtrSList` public member function is the copy constructor for the single linked list class. All of the list elements are copied to the new list, as well as the exception trap states, and any registered *allocator* and *deallocator* functions.

If all of the elements cannot be copied and the `out_of_memory` is enabled in the list being copied, the exception is thrown. The new list is created in a valid state, even if all of the list elements could not be copied.

Results: The `WCPtrSList` public member function produces a copy of the list.

See Also: `WCPtrSList`, `~WCPtrSList`, `clear`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wclist.h>
public:
~WCPtrSList();
```

Semantics: The ~WCPtrSList public member function destroys the WCPtrSList object. If the list is not empty and the not_empty exception is enabled, the exception is thrown. If the not_empty exception is not enabled and the list is not empty, the list is cleared using the clear member function. The call to the ~WCPtrSList public member function is inserted implicitly by the compiler at the point where the WCPtrSList object goes out of scope.

Results: The WCPtrSList object is destroyed.

See Also: WCPtrSList, clear, clearAndDestroy, WCExcept::not_empty

WCPtrDList<Type>::WCPtrDList()

Synopsis: `#include <wclist.h>`
 `public:`
 `WCPtrDList();`

Semantics: The WCPtrDList public member function creates an empty WCPtrDList object.

Results: The WCPtrDList public member function produces an initialized WCPtrDList object.

See Also: WCPtrDList, ~WCPtrDList

Synopsis:

```
#include <wclist.h>
public:
WCPtrDList( void *(*allocator)( size_t ),
void (*deallocator)( void *, size_t ) );
```

Semantics: The WCPtrDList public member function creates an empty WCPtrDList<Type> object. The *allocator* function is registered to perform all memory allocations of the list elements, and the *deallocator* function to perform all freeing of the list elements' memory. These functions provide the ability to control how the allocation and freeing of memory is performed, allowing for more efficient memory handling than the general purpose global operator new() and operator delete() can provide. Memory management optimizations may potentially be made through the *allocator* and *deallocator* functions, but are not recommended before managing memory is understood and determined to be worth while.

The *allocator* function shall return a pointer to allocated memory of size at least the argument, or zero(0) if the allocation cannot be performed. Initialization of the memory returned is performed by the WCPtrDList<Type> class.

The WCPtrDList<Type> class calls the *deallocator* function only on memory allocated by the *allocator* function. The *deallocator* shall free the memory pointed to by the first argument which is of size the second argument. The size passed to the *deallocator* function is guaranteed to be the same size passed to the *allocator* function when the memory was allocated.

The *allocator* and *deallocator* functions may assume that for a list object instance, the *allocator* is always called with the same first argument (the size of the memory to be allocated). The WCValDListItemSize(Type) macro returns the size of the elements which are allocated by the *allocator* function.

Results: The WCPtrDList public member function creates an initialized WCPtrDList<Type> object and registers the *allocator* and *deallocator* functions.

See Also: WCPtrDList, ~WCPtrDList

`WCPtrDList<Type>::WCPtrDList()`

Synopsis:

```
#include <wclist.h>
public:
WCPtrDList( const WCPtrDList & );
```

Semantics: The `WCPtrDList` public member function is the copy constructor for the double linked list class. All of the list elements are copied to the new list, as well as the exception trap states, and any registered *allocator* and *deallocator* functions.

If all of the elements cannot be copied and the `out_of_memory` is enabled in the list being copied, the exception is thrown. The new list is created in a valid state, even if all of the list elements could not be copied.

Results: The `WCPtrDList` public member function produces a copy of the list.

See Also: `WCPtrDList`, `~WCPtrDList`, `clear`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wclist.h>
public:
~WCPtrDList();
```

Semantics: The ~WCPtrDList public member function destroys the WCPtrDList object. If the list is not empty and the not_empty exception is enabled, the exception is thrown. If the not_empty exception is not enabled and the list is not empty, the list is cleared using the clear member function. The call to the ~WCPtrDList public member function is inserted implicitly by the compiler at the point where the WCPtrDList object goes out of scope.

Results: The WCPtrDList object is destroyed.

See Also: WCPtrDList, clear, clearAndDestroy, WCExcept::not_empty

WCPtrSList<Type>::append(), WCPtrDList<Type>::append()

Synopsis:

```
#include <wclist.h>
public:
    int append( Type * );
```

Semantics: The append public member function is used to append the data to the end of the list.

If the `out_of_memory` exception is enabled and the append fails, the exception is thrown.

Results: The data element is appended to the end of the list. A TRUE value (non-zero) is returned if the append is successful. A FALSE (zero) result is returned if the append fails.

See Also: `insert`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wclist.h>
public:
void clear();
```

Semantics: The `clear` public member function is used to clear the list object and set it to the state of the object just after the initial construction. The list object is not destroyed and re-created by this operator, so the object destructor is not invoked.

Results: The `clear` public member function resets the list object to the state of the object immediately after the initial construction.

See Also: `~WCPtrSList`, `~WCPtrDList`, `clearAndDestroy`, `get`, `operator =`

Synopsis:

```
#include <wclist.h>
public:
void clearAndDestroy();
```

Semantics: The `clearAndDestroy` public member function is used to clear the list object and set it to the state of the object just after the initial construction. The list object is not destroyed and re-created by this operator, so the object destructor is not invoked. Before the list object is re-initialized, the the values pointed to by the list elements are deleted.

Results: The `clearAndDestroy` public member function resets the list object to the initial state of the object immediately after the initial construction and deletes the list elements.

See Also: `clear`, `get`

Synopsis:

```
#include <wclist.h>
public:
    int contains( const Type * ) const;
```

Semantics: The `contains` public member function is used to determine if a list element object is already contained in the list. Each list element is compared to the passed element using `Type`'s `operator ==` to determine if the passed element is contained in the list. Note that the comparison is of the objects pointed to.

Results: Zero(0) is returned if the passed list element object is not found in the list. A non-zero result is returned if the element is found in the list.

See Also: `find`, `index`

Synopsis:

```
#include <wclist.h>
public:
    int entries() const;
```

Semantics: The `entries` public member function is used to determine the number of list elements contained in the list object.

Results: The number of entries stored in the list is returned, zero(0) is returned if there are no list elements.

See Also: `isEmpty`

Synopsis:

```
#include <wclist.h>
public:
    Type * find( int = 0 ) const;
```

Semantics: The `find` public member function returns the value of a list element in the list object. The optional parameter specifies which element to locate, and defaults to the first element. Since the first element of the list is the zero'th element, the last element will be the number of list entries minus one.

If the list is empty and the `empty_container` exception is enabled, the exception is thrown. If the `index_range` exception is enabled, the exception is thrown if the index value is negative or is greater than the number of list entries minus one.

Results: The value of the selected list element or the closest element is returned. If the index value is negative, the closest list element is the first element. The last element is the closest element if the index value is greater than the number of list entries minus one. An uninitialized pointer is returned if there are no elements in the list.

See Also: `findLast`, `get`, `index`, `isEmpty`, `WCExcept::empty_container`,
`WCExcept::index_range`

Synopsis:

```
#include <wclist.h>
public:
    Type * findLast() const;
```

Semantics: The `findLast` public member function returns the value of the last list element in the list object.

If the list is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, it is thrown. The `index_range` exception is thrown if it is enabled and the `empty_container` exception is not enabled.

Results: The value of the last list element is returned. An uninitialized pointer is returned if there are no elements in the list.

See Also: `find`, `get`, `isEmpty`, `WCExcept::empty_container`, `WCExcept::index_range`

Synopsis:

```
#include <wclist.h>
public:
void forAll( void (*) ( Type *, void * ), void * ) const;
```

Semantics: The `forAll` public member function is used to cause the function *fn* to be invoked for each list element. The *fn* function should have the prototype

```
void (*fn) ( Type *, void * )
```

The first parameter of *fn* shall accept the value of the list element currently active. The second argument passed to *fn* is the second argument of the `forAll` function. This allows a callback function to be defined which can accept data appropriate for the point at which the `forAll` function is invoked.

See Also: `WCPtrConstSListIter`, `WCPtrConstDListIter`, `WCPtrSListIter`, `WCPtrDListIter`

Synopsis:

```
#include <wclist.h>
public:
    Type * get( int = 0 );
```

Semantics: The `get` public member function returns the value of the list element in the list object. The list element is also removed from the list. The optional parameter specifies which element to remove, and defaults to the first element. Since the first element of the list is the zero'th element, the last element will be the number of list entries minus one.

If the list is empty and the `empty_container` exception is enabled, the exception is thrown. If the `index_range` exception trap is enabled, the exception is thrown if the index value is negative or is greater than the number of list entries minus one.

Results: The value of the selected list element or the closest element is removed and returned. If the index value is negative, the closest list element is the first element. The last element is the closest element if the index value is greater than the number of list entries minus one. An uninitialized pointer is returned if there are no elements in the list.

See Also: `clear`, `clearAndDestroy`, `find`, `index`, `WCExcept::empty_container`, `WCExcept::index_range`

Synopsis:

```
#include <wclist.h>
public:
    int index( const Type * ) const;
```

Semantics: The `index` public member function is used to determine the index of the first list element equivalent to the passed element. Each list element is compared to the passed element using `Type's operator ==` until the passed element is found, or all list elements have been checked. Note that the comparison is of the objects pointed to.

Results: The index of the first element equivalent to the passed element is returned. If the passed element is not in the list, negative one (-1) is returned.

See Also: `contains`, `find`, `get`

WCPtrSList<Type>::insert(), WCPtrDList<Type>::insert()

Synopsis:

```
#include <wclist.h>
public:
    int insert( Type * );
```

Semantics: The `insert` public member function is used to insert the data as the first element of the list.

If the `out_of_memory` exception is enabled and the insert fails, the exception is thrown.

Results: The data element is inserted into the beginning of the list. A TRUE value (non-zero) is returned if the insert is successful. A FALSE (zero) result is returned if the insert fails.

See Also: `append`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wclist.h>
public:
    int isEmpty() const;
```

Semantics: The `isEmpty` public member function is used to determine if a list object has any list elements contained in it.

Results: A TRUE value (non-zero) is returned if the list object does not have any list elements contained within it. A FALSE (zero) result is returned if the list contains at least one element.

See Also: `entries`

WCPtrSList<Type>::operator =(), WCPtrDList<Type>::operator =()

Synopsis:

```
#include <wclist.h>
public:
WCPtrSList & WCPtrSList::operator =( const WCPtrSList & );
WCPtrDList & WCPtrDList::operator =( const WCPtrDList & );
```

Semantics: The `operator =` public member function is the assignment operator for the class. The left hand side of the assignment is first cleared with the `clear` member function. All elements in the right hand side list are then copied, as well as the exception trap states, and any registered *allocator* and *deallocator* functions.

If all of the elements cannot be copied and the `out_of_memory` is enabled in the right hand side list, the exception is thrown. The new list is created in a valid state, even if all of the list elements could not be copied.

Results: The `operator =` public member function assigns the right hand side to the left hand side and returns a reference to the left hand side.

See Also: `WCPtrSList`, `WCPtrDList`, `clear`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wclist.h>
public:
    int WCPtrSList::operator ==( const WCPtrSList & ) const;
    int WCPtrDList::operator ==( const WCPtrDList & ) const;
```

Semantics: The operator == public member function is the equivalence operator for the WCPtrSList<Type> and WCPtrDList<Type> classes. Two list objects are equivalent if they are the same object and share the same address.

Results: A TRUE (non-zero) value is returned if the left hand side object and the right hand side objects are the same object. A FALSE (zero) value is returned otherwise.

Declared: wclcom.h

Derived by: WCDLink

The `WCSLink` class is the building block for all of the list classes. It provides the link that is used to traverse the list elements. The double link classes use the `WCSLink` class to implement both links. Since no user data is stored directly with it, the `WCSLink` class should only be used as a base class to derive a user defined class.

When creating a single linked intrusive list, the `WCSLink` class is used to derive the user defined class that holds the data to be inserted into the list.

The `wclcom.h` header file is included by the `wclist.h` header file. There is no need to explicitly include the `wclcom.h` header file unless the `wclist.h` header file is not included. No errors will result if it is included unnecessarily.

Note that the destructor is non-virtual so that list elements are of minimum size. Objects created as a class derived from the `WCSLink` class, but destroyed while typed as a `WCSLink` object will not invoke the destructor of the derived class..

Public Member Functions

The following public member functions are declared:

```
WCSLink();  
~WCSLink();
```

See Also: WCDLink

Synopsis:

```
#include <wclcom.h>
public:
WCSLink();
```

Semantics: The public `WCSLink` constructor creates an `WCSLink` object. The public `WCSLink` constructor is used implicitly by the compiler when it generates a constructor for a derived class.

Results: The public `WCSLink` constructor produces an initialized `WCSLink` object.

See Also: `~WCSLink`

WCSLink::~WCSLink()

Synopsis:

```
#include <wclcom.h>
public:
~WCSLink();
```

Semantics: The public ~WCSLink destructor does not do anything explicit. The call to the public ~WCSLink destructor is inserted implicitly by the compiler at the point where the object derived from WCSLink goes out of scope.

Results: The object derived from WCSLink is destroyed.

See Also: WCSLink

Declared: wclist.h

The `WCValSList<Type>` and `WCValDList<Type>` classes are the templated classes used to create objects which are single or double linked lists. Values are copied into the list, which could be undesirable if the stored objects are complicated and copying is expensive. Value lists should not be used to store objects of a base class if any derived types of different sizes would be stored in the list, or if the destructor for a derived class must be called.

In the description of each member function, the text `Type` is used to indicate the type value specified as the template parameter. `Type` is the type of the values stored in the list.

The `WCExcept` class is a base class of the `WCValSList<Type>` and `WCValDList<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCValSList<Type>` and `WCValDList<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

Requirements of Type

The `WCValSList<Type>` and `WCValDList<Type>` classes requires `Type` to have:

- (1) a default constructor (`Type::Type()`).
- (2) a well defined copy constructor (`Type::Type(const Type &)`).
- (3) an equivalence operator with constant parameters
`Type::operator ==(const Type &) const`

Public Member Functions

The following member functions are declared in the public interface:

```
WCValSList();
WCValSList( void * (*)( size_t ), void (*)( void *, size_t ) );
WCValSList( const WCValSList & );
~WCValSList();
WCValDList();
WCValDList( void * (*)( size_t ), void (*)( void *, size_t ) );
WCValDList( const WCValDList & );
~WCValDList();
int append( const Type & );
void clear();
void clearAndDestroy();
int contains( const Type & ) const;
int entries() const;
Type find( int = 0 ) const;
Type findLast() const;
void forAll( void (*)( Type, void * ), void * ) const;
Type get( int = 0 );
int index( const Type & ) const;
int insert( const Type & );
int isEmpty() const;
```

Public Member Operators

The following member operators are declared in the public interface:

```
WCValSList & WCValSList::operator =( const WCValSList & );
WCValDList & WCValDList::operator =( const WCValDList & );
int WCValSList::operator ==( const WCValSList & ) const;
int WCValDList::operator ==( const WCValDList & ) const;
```

Sample Program Using a Value List

```
#include <wclist.h>
#include <iostream.h>

static void test1( void );

void data_val_prt( int data, void * str ) {
    cout << (char *)str << "[" << data << "]\\n";
}

void main() {
    try {
        test1();
    } catch( ... ) {
        cout << "we caught an unexpected exception\\n";
    }
    cout.flush();
}

void test1 ( void ) {
    WCValDList<int>           list;

    list.append( 2 );
    list.append( 3 );
    list.append( 4 );

    list.insert( 1 );
    list.append( 5 );
    cout << "<value double list for int>\\n";
    list.forAll( data_val_prt, "" );
    data_val_prt( list.find( 3 ), "<the fourth element>" );
    data_val_prt( list.get( 2 ), "<the third element>" );
    data_val_prt( list.get(), "<the first element>" );
    list.clear();
    cout.flush();
}
```

Synopsis:

```
#include <wclist.h>
public:
WCValSList();
```

Semantics: The *WCValSList* public member function creates an empty *WCValSList* object.

Results: The *WCValSList* public member function produces an initialized *WCValSList* object.

See Also: *WCValSList*, *~WCValSList*

WCValsList<Type>::WCValsList()

Synopsis:

```
#include <wcclist.h>
public:
WCValsList( void *(*allocator)( size_t ),  
void (*deallocator)( void *, size_t ) );
```

Semantics: The `WCValsList` public member function creates an empty `WCValsList<Type>` object. The *allocator* function is registered to perform all memory allocations of the list elements, and the *deallocator* function to perform all freeing of the list elements' memory. These functions provide the ability to control how the allocation and freeing of memory is performed, allowing for more efficient memory handling than the general purpose global operator `new()` and operator `delete()` can provide. Memory management optimizations may potentially be made through the *allocator* and *deallocator* functions, but are not recommended before managing memory is understood and determined to be worth while.

The *allocator* function shall return a pointer to allocated memory of size at least the argument, or zero(0) if the allocation cannot be performed. Initialization of the memory returned is performed by the `WCValsList<Type>` class.

The `WCValsList<Type>` class calls the *deallocator* function only on memory allocated by the *allocator* function. The *deallocator* shall free the memory pointed to by the first argument which is of size the second argument. The size passed to the *deallocator* function is guaranteed to be the same size passed to the *allocator* function when the memory was allocated.

The *allocator* and *deallocator* functions may assume that for a list object instance, the *allocator* is always called with the same first argument (the size of the memory to be allocated). The `WCValsListItemSize(Type)` macro returns the size of the elements which are allocated by the *allocator* function.

Results: The `WCValsList` public member function creates an initialized `WCValsList<Type>` object and registers the *allocator* and *deallocator* functions.

See Also: `WCValsList`, `~WCValsList`

Synopsis:

```
#include <wclist.h>
public:
void WCValSList( const WCValSList & );
```

Semantics: The *WCValSList* public member function is the copy constructor for the single linked list class. All of the list elements are copied to the new list, as well as the exception trap states, and any registered *allocator* and *deallocator* functions. *Type*'s copy constructor is invoked to copy the values contained by the list elements.

If all of the elements cannot be copied and the *out_of_memory* is enabled in the list being copied, the exception is thrown. The new list is created in a valid state, even if all of the list elements could not be copied.

Results: The *WCValSList* public member function produces a copy of the list.

See Also: *WCValSList*, *~WCValSList*, *clear*, *WCExcept*::*out_of_memory*

WCValSList<Type>::~*WCValSList*()

Synopsis:

```
#include <wclist.h>
public:
~WCValSList();
```

Semantics: The ~WCValSList public member function destroys the WCValSList object. If the list is not empty and the not_empty exception is enabled, the exception is thrown. If the not_empty exception is not enabled and the list is not empty, the list is cleared using the clear member function. The call to the ~WCValSList public member function is inserted implicitly by the compiler at the point where the WCValSList object goes out of scope.

Results: The WCValSList object is destroyed.

See Also: WCValSList, clear, clearAndDestroy, WCExcept::not_empty

Synopsis:

```
#include <wclist.h>
public:
WCValDList();
```

Semantics: The *WCValDList* public member function creates an empty *WCValDList* object.

Results: The *WCValDList* public member function produces an initialized *WCValDList* object.

See Also: *WCValDList*, *~WCValDList*

WCValDList<Type>::WCValDList()

Synopsis:

```
#include <wclist.h>
public:
    WCValDList( void *(*allocator)( size_t ),  
                void (*deallocator)( void *, size_t ) );
```

Semantics: The `WCValDList` public member function creates an empty `WCValDList<Type>` object. The *allocator* function is registered to perform all memory allocations of the list elements, and the *deallocator* function to perform all freeing of the list elements' memory. These functions provide the ability to control how the allocation and freeing of memory is performed, allowing for more efficient memory handling than the general purpose global operator `new()` and operator `delete()` can provide. Memory management optimizations may potentially be made through the *allocator* and *deallocator* functions, but are not recommended before managing memory is understood and determined to be worth while.

The *allocator* function shall return a pointer to allocated memory of size at least the argument, or zero(0) if the allocation cannot be performed. Initialization of the memory returned is performed by the `WCValDList<Type>` class.

The `WCValDList<Type>` class calls the *deallocator* function only on memory allocated by the *allocator* function. The *deallocator* shall free the memory pointed to by the first argument which is of size the second argument. The size passed to the *deallocator* function is guaranteed to be the same size passed to the *allocator* function when the memory was allocated.

The *allocator* and *deallocator* functions may assume that for a list object instance, the *allocator* is always called with the same first argument (the size of the memory to be allocated). The `WCValDListItemSize(Type)` macro returns the size of the elements which are allocated by the *allocator* function.

Results: The `WCValDList` public member function creates an initialized `WCValDList<Type>` object and registers the *allocator* and *deallocator* functions.

See Also: `WCValDList`, `~WCValDList`

Synopsis:

```
#include <wclist.h>
public:
WCValDList( const WCValDList & );
```

Semantics: The *WCValDList* public member function is the copy constructor for the double linked list class. All of the list elements are copied to the new list, as well as the exception trap states, and any registered *allocator* and *deallocator* functions. *Type*'s copy constructor is invoked to copy the values contained by the list elements.

If all of the elements cannot be copied and the *out_of_memory* is enabled in the list being copied, the exception is thrown. The new list is created in a valid state, even if all of the list elements could not be copied.

Results: The *WCValDList* public member function produces a copy of the list.

See Also: *WCValDList*, *~WCValDList*, *clear*, *WCExcept*::*out_of_memory*

WCValDList<Type>::~*WCValDList*()

Synopsis:

```
#include <wclist.h>
public:
~WCValDList();
```

Semantics: The ~WCValDList public member function destroys the WCValDList object. If the list is not empty and the not_empty exception is enabled, the exception is thrown. If the not_empty exception is not enabled and the list is not empty, the list is cleared using the clear member function. The call to the ~WCValDList public member function is inserted implicitly by the compiler at the point where the WCValDList object goes out of scope.

Results: The WCValDList object is destroyed.

See Also: WCValDList, clear, clearAndDestroy, WCExcept::not_empty

Synopsis:

```
#include <wclist.h>
public:
    int append( const Type & );
```

Semantics: The append public member function is used to append the data to the end of the list. The data stored in the list is a copy of the data passed as a parameter.

If the `out_of_memory` exception is enabled and the append fails, the exception is thrown.

Results: The data element is appended to the end of the list. A TRUE value (non-zero) is returned if the append is successful. A FALSE (zero) result is returned if the append fails.

See Also: `insert`, `WCExcept::out_of_memory`

WCValSList<Type>::clear(), WCValDList<Type>::clear()

Synopsis:

```
#include <wclist.h>
public:
void clear();
```

Semantics: The `clear` public member function is used to clear the list object and set it to the state of the object just after the initial construction. The list object is not destroyed and re-created by this operator, so the object destructor is not invoked.

The `clear` public member function has the same semantics as the `clearAndDestroy` member function.

Results: The `clear` public member function resets the list object to the state of the object immediately after the initial construction.

See Also: `~WCValSList`, `~WCValDList`, `clearAndDestroy`, `get`, `operator =`

Synopsis:

```
#include <wclist.h>
public:
void clearAndDestroy();
```

Semantics: The `clearAndDestroy` public member function is used to clear the list object and set it to the state of the object just after the initial construction. The list object is not destroyed and re-created by this operator, so the object destructor is not invoked.

Before the list object is re-initialized, the delete operator is called for each list element.

Results: The `clearAndDestroy` public member function resets the list object to the initial state of the object immediately after the initial construction.

See Also: `clear`, `get`

WCValSList<Type>::contains(), WCValDList<Type>::contains()

Synopsis:

```
#include <wclist.h>
public:
    int contains( const Type & ) const;
```

Semantics: The `contains` public member function is used to determine if a list element object is already contained in the list. Each list element is compared to the passed element using `Type`'s `operator ==` to determine if the passed element is contained in the list.

Results: Zero(0) is returned if the passed list element object is not found in the list. A non-zero result is returned if the element is found in the list.

See Also: `find`, `index`

Synopsis:

```
#include <wclist.h>
public:
    int entries() const;
```

Semantics: The `entries` public member function is used to determine the number of list elements contained in the list object.

Results: The number of entries stored in the list is returned, zero(0) is returned if there are no list elements.

See Also: `isEmpty`

WCValSList<Type>::find(), WCValDList<Type>::find()

Synopsis:

```
#include <wclist.h>
public:
    Type find( int = 0 ) const;
```

Semantics: The `find` public member function returns the value of a list element in the list object. The optional parameter specifies which element to locate, and defaults to the first element. Since the first element of the list is the zero'th element, the last element will be the number of list entries minus one.

If the list is empty and the `empty_container` exception is enabled, the exception is thrown. If the `index_range` exception is enabled, the exception is thrown if the index value is negative or is greater than the number of list entries minus one.

Results: The value of the selected list element or the closest element is returned. If the index value is negative, the closest list element is the first element. The last element is the closest element if the index value is greater than the number of list entries minus one. A default initialized value is returned if there are no elements in the list.

See Also: `findLast`, `get`, `index`, `isEmpty`, `WCExcept::empty_container`, `WCExcept::index_range`

Synopsis:

```
#include <wclist.h>
public:
    Type findLast() const;
```

Semantics: The `findLast` public member function returns the value of the last list element in the list object.

If the list is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, it is thrown. The `index_range` exception is thrown if it is enabled and the `empty_container` exception is not enabled.

Results: The value of the last list element is returned. A default initialized value is returned if there are no elements in the list.

See Also: `find`, `get`, `isEmpty`, `WCExcept::empty_container`, `WCExcept::index_range`

WCValSList<Type>::forAll(), WCValDList<Type>::forAll()

Synopsis:

```
#include <wclist.h>
public:
    void forAll( void (*) ( Type, void * ), void * ) const;
```

Semantics: The `forAll` public member function is used to cause the function *fn* to be invoked for each list element. The *fn* function should have the prototype

```
void (*fn) ( Type, void * )
```

The first parameter of *fn* shall accept the value of the list element currently active. The second argument passed to *fn* is the second argument of the `forAll` function. This allows a callback function to be defined which can accept data appropriate for the point at which the `forAll` function is invoked.

See Also: `WCValConstSListIter`, `WCValConstDListIter`, `WCValSListIter`, `WCValDListIter`

Synopsis:

```
#include <wclist.h>
public:
    Type get( int = 0 );
```

Semantics: The `get` public member function returns the value of the list element in the list object. The list element is also removed from the list. The optional parameter specifies which element to remove, and defaults to the first element. Since the first element of the list is the zero'th element, the last element will be the number of list entries minus one.

If the list is empty and the `empty_container` exception is enabled, the exception is thrown. If the `index_range` exception trap is enabled, the exception is thrown if the index value is negative or is greater than the number of list entries minus one.

Results: The value of the selected list element or the closest element is removed and returned. If the index value is negative, the closest list element is the first element. The last element is the closest element if the index value is greater than the number of list entries minus one. A default initialized value is returned if there are no elements in the list.

See Also: `clear`, `clearAndDestroy`, `find`, `index`, `WCEexcept::empty_container`, `WCEexcept::index_range`

WCValSList<Type>::index(), WCValDList<Type>::index()

Synopsis:

```
#include <wclist.h>
public:
    int index( const Type & ) const;
```

Semantics: The `index` public member function is used to determine the index of the first list element equivalent to the passed element. Each list element is compared to the passed element using `Type`'s `operator ==` until the passed element is found, or all list elements have been checked.

Results: The index of the first element equivalent to the passed element is returned. If the passed element is not in the list, negative one (-1) is returned.

See Also: `contains`, `find`, `get`

Synopsis:

```
#include <wclist.h>
public:
    int insert( const Type & );
```

Semantics: The `insert` public member function is used to insert the data as the first element of the list. The data stored in the list is a copy of the data passed as a parameter.

If the `out_of_memory` exception is enabled and the `insert` fails, the exception is thrown.

Results: The data element is inserted into the beginning of the list. A TRUE value (non-zero) is returned if the `insert` is successful. A FALSE (zero) result is returned if the `insert` fails.

See Also: `append`, `WCExcept::out_of_memory`

WCValSList<Type>::isEmpty(), WCValDList<Type>::isEmpty()

Synopsis:

```
#include <wclist.h>
public:
    int isEmpty() const;
```

Semantics: The `isEmpty` public member function is used to determine if a list object has any list elements contained in it.

Results: A TRUE value (non-zero) is returned if the list object does not have any list elements contained within it. A FALSE (zero) result is returned if the list contains at least one element.

See Also: `entries`

Synopsis:

```
#include <wclist.h>
public:
WCValSList & WCValSList::operator =( const WCValSList & );
WCValDList & WCValDList::operator =( const WCValDList & );
```

Semantics: The `operator =` public member function is the assignment operator for the class. The left hand side of the assignment is first cleared with the `clear` member function. All elements in the right hand side list are then copied, as well as the exception trap states, and any registered *allocator* and *deallocator* functions. `Type`'s copy constructor is invoked to copy the values contained by the list elements.

If all of the elements cannot be copied and the `out_of_memory` is enabled in the right hand side list, the exception is thrown. The new list is created in a valid state, even if all of the list elements could not be copied.

Results: The `operator =` public member function assigns the right hand side to the left hand side and returns a reference to the left hand side.

See Also: `WCValSList`, `WCValDList`, `clear`, `WCExcept::out_of_memory`

WCValSList<Type>::operator ==(), WCValDList<Type>::operator ==()

Synopsis:

```
#include <wclist.h>
public:
    int WCValSList::operator ==( const WCValSList & ) const;
    int WCValDList::operator ==( const WCValDList & ) const;
```

Semantics:

The operator == public member function is the equivalence operator for the WCValSList<Type> and WCValDList<Type> classes. Two list objects are equivalent if they are the same object and share the same address.

Results:

A TRUE (non-zero) value is returned if the left hand side object and the right hand side objects are the same object. A FALSE (zero) value is returned otherwise.

13 List Iterators

List iterators operate on single or double linked lists. They are used to step through a list one or more elements at a time. The choice of which type of iterator to use is determined by the list you wish to iterate over. For example, to iterate over a non-constant `WCISvDList<Type>` object, use the `WCISvDListIter<Type>` class. A constant `WCValSList<Type>` object can be iterated using the `WCValConstSListIter<Type>` class. The iterators which correspond to the single link list containers have some functionality inhibited. If backward traversal is required, the double linked containers and corresponding iterators must be used.

Like all WATCOM iterators, newly constructed and reset iterators are positioned before the first element in the list. The list may be traversed one element at a time using the pre-increment or call operator. An increment operation causing the iterator to be positioned after the end of the list returns zero. Further increments will cause the `undef_iter` exception to be thrown, if it is enabled. This behaviour allows lists to be traversed simply using a while loop, and is demonstrated in the examples for the iterator classes.

The classes are presented in alphabetical order. The `WCIterExcept` class provides the common exception handling control interface for all of the iterators.

Since the iterator classes are all template classes, deriving most of the functionality from common base classes was used. In the listing of class member functions, those public member functions which appear to be in the iterator class but are actually defined in the common base class are identified as if they were explicitly specified in the iterator class.

WCIsvConstSListIter<Type>, WCIsvConstDListIter<Type>

Declared: wclistit.h

The WCIsvConstSListIter<Type> and WCIsvConstDListIter<Type> classes are the templated classes used to create iterator objects for constant single and double linked list objects. These classes may be used to iterate over non-constant lists, but the WCIsvDListIter<Type> and WCIsvSListIter<Type> classes provide additional functionality for only non-constant lists.

In the description of each member function, the text Type is used to indicate the list element type specified as the template parameter.

The WCIterExcept class is a base class of the WCIsvConstSListIter<Type> and WCIsvConstDListIter<Type> classes and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCIsvConstSListIter<Type> and WCIsvConstDListIter<Type> objects. No exceptions are enabled unless they are set by the exceptions member function.

Private Member Functions

Some functionality supported by base classes of the iterator are not appropriate for the constant list iterator classes. Setting those functions as private members in the derived class is the standard mechanism to prevent them from being invoked.

```
int append( Type * );
int insert( Type * );
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCIsvConstSListIter();
WCIsvConstSListIter( const WCIsvSList<Type> & );
~WCIsvConstSListIter();
WCIsvConstDListIter();
WCIsvConstDListIter( const WCIsvDList<Type> & );
~WCIsvConstDListIter();
const WCIsvSList<Type> *WCIsvConstSListIter<Type>::container() const;
const WCIsvDList<Type> *WCIsvConstDListIter<Type>::container() const;
Type * current() const;
void reset();
void WCIsvConstSListIter<Type>::reset( const WCIsvSList<Type> & );
void WCIsvConstDListIter<Type>::reset( const WCIsvDList<Type> & );
```

Public Member Operators

The following member operators are declared in the public interface:

```
Type * operator ()();
Type * operator ++();
Type * operator +=( int );
```

In the iterators for double linked lists only:

```
Type * operator --();
Type * operator ==( int );
```

See Also: WCIsvSList::forAll, WCIsvDList::forAll

Synopsis:

```
#include <wclistit.h>
public:
WCIsvConstSListIter();
```

Semantics: The `WCIsvConstSListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCIsvConstSListIter` public member function creates an initialized `WCIsvConstSListIter` object.

See Also: `WCIsvConstSListIter`, `~WCIsvConstSListIter`, `reset`

WCIsvConstSListIter<Type>::WCIsvConstSListIter()

Synopsis:	<pre>#include <wclistit.h> public: WCIsvConstSListIter(const WCIsvSList<Type> &);</pre>
Semantics:	The WCIsvConstSListIter public member function is a constructor for the class. The value passed as a parameter is a WCIsvSList list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator <code>++</code> , operator <code>()</code> , or operator <code>+=</code> operators.
Results:	The WCIsvConstSListIter public member function creates an initialized WCIsvConstSListIter object positioned before the first element in the list.
See Also:	<code>~WCIsvConstSListIter</code> , <code>operator ()</code> , <code>operator ++</code> , <code>operator +=</code> , <code>reset</code>

Synopsis:

```
#include <wclistit.h>
public:
~WCIsvConstSListIter();
```

Semantics: The ~WCIsvConstSListIter public member function is the destructor for the class. The call to the ~WCIsvConstSListIter public member function is inserted implicitly by the compiler at the point where the WCIsvConstSListIter object goes out of scope.

Results: The WCIsvConstSListIter object is destroyed.

See Also: WCIsvConstSListIter

WCIsvConstDListIter<Type>::WCIsvConstDListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCIsvConstDListIter();
```

Semantics: The `WCIsvConstDListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCIsvConstDListIter` public member function creates an initialized `WCIsvConstDListIter` object.

See Also: `WCIsvConstDListIter`, `~WCIsvConstDListIter`, `reset`

Synopsis:

```
#include <wclistit.h>
public:
WCIsvConstDListIter( const WCIsvDList<Type> & );
```

Semantics: The WCIsvConstDListIter public member function is a constructor for the class. The value passed as a parameter is the WCIsvDList list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The WCIsvConstDListIter public member function creates an initialized WCIsvConstDListIter object positioned before the first list element.

See Also: WCIsvConstDListIter, ~WCIsvConstDListIter, operator `()`, operator `++`, operator `+=`, reset

WCIsvConstDListIter<Type>::~WCIsvConstDListIter()

Synopsis:

```
#include <wclistit.h>
public:
~WCIsvConstDListIter();
```

Semantics: The ~WCIsvConstDListIter public member function is the destructor for the class. The call to the ~WCIsvConstDListIter public member function is inserted implicitly by the compiler at the point where the WCIsvConstDListIter object goes out of scope.

Results: The WCIsvConstDListIter object is destroyed.

See Also: WCIsvConstDListIter

Synopsis:

```
#include <wclistit.h>
public:
const WCIsvSList<Type> *WCIsvConstSListIter<Type>::container() const;
const WCIsvDList<Type> *WCIsvConstDListIter<Type>::container() const;
```

Semantics: The `container` public member function returns a pointer to the list container object. If the iterator has not been initialized with a list object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the list object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a list.

See Also: `WCIsvConstSListIter`, `WCIsvConstDListIter`, `reset`, `WCIterExcept::undef_iter`

WCIsvConstSListIter<Type>::current(), WCIsvConstDListIter<Type>::current()

Synopsis:

```
#include <wclistit.h>
public:
    Type * current();
```

Semantics: The `current` public member function returns a pointer to the list item at the current iterator position.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: A pointer to the current list element is returned. If the current element is undefined, `NULL(0)` is returned.

See Also: `operator ()`, `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_item`

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is incremented past the end of the list.

See Also: `operator ++, operator +=, operator --, operator -=, reset,`
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator +=`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator +=( int );
```

Semantics: The operator `+=` public member function accepts an integer value that causes the iterator to move that many elements after the current item. If the iterator was positioned before the first element in the list, the operation will set the current item to be the given element in the list.

If the current item was after the last element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to increment the iterator position more than element after the end of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `+=` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator --();
```

Semantics: The operator -- public member function is the pre-decrement operator for the class. The list element previous to the current item is set to be the new current item. If the current item was the first element in the list, the iterator is positioned before the first element in the list. If the list is empty, the iterator will be positioned before the start of the list.

If the iterator was positioned after the last element in the list, the current item will be set to the last element.

If the iterator is not associated with a list or the iterator position previous to the decrement was before the first element the list, the `undef_iter` exception is thrown, if enabled.

Results: The operator -- public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is decremented past the first element of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator -=`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator -( int );
```

Semantics: The operator `-=` public member function accepts an integer value that causes the iterator to move that many elements before the current item. If the iterator was positioned after the last element in the list, the operation will set the current item to be the given number of elements from the end of the list.

If the current item was before the first element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to decrement the iterator position more than one element before the beginning of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `-=` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is decremented past the first element in the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator --`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

WCIsvConstSListIter<Type>::reset(), WCIsvConstDListIter<Type>::reset()

Synopsis:

```
#include <wclistit.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated list.

Results: The iterator is positioned before the first list element.

See Also: `WCIsvConstSListIter`, `WCIsvConstDListIter`, `container`

Synopsis:

```
#include <wclistit.h>
public:
void WCIsvConstSListIter<Type>::reset( const WCIsvSList<Type> & );
void WCIsvConstDListIter<Type>::reset( const WCIsvDList<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified list. The iterator is positioned before the first element in the list.

Results: The iterator is positioned before the first element of the specified list.

See Also: `WCIsvConstSListIter`, `WCIsvConstDListIter`, `container`

Declared: wclistit.h

The WCIsvSListIter<Type> and WCIsvDListIter<Type> classes are the templated classes used to create iterator objects for single and double linked list objects. These classes can be used only for non-constant lists. The WCIsvDConstListIter<Type> and WCIsvSConstListIter<Type> classes are provided to iterate over constant lists.

In the description of each member function, the text Type is used to indicate the list element type specified as the template parameter.

The WCIterExcept class is a base class of the WCIsvSListIter<Type> and WCIsvDListIter<Type> classes and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCIsvSListIter<Type> and WCIsvDListIter<Type> objects. No exceptions are enabled unless they are set by the exceptions member function.

Private Member Functions

Some functionality supported by base classes of the iterator are not appropriate in the single linked list iterator classes. Setting those functions as private members in the derived class is the standard mechanism to prevent them from being invoked. The following member functions are declared in the single linked list iterator private interface:

```
Type * operator --();
Type * operator --( int );
int insert( Type * );
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCIsvSListIter();
WCIsvSListIter( WCIsvSList<Type> & );
~WCIsvSListIter();
WCIsvDListIter();
WCIsvDListIter( WCIsvDList<Type> & );
~WCIsvDListIter();
int append( Type * );
WCIsvSList<Type> *WCIsvSListIter<Type>::container() const;
WCIsvDList<Type> *WCIsvDListIter<Type>::container() const;
Type * current() const;
void reset();
void WCIsvSListIter<Type>::reset( WCIsvSList<Type> & );
void WCIsvDListIter<Type>::reset( WCIsvDList<Type> & );
```

In the iterators for double linked lists only:

```
int insert( Type * );
```

Public Member Operators

The following member operators are declared in the public interface:

```
Type * operator ()();
Type * operator ++();
Type * operator +=( int );
```

In the iterators for double linked lists only:

```
Type * operator --();  
Type * operator --( int );
```

See Also: [WCIsvSList::forAll](#), [WCIsvDList::forAll](#)

WCIsvSListIter<Type>::WCIsvSListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCIsvSListIter();
```

Semantics: The `WCIsvSListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCIsvSListIter` public member function creates an initialized `WCIsvSListIter` object.

See Also: `WCIsvSListIter`, `~WCIsvSListIter`, `reset`

Synopsis:

```
#include <wcclistit.h>
public:
WCIsvSListIter( WCIsvSList<Type> & );
```

Semantics: The `WCIsvSListIter` public member function is a constructor for the class. The value passed as a parameter is a `WCIsvSList` list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The `WCIsvSListIter` public member function creates an initialized `WCIsvSListIter` object positioned before the first element in the list.

See Also: `~WCIsvSListIter`, `operator ()`, `operator ++`, `operator +=`, `reset`

WCIsvSListIter<Type>::~WCIsvSListIter()

Synopsis:

```
#include <wcclistit.h>
public:
~WCIsvSListIter();
```

Semantics: The ~WCIsvSListIter public member function is the destructor for the class. The call to the ~WCIsvSListIter public member function is inserted implicitly by the compiler at the point where the WCIsvSListIter object goes out of scope.

Results: The WCIsvSListIter object is destroyed.

See Also: WCIsvSListIter

Synopsis:

```
#include <wclistit.h>
public:
WCIsvDListIter();
```

Semantics: The `WCIsvDListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCIsvDListIter` public member function creates an initialized `WCIsvDListIter` object.

See Also: `WCIsvDListIter`, `~WCIsvDListIter`, `reset`

WCIsvDListIter<Type>::WCIsvDListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCIsvDListIter( WCIsvDList<Type> & );
```

Semantics: The `WCIsvDListIter` public member function is a constructor for the class. The value passed as a parameter is the `WCIsvDList` list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The `WCIsvDListIter` public member function creates an initialized `WCIsvDListIter` object positioned before the first list element.

See Also: `WCIsvDListIter`, `~WCIsvDListIter`, operator `()`, operator `++`, operator `+=`, `reset`

Synopsis:

```
#include <wclistit.h>
public:
~WCIsvDListIter();
```

Semantics: The `~WCIsvDListIter` public member function is the destructor for the class. The call to the `~WCIsvDListIter` public member function is inserted implicitly by the compiler at the point where the `WCIsvDListIter` object goes out of scope.

Results: The `WCIsvDListIter` object is destroyed.

See Also: `WCIsvDListIter`

WCIsvSListIter<Type>::append(), WCIsvDListIter<Type>::append()

Synopsis:

```
#include <wcclistit.h>
public:
    int append( Type * );
```

Semantics: The append public member function inserts a new element into the list container object. The new element is inserted after the current iterator item.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. The element is not appended. If the `undef_iter` exception is enabled, it is thrown.

Results: The new element is inserted after the current iterator item. A TRUE value (non-zero) is returned if the append is successful. A FALSE (zero) result is returned if the append fails.

See Also: `insert`, `WCExcept::out_of_memory`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
WCIsvSList<Type> *WCIsvSListIter<Type>::container() const;
WCIsvDList<Type> *WCIsvDListIter<Type>::container() const;
```

Semantics: The `container` public member function returns a pointer to the list container object. If the iterator has not been initialized with a list object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the list object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a list.

See Also: `WCIsvSListIter`, `WCIsvDListIter`, `reset`, `WCIterExcept::undef_iter`

WCIsvSListIter<Type>::current(), WCIsvDListIter<Type>::current()

Synopsis:

```
#include <wclistit.h>
public:
    Type * current();
```

Semantics: The *current* public member function returns a pointer to the list item at the current iterator position.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. In this case the *undef_item* exception is thrown, if enabled.

Results: A pointer to the current list element is returned. If the current element is undefined, NULL(0) is returned.

See Also: operator (), operator ++, operator +=, operator --, operator -=, reset,
WCIterExcept::*undef_item*

Synopsis:

```
#include <wclistit.h>
public:
    int insert( Type * );
```

Semantics: The `insert` public member function inserts a new element into the list container object. The new element is inserted before the current iterator item. This process uses the previous link in the double linked list, so the `insert` public member function is not allowed with single linked lists.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. The element is not inserted. If the `undef_iter` exception is enabled, the exception is thrown.

Results: The new element is inserted before the current iterator item. A TRUE value (non-zero) is returned if the insert is successful. A FALSE (zero) result is returned if the insert fails.

See Also: `append`, `WCExcept::out_of_memory`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is incremented past the end of the list.

See Also: `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator +=`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

WCIsvSListIter<Type>, WCIsvDListIter<Type>::operator +=()

Synopsis:

```
#include <wclistit.h>
public:
    Type * operator +=( int );
```

Semantics: The `operator +=` public member function accepts an integer value that causes the iterator to move that many elements after the current item. If the iterator was positioned before the first element in the list, the operation will set the current item to be the given element in the list.

If the current item was after the last element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to increment the iterator position more than element after the end of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The `operator +=` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wcclistit.h>
public:
    Type * operator --();
```

Semantics: The operator -- public member function is the pre-decrement operator for the class. The list element previous to the current item is set to be the new current item. If the current item was the first element in the list, the iterator is positioned before the first element in the list. If the list is empty, the iterator will be positioned before the start of the list.

If the iterator was positioned after the last element in the list, the current item will be set to the last element.

If the iterator is not associated with a list or the iterator position previous to the decrement was before the first element the list, the `undef_iter` exception is thrown, if enabled.

Results: The operator -- public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is decremented past the first element of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

WCIsvDListIter<Type>::operator -=()

Synopsis:

```
#include <wcclistit.h>
public:
    Type * operator -=( int );
```

Semantics: The operator `-=` public member function accepts an integer value that causes the iterator to move that many elements before the current item. If the iterator was positioned after the last element in the list, the operation will set the current item to be the given number of elements from the end of the list.

If the current item was before the first element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to decrement the iterator position more than one element before the beginning of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `-=` public member function returns a pointer to the new current item. `NULL(0)` is returned when the iterator is decremented past the first element in the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator --`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wcclistit.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated list.

Results: The iterator is positioned before the first list element.

See Also: `WCIsvSListIter`, `WCIsvDListIter`, `container`

WCIsvSListIter<Type>::reset(), WCIsvDListIter<Type>::reset()

Synopsis:

```
#include <wcclistit.h>
public:
void WCIsvSListIter<Type>::reset( WCIsvSList<Type> & );
void WCIsvDListIter<Type>::reset( WCIsvDList<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified list. The iterator is positioned before the first element in the list.

Results: The iterator is positioned before the first element of the specified list.

See Also: `WCIsvSListIter`, `WCIsvDListIter`, `container`

Declared: wclistit.h

The `WCPtrConstSListIter<Type>` and `WCPtrConstDListIter<Type>` classes are the templated classes used to create iterator objects for constant single and double linked list objects. These classes may be used to iterate over non-constant lists, but the `WCPtrDListIter<Type>` and `WCPtrSListIter<Type>` classes provide additional functionality for only non-constant lists.

In the description of each member function, the text `Type` is used to indicate the list element type specified as the template parameter.

The `WCIterExcept` class is a base class of the `WCPtrConstSListIter<Type>` and `WCPtrConstDListIter<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCPtrConstSListIter<Type>` and `WCPtrConstDListIter<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

Private Member Functions

Some functionality supported by base classes of the iterator are not appropriate for the constant list iterator classes. Setting those functions as private members in the derived class is the standard mechanism to prevent them from being invoked.

```
int append( Type * );
int insert( Type * );
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrConstSListIter();
WCPtrConstSListIter( const WCPtrSList<Type> & );
~WCPtrConstSListIter();
WCPtrConstDListIter();
WCPtrConstDListIter( const WCPtrDList<Type> & );
~WCPtrConstDListIter();
const WCPtrSList<Type> *WCPtrConstSListIter<Type>::container() const;
const WCPtrDList<Type> *WCPtrConstDListIter<Type>::container() const;
Type * current() const;
void reset();
void WCPtrConstSListIter<Type>::reset( const WCPtrSList<Type> & );
void WCPtrConstDListIter<Type>::reset( const WCPtrDList<Type> & );
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
int operator +=( int );
```

In the iterators for double linked lists only:

```
int operator --();
int operator -=( int );
```

See Also: `WCPtrSList::forAll`, `WCPtrDList::forAll`

WCPtrConstSListIter<Type>::WCPtrConstSListIter()

Synopsis:

```
#include <wclistit.h>
public:
    WCPtrConstSListIter();
```

Semantics: The `WCPtrConstSListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCPtrConstSListIter` public member function creates an initialized `WCPtrConstSListIter` object.

See Also: `WCPtrConstSListIter`, `~WCPtrConstSListIter`, `reset`

Synopsis:	<pre>#include <wclistit.h> public: WCPtrConstSListIter(const WCPtrSList<Type> &);</pre>
Semantics:	The <code>WCPtrConstSListIter</code> public member function is a constructor for the class. The value passed as a parameter is a <code>WCPtrSList</code> list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator <code>++</code> , operator <code>()</code> , or operator <code>+=</code> operators.
Results:	The <code>WCPtrConstSListIter</code> public member function creates an initialized <code>WCPtrConstSListIter</code> object positioned before the first element in the list.
See Also:	<code>~WCPtrConstSListIter</code> , operator <code>()</code> , operator <code>++</code> , operator <code>+=</code> , <code>reset</code>

WCPtrConstSListIter<Type>::~WCPtrConstSListIter()

Synopsis:

```
#include <wclistit.h>
public:
~WCPtrConstSListIter();
```

Semantics: The ~WCPtrConstSListIter public member function is the destructor for the class. The call to the ~WCPtrConstSListIter public member function is inserted implicitly by the compiler at the point where the WCPtrConstSListIter object goes out of scope.

Results: The WCPtrConstSListIter object is destroyed.

See Also: WCPtrConstSListIter

Synopsis:

```
#include <wclistit.h>
public:
WCPtrConstDListIter();
```

Semantics: The `WCPtrConstDListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCPtrConstDListIter` public member function creates an initialized `WCPtrConstDListIter` object.

See Also: `WCPtrConstDListIter`, `~WCPtrConstDListIter`, `reset`

WCPtrConstDListIter<Type>::WCPtrConstDListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCPtrConstDListIter( const WCPtrDList<Type> & );
```

Semantics: The `WCPtrConstDListIter` public member function is a constructor for the class. The value passed as a parameter is the `WCPtrDList` list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The `WCPtrConstDListIter` public member function creates an initialized `WCPtrConstDListIter` object positioned before the first list element.

See Also: `WCPtrConstDListIter`, `~WCPtrConstDListIter`, operator `()`, operator `++`, operator `+=`, `reset`

Synopsis:

```
#include <wclistit.h>
public:
~WCPtrConstDListIter();
```

Semantics: The `~WCPtrConstDListIter` public member function is the destructor for the class. The call to the `~WCPtrConstDListIter` public member function is inserted implicitly by the compiler at the point where the `WCPtrConstDListIter` object goes out of scope.

Results: The `WCPtrConstDListIter` object is destroyed.

See Also: `WCPtrConstDListIter`

Synopsis:

```
#include <wclistit.h>
public:
const WCPtrSList<Type> *WCPtrConstSListIter<Type>::container() const;
const WCPtrDList<Type> *WCPtrConstDListIter<Type>::container() const;
```

Semantics: The `container` public member function returns a pointer to the list container object. If the iterator has not been initialized with a list object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the list object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a list.

See Also: `WCPtrConstSListIter`, `WCPtrConstDListIter`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * current();
```

Semantics: The `current` public member function returns a pointer to the list item at the current iterator position.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: A pointer to the current list element is returned. If the current element is undefined, an uninitialized pointer is returned.

See Also: `operator ()`, `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_item`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `WCIterExcept::undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `operator ++, operator +=, operator --, operator -=, reset,`
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `WCIterExcept::undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator +=( int );
```

Semantics: The operator `+=` public member function accepts an integer value that causes the iterator to move that many elements after the current item. If the iterator was positioned before the first element in the list, the operation will set the current item to be the given element in the list.

If the current item was after the last element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to increment the iterator position more than element after the end of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `+=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator --();
```

Semantics: The operator -- public member function is the pre-decrement operator for the class. The list element previous to the current item is set to be the new current item. If the current item was the first element in the list, the iterator is positioned before the first element in the list. If the list is empty, the iterator will be positioned before the start of the list.

If the iterator was positioned after the last element in the list, the current item will be set to the last element.

If the iterator is not associated with a list or the iterator position previous to the decrement was before the first element the list, the `undef_iter` exception is thrown, if enabled.

Results: The operator -- public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator -=`, `reset`, `WCIterExcept::undef_iter`

WCPtrConstDListIter<Type>::operator -=()

Synopsis:

```
#include <wclistit.h>
public:
    int operator -=( int );
```

Semantics: The operator `-=` public member function accepts an integer value that causes the iterator to move that many elements before the current item. If the iterator was positioned after the last element in the list, the operation will set the current item to be the given number of elements from the end of the list.

If the current item was before the first element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to decrement the iterator position more than one element before the beginning of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `-=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element in the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator --`, `reset`, `WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated list.

Results: The iterator is positioned before the first list element.

See Also: `WCPtrConstSListIter`, `WCPtrConstDListIter`, `container`

WCPtrConstSListIter<Type>::reset(), WCPtrConstDListIter<Type>::reset()

Synopsis:

```
#include <wclistit.h>
public:
void WCPtrConstSListIter<Type>::reset( const WCPtrSList<Type> & );
void WCPtrConstDListIter<Type>::reset( const WCPtrDList<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified list. The iterator is positioned before the first element in the list.

Results: The iterator is positioned before the first element of the specified list.

See Also: `WCPtrConstSListIter`, `WCPtrConstDListIter`, `container`

Declared: wclistit.h

The *WCPtrSListIter<Type>* and *WCPtrDListIter<Type>* classes are the templated classes used to create iterator objects for single and double linked list objects. These classes can be used only for non-constant lists. The *WCPtrDConstListIter<Type>* and *WCPtrSConstListIter<Type>* classes are provided to iterate over constant lists.

In the description of each member function, the text *Type* is used to indicate the list element type specified as the template parameter.

The *WCIterExcept* class is a base class of the *WCPtrSListIter<Type>* and *WCPtrDListIter<Type>* classes and provides the *exceptions* member function. This member function controls the exceptions which can be thrown by the *WCPtrSListIter<Type>* and *WCPtrDListIter<Type>* objects. No exceptions are enabled unless they are set by the *exceptions* member function.

Private Member Functions

Some functionality supported by base classes of the iterator are not appropriate in the single linked list iterator classes. Setting those functions as private members in the derived class is the standard mechanism to prevent them from being invoked. The following member functions are declared in the single linked list iterator private interface:

```
int operator --();
int operator --( int );
int insert( Type * );
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrSListIter();
WCPtrSListIter( WCPtrSList<Type> & );
~WCPtrSListIter();
WCPtrDListIter();
WCPtrDListIter( WCPtrDList<Type> & );
~WCPtrDListIter();
int append( Type * );
WCPtrSList<Type> *WCPtrSListIter<Type>::container() const;
WCPtrDList<Type> *WCPtrDListIter<Type>::container() const;
Type * current() const;
void reset();
void WCPtrSListIter<Type>::reset( WCPtrSList<Type> & );
void WCPtrDListIter<Type>::reset( WCPtrDList<Type> & );
```

In the iterators for double linked lists only:

```
int insert( Type * );
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
int operator +=( int );
```

WCPtrSListIter<Type>, WCPtrDListIter<Type>

In the iterators for double linked lists only:

```
int operator --();
int operator --( int );
```

See Also: [WCPtrSList::forAll](#), [WCPtrDList::forAll](#)

Synopsis:

```
#include <wclistit.h>
public:
WCPtrSListIter();
```

Semantics: The `WCPtrSListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCPtrSListIter` public member function creates an initialized `WCPtrSListIter` object.

See Also: `WCPtrSListIter`, `~WCPtrSListIter`, `reset`

WCPtrSListIter<Type>::WCPtrSListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCPtrSListIter( WCPtrSList<Type> & );
```

Semantics: The `WCPtrSListIter` public member function is a constructor for the class. The value passed as a parameter is a `WCPtrSList` list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The `WCPtrSListIter` public member function creates an initialized `WCPtrSListIter` object positioned before the first element in the list.

See Also: `~WCPtrSListIter`, `operator ()`, `operator ++`, `operator +=`, `reset`

Synopsis:

```
#include <wclistit.h>
public:
~WCPtrSListIter();
```

Semantics: The `~WCPtrSListIter` public member function is the destructor for the class. The call to the `~WCPtrSListIter` public member function is inserted implicitly by the compiler at the point where the `WCPtrSListIter` object goes out of scope.

Results: The `WCPtrSListIter` object is destroyed.

See Also: `WCPtrSListIter`

WCPtrDListIter<Type>::WCPtrDListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCPtrDListIter();
```

Semantics: The `WCPtrDListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCPtrDListIter` public member function creates an initialized `WCPtrDListIter` object.

See Also: `WCPtrDListIter`, `~WCPtrDListIter`, `reset`

Synopsis:

```
#include <wclistit.h>
public:
WCPtrDListIter( WCPtrDList<Type> & );
```

Semantics: The `WCPtrDListIter` public member function is a constructor for the class. The value passed as a parameter is the `WCPtrDList` list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The `WCPtrDListIter` public member function creates an initialized `WCPtrDListIter` object positioned before the first list element.

See Also: `WCPtrDListIter`, `~WCPtrDListIter`, operator `()`, operator `++`, operator `+=`, `reset`

WCPtrDListIter<Type>::~WCPtrDListIter()

Synopsis:

```
#include <wclistit.h>
public:
~WCPtrDListIter();
```

Semantics: The `~WCPtrDListIter` public member function is the destructor for the class. The call to the `~WCPtrDListIter` public member function is inserted implicitly by the compiler at the point where the `WCPtrDListIter` object goes out of scope.

Results: The `WCPtrDListIter` object is destroyed.

See Also: `WCPtrDListIter`

Synopsis:

```
#include <wclistit.h>
public:
    int append( Type * );
```

Semantics: The append public member function inserts a new element into the list container object. The new element is inserted after the current iterator item.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. The element is not appended. If the `undef_iter` exception is enabled, it is thrown.

If the append fails, the `out_of_memory` exception is thrown, if enabled in the list being iterated over. The list remains unchanged.

Results: The new element is inserted after the current iterator item. A TRUE value (non-zero) is returned if the append is successful. A FALSE (zero) result is returned if the append fails.

See Also: `insert`, `WCExcept::out_of_memory`, `WCIterExcept::undef_iter`

WCPtrSListIter<Type>, WCPtrDListIter<Type>::container()

Synopsis:

```
#include <wclistit.h>
public:
    WCPtrSList<Type> *WCPtrSListIter<Type>::container() const;
    WCPtrDList<Type> *WCPtrDListIter<Type>::container() const;
```

Semantics:

The `container` public member function returns a pointer to the list container object. If the iterator has not been initialized with a list object, and the `undef_iter` exception is enabled, the exception is thrown.

Results:

A pointer to the list object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a list.

See Also:

`WCPtrSListIter`, `WCPtrDListIter`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type * current();
```

Semantics: The `current` public member function returns a pointer to the list item at the current iterator position.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: A pointer to the current list element is returned. If the current element is undefined, an uninitialized pointer is returned.

See Also: `operator ()`, `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_item`

WCPtrDListIter<Type>::insert()

Synopsis:

```
#include <wclistit.h>
public:
    int insert( Type * );
```

Semantics: The `insert` public member function inserts a new element into the list container object. The new element is inserted before the current iterator item. This process uses the previous link in the double linked list, so the `insert` public member function is not allowed with single linked lists.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. The element is not inserted. If the `undef_iter` exception is enabled, the exception is thrown.

If the insert fails and the `out_of_memory` exception is enabled in the list being iterated over, the exception is thrown. The list remains unchanged.

Results: The new element is inserted before the current iterator item. A TRUE value (non-zero) is returned if the insert is successful. A FALSE (zero) result is returned if the insert fails.

See Also: `append`, `WCExcept::out_of_memory`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `WCIterExcept::undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `operator ++, operator +=, operator --, operator -=, reset,`
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ++();
```

Semantics: The `operator ++` public member function is the pre-increment operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ++` public member function has the same semantics as the call operator, `operator ()`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ++` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator +=( int );
```

Semantics: The operator `+=` public member function accepts an integer value that causes the iterator to move that many elements after the current item. If the iterator was positioned before the first element in the list, the operation will set the current item to be the given element in the list.

If the current item was after the last element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to increment the iterator position more than element after the end of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `+=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

WCPtrDListIter<Type>::operator --()

Synopsis:

```
#include <wclistit.h>
public:
    int operator --();
```

Semantics: The operator -- public member function is the pre-decrement operator for the class. The list element previous to the current item is set to be the new current item. If the current item was the first element in the list, the iterator is positioned before the first element in the list. If the list is empty, the iterator will be positioned before the start of the list.

If the iterator was positioned after the last element in the list, the current item will be set to the last element.

If the iterator is not associated with a list or the iterator position previous to the decrement was before the first element the list, the `undef_iter` exception is thrown, if enabled.

Results: The operator -- public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator -=`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator -(= ( int ) ;
```

Semantics: The operator `-=` public member function accepts an integer value that causes the iterator to move that many elements before the current item. If the iterator was positioned after the last element in the list, the operation will set the current item to be the given number of elements from the end of the list.

If the current item was before the first element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to decrement the iterator position more than one element before the beginning of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `-=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element in the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator --`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated list.

Results: The iterator is positioned before the first list element.

See Also: `WCPtrSListIter`, `WCPtrDListIter`, `container`

Synopsis:

```
#include <wclistit.h>
public:
void WCPtrSListIter<Type>::reset( WCPtrSList<Type> & );
void WCPtrDListIter<Type>::reset( WCPtrDList<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified list. The iterator is positioned before the first element in the list.

Results: The iterator is positioned before the first element of the specified list.

See Also: `WCPtrSListIter`, `WCPtrDListIter`, `container`

Declared: wclistit.h

The `WCValConstSListIter<Type>` and `WCValConstDListIter<Type>` classes are the templated classes used to create iterator objects for constant single and double linked list objects. These classes may be used to iterate over non-constant lists, but the `WCValDListIter<Type>` and `WCValSListIter<Type>` classes provide additional functionality for only non-constant lists.

In the description of each member function, the text `Type` is used to indicate the list element type specified as the template parameter.

The `WCIterExcept` class is a base class of the `WCValConstSListIter<Type>` and `WCValConstDListIter<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCValConstSListIter<Type>` and `WCValConstDListIter<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

Private Member Functions

Some functionality supported by base classes of the iterator are not appropriate for the constant list iterator classes. Setting those functions as private members in the derived class is the standard mechanism to prevent them from being invoked.

```
int append( Type & );
int insert( Type & );
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCValConstSListIter();
WCValConstSListIter( const WCValSList<Type> & );
~WCValConstSListIter();
WCValConstDListIter();
WCValConstDListIter( const WCValDList<Type> & );
~WCValConstDListIter();
const WCValSList<Type> *WCValConstSListIter<Type>::container() const;
const WCValDList<Type> *WCValConstDListIter<Type>::container() const;
Type current() const;
void reset();
void WCValConstSListIter<Type>::reset( const WCValSList<Type> & );
void WCValConstDListIter<Type>::reset( const WCValDList<Type> & );
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
int operator +=( int );
```

In the iterators for double linked lists only:

```
int operator --();
int operator -=( int );
```

See Also: `WCValSList::forAll`, `WCValDList::forAll`

Synopsis:

```
#include <wclistit.h>
public:
WCValConstSListIter();
```

Semantics: The `WCValConstSListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCValConstSListIter` public member function creates an initialized `WCValConstSListIter` object.

See Also: `WCValConstSListIter`, `~WCValConstSListIter`, `reset`

WCValConstSListIter<Type>::WCValConstSListIter()

Synopsis:	<pre>#include <wclistit.h> public: WCValConstSListIter(const WCValSList<Type> &);</pre>
Semantics:	The WCValConstSListIter public member function is a constructor for the class. The value passed as a parameter is a WCValSList list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator <code>++</code> , operator <code>()</code> , or operator <code>+=</code> operators.
Results:	The WCValConstSListIter public member function creates an initialized WCValConstSListIter object positioned before the first element in the list.
See Also:	<code>~WCValConstSListIter</code> , <code>operator ()</code> , <code>operator ++</code> , <code>operator +=</code> , <code>reset</code>

Synopsis:

```
#include <wclistit.h>
public:
~WCValConstSListIter();
```

Semantics: The ~WCValConstSListIter public member function is the destructor for the class. The call to the ~WCValConstSListIter public member function is inserted implicitly by the compiler at the point where the WCValConstSListIter object goes out of scope.

Results: The WCValConstSListIter object is destroyed.

See Also: WCValConstSListIter

WCValConstDListIter<Type>::WCValConstDListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCValConstDListIter();
```

Semantics: The `WCValConstDListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCValConstDListIter` public member function creates an initialized `WCValConstDListIter` object.

See Also: `WCValConstDListIter`, `~WCValConstDListIter`, `reset`

Synopsis:	#include <wclistit.h> public: WCValConstDListIter(const WCValDList<Type> &);
Semantics:	The WCValConstDListIter public member function is a constructor for the class. The value passed as a parameter is the WCValDList list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator <code>++</code> , operator <code>()</code> , or operator <code>+=</code> operators.
Results:	The WCValConstDListIter public member function creates an initialized WCValConstDListIter object positioned before the first list element.
See Also:	WCValConstDListIter, ~WCValConstDListIter, operator <code>()</code> , operator <code>++</code> , operator <code>+=</code> , reset

WCValConstDListIter<Type>::~WCValConstDListIter()

Synopsis:

```
#include <wclistit.h>
public:
~WCValConstDListIter();
```

Semantics: The ~WCValConstDListIter public member function is the destructor for the class. The call to the ~WCValConstDListIter public member function is inserted implicitly by the compiler at the point where the WCValConstDListIter object goes out of scope.

Results: The WCValConstDListIter object is destroyed.

See Also: WCValConstDListIter

Synopsis:

```
#include <wclistit.h>
public:
const WCValSList<Type> *WCValConstSListIter<Type>::container() const;
const WCValDList<Type> *WCValConstDListIter<Type>::container() const;
```

Semantics: The `container` public member function returns a pointer to the list container object. If the iterator has not been initialized with a list object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the list object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a list.

See Also: `WCValConstSListIter`, `WCValConstDListIter`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    Type current();
```

Semantics: The `current` public member function returns the value of the list element at the current iterator position.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: The value at the current iterator element is returned. If the current element is undefined, a default initialized object is returned.

See Also: `operator ()`, `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_item`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ++();
```

Semantics: The operator `++` public member function is the pre-increment operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The operator `++` public member function has the same semantics as the call operator, `operator ()`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `WCIterExcept::undef_iter` exception is thrown, if enabled.

Results: The operator `++` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator +=( int );
```

Semantics: The operator `+=` public member function accepts an integer value that causes the iterator to move that many elements after the current item. If the iterator was positioned before the first element in the list, the operation will set the current item to be the given element in the list.

If the current item was after the last element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to increment the iterator position more than element after the end of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `+=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

WCValConstDListIter<Type>::operator --()

Synopsis:

```
#include <wclistit.h>
public:
    int operator --();
```

Semantics: The operator -- public member function is the pre-decrement operator for the class. The list element previous to the current item is set to be the new current item. If the current item was the first element in the list, the iterator is positioned before the first element in the list. If the list is empty, the iterator will be positioned before the start of the list.

If the iterator was positioned after the last element in the list, the current item will be set to the last element.

If the iterator is not associated with a list or the iterator position previous to the decrement was before the first element the list, the `undef_iter` exception is thrown, if enabled.

Results: The operator -- public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator -(= ( int ) ;
```

Semantics: The operator `-=` public member function accepts an integer value that causes the iterator to move that many elements before the current item. If the iterator was positioned after the last element in the list, the operation will set the current item to be the given number of elements from the end of the list.

If the current item was before the first element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to decrement the iterator position more than one element before the beginning of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `-=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element in the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator --`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated list.

Results: The iterator is positioned before the first list element.

See Also: `WCValConstSListIter`, `WCValConstDListIter`, `container`

Synopsis:

```
#include <wclistit.h>
public:
void WCValConstSListIter<Type>::reset( const WCValSList<Type> & );
void WCValConstDListIter<Type>::reset( const WCValDList<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified list. The iterator is positioned before the first element in the list.

Results: The iterator is positioned before the first element of the specified list.

See Also: `WCValConstSListIter`, `WCValConstDListIter`, `container`

Declared: wclistit.h

The `WCValSListIter<Type>` and `WCValDListIter<Type>` classes are the templated classes used to create iterator objects for single and double linked list objects. These classes can be used only for non-constant lists. The `WCValDConstListIter<Type>` and `WCValSConstListIter<Type>` classes are provided to iterate over constant lists.

In the description of each member function, the text `Type` is used to indicate the list element type specified as the template parameter.

The `WCIterExcept` class is a base class of the `WCValSListIter<Type>` and `WCValDListIter<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCValSListIter<Type>` and `WCValDListIter<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

Private Member Functions

Some functionality supported by base classes of the iterator are not appropriate in the single linked list iterator classes. Setting those functions as private members in the derived class is the standard mechanism to prevent them from being invoked. The following member functions are declared in the single linked list iterator private interface:

```
int operator --();
int operator --( int );
int insert( Type & );
```

Public Member Functions

The following member functions are declared in the public interface:

```
WCValSListIter();
WCValSListIter( WCValSList<Type> & );
~WCValSListIter();
WCValDListIter();
WCValDListIter( WCValDList<Type> & );
~WCValDListIter();
int append( Type & );
WCValSList<Type> *WCValSListIter<Type>::container() const;
WCValDList<Type> *WCValDListIter<Type>::container() const;
Type current() const;
void reset();
void WCValSListIter<Type>::reset( WCValSList<Type> & );
void WCValDListIter<Type>::reset( WCValDList<Type> & );
```

In the iterators for double linked lists only:

```
int insert( Type & );
```

Public Member Operators

The following member operators are declared in the public interface:

```
int operator ()();
int operator ++();
int operator +=( int );
```

In the iterators for double linked lists only:

```
int operator --();
int operator --( int );
```

See Also: WCValSList::forAll, WCValDList::forAll

Sample Program Using Value List Iterators

```
#include <wclistit.h>
#include <iostream.h>

//  
// insert elem after all elements in the list less than or equal to  
// elem  
//  
  
void insert_in_order( WCValDList<int> &list, int elem ) {  
    if( list.entries() == 0 ) {  
        // cannot insert in an empty list using a iterator  
        list.insert( elem );  
    } else {  
  
        WCValDListIter<int> iter( list );  
        while( ++iter ) {  
            if( iter.current() > elem ) {  
                // insert elem before first element in list greater  
                // than elem  
                iter.insert( elem );  
                return;  
            }  
        }  
  
        // iterated past the end of the list  
        // append elem to the end of the list  
        list.append( elem );  
    }  
}  
  
void main() {  
    WCValDList<int> list;  
  
    insert_in_order( list, 5 );
    insert_in_order( list, 20 );
    insert_in_order( list, 1 );
    insert_in_order( list, 25 );
  
    cout << "List elements in ascending order:\n";
    WCValDListIter<int> iter( list );
    while( ++iter ) {
        cout << iter.current() << "\n";
    }
  
    cout << "List elements in descending order\n";
  
    // iterator is past the end of the list
    while( --iter ) {
        cout << iter.current() << "\n";
    }
}
```

WCValSListIter<Type>::WCValSListIter()

Synopsis:

```
#include <wclistit.h>
public:
WCValSListIter();
```

Semantics: The `WCValSListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCValSListIter` public member function creates an initialized `WCValSListIter` object.

See Also: `WCValSListIter`, `~WCValSListIter`, `reset`

Synopsis:

```
#include <wclistit.h>
public:
WCValSListIter( WCValSList<Type> & );
```

Semantics: The `WCValSListIter` public member function is a constructor for the class. The value passed as a parameter is a `WCValSList` list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The `WCValSListIter` public member function creates an initialized `WCValSListIter` object positioned before the first element in the list.

See Also: `~WCValSListIter`, `operator ()`, `operator ++`, `operator +=`, `reset`

WCValSListIter<Type>::~WCValSListIter()

Synopsis:

```
#include <wclistit.h>
public:
~WCValSListIter();
```

Semantics: The ~WCValSListIter public member function is the destructor for the class. The call to the ~WCValSListIter public member function is inserted implicitly by the compiler at the point where the WCValSListIter object goes out of scope.

Results: The WCValSListIter object is destroyed.

See Also: WCValSListIter

Synopsis:

```
#include <wclistit.h>
public:
WCValDListIter();
```

Semantics: The `WCValDListIter` public member function is the default constructor for the class and initializes the iterator with no list to operate on. The `reset` member function must be called to provide the iterator with a list to iterate over.

Results: The `WCValDListIter` public member function creates an initialized `WCValDListIter` object.

See Also: `WCValDListIter`, `~WCValDListIter`, `reset`

WCValDListIter<Type>::WCValDListIter()

Synopsis:

```
#include <wcclistit.h>
public:
WCValDListIter( WCValDList<Type> & );
```

Semantics: The `WCValDListIter` public member function is a constructor for the class. The value passed as a parameter is the `WCValDList` list object. The iterator will be initialized for that list object and positioned before the first list element. To position the iterator to a valid element within the list, increment it using any of the operator `++`, operator `()`, or operator `+=` operators.

Results: The `WCValDListIter` public member function creates an initialized `WCValDListIter` object positioned before the first list element.

See Also: `WCValDListIter`, `~WCValDListIter`, operator `()`, operator `++`, operator `+=`, `reset`

Synopsis:

```
#include <wclistit.h>
public:
~WCValDListIter();
```

Semantics: The `~WCValDListIter` public member function is the destructor for the class. The call to the `~WCValDListIter` public member function is inserted implicitly by the compiler at the point where the `WCValDListIter` object goes out of scope.

Results: The `WCValDListIter` object is destroyed.

See Also: `WCValDListIter`

WCValSListIter<Type>::append(), WCValDListIter<Type>::append()

Synopsis:

```
#include <wclistit.h>
public:
    int append( Type & ) ;
```

Semantics: The append public member function inserts a new element into the list container object. The new element is inserted after the current iterator item.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. The element is not appended. If the `undef_iter` exception is enabled, it is thrown.

If the append fails, the `out_of_memory` exception is thrown, if enabled in the list being iterated over. The list remains unchanged.

Results: The new element is inserted after the current iterator item. A TRUE value (non-zero) is returned if the append is successful. A FALSE (zero) result is returned if the append fails.

See Also: `insert`, `WCExcept::out_of_memory`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
WCValSList<Type> *WCValSListIter<Type>::container() const;
WCValDList<Type> *WCValDListIter<Type>::container() const;
```

Semantics: The `container` public member function returns a pointer to the list container object. If the iterator has not been initialized with a list object, and the `undef_iter` exception is enabled, the exception is thrown.

Results: A pointer to the list object associated with the iterator is returned, or `NULL(0)` if the iterator has not been initialized with a list.

See Also: `WCValSListIter`, `WCValDListIter`, `reset`, `WCIterExcept::undef_iter`

WCValSListIter<Type>::current(), WCValDListIter<Type>::current()

Synopsis:

```
#include <wclistit.h>
public:
    Type current();
```

Semantics: The `current` public member function returns the value of the list element at the current iterator position.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. In this case the `undef_item` exception is thrown, if enabled.

Results: The value at the current iterator element is returned. If the current element is undefined, a default initialized object is returned.

See Also: `operator ()`, `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_item`

Synopsis:

```
#include <wclistit.h>
public:
    int insert( Type & );
```

Semantics: The `insert` public member function inserts a new element into the list container object. The new element is inserted before the current iterator item. This process uses the previous link in the double linked list, so the `insert` public member function is not allowed with single linked lists.

If the iterator is not associated with a list, or the iterator position is either before the first element or past the last element in the list, the current iterator position is undefined. The element is not inserted. If the `undef_iter` exception is enabled, the exception is thrown.

If the insert fails and the `out_of_memory` exception is enabled in the list being iterated over, the exception is thrown. The list remains unchanged.

Results: The new element is inserted before the current iterator item. A TRUE value (non-zero) is returned if the insert is successful. A FALSE (zero) result is returned if the insert fails.

See Also: `append`, `WCExcept::out_of_memory`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ()();
```

Semantics: The `operator ()` public member function is the call operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The `operator ()` public member function has the same semantics as the pre-increment operator, `operator ++`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `undef_iter` exception is thrown, if enabled.

Results: The `operator ()` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `operator ++`, `operator +=`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
    int operator ++();
```

Semantics: The operator `++` public member function is the pre-increment operator for the class. The list element which follows the current item is set to be the new current item. If the previous current item was the last element in the list, the iterator is positioned after the end of the list.

The operator `++` public member function has the same semantics as the call operator, `operator ()`.

If the iterator was positioned before the first element in the list, the current item will be set to the first element in the list. If the list is empty, the iterator will be positioned after the end of the list.

If the iterator is not associated with a list or the iterator position before the increment was past the last element the list, the `WCIterExcept::undef_iter` exception is thrown, if enabled.

Results: The operator `++` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator +=`, `operator --`, `operator -=`, `reset`, `WCIterExcept::undef_iter`

WCValSListIter<Type>, WCValDListIter<Type>::operator +=()

Synopsis:

```
#include <wcclistit.h>
public:
    int operator +=( int );
```

Semantics: The `operator +=` public member function accepts an integer value that causes the iterator to move that many elements after the current item. If the iterator was positioned before the first element in the list, the operation will set the current item to be the given element in the list.

If the current item was after the last element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to increment the iterator position more than element after the end of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The `operator +=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is incremented past the end of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator --`, `operator -=`, `reset`,
`WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wcclistit.h>
public:
    int operator --();
```

Semantics: The operator -- public member function is the pre-decrement operator for the class. The list element previous to the current item is set to be the new current item. If the current item was the first element in the list, the iterator is positioned before the first element in the list. If the list is empty, the iterator will be positioned before the start of the list.

If the iterator was positioned after the last element in the list, the current item will be set to the last element.

If the iterator is not associated with a list or the iterator position previous to the decrement was before the first element the list, the `undef_iter` exception is thrown, if enabled.

Results: The operator -- public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element of the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator -=`, `reset`,
`WCIterExcept::undef_iter`

WCValDListIter<Type>::operator -=()

Synopsis:

```
#include <wcclistit.h>
public:
    int operator -=( int );
```

Semantics: The operator `-=` public member function accepts an integer value that causes the iterator to move that many elements before the current item. If the iterator was positioned after the last element in the list, the operation will set the current item to be the given number of elements from the end of the list.

If the current item was before the first element in the list previous to the iteration, and the `undef_iter` exception is enabled, the exception will be thrown. Attempting to decrement the iterator position more than one element before the beginning of the list, or by less than one element causes the `iter_range` exception to be thrown, if enabled.

Results: The operator `-=` public member function returns a non-zero value if the iterator is positioned on a list item. Zero(0) is returned when the iterator is decremented past the first element in the list.

See Also: `current`, `operator ()`, `operator ++`, `operator +=`, `operator --`, `reset`, `WCIterExcept::iter_range`, `WCIterExcept::undef_iter`

Synopsis:

```
#include <wclistit.h>
public:
void reset();
```

Semantics: The `reset` public member function resets the iterator to the initial state, positioning the iterator before the first element in the associated list.

Results: The iterator is positioned before the first list element.

See Also: `WCValSListIter`, `WCValDListIter`, `container`

WCValSListIter<Type>::reset(), WCValDListIter<Type>::reset()

Synopsis:

```
#include <wclistit.h>
public:
void WCValSListIter<Type>::reset( WCValSList<Type> & );
void WCValDListIter<Type>::reset( WCValDList<Type> & );
```

Semantics: The `reset` public member function resets the iterator to operate on the specified list. The iterator is positioned before the first element in the list.

Results: The iterator is positioned before the first element of the specified list.

See Also: `WCValSListIter`, `WCValDListIter`, `container`

14 Queue Container

Queue containers maintain an ordered collection of data which is retrieved in the order in which the data was entered into the queue. The queue class is implemented as a templated class, allowing the use of any data type as the queue data.

A second template parameter specifies the storage class used to implement the queue. The `WCValsList`, `WCIsvSList` and `WCPtrSList` classes are appropriate storage classes.

WCQueue<Type,FType>

Declared: wcqueue.h

The WCQueue<Type,FType> class is a templated class used to create objects which maintain data in a queue.

In the description of each member function, the text Type is used to indicate the template parameter defining the type of the elements stored in the queue. The text FType is used to indicate the template parameter defining the storage class used to maintain the queue.

For example, to create a queue of integers, the WCQueue<int,WCValSList<int>> class can be used. The WCQueue<int *,WCPtrSList<int>> class will create a queue of pointers to integers. To create an intrusive queue of objects of type *isv_link* (derived from the WCSLink class), the WCQueue<*isv_link* *,WCISvSList<*isv_link*>> class can be used.

The WCExcept class is a base class of the WCQueue<Type,FType> class and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCQueue<Type,FType> object. No exceptions are enabled unless they are set by the exceptions member function.

Requirements of Type

Type must provide any constructors and/or operators required by the FType class.

Public Member Functions

The following member functions are declared in the public interface:

```
WCQueue();
WCQueue( void *(*)( size_t ), void (*)( void *, size_t ) );
~WCQueue();
void clear();
int entries() const;
Type first() const;
Type get();
int insert( const Type & );
int isEmpty() const;
Type last() const;
```

Sample Program Using a Queue

```
#include <wcqueue.h>
#include <iostream.h>

main() {
    WCQueue<int,WCValSList<int> > queue;

    queue.insert( 7 );
    queue.insert( 8 );
    queue.insert( 9 );
    queue.insert( 10 );

    cout << "\nNumber of queue entries: " << queue.entries() << "\n";
    cout << "First entry = [" << queue.first() << "]\n";
    cout << "Last entry = [" << queue.last() << "]\n";
    while( !queue.isEmpty() ) {
        cout << queue.get() << "\n";
    };
    cout.flush();
}
```

Synopsis:

```
#include <wcqueue.h>
public:
WCQueue();
```

Semantics: The public `WCQueue<Type,FType>` constructor creates an empty `WCQueue<Type,FType>` object. The `FType` storage class constructor performs the initialization.

Results: The public `WCQueue<Type,FType>` constructor creates an initialized `WCQueue<Type,FType>` object.

See Also: `~WCQueue<Type,FType>`

WCQueue<Type,FType>::WCQueue()

Synopsis:

```
#include <wcqueue.h>
public:
    WCQueue( void *(*allocator)( size_t ),
              void (*deallocator)( void *, size_t ) );
```

Semantics: The public `WCQueue<Type,FType>` constructor creates an empty `WCQueue<Type,FType>` object. If `FType` is either the `WCValSList` or `WCPtrSList` class, then the *allocator* function is registered to perform all memory allocations of the queue elements, and the *deallocator* function to perform all freeing of the queue elements' memory. The *allocator* and *deallocator* functions are ignored if `FType` is the `WCISvSList` class. These functions provide the ability to control how the allocation and freeing of memory is performed, allowing for more efficient memory handling than the general purpose global operator `new()` and operator `delete()` can provide. Memory management optimizations may potentially be made through the *allocator* and *deallocator* functions, but are not recommended before managing memory is understood and determined to be worth while.

The *allocator* function shall return a pointer to allocated memory of size at least the argument, or zero(0) if the allocation cannot be performed. Initialization of the memory returned is performed by the `WCQueue<Type,FType>` class.

The `WCQueue<Type,FType>` class calls the *deallocator* function only on memory allocated by the *allocator* function. The *deallocator* shall free the memory pointed to by the first argument which is of size the second argument. The size passed to the *deallocator* function is guaranteed to be the same size passed to the *allocator* function when the memory was allocated.

The *allocator* and *deallocator* functions may assume that for a list object instance, the *allocator* is always called with the same first argument (the size of the memory to be allocated). If `FType` is the `WCValSList<Type>` class, then the `WCValSListItemSize(Type)` macro returns the size of the elements which are allocated by the *allocator* function. Similarly, the `WCPtrSListItemSize(Type)` macro returns the size of `WCPtrSList<Type>` elements.

The `FType` storage class constructor performs the initialization of the queue.

Results: The public `WCQueue<Type,FType>` constructor creates an initialized `WCQueue<Type,FType>` object and registers the *allocator* and *deallocator* functions.

See Also: `WCQueue<Type,FType>`, `~WCQueue<Type,FType>`

Synopsis:

```
#include <wcqueue.h>
public:
virtual ~WCQueue();
```

Semantics: The public `~WCQueue<Type, FType>` destructor destroys the `WCQueue<Type, FType>` object. The `FType` storage class destructor performs the destruction. The call to the public `~WCQueue<Type, FType>` destructor is inserted implicitly by the compiler at the point where the `WCQueue<Type, FType>` object goes out of scope.

If the `not_empty` exception is enabled, the exception is thrown if the queue is not empty of queue elements.

Results: The `WCQueue<Type, FType>` object is destroyed.

See Also: `WCQueue<Type, FType>, clear, WCExcept::not_empty`

WCQueue<Type,FType>::clear()

Synopsis:

```
#include <wcqueue.h>
public:
void clear();
```

Semantics: The `clear` public member function is used to clear the queue object and set it to the state of the object just after the initial construction. The queue object is not destroyed and re-created by this operator, so the object destructor is not invoked. The queue elements are not cleared by the queue class. However, the class used to maintain the queue, `FType`, may clear the items as part of the `clear` function for that class. If it does not clear the items, any queue items still in the list are lost unless pointed to by some pointer object in the program code.

Results: The `clear` public member function resets the queue object to the state of the object immediately after the initial construction.

See Also: `~WCQueue<Type,FType>`, `isEmpty`

Synopsis:

```
#include <wcqueue.h>
public:
    int entries() const;
```

Semantics: The `entries` public member function is used to determine the number of queue elements contained in the list object.

Results: The number of elements in the queue is returned. Zero(0) is returned if there are no queue elements.

See Also: `isEmpty`

WCQueue<Type,FType>::first()

Synopsis:

```
#include <wcqueue.h>
public:
    Type first() const;
```

Semantics: The `first` public member function returns a queue element from the beginning of the queue object. The queue element is not removed from the queue.

If the queue is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, then it will be thrown. Otherwise, the `index_range` exception will be thrown, if enabled.

Results: The first queue element is returned. If there are no elements in the queue, the return value is determined by the `find` member function of the `FType` class.

See Also: `get`, `isEmpty`, `last`, `WCExcept::empty_container`, `WCExcept::index_range`, `FType::find`

Synopsis:

```
#include <wcqueue.h>
public:
    Type get();
```

Semantics: The `get` public member function returns the queue element which was first inserted into the queue object. The queue element is also removed from the queue.

If the queue is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, then it will be thrown. Otherwise, the `index_range` exception will be thrown, if enabled.

Results: The first element in the queue is removed and returned. If there are no elements in the queue, the return value is determined by the `get` member function of the `FType` class.

See Also: `first`, `insert`, `isEmpty`, `WCExcept::empty_container`, `WCExcept::index_range`, `FType::get`

WCQueue<Type,FType>::insert()

Synopsis:

```
#include <wcqueue.h>
public:
    int insert( const Type & );
```

Semantics: The `insert` public member function is used to insert the data into the queue. It will be the last element in the queue, and the last to be retrieved.

If the insert fails, the `out_of_memory` exception will be thrown, if enabled. The queue will remain unchanged.

Results: The queue element is inserted at the end of the queue. A TRUE value (non-zero) is returned if the insert is successful. A FALSE (zero) result is returned if the insert fails.

See Also: `get`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wcqueue.h>
public:
    int isEmpty() const;
```

Semantics: The `isEmpty` public member function is used to determine if a queue object has any queue elements contained in it.

Results: A TRUE value (non-zero) is returned if the queue object does not have any queue elements contained within it. A FALSE (zero) result is returned if the queue contains at least one element.

See Also: `entries`

WCQueue<Type,FType>::last()

Synopsis:

```
#include <wcqueue.h>
public:
    Type last() const;
```

Semantics: The `last` public member function returns a queue element from the end of the queue object. The queue element is not removed from the queue.

If the queue is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, then it will be thrown. Otherwise, the `index_range` exception will be thrown, if enabled.

Results: The last queue element is returned. If there are no elements in the queue, the return value is determined by the `find` member function of the `FType` class.

See Also: `first`, `get`, `isEmpty`, `WCExcept::empty_container`, `WCExcept::index_range`, `FType::find`

15 Skip List Containers

This chapter describes skip list containers.

WCPtrSkipListDict<Key,Value>

Declared: wcskip.h

The WCPtrSkipListDict<Key,Value> class is a templated class used to store objects in a dictionary. Dictionaries store values with an associated key, which may be of any type. One example of a dictionary used in everyday life is the phone book. The phone numbers are the data values, and the customer name is the key. The equality operator of the key's type is used to locate the key-value pairs.

In the description of each member function, the text `Key` is used to indicate the template parameter defining the type of the indices pointed to by the pointers stored in the dictionary. The text `Value` is used to indicate the template parameter defining the type of the data pointed to by the pointers stored in the dictionary.

Note that pointers to the key values are stored in the dictionary. Destructors are not called on the keys pointed to. The key values pointed to in the dictionary should not be changed such that the equivalence to the old value is modified.

The iterator classes for skip lists have the same function and operator interface as the hash iterators classes. See the chapter on hash iterators for more information.

The WCExcept class is a base class of the WCPtrSkipListDict<Key,Value> class and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCPtrSkipListDict<Key,Value> object. No exceptions are enabled unless they are set by the exceptions member function.

Requirements of Key

The WCPtrSkipListDict<Key,Value> class requires `Key` to have:

A well defined equivalence operator with constant parameters
`(int operator ==(const Key &) const).`

A well defined operator less than with constant parameters
`(int operator <(const Key &) const).`

Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrSkipListDict( unsigned = WCSkipListDict_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS );
WCPtrSkipListDict( unsigned = WCSkipListDict_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS, void * (*user_alloc)( size_t size ),
void (*user_dealloc)( void *old, size_t size ) );
WCPtrSkipListDict( const WCPtrSkipListDict & );
virtual ~WCPtrSkipListDict();
void clear();
void clearAndDestroy();
int contains( const Key * ) const;
unsigned entries() const;
Value * find( const Key * ) const;
Value * findKeyAndValue( const Key *, Key * & ) const;
void forAll( void (*user_fn)( Key *, Value *, void * ), void * );
int insert( Key *, Value * );
int isEmpty() const;
Value * remove( const Key * );
```

Public Member Operators

The following member operators are declared in the public interface:

```
Value * & operator []( const Key * );
Value * const & operator []( const Key * ) const;
WCPtrSkipListDict & operator =( const WCPtrSkipListDict & );
int operator ==( const WCPtrSkipListDict & ) const;
```

WCPtrSkipListDict<Key,Value>::WCPtrSkipListDict()

Synopsis:

```
#include <wcskip.h>
public:
WCPtrSkipListDict( unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS );
```

Semantics: The public WCPtrSkipListDict<Key,Value> constructor creates an WCPtrSkipListDict<Key,Value> object with no entries. The first optional parameter, which defaults to the constant WCSKIPLIST_PROB_QUARTER, determines the probability of having a certain number of pointers in each skip list node. The second optional parameter, which defaults to the constant WCDEFAULT_SKIPLIST_MAX_PTRS, determines the maximum number of pointers that are allowed in any skip list node. WCDEFAULT_SKIPLIST_MAX_PTRS is the maximum effective value of the second parameter. If an allocation failure occurs while creating the skip list, the `out_of_memory` exception is thrown if the `out_of_memory` exception is enabled.

Results: The public WCPtrSkipListDict<Key,Value> constructor creates an initialized WCPtrSkipListDict<Key,Value> object.

See Also: `~WCPtrSkipListDict<Key,Value>`, `WCExcept::out_of_memory`

Synopsis:

```
#include <wcskip.h>
public:
WCPtrSkipListDict( unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS,
void * (*user_alloc)( size_t ),
void (*user_dealloc)( void *, size_t ) );
```

Semantics: Allocator and deallocator functions are specified for use when entries are inserted and removed from the list dictionary. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a list dictionary. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:
WCPtrSkipListDictItemSize(Key, Value, num_of_pointers)

Results: The public WCPtrSkipListDict<Key,Value> constructor creates an initialized WCPtrSkipListDict<Key,Value> object.

See Also: ~WCPtrSkipListDict<Key,Value>, WCEexcept::out_of_memory

WCPtrSkipListDict<Key,Value>::WCPtrSkipListDict()

Synopsis:

```
#include <wcskip.h>
public:
    WCPtrSkipListDict( const WCPtrSkipListDict & );
```

Semantics: The public `WCPtrSkipListDict<Key,Value>` constructor is the copy constructor for the `WCPtrSkipListDict<Key,Value>` class. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

Results: The public `WCPtrSkipListDict<Key,Value>` constructor creates an `WCPtrSkipListDict<Key,Value>` object which is a copy of the passed dictionary.

See Also: `operator =, WCExcept::out_of_memory`

Synopsis:

```
#include <wcskip.h>
public:
    virtual ~WCPtrSkipListDict();
```

Semantics: The public `~WCPtrSkipListDict<Key,Value>` destructor is the destructor for the `WCPtrSkipListDict<Key,Value>` class. If the number of dictionary elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the dictionary elements are cleared using the `clear` member function. The objects which the dictionary elements point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the public `~WCPtrSkipListDict<Key,Value>` destructor is inserted implicitly by the compiler at the point where the `WCPtrSkipListDict<Key,Value>` object goes out of scope.

Results: The public `~WCPtrSkipListDict<Key,Value>` destructor destroys an `WCPtrSkipListDict<Key,Value>` object.

See Also: `clear`, `clearAndDestroy`, `WCExcept::not_empty`

WCPtrSkipListDict<Key,Value>::clear()

Synopsis:

```
#include <wcskip.h>
public:
void clear();
```

Semantics: The `clear` public member function is used to clear the dictionary so that it has no entries. Objects pointed to by the dictionary elements are not deleted. The dictionary object is not destroyed and re-created by this function, so the object destructor is not invoked.

Results: The `clear` public member function clears the dictionary to have no elements.

See Also: `~WCPtrSkipListDict<Key,Value>`, `clearAndDestroy`, `operator =`

Synopsis:

```
#include <wcskip.h>
public:
void clearAndDestroy();
```

Semantics: The `clearAndDestroy` public member function is used to clear the dictionary and delete the objects pointed to by the dictionary elements. The dictionary object is not destroyed and re-created by this function, so the dictionary object destructor is not invoked.

Results: The `clearAndDestroy` public member function clears the dictionary by deleting the objects pointed to by the dictionary elements.

See Also: `clear`

WCPtrSkipListDict<Key,Value>::contains()

Synopsis:

```
#include <wcskip.h>
public:
    int contains( const Key * ) const;
```

Semantics: The `contains` public member function returns non-zero if an element with the specified key is stored in the dictionary, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the `Key` type.

Results: The `contains` public member function returns a non-zero value if the `Key` is found in the dictionary.

See Also: `find`, `findKeyAndValue`

Synopsis:

```
#include <wcskip.h>
public:
    unsigned entries() const;
```

Semantics: The `entries` public member function is used to return the current number of elements stored in the dictionary.

Results: The `entries` public member function returns the number of elements in the dictionary.

See Also: `isEmpty`

WCPtrSkipListDict<Key,Value>::find()

Synopsis:

```
#include <wcskip.h>
public:
    Value * find( const Key * ) const;
```

Semantics: The `find` public member function is used to find an element with an equivalent key in the dictionary. If an equivalent element is found, a pointer to the element `Value` is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

Results: The element equivalent to the passed key is located in the dictionary.

See Also: `findKeyAndValue`

Synopsis:

```
#include <wcskip.h>
public:
    Value * findKeyAndValue( const Key *, Key * & ) const;
```

Semantics: The `findKeyAndValue` public member function is used to find an element in the dictionary with a key equivalent to the first parameter. If an equivalent element is found, a pointer to the element `Value` is returned. The reference to a `Key` passed as the second parameter is assigned the found element's key. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

Results: The element equivalent to the passed key is located in the dictionary.

See Also: `findKeyAndValue`

WCPtrSkipListDict<Key,Value>::forAll()

Synopsis:

```
#include <wcskip.h>
public:
void forAll(
void (*user_fn)( Key *, Value *, void * ),
void * );
```

Semantics: The `forAll` public member function causes the user supplied function to be invoked for every key-value pair in the dictionary. The user function has the prototype

```
void user_func( Key * key, Value * value, void * data );
```

As the elements are visited, the user function is invoked with the `Key` and `Value` components of the element passed as the first two parameters. The second parameter of the `forAll` function is passed as the third parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

Results: The elements in the dictionary are all visited, with the user function being invoked for each one.

See Also: `find`, `findKeyAndValue`

Synopsis:

```
#include <wcskip.h>
public:
    int insert( Key *, Value * );
```

Semantics: The `insert` public member function inserts a key and value into the dictionary. If allocation of the node to store the key-value pair fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

Results: The `insert` public member function inserts a key and value into the dictionary. If the insert is successful, a non-zero will be returned. A zero will be returned if the insert fails.

See Also: `operator =, WCExcept::out_of_memory`

WCPtrSkipListDict<Key,Value>::isEmpty()

Synopsis:

```
#include <wcskip.h>
public:
    int isEmpty() const;
```

Semantics: The `isEmpty` public member function is used to determine if the dictionary is empty.

Results: The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the dictionary is empty.

See Also: `entries`

Synopsis:

```
#include <wcskip.h>
public:
Value * & operator[]( const Key * );
```

Semantics: `operator []` is the dictionary index operator. A reference to the object stored in the dictionary with the given `Key` is returned. If no equivalent element is found, then a new key-value pair is created with the specified `Key` value, and initialized with the default constructor. The returned reference can then be assigned to, so that insertions can be made with the operator. If an allocation error occurs while inserting a new key-value pair, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

Results: The `operator []` public member function returns a reference to the element at the given key value. If the key does not exist, a reference to a created element is returned. The result of the operator may be assigned to.

See Also: `WCExcept::out_of_memory`

WCPtrSkipListDict<Key,Value>::operator []()

Synopsis:

```
#include <wcskip.h>
public:
    Value * const & operator[]( const Key * ) const;
```

Semantics: `operator []` is the dictionary index operator. A constant reference to the object stored in the dictionary with the given `Key` is returned. If no equivalent element is found, then the `index_range` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

Results: The `operator []` public member function returns a constant reference to the element at the given key value. The result of the operator may not be assigned to.

See Also: `WCExcept::index_range`

Synopsis:

```
#include <wcskip.h>
public:
    WCPtrSkipListDict & operator =( const WCPtrSkipListDict & );
```

Semantics: The `operator =` public member function is the assignment operator for the `WCPtrSkipListDict<Key,Value>` class. The left hand side dictionary is first cleared using the `clear` member function, and then the right hand side dictionary is copied. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values or pointers in the dictionary, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

Results: The `operator =` public member function assigns the left hand side dictionary to be a copy of the right hand side.

See Also: `clear`, `WCExcept::out_of_memory`

WCPtrSkipListDict<Key,Value>::operator ==()

- Synopsis:**
- ```
#include <wcskip.h>
public:
 int operator ==(const WCPtrSkipListDict &) const;
```
- Semantics:** The operator == public member function is the equivalence operator for the WCPtrSkipListDict<Key,Value> class. Two dictionary objects are equivalent if they are the same object and share the same address.
- Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side dictionary are the same object. A FALSE (zero) value is returned otherwise.

**Synopsis:**

```
#include <wcskip.h>
public:
Value * remove(const Key *);
```

**Semantics:** The `remove` public member function is used to remove the specified element from the dictionary. If an equivalent element is found, the pointer value is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The element is removed from the dictionary if it found.

## **WCPtrSkipList<Type>, WCPtrSkipListSet<Type>**

---

**Declared:** wcskip.h

`WCPtrSkipList<Type>` and `WCPtrSkipListSet<Type>` classes are templated classes used to store objects in a skip list. A skip list is a probabilistic alternative to balanced trees, and provides a reasonable performance balance to insertion, search, and deletion. A skip list allows more than one copy of an element that is equivalent, while the skip list set allows only one copy. The equality operator of the element's type is used to locate the value.

In the description of each member function, the text `Type` is used to indicate the template parameter defining the type of the data pointed to by the pointers stored in the list.

Note that pointers to the elements are stored in the list. Destructors are not called on the elements pointed to. The data values pointed to in the list should not be changed such that the equivalence to the old value is modified.

The iterator classes for skip lists have the same function and operator interface as the hash iterators classes. See the chapter on hash iterators for more information.

The `WCExcept` class is a base class of the `WCPtrSkipList<Type>` and `WCPtrSkipListSet<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCPtrSkipList<Type>` and `WCPtrSkipListSet<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

### **Requirements of Type**

The `WCPtrSkipList<Type>` and `WCPtrSkipListSet<Type>` classes requires `Type` to have:

A well defined equivalence operator

`(int operator ==( const Type & ) const).`

A well defined less than operator

`(int operator <( const Type & ) const).`

### **Public Member Functions**

The following member functions are declared in the public interface:

```
WCPtrSkipList(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS);
WCPtrSkipList(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS, void * (*user_alloc)(size_t size),
void (*user_dealloc)(void *old, size_t size));
WCPtrSkipList(const WCPtrSkipList &);
virtual ~WCPtrSkipList();
WCPtrSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS);
WCPtrSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS, void * (*user_alloc)(size_t size),
void (*user_dealloc)(void *old, size_t size));
WCPtrSkipListSet(const WCPtrSkipListSet &);
virtual ~WCPtrSkipListSet();
void clear();
void clearAndDestroy();
int contains(const Type *) const;
```

```
unsigned entries() const;
Type * find(const Type *) const;
void forAll(void (*user_fn)(Type *, void *) , void *);
int insert(Type *);
int isEmpty() const;
Type * remove(const Type *);
```

The following public member functions are available for the `WCPtrSkipList` class only:

```
unsigned occurrencesOf(const Type *) const;
unsigned removeAll(const Type *);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
WCPtrSkipList & operator =(const WCPtrSkipList &);
int operator ==(const WCPtrSkipList &) const;
WCPtrSkipListSet & operator =(const WCPtrSkipListSet &);
int operator ==(const WCPtrSkipListSet &) const;
```

## **WCPtrSkipListSet<Type>::WCPtrSkipListSet()**

---

**Synopsis:**

```
#include <wcskip.h>
public:
WCPtrSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS);
```

**Semantics:** The WCPtrSkipListSet<Type> constructor creates a WCPtrSkipListSet object with no entries. The first optional parameter, which defaults to the constant WCSKIPLIST\_PROB\_QUARTER, determines the probability of having a certain number of pointers in each skip list node. The second optional parameter, which defaults to the constant WCDEFAULT\_SKIPLIST\_MAX\_PTRS, determines the maximum number of pointers that are allowed in any skip list node. WCDEFAULT\_SKIPLIST\_MAX\_PTRS is the maximum effective value of the second parameter. If an allocation failure occurs while creating the skip list, the `out_of_memory` exception is thrown if the `out_of_memory` exception is enabled.

**Results:** The WCPtrSkipListSet<Type> constructor creates an initialized WCPtrSkipListSet object.

**See Also:** `~WCPtrSkipList<Type>`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
WCPtrSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS,
void * (*user_alloc)(size_t),
void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the list. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a skip list. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
WCPtrSkipListSetItemSize( Type, num\_of\_pointers )

**Results:** The WCPtrSkipListSet<Type> constructor creates an initialized WCPtrSkipListSet object.

**See Also:** ~WCPtrSkipList<Type>, WCExcept::out\_of\_memory

## **WCPtrSkipListSet<Type>::WCPtrSkipListSet()**

---

**Synopsis:**

```
#include <wcskip.h>
public:
 WCPtrSkipListSet(const WCPtrSkipListSet &);
```

**Semantics:** The WCPtrSkipListSet<Type> constructor is the copy constructor for the WCPtrSkipListSet class. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The WCPtrSkipListSet<Type> constructor creates a WCPtrSkipListSet object which is a copy of the passed list.

**See Also:** `operator =, WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
 virtual ~WCPtrSkipListSet();
```

**Semantics:** The `WCPtrSkipListSet<Type>` destructor is the destructor for the `WCPtrSkipListSet` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the list elements are cleared using the `clear` member function. The objects which the list elements point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the `WCPtrSkipListSet<Type>` destructor is inserted implicitly by the compiler at the point where the `WCPtrSkipListSet` object goes out of scope.

**Results:** The call to the `WCPtrSkipListSet<Type>` destructor destroys a `WCPtrSkipListSet` object.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::not_empty`

## **WCPtrSkipList<Type>::WCPtrSkipList()**

---

**Synopsis:**

```
#include <wcskip.h>
public:
WCPtrSkipList(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS);
```

**Semantics:**

The `WCPtrSkipList<Type>` constructor creates a `WCPtrSkipList` object with no entries. The first optional parameter, which defaults to the constant `WCSKIPLIST_PROB_QUARTER`, determines the probability of having a certain number of pointers in each skip list node. The second optional parameter, which defaults to the constant `WCDEFAULT_SKIPLIST_MAX_PTRS`, determines the maximum number of pointers that are allowed in any skip list node.

`WCDEFAULT_SKIPLIST_MAX_PTRS` is the maximum effective value of the second parameter. If an allocation failure occurs while creating the skip list, the `out_of_memory` exception is thrown if the `out_of_memory` exception is enabled.

**Results:**

The `WCPtrSkipList<Type>` constructor creates an initialized `WCPtrSkipList` object.

**See Also:**

`~WCPtrSkipList<Type>`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
WCPtrSkipList(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS,
void * (*user_alloc)(size_t),
void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the list. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a skip list. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
WCPtrSkipListItemSize( Type, num\_of\_pointers )

**Results:** The `WCPtrSkipList<Type>` constructor creates an initialized `WCPtrSkipList` object.

**See Also:** `~WCPtrSkipList<Type>`, `WCExcept::out_of_memory`

## *WCPtrSkipList<Type>::WCPtrSkipList()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
WCPtrSkipList(const WCPtrSkipList &);
```

**Semantics:** The `WCPtrSkipList<Type>` constructor is the copy constructor for the `WCPtrSkipList` class. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The `WCPtrSkipList<Type>` constructor creates a `WCPtrSkipList` object which is a copy of the passed list.

**See Also:** `operator =, WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
 virtual ~WCPtrSkipList();
```

**Semantics:** The `WCPtrSkipList<Type>` destructor is the destructor for the `WCPtrSkipList` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the list elements are cleared using the `clear` member function. The objects which the list elements point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the `WCPtrSkipList<Type>` destructor is inserted implicitly by the compiler at the point where the `WCPtrSkipList` object goes out of scope.

**Results:** The call to the `WCPtrSkipList<Type>` destructor destroys a `WCPtrSkipList` object.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::not_empty`

## *WCPtrSkipList<Type>::clear(), WCPtrSkipListSet<Type>::clear()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the list so that it has no entries. Objects pointed to by the list elements are not deleted. The list object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the list to have no elements.

**See Also:** `~WCPtrSkipList<Type>`, `clearAndDestroy`, `operator =`

**Synopsis:**

```
#include <wcskip.h>
public:
void clearAndDestroy();
```

**Semantics:** The `clearAndDestroy` public member function is used to clear the list and delete the objects pointed to by the list elements. The list object is not destroyed and re-created by this function, so the list object destructor is not invoked.

**Results:** The `clearAndDestroy` public member function clears the list by deleting the objects pointed to by the list elements, and then removing the list elements from the list.

**See Also:** `clear`

## *WCPtrSkipList<Type>::contains(), WCPtrSkipListSet<Type>::contains()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 int contains(const Type *) const;
```

**Semantics:** The `contains` public member function returns non-zero if the element is stored in the list, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The `contains` public member function returns a non-zero value if the element is found in the list.

**See Also:** `find`

**Synopsis:**

```
#include <wcskip.h>
public:
 unsigned entries() const;
```

**Semantics:** The `entries` public member function is used to return the current number of elements stored in the list.

**Results:** The `entries` public member function returns the number of elements in the list.

**See Also:** `isEmpty`

## *WCPtrSkipList<Type>::find(), WCPtrSkipListSet<Type>::find()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 Type * find(const Type *) const;
```

**Semantics:** The `find` public member function is used to find an element with an equivalent value in the list. If an equivalent element is found, a pointer to the element is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The element equivalent to the passed value is located in the list.

**Synopsis:**

```
#include <wcskip.h>
public:
void forAll(
void (*user_fn)(Type *, void *),
void *);
```

**Semantics:** The `forAll` public member function causes the user supplied function to be invoked for every value in the list. The user function has the prototype

```
void user_func(Type * value, void * data);
```

As the elements are visited, the user function is invoked with the element passed as the first. The second parameter of the `forAll` function is passed as the second parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

**Results:** The elements in the list are all visited, with the user function being invoked for each one.

**See Also:** `find`

**Synopsis:**

```
#include <wcskip.h>
public:
 int insert(Type *);
```

**Semantics:** The `insert` public member function inserts a value into the list. If allocation of the node to store the value fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the `insert` will not be completed.

With a `WCPtrSkipListSet`, there must be only one equivalent element in the set. If an element equivalent to the inserted element is already in the list set, the list set will remain unchanged, and the `not_unique` exception is thrown if it is enabled. If the exception is not enabled, the `insert` will not be completed.

**Results:** The `insert` public member function inserts a value into the list. If the `insert` is successful, a non-zero will returned. A zero will be returned if the `insert` fails.

**See Also:** `operator =`, `WCExcept::out_of_memory`, `WCExcept::not_unique`

**Synopsis:**

```
#include <wcskip.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if the list is empty.

**Results:** The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the list is empty.

**See Also:** `entries`

## *WCPtrSkipList<Type>::occurrencesOf()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 unsigned occurrencesOf(const Type *) const;
```

**Semantics:** The `occurrencesOf` public member function is used to return the current number of elements stored in the list which are equivalent to the passed value. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The `occurrencesOf` public member function returns the number of elements in the list which are equivalent to the passed value.

**See Also:** `entries`, `find`, `isEmpty`

**Synopsis:**

```
#include <wcskip.h>
public:
WCPtrSkipList & operator =(const WCPtrSkipList &);
WCPtrSkipListSet & operator =(const WCPtrSkipListSet &);
```

**Semantics:**

The `operator =` public member function is the assignment operator for the `WCPtrSkipList<Type>` and `WCPtrSkipListSet<Type>` classes. The left hand side list is first cleared using the `clear` member function, and then the right hand side list is copied. The list function, exception trap states, and all of the list elements are copied. If there is not enough memory to copy all of the values or pointers in the list, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

**Results:**

The `operator =` public member function assigns the left hand side list to be a copy of the right hand side.

**See Also:**

`clear`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
 int operator ==(const WCPtrSkipList &) const;
 int operator ==(const WCPtrSkipListSet &) const;
```

**Semantics:** The operator == public member function is the equivalence operator for the `WCPtrSkipList<Type>` and `WCPtrSkipListSet<Type>` classes. Two list objects are equivalent if they are the same object and share the same address.

**Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side list are the same object. A FALSE (zero) value is returned otherwise.

**Synopsis:**

```
#include <wcskip.h>
public:
 Type * remove(const Type *);
```

**Semantics:** The `remove` public member function is used to remove the specified element from the list. If an equivalent element is found, the pointer value is returned. Zero is returned if the element is not found. If the list is a `WCPtrSkipList` and there is more than one element equivalent to the specified element, then the last equivalent element added to the `WCPtrSkipList` is removed. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The element is removed from the list.

## *WCPtrSkipList<Type>::removeAll()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 unsigned removeAll(const Type *);
```

**Semantics:** The `removeAll` public member function is used to remove all elements equivalent to the specified element from the list. Zero is returned if no equivalent elements are found. Note that equivalence is based on the equivalence operator of the element type.

**Results:** All equivalent elements are removed from the list.

**Declared:** wcskip.h

The `WCValSkipListDict<Key,Value>` class is a templated class used to store objects in a dictionary. Dictionaries store values with an associated key, which may be of any type. One example of a dictionary used in everyday life is the phone book. The phone numbers are the data values, and the customer name is the key. The equality operator of the key's type is used to locate the key-value pairs.

In the description of each member function, the text `Key` is used to indicate the template parameter defining the type of the indices used to store data in the dictionary. The text `Value` is used to indicate the template parameter defining the type of the data stored in the dictionary.

Values are copied into the dictionary, which could be undesirable if the stored objects are complicated and copying is expensive. Value dictionaries should not be used to store objects of a base class if any derived types of different sizes would be stored in the dictionary, or if the destructor for a derived class must be called.

The iterator classes for skip lists have the same function and operator interface as the hash iterators classes. See the chapter on hash iterators for more information.

The `WCExcept` class is a base class of the `WCValSkipListDict<Key,Value>` class and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCValSkipListDict<Key,Value>` object. No exceptions are enabled unless they are set by the `exceptions` member function.

### **Requirements of Key and Value**

The `WCValSkipListDict<Key,Value>` class requires `Key` to have:

A default constructor (`Key::Key()`).

A well defined copy constructor (`Key::Key( const Key & )`).

A well defined assignment operator (`Key & operator =( const Key & )`).

A well defined equivalence operator with constant parameters  
(`int operator ==( const Key & ) const`).

A well defined operator less than with constant parameters  
(`int operator <( const Key & ) const`).

The `WCValSkipListDict<Key,Value>` class requires `Value` to have:

A default constructor (`Value::Value()`).

A well defined copy constructor (`Value::Value( const Value & )`).

A well defined assignment operator (`Value & operator =( const Value & )`).

### **Public Member Functions**

The following member functions are declared in the public interface:

```
WCValSkipListDict(unsigned = WCSkipListDict_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS);
```

## *WCValSkipListDict<Key, Value>*

---

```
WCValSkipListDict(unsigned = WCSkipListDict_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS, void * (*user_alloc)(size_t size),
void (*user_dealloc)(void *old, size_t size));
WCValSkipListDict(const WCValSkipListDict &);
virtual ~WCValSkipListDict();
void clear();
int contains(const Key &) const;
unsigned entries() const;
int find(const Key &, Value &) const;
int findKeyAndValue(const Key &, Key &, Value &) const;
void forAll(void (*user_fn)(Key, Value, void *), void *);
int insert(const Key &, const Value &);
int isEmpty() const;
int remove(const Key &);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
Value & operator [](const Key &);
const Value & operator [](const Key &) const;
WCValSkipListDict & operator =(const WCValSkipListDict &);
int operator ==(const WCValSkipListDict &) const;
```

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipListDict(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS);
```

**Semantics:** The public `WCValSkipListDict<Key,Value>` constructor creates an `WCValSkipListDict<Key,Value>` object with no entries. The first optional parameter, which defaults to the constant `WCSKIPLIST_PROB_QUARTER`, determines the probability of having a certain number of pointers in each skip list node. The second optional parameter, which defaults to the constant `WCDEFAULT_SKIPLIST_MAX_PTRS`, determines the maximum number of pointers that are allowed in any skip list node. `WCDEFAULT_SKIPLIST_MAX_PTRS` is the maximum effective value of the second parameter. If an allocation failure occurs while creating the skip list, the `out_of_memory` exception is thrown if the `out_of_memory` exception is enabled.

**Results:** The public `WCValSkipListDict<Key,Value>` constructor creates an initialized `WCValSkipListDict<Key,Value>` object.

**See Also:** `~WCValSkipListDict<Key,Value>`, `WCExcept::out_of_memory`

## *WCValSkipListDict<Key,Value>::WCValSkipListDict()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 WCValSkipListDict(unsigned = WCSKIPLIST_PROB_QUARTER,
 unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS,
 void * (*user_alloc)(size_t),
 void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the list dictionary. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a list dictionary. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
WCValSkipListDictItemSize( Key, Value, num\_of\_pointers )

**Results:** The public WCValSkipListDict<Key,Value> constructor creates an initialized WCValSkipListDict<Key,Value> object.

**See Also:** ~WCValSkipListDict<Key,Value>, WCEexcept::out\_of\_memory

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipListDict(const WCValSkipListDict &);
```

**Semantics:** The public `WCValSkipListDict<Key,Value>` constructor is the copy constructor for the `WCValSkipListDict<Key,Value>` class. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The public `WCValSkipListDict<Key,Value>` constructor creates an `WCValSkipListDict<Key,Value>` object which is a copy of the passed dictionary.

**See Also:** `operator =, WCExcept::out_of_memory`

## *WCValSkipListDict<Key,Value>::~WCValSkipListDict()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 virtual ~WCValSkipListDict();
```

**Semantics:** The public `~WCValSkipListDict<Key, Value>` destructor is the destructor for the `WCValSkipListDict<Key, Value>` class. If the number of dictionary elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the dictionary elements are cleared using the `clear` member function. The call to the public `~WCValSkipListDict<Key, Value>` destructor is inserted implicitly by the compiler at the point where the `WCValSkipListDict<Key, Value>` object goes out of scope.

**Results:** The public `~WCValSkipListDict<Key, Value>` destructor destroys an `WCValSkipListDict<Key, Value>` object.

**See Also:** `clear`, `WCExcept::not_empty`

**Synopsis:**

```
#include <wcskip.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the dictionary so that it has no entries. Elements stored in the dictionary are destroyed using the destructors of `Key` and of `Value`. The dictionary object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the dictionary to have no elements.

**See Also:** `~WCValSkipListDict<Key,Value>`, `operator =`

## *WCValSkipListDict<Key,Value>::contains()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 int contains(const Key &) const;
```

**Semantics:** The `contains` public member function returns non-zero if an element with the specified key is stored in the dictionary, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The `contains` public member function returns a non-zero value if the `Key` is found in the dictionary.

**See Also:** `find`, `findKeyAndValue`

**Synopsis:**

```
#include <wcskip.h>
public:
 unsigned entries() const;
```

**Semantics:** The `entries` public member function is used to return the current number of elements stored in the dictionary.

**Results:** The `entries` public member function returns the number of elements in the dictionary.

**See Also:** `isEmpty`

## *WCValSkipListDict<Key,Value>::find()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 int find(const Key &, Value &) const;
```

**Semantics:** The `find` public member function is used to find an element with an equivalent key in the dictionary. If an equivalent element is found, a non-zero value is returned. The reference to a `Value` passed as the second argument is assigned the found element's `Value`. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The element equivalent to the passed key is located in the dictionary.

**See Also:** `findKeyAndValue`

**Synopsis:**

```
#include <wcskip.h>
public:
 int findKeyAndValue(const Key &,
 Key &, Value &) const;
```

**Semantics:** The `findKeyAndValue` public member function is used to find an element in the dictionary with a key equivalent to the first parameter. If an equivalent element is found, a non-zero value is returned. The reference to a `Key` passed as the second parameter is assigned the found element's `key`. The reference to a `Value` passed as the third argument is assigned the found element's `Value`. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The element equivalent to the passed key is located in the dictionary.

**See Also:** `findKeyAndValue`

## *WCValSkipListDict<Key,Value>::forAll()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
void forAll(
void (*user_fn)(Key, Value, void *),
void *);
```

**Semantics:** The `forAll` public member function causes the user supplied function to be invoked for every key-value pair in the dictionary. The user function has the prototype

```
void user_func(Key key, Value value, void * data);
```

As the elements are visited, the user function is invoked with the `Key` and `Value` components of the element passed as the first two parameters. The second parameter of the `forAll` function is passed as the third parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

**Results:** The elements in the dictionary are all visited, with the user function being invoked for each one.

**See Also:** `find`, `findKeyAndValue`

**Synopsis:**

```
#include <wcskip.h>
public:
 int insert(const Key &, const Value &);
```

**Semantics:** The `insert` public member function inserts a key and value into the dictionary. If allocation of the node to store the key-value pair fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the insert will not be completed.

**Results:** The `insert` public member function inserts a key and value into the dictionary. If the insert is successful, a non-zero will be returned. A zero will be returned if the insert fails.

**See Also:** `operator =, WCExcept::out_of_memory`

## *WCValSkipListDict<Key,Value>::isEmpty()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if the dictionary is empty.

**Results:** The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the dictionary is empty.

**See Also:** `entries`

**Synopsis:**

```
#include <wcskip.h>
public:
 Value & operator[](const Key &);
```

**Semantics:** `operator []` is the dictionary index operator. A reference to the object stored in the dictionary with the given `Key` is returned. If no equivalent element is found, then a new key-value pair is created with the specified `Key` value, and initialized with the default constructor. The returned reference can then be assigned to, so that insertions can be made with the operator. If an allocation error occurs while inserting a new key-value pair, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

**Results:** The `operator []` public member function returns a reference to the element at the given key value. If the key does not exist, a reference to a created element is returned. The result of the operator may be assigned to.

**See Also:** `WCExcept::out_of_memory`

## *WCValSkipListDict<Key,Value>::operator []()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 const Value & operator[](const Key &) const;
```

**Semantics:** operator [] is the dictionary index operator. A constant reference to the object stored in the dictionary with the given Key is returned. If no equivalent element is found, then the `index_range` exception is thrown if it is enabled. If the exception is not enabled, then a reference to address zero will be returned. This will result in a run-time error on systems which trap address zero references.

**Results:** The operator [] public member function returns a constant reference to the element at the given key value. The result of the operator may not be assigned to.

**See Also:** `WCExcept::index_range`

**Synopsis:**

```
#include <wcskip.h>
public:
 WCValSkipListDict & operator =(const WCValSkipListDict &);
```

**Semantics:** The `operator =` public member function is the assignment operator for the `WCValSkipListDict<Key,Value>` class. The left hand side dictionary is first cleared using the `clear` member function, and then the right hand side dictionary is copied. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values or pointers in the dictionary, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

**Results:** The `operator =` public member function assigns the left hand side dictionary to be a copy of the right hand side.

**See Also:** `clear`, `WCExcept::out_of_memory`

## *WCValSkipListDict<Key,Value>::operator ==()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 int operator ==(const WCValSkipListDict &) const;
```

**Semantics:**

The operator == public member function is the equivalence operator for the WCValSkipListDict<Key,Value> class. Two dictionary objects are equivalent if they are the same object and share the same address.

**Results:**

A TRUE (non-zero) value is returned if the left hand side and right hand side dictionary are the same object. A FALSE (zero) value is returned otherwise.

**Synopsis:**

```
#include <wcskip.h>
public:
 int remove(const Key &);
```

**Semantics:** The `remove` public member function is used to remove the specified element from the dictionary. If an equivalent element is found, a non-zero value is returned. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the `Key` type.

**Results:** The element is removed from the dictionary if it found.

## **WCValSkipList<Type>, WCValSkipListSet<Type>**

---

**Declared:** wcskip.h

`WCValSkipList<Type>` and `WCValSkipListSet<Type>` classes are templated classes used to store objects in a skip list. A skip list is a probabilistic alternative to balanced trees, and provides a reasonable performance balance to insertion, search, and deletion. A skip list allows more than one copy of an element that is equivalent, while the skip list set allows only one copy. The equality operator of the element's type is used to locate the value.

In the description of each member function, the text `Type` is used to indicate the template parameter defining the type of the data to be stored in the list.

Values are copied into the list, which could be undesirable if the stored objects are complicated and copying is expensive. Value skip lists should not be used to store objects of a base class if any derived types of different sizes would be stored in the list, or if the destructor for a derived class must be called.

The iterator classes for skip lists have the same function and operator interface as the hash iterators classes. See the chapter on hash iterators for more information.

The `WCExcept` class is a base class of the `WCValSkipList<Type>` and `WCValSkipListSet<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCValSkipList<Type>` and `WCValSkipListSet<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

### **Requirements of Type**

The `WCValSkipList<Type>` and `WCValSkipListSet<Type>` classes requires `Type` to have:

A default constructor (`Type::Type()`).

A well defined copy constructor (`Type::Type( const Type & )`).

A well defined equivalence operator  
(`int operator ==( const Type & ) const`).

A well defined less than operator  
(`int operator <( const Type & ) const`).

### **Public Member Functions**

The following member functions are declared in the public interface:

```
WCValSkipList(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS);
WCValSkipList(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS, void * (*user_alloc)(size_t size),
void (*user_dealloc)(void *old, size_t size));
WCValSkipList(const WCValSkipList &);
virtual ~WCValSkipList();
WCValSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS);
WCValSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER, unsigned =
WCDEFAULT_SKIPLIST_MAX_PTRS, void * (*user_alloc)(size_t size),
void (*user_dealloc)(void *old, size_t size));
WCValSkipListSet(const WCValSkipListSet &);
```

```
virtual ~WCValSkipListSet();
void clear();
int contains(const Type &) const;
unsigned entries() const;
int find(const Type &, Type &) const;
void forAll(void (*user_fn)(Type, void *), void *);
int insert(const Type &);
int isEmpty() const;
int remove(const Type &);
```

The following public member functions are available for the WCValSkipList class only:

```
unsigned occurrencesOf(const Type &) const;
unsigned removeAll(const Type &);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
WCValSkipList & operator =(const WCValSkipList &);
int operator ==(const WCValSkipList &) const;
WCValSkipListSet & operator =(const WCValSkipListSet &);
int operator ==(const WCValSkipListSet &) const;
```

## `WCValSkipListSet<Type>::WCValSkipListSet()`

---

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS);
```

**Semantics:** The `WCValSkipListSet<Type>` constructor creates a `WCValSkipListSet` object with no entries. The first optional parameter, which defaults to the constant `WCSKIPLIST_PROB_QUARTER`, determines the probability of having a certain number of pointers in each skip list node. The second optional parameter, which defaults to the constant `WCDEFAULT_SKIPLIST_MAX_PTRS`, determines the maximum number of pointers that are allowed in any skip list node. `WCDEFAULT_SKIPLIST_MAX_PTRS` is the maximum effective value of the second parameter. If an allocation failure occurs while creating the skip list, the `out_of_memory` exception is thrown if the `out_of_memory` exception is enabled.

**Results:** The `WCValSkipListSet<Type>` constructor creates an initialized `WCValSkipListSet` object.

**See Also:** `~WCValSkipList<Type>`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipListSet(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS,
void * (*user_alloc)(size_t),
void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the list. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a skip list. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
WCValSkipListSetItemSize( Type, num\_of\_pointers )

**Results:** The `WCValSkipListSet<Type>` constructor creates an initialized `WCValSkipListSet` object.

**See Also:** `~WCValSkipList<Type>`, `WCExcept::out_of_memory`

## *WCValSkipListSet<Type>::WCValSkipListSet()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipListSet(const WCValSkipListSet &);
```

**Semantics:** The `WCValSkipListSet<Type>` constructor is the copy constructor for the `WCValSkipListSet` class. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The `WCValSkipListSet<Type>` constructor creates a `WCValSkipListSet` object which is a copy of the passed list.

**See Also:** `operator =, WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
 virtual ~WCValSkipListSet();
```

**Semantics:** The `WCValSkipListSet<Type>` destructor is the destructor for the `WCValSkipListSet` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the list elements are cleared using the `clear` member function. The call to the `WCValSkipListSet<Type>` destructor is inserted implicitly by the compiler at the point where the `WCValSkipListSet` object goes out of scope.

**Results:** The call to the `WCValSkipListSet<Type>` destructor destroys a `WCValSkipListSet` object.

**See Also:** `clear`, `WCExcept::not_empty`

## *WCValSkipList*<Type>::*WCValSkipList*()

---

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipList(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS);
```

**Semantics:**

The *WCValSkipList*<Type> constructor creates a *WCValSkipList* object with no entries. The first optional parameter, which defaults to the constant *WCSKIPLIST\_PROB\_QUARTER*, determines the probability of having a certain number of pointers in each skip list node. The second optional parameter, which defaults to the constant *WCDEFAULT\_SKIPLIST\_MAX\_PTRS*, determines the maximum number of pointers that are allowed in any skip list node.

*WCDEFAULT\_SKIPLIST\_MAX\_PTRS* is the maximum effective value of the second parameter. If an allocation failure occurs while creating the skip list, the *out\_of\_memory* exception is thrown if the *out\_of\_memory* exception is enabled.

**Results:**

The *WCValSkipList*<Type> constructor creates an initialized *WCValSkipList* object.

**See Also:**

*~WCValSkipList*<Type>, *WCExcept*::*out\_of\_memory*

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipList(unsigned = WCSKIPLIST_PROB_QUARTER,
unsigned = WCDEFAULT_SKIPLIST_MAX_PTRS,
void * (*user_alloc)(size_t),
void (*user_dealloc)(void *, size_t));
```

**Semantics:** Allocator and deallocator functions are specified for use when entries are inserted and removed from the list. The semantics of this constructor are the same as the constructor without the memory management functions.

The allocation function must return a zero if it cannot perform the allocation. The deallocation function is passed the size as well as the pointer to the data. Your allocation system may take advantage of the characteristic that the allocation function will always be called with the same size value for any particular instantiation of a skip list. To determine the size of the objects that the memory management functions will be required to allocate and free, the following macro may be used:  
WCValSkipListItemSize( Type, num\_of\_pointers )

**Results:** The `WCValSkipList<Type>` constructor creates an initialized `WCValSkipList` object.

**See Also:** `~WCValSkipList<Type>`, `WCExcept::out_of_memory`

## *WCValSkipList<Type>::WCValSkipList()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
WCValSkipList(const WCValSkipList &);
```

**Semantics:** The `WCValSkipList<Type>` constructor is the copy constructor for the `WCValSkipList` class. The new skip list is created with the same probability and maximum pointers, all values or pointers stored in the list, and the exception trap states. If there is not enough memory to copy all of the values, then only some will be copied, and the number of entries will correctly reflect the number copied. If all of the elements cannot be copied, then the `out_of_memory` exception is thrown if it is enabled.

**Results:** The `WCValSkipList<Type>` constructor creates a `WCValSkipList` object which is a copy of the passed list.

**See Also:** `operator =, WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
 virtual ~WCValSkipList();
```

**Semantics:** The `WCValSkipList<Type>` destructor is the destructor for the `WCValSkipList` class. If the number of elements is not zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the list elements are cleared using the `clear` member function. The call to the `WCValSkipList<Type>` destructor is inserted implicitly by the compiler at the point where the `WCValSkipList` object goes out of scope.

**Results:** The call to the `WCValSkipList<Type>` destructor destroys a `WCValSkipList` object.

**See Also:** `clear`, `WCExcept::not_empty`

## *WCValSkipList<Type>::clear(), WCValSkipListSet<Type>::clear()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the list so that it has no entries. Elements stored in the list are destroyed using the destructors of `Type`. The list object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the list to have no elements.

**See Also:** `~WCValSkipList<Type>`, `operator =`

**Synopsis:**

```
#include <wcskip.h>
public:
 int contains(const Type &) const;
```

**Semantics:** The `contains` public member function returns non-zero if the element is stored in the list, or zero if there is no equivalent element. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The `contains` public member function returns a non-zero value if the element is found in the list.

**See Also:** `find`

## *WCValSkipList<Type>::entries(), WCValSkipListSet<Type>::entries()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 unsigned entries() const;
```

**Semantics:** The `entries` public member function is used to return the current number of elements stored in the list.

**Results:** The `entries` public member function returns the number of elements in the list.

**See Also:** `isEmpty`

**Synopsis:**

```
#include <wcskip.h>
public:
 int find(const Type &, Type &) const;
```

**Semantics:** The `find` public member function is used to find an element with an equivalent value in the list. If an equivalent element is found, a non-zero value is returned. The reference to the element passed as the second argument is assigned the found element's value. Zero is returned if the element is not found. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The element equivalent to the passed value is located in the list.

**Synopsis:**

```
#include <wcskip.h>
public:
void forAll(
void (*user_fn)(Type, void *),
void *);
```

**Semantics:** The `forAll` public member function causes the user supplied function to be invoked for every value in the list. The user function has the prototype

```
void user_func(Type & value, void * data);
```

As the elements are visited, the user function is invoked with the element passed as the first. The second parameter of the `forAll` function is passed as the second parameter to the user function. This value can be used to pass any appropriate data from the main code to the user function.

**Results:** The elements in the list are all visited, with the user function being invoked for each one.

**See Also:** `find`

**Synopsis:**

```
#include <wcskip.h>
public:
 int insert(const Type &);
```

**Semantics:** The `insert` public member function inserts a value into the list. If allocation of the node to store the value fails, then the `out_of_memory` exception is thrown if it is enabled. If the exception is not enabled, the `insert` will not be completed.

With a `WCValSkipListSet`, there must be only one equivalent element in the set. If an element equivalent to the inserted element is already in the list set, the list set will remain unchanged, and the `not_unique` exception is thrown if it is enabled. If the exception is not enabled, the `insert` will not be completed.

**Results:** The `insert` public member function inserts a value into the list. If the `insert` is successful, a non-zero will be returned. A zero will be returned if the `insert` fails.

**See Also:** `operator =`, `WCExcept::out_of_memory`, `WCExcept::not_unique`

## *WCValSkipList<Type>::isEmpty(), WCValSkipListSet<Type>::isEmpty()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if the list is empty.

**Results:** The `isEmpty` public member function returns zero if it contains at least one entry, non-zero if the list is empty.

**See Also:** `entries`

**Synopsis:**

```
#include <wcskip.h>
public:
 unsigned occurrencesOf(const Type &) const;
```

**Semantics:** The `occurrencesOf` public member function is used to return the current number of elements stored in the list which are equivalent to the passed value. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The `occurrencesOf` public member function returns the number of elements in the list which are equivalent to the passed value.

**See Also:** `entries`, `find`, `isEmpty`

## *WCValSkipList<Type>::operator =(), WCValSkipListSet<Type>::operator =()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 WCValSkipList & operator =(const WCValSkipList &);
 WCValSkipListSet & operator =(const WCValSkipListSet &);
```

**Semantics:** The `operator =` public member function is the assignment operator for the `WCValSkipList<Type>` and `WCValSkipListSet<Type>` classes. The left hand side list is first cleared using the `clear` member function, and then the right hand side list is copied. The list function, exception trap states, and all of the list elements are copied. If there is not enough memory to copy all of the values or pointers in the list, then only some will be copied, and the `out_of_memory` exception is thrown if it is enabled. The number of entries will correctly reflect the number copied.

**Results:** The `operator =` public member function assigns the left hand side list to be a copy of the right hand side.

**See Also:** `clear`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcskip.h>
public:
 int operator ==(const WCValSkipList &) const;
 int operator ==(const WCValSkipListSet &) const;
```

**Semantics:** The operator == public member function is the equivalence operator for the WCValSkipList<Type> and WCValSkipListSet<Type> classes. Two list objects are equivalent if they are the same object and share the same address.

**Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side list are the same object. A FALSE (zero) value is returned otherwise.

## *WCValSkipList<Type>::remove(), WCValSkipListSet<Type>::remove()*

---

**Synopsis:**

```
#include <wcskip.h>
public:
 int remove(const Type &);
```

**Semantics:** The `remove` public member function is used to remove the specified element from the list. If an equivalent element is found, a non-zero value is returned. Zero is returned if the element is not found. If the list is a `WCValSkipList` and there is more than one element equivalent to the specified element, then the last equivalent element added to the `WCValSkipList` is removed. Note that equivalence is based on the equivalence operator of the element type.

**Results:** The element is removed from the list.

**Synopsis:**

```
#include <wcskip.h>
public:
 unsigned removeAll(const Type &);
```

**Semantics:** The `removeAll` public member function is used to remove all elements equivalent to the specified element from the list. Zero is returned if no equivalent elements are found. Note that equivalence is based on the equivalence operator of the element type.

**Results:** All equivalent elements are removed from the list.



---

# **16 Stack Container**

Stack containers maintain an ordered collection of data which is retrieved in the reverse order to which the data was entered into the stack. The stack class is implemented as a templated class, allowing the stacking of any data type.

A second template parameter specifies the storage class used to implement the stack. The `WCValsList`, `WCIsvSList` and `WCPtrSList` classes are appropriate storage classes.

## WCStack<Type,FType>

---

**Declared:** wcstack.h

The WCStack<Type, FType> class is a templated class used to create objects which maintain data in a stack.

In the description of each member function, the text Type is used to indicate the template parameter defining the type of the elements stored in the stack. The text FType is used to indicate the template parameter defining the storage class used to maintain the stack.

For example, to create a stack of integers, the WCStack<int, WCValsList<int> > class can be used. The WCStack<int \*, WCPtrsList<int> > class will create a stack of pointers to integers. To create an intrusive stack of objects of type *isv\_link* (derived from the WCSLink class), the WCStack<*isv\_link* \*, WCIsvSList<*isv\_link*> > class can be used.

The WCExcept class is a base class of the WCStack<Type, FType> class and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCStack<Type, FType> object. No exceptions are enabled unless they are set by the exceptions member function.

### Requirements of Type

Type must provide any constructors and/or operators required by the FType class.

### Public Member Functions

The following member functions are declared in the public interface:

```
WCStack();
WCStack(void *(*)(size_t), void (*)(void *, size_t));
~WCStack();
void clear();
int entries() const;
int isEmpty() const;
Type pop();
int push(const Type &);
Type top() const;
```

### Sample Program Using a Stack

```
#include <wcstack.h>
#include <iostream.h>

void main() {
 WCStack<int, WCValsList<int> > stack;

 stack.push(7);
 stack.push(8);
 stack.push(9);
 stack.push(10);

 cout << "\nNumber of stack entries: " << stack.entries() << "\n";
 cout << "Top entry = [" << stack.top() << "]\n";
 while(!stack.isEmpty()) {
 cout << stack.pop() << "\n";
 };
 cout.flush();
}
```

**Synopsis:**

```
#include <wcstack.h>
public:
WCStack();
```

**Semantics:** The public `WCStack<Type,FType>` constructor creates an empty `WCStack<Type,FType>` object. The `FType` storage class constructor performs the initialization.

**Results:** The public `WCStack<Type,FType>` constructor creates an initialized `WCStack<Type,FType>` object.

**See Also:** `~WCStack<Type,FType>`

## WCStack<Type,FType>::WCStack()

---

**Synopsis:**

```
#include <wcstack.h>
public:
 WCStack(void *(*allocator)(size_t),
 void (*deallocator)(void *, size_t));
```

**Semantics:** The public `WCStack<Type,FType>` constructor creates an empty `WCStack<Type,FType>` object. If `FType` is either the `WCValSList` or `WCPtrSList` class, then the *allocator* function is registered to perform all memory allocations of the stack elements, and the *deallocator* function to perform all freeing of the stack elements' memory. The *allocator* and *deallocator* functions are ignored if `FType` is the `WCIsvSList` class. These functions provide the ability to control how the allocation and freeing of memory is performed, allowing for more efficient memory handling than the general purpose global operator `new()` and operator `delete()` can provide. Memory management optimizations may potentially be made through the *allocator* and *deallocator* functions, but are not recommended before managing memory is understood and determined to be worth while.

The *allocator* function shall return a pointer to allocated memory of size at least the argument, or zero(0) if the allocation cannot be performed. Initialization of the memory returned is performed by the `WCStack<Type,FType>` class.

The `WCStack<Type,FType>` class calls the *deallocator* function only on memory allocated by the *allocator* function. The *deallocator* shall free the memory pointed to by the first argument which is of size the second argument. The size passed to the *deallocator* function is guaranteed to be the same size passed to the *allocator* function when the memory was allocated.

The *allocator* and *deallocator* functions may assume that for a list object instance, the *allocator* is always called with the same first argument (the size of the memory to be allocated). If `FType` is the `WCValSList<Type>` class, then the `WCValSListItemSize(Type)` macro returns the size of the elements which are allocated by the *allocator* function. Similarly, the `WCPtrSListItemSize(Type)` macro returns the size of `WCPtrSList<Type>` elements.

The `FType` storage class constructor performs the initialization of the stack.

**Results:** The public `WCStack<Type,FType>` constructor creates an initialized `WCStack<Type,FType>` object and registers the *allocator* and *deallocator* functions.

**See Also:** `WCStack<Type,FType>`, `~WCStack<Type,FType>`

**Synopsis:**

```
#include <wcstack.h>
public:
 virtual ~WCStack();
```

**Semantics:** The public `~WCStack<Type, FType>` destructor destroys the `WCStack<Type, FType>` object. The `FType` storage class destructor performs the destruction. The call to the public `~WCStack<Type, FType>` destructor is inserted implicitly by the compiler at the point where the `WCStack<Type, FType>` object goes out of scope.

If the `not_empty` exception is enabled, the exception is thrown if the stack is not empty of stack elements.

**Results:** The `WCStack<Type, FType>` object is destroyed.

**See Also:** `WCStack<Type, FType>, clear, WCExcept::not_empty`

## **WCStack<Type,FType>::clear()**

---

**Synopsis:**

```
#include <wcstack.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the stack object and set it to the state of the object just after the initial construction. The stack object is not destroyed and re-created by this operator, so the object destructor is not invoked. The stack elements are not cleared by the stack class. However, the class used to maintain the stack, `FType`, may clear the items as part of the `clear` member function for that class. If it does not clear the items, any stack items still in the list are lost unless pointed to by some pointer object in the program code.

**Results:** The `clear` public member function resets the stack object to the state of the object immediately after the initial construction.

**See Also:** `~WCStack<Type,FType>`, `isEmpty`

**Synopsis:**

```
#include <wcstack.h>
public:
 int entries() const;
```

**Semantics:** The `entries` public member function is used to determine the number of stack elements contained in the list object.

**Results:** The number of elements on the stack is returned. Zero(0) is returned if there are no stack elements.

**See Also:** `isEmpty`

## *WCStack<Type,FType>::isEmpty()*

---

**Synopsis:**

```
#include <wcstack.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if a stack object has any stack elements contained in it.

**Results:** A TRUE value (non-zero) is returned if the stack object does not have any stack elements contained within it. A FALSE (zero) result is returned if the stack contains at least one element.

**See Also:** [entries](#)

**Synopsis:**

```
#include <wcstack.h>
public:
 Type pop();
```

**Semantics:** The `pop` public member function returns the top stack element from the stack object. The top stack element is the last element pushed onto the stack. The stack element is also removed from the stack.

If the stack is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, then it will be thrown. Otherwise, the `index_range` exception will be thrown, if enabled.

**Results:** The top stack element is removed and returned. The return value is determined by the `get` member function of the `FType` class if there are no elements on the stack.

**See Also:** `isEmpty`, `push`, `top`, `WCExcept::empty_container`, `WCExcept::index_range`, `FType::get`

## *WCStack<Type,FType>::push()*

---

**Synopsis:**

```
#include <wcstack.h>
public:
 int push(const Type &);
```

**Semantics:** The push public member function is used to push the data onto the top of the stack. It will be the first element on the stack to be popped.

If the push fails, the `out_of_memory` exception will be thrown, if enabled, and the stack will remain unchanged.

**Results:** The stack element is pushed onto the top of the stack. A TRUE value (non-zero) is returned if the push is successful. A FALSE (zero) result is returned if the push fails.

**See Also:** `pop`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcstack.h>
public:
 Type top() const;
```

**Semantics:** The `top` public member function returns the top stack element from the stack object. The top stack element is the last element pushed onto the stack. The stack element is not removed from the stack.

If the stack is empty, one of two exceptions can be thrown. If the `empty_container` exception is enabled, then it will be thrown. Otherwise, the `index_range` exception will be thrown, if enabled.

**Results:** The top stack element is returned. The return value is determined by the `find` member function of the `FType` class if there are no elements on the stack.

**See Also:** `isEmpty`, `pop`, `WCExcept::empty_container`, `WCExcept::index_range`, `FType::find`

## *WCStack<Type,FType>::top()*

---

---

# **17** *Vector Containers*

This chapter describes vector containers.

## **WCPtrSortedVector<Type>, WCPtrOrderedVector<Type>**

---

**Declared:** wcvector.h

The `WCPtrSortedVector<Type>` and `WCPtrOrderedVector<Type>` classes are templated classes used to store objects in a vector. Ordered and Sorted vectors are powerful arrays which can be resized and provide an abstract interface to insert, find and remove elements. An ordered vector maintains the order in which elements are added, and allows more than one copy of an element that is equivalent. The sorted vector allow only one copy of an equivalent element, and inserts them in a sorted order. The sorted vector is less efficient when inserting elements, but can provide a faster retrieval time.

Elements cannot be inserted into these vectors by assigning to a vector index. Vectors automatically grow when necessary to insert an element if the `resize_required` exception is not enabled.

In the description of each member function, the text `Type` is used to indicate the template parameter defining the type pointed to by the pointers stored in the vector.

Note that lookups are performed on the types pointed to, not just by comparing pointers. Two pointer elements are equivalent if the values they point to are equivalent. The values pointed to do not need to be the same object.

The `WCPtrOrderedVector` class stores elements in the order which they are inserted using the `insert`, `append`, `prepend` and `insertAt` member functions. Linear searches are performed to locate entries, and the less than operator is not required.

The `WCPtrSortedVector` class stores elements in ascending order. This requires that `Type` provides a less than operator. Insertions are more expensive than inserting or appending into an ordered vector, since entries must be moved to make room for the new element. A binary search is used to locate elements in a sorted vector, making searches quicker than in the ordered vector.

Care must be taken when using the `WCPtrSortedVector` class not to change the ordering of the vector elements. An object pointed to by a vector element must not be changed so that it is not equivalent to the value when the pointer was inserted into the vector. The index operator and the member functions `find`, `first`, and `last` all return pointers to the elements pointed to by the vector elements. Lookups assume elements are in sorted order, so you should not use the returned pointers to change the ordering of the value pointed to.

The `WCPtrVector` class is also available. It provides a resizable and boundary safe vector similar to standard arrays.

The `WCExcept` class is a base class of the `WCPtrSortedVector<Type>` and `WCPtrOrderedVector<Type>` classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the `WCPtrSortedVector<Type>` and `WCPtrOrderedVector<Type>` objects. No exceptions are enabled unless they are set by the `exceptions` member function.

### **Requirements of Type**

Both the `WCPtrSortedVector<Type>` and `WCPtrOrderedVector<Type>` classes require `Type` to have:

A well defined equivalence operator with constant parameters  
(`int operator ==( const Type & ) const`).

Additionally the `WCPtrSortedVector` class requires `Type` to have:

A well defined less than operator with constant parameters  
( int operator <( const Type & ) const ).

### **Public Member Functions**

The following member functions are declared in the public interface:

```
WCPtrOrderedVector(size_t = WCDEFAULT_VECTOR_LENGTH, unsigned =
WCDEFAULT_VECTOR_RESIZE_GROW);
WCPtrOrderedVector(const WCPtrOrderedVector &);
virtual ~WCPtrOrderedVector();
WCPtrSortedVector(size_t = WCDEFAULT_VECTOR_LENGTH, unsigned =
WCDEFAULT_VECTOR_RESIZE_GROW);
WCPtrSortedVector(const WCPtrSortedVector &);
virtual ~WCPtrSortedVector();
void clear();
void clearAndDestroy();
int contains(const Type *) const;
unsigned entries() const;
Type * find(const Type *) const;
Type * first() const;
int index(const Type *) const;
int insert(Type *);
int isEmpty() const;
Type * last() const;
int occurrencesOf(const Type *) const;
Type * remove(const Type *);
unsigned removeAll(const Type *);
Type * removeAt(int);
Type * removeFirst();
Type * removeLast();
int resize(size_t);
```

The following public member functions are available for the `WCPtrOrderedVector` class only:

```
int append(Type *);
int insertAt(int, Type *);
int prepend(Type *);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
Type * & operator [](int);
Type * const & operator [](int) const;
WCPtrOrderedVector & WCPtrOrderedVector::operator =(const
WCPtrOrderedVector &);
WCPtrSortedVector & WCPtrSortedVector::operator =(const
WCPtrSortedVector &);
int WCPtrOrderedVector::operator ==(const WCPtrOrderedVector &)
const;
int WCPtrSortedVector::operator ==(const WCPtrSortedVector &)
const;
```

## *WCPtrOrderedVector<Type>::WCPtrOrderedVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
WCPtrOrderedVector(size_t = WCDEFAULT_VECTOR_LENGTH,
unsigned = WCDEFAULT_VECTOR_RESIZE_GROW);
```

**Semantics:**

The `WCPtrOrderedVector<Type>` constructor creates an empty `WCPtrOrderedVector` object able to store the number of elements specified in the first optional parameter, which defaults to the constant `WCDEFAULT_VECTOR_LENGTH` (currently defined as 10). If the `resize_required` exception is not enabled, then the second optional parameter is used to specify the value to increase the vector size when an element is inserted into a full vector. If zero(0) is specified as the second parameter, any attempt to insert into a full vector fails. This parameter defaults to the constant `WCDEFAULT_VECTOR_RESIZE_GROW` (currently defined as 5).

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:**

The `WCPtrOrderedVector<Type>` constructor creates an empty initialized `WCPtrOrderedVector` object.

**See Also:**

`WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
WCPtrOrderedVector(const WCPtrOrderedVector &);
```

**Semantics:**

The `WCPtrOrderedVector<Type>` constructor is the copy constructor for the `WCPtrOrderedVector` class. The new vector is created with the same length and resize value as the passed vector. All of the vector elements and exception trap states are copied.

If the new vector cannot be fully created, it will have length zero. The `out_of_memory` exception is thrown if enabled in the vector being copied.

**Results:**

The `WCPtrOrderedVector<Type>` creates a `WCPtrOrderedVector` object which is a copy of the passed vector.

**See Also:**

`operator =, WCExcept::out_of_memory`

## *WCPtrOrderedVector<Type>::~WCPtrOrderedVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 virtual ~WCPtrOrderedVector();
```

**Semantics:** The `WCPtrOrderedVector<Type>` destructor is the destructor for the `WCPtrOrderedVector` class. If the vector is not length zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the vector entries are cleared using the `clear` member function. The objects which the vector entries point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the `WCPtrOrderedVector<Type>` destructor is inserted implicitly by the compiler at the point where the `WCPtrOrderedVector` object goes out of scope.

**Results:** The `WCPtrOrderedVector<Type>` destructor destroys an `WCPtrOrderedVector` object.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::not_empty`

**Synopsis:**

```
#include <wcvector.h>
public:
WCPtrSortedVector(size_t = WCDEFAULT_VECTOR_LENGTH,
unsigned = WCDEFAULT_VECTOR_RESIZE_GROW);
```

**Semantics:** The `WCPtrSortedVector<Type>` constructor creates an empty `WCPtrSortedVector` object able to store the number of elements specified in the first optional parameter, which defaults to the constant `WCDEFAULT_VECTOR_LENGTH` (currently defined as 10). If the `resize_required` exception is not enabled, then the second optional parameter is used to specify the value to increase the vector size when an element is inserted into a full vector. If zero(0) is specified as the second parameter, any attempt to insert into a full vector fails. This parameter defaults to the constant `WCDEFAULT_VECTOR_RESIZE_GROW` (currently defined as 5).

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:** The `WCPtrSortedVector<Type>` constructor creates an empty initialized `WCPtrSortedVector` object.

**See Also:** `WCExcept::resize_required`

## *WCPtrSortedVector<Type>::WCPtrSortedVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 WCPtrSortedVector(const WCPtrSortedVector &);
```

**Semantics:** The `WCPtrSortedVector<Type>` constructor is the copy constructor for the `WCPtrSortedVector` class. The new vector is created with the same length and resize value as the passed vector. All of the vector elements and exception trap states are copied.

If the new vector cannot be fully created, it will have length zero. The `out_of_memory` exception is thrown if enabled in the vector being copied.

**Results:** The `WCPtrSortedVector<Type>` constructor creates a `WCPtrSortedVector` object which is a copy of the passed vector.

**See Also:** `operator =, WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcvector.h>
public:
 virtual ~WCPtrSortedVector();
```

**Semantics:** The `WCPtrSortedVector<Type>` destructor is the destructor for the `WCPtrSortedVector` class. If the vector is not length zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the vector entries are cleared using the `clear` member function. The objects which the vector entries point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the `WCPtrSortedVector<Type>` destructor is inserted implicitly by the compiler at the point where the `WCPtrSortedVector` object goes out of scope.

**Results:** The `WCPtrSortedVector<Type>` destructor destroys an `WCPtrSortedVector` object.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::not_empty`

## *WCPtrOrderedVector<Type>::append()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int append(Type *);
```

**Semantics:** The append public member function appends the passed element to be the last element in the vector. This member function has the same semantics as the `WCPtrOrderedVector::insert` member function.

This function is not provided by the `WCPtrSortedVector` class, since all elements must be inserted in sorted order by the `insert` member function.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the append fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not appended to the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The append public member function appends an element to the `WCPtrOrderedVector` object. A TRUE (non-zero) value is returned if the append is successful. If the append fails, a FALSE (zero) value is returned.

**See Also:** `insert`, `insertAt`, `prepend`, `WCExcept::out_of_memory`,  
`WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the vector so that it contains no entries, and is zero size. Objects pointed to by the vector elements are not deleted. The vector object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the vector to have zero length and no entries.

**See Also:** `~WCPtrOrderedVector`, `clearAndDestroy`, `operator =`

## *WCPtrSortedVector<Type>, WCPtrOrderedVector<Type>::clearAndDestroy()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
void clearAndDestroy();
```

**Semantics:** The `clearAndDestroy` public member function is used to clear the vector to have zero length and delete the objects pointed to by the vector elements. The vector object is not destroyed and re-created by this function, so the vector object destructor is not invoked.

**Results:** The `clearAndDestroy` public member function clears the vector by deleting the objects pointed to by the vector elements and makes the vector zero length.

**See Also:** `clear`

**Synopsis:**

```
#include <wcvector.h>
public:
 int contains(const Type *) const;
```

**Semantics:** The `contains` public member function is used to determine if a value is contained by a vector. Note that comparisons are done on the objects pointed to, not the pointers themselves. A linear search is used by the `WCPtrOrderedVector` class to find the value. The `WCPtrSortedVector` class uses a binary search.

**Results:** The `contains` public member function returns a TRUE (non-zero) value if the element is found in the vector. A FALSE (zero) value is returned if the vector does not contain the element.

**See Also:** `index`, `find`

## *WCPtrSortedVector<Type>::entries(), WCPtrOrderedVector<Type>::entries()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 unsigned entries() const;
```

**Semantics:** The `entries` public member function is used to find the number of elements which are stored in the vector.

**Results:** The `entries` public member function returns the number of elements in the vector.

**See Also:** `isEmpty`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * find(const Type *) const;
```

**Semantics:** The `find` public member function is used to find an element equivalent to the element passed. Note that comparisons are done on the objects pointed to, not the pointers themselves. The `WCPtrOrderedVector` class uses a linear search to find the element, and the `WCPtrSortedVector` class uses a binary search.

**Results:** A pointer to the first equivalent element is returned. `NULL(0)` is returned if the element is not in the vector.

**See Also:** `contains`, `first`, `index`, `last`, `occurrencesOf`, `remove`

## *WCPtrSortedVector<Type>::first(), WCPtrOrderedVector<Type>::first()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * first() const;
```

**Semantics:** The `first` public member function returns the first element in the vector. The element is not removed from the vector.

If the vector is empty, one of two exceptions can be thrown. The `empty_container` exception is thrown if it is enabled. Otherwise, if the `index_range` exception is enabled, it is thrown. If neither exception is enabled, a first element of the vector is added with a NULL value.

**Results:** The `first` public member function returns the value of the first element in the vector.

**See Also:** `last`, `removeFirst`, `WCExcept::index_range`, `WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 int index(const Type *) const;
```

**Semantics:** The `index` public member function is used find the index of the first element equivalent to the passed element. Note that comparisons are done on the objects pointed to, not the pointers themselves. A linear search is used by the `WCPtrOrderedVector` class to find the element. The `WCPtrSortedVector` class uses a binary search.

**Results:** The `index` public member function returns the index of the first element equivalent to the parameter. If the passed value is not contained in the vector, negative one (-1) is returned.

**See Also:** `contains`, `find`, `insertAt`, `operator []`, `removeAt`

## *WCPtrSortedVector<Type>::insert(), WCPtrOrderedVector<Type>::insert()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int insert(Type *);
```

**Semantics:** The `insert` public member function inserts the value into the vector.

The `WCPtrOrderedVector::insert` function inserts the value as the last element of the vector, and has the same semantics as the `WCPtrOrderedVector::append` member function.

A binary search is performed to determine where the value should be inserted for the `WCPtrSortedVector::insert` function. Note that comparisons are done on the objects pointed to, not the pointers themselves. Any elements greater than the inserted value are copied up one index so that the new element is after all elements with value less than or equal to it.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the `insert` fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not inserted to the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The `insert` public member function inserts an element in to the vector. A TRUE (non-zero) value is returned if the insert is successful. If the insert fails, a FALSE (zero) value is returned.

**See Also:** `append`, `insertAt`, `prepend`, `WCExcept::out_of_memory`,  
`WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 int insertAt(int, Type *);
```

**Semantics:** The `insertAt` public member function inserts the second argument into the vector before the element at index given by the first argument. If the passed index is equal to the number of entries in the vector, the new value is appended to the vector as the last element. All vector elements with indexes greater than or equal to the first parameter are copied up one index.

This function is not provided by the `WCPtrSortedVector` class, since all elements must be inserted in sorted order by the `insert` member function.

If the passed index is negative or greater than the number of entries in the vector and the `index_range` exception is enabled, the exception is thrown. If the exception is not enabled, the new element is inserted as the first element when the index is negative, or as the last element when the index is too large.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the insert fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not inserted into the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The `insertAt` public member function inserts an element into the `WCPtrOrderedVector` object before the element at the given index. A TRUE (non-zero) value is returned if the insert is successful. If the insert fails, a FALSE (zero) value is returned.

**See Also:** `append`, `insert`, `prepend`, `operator []`, `removeAt`, `WCExcept::index_range`, `WCExcept::out_of_memory`, `WCExcept::resize_required`

## *WCPtrSortedVector<Type>, WCPtrOrderedVector<Type>::isEmpty()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if a vector object has any entries contained in it.

**Results:** A TRUE value (non-zero) is returned if the vector object does not have any vector elements contained within it. A FALSE (zero) result is returned if the vector contains at least one element.

**See Also:** `entries`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * last() const;
```

**Semantics:** The `last` public member function returns the last element in the vector. The element is not removed from the vector.

If the vector is empty, one of two exceptions can be thrown. The `empty_container` exception is thrown if it is enabled. Otherwise, if the `index_range` exception is enabled, it is thrown. If neither exception is enabled, a first element of the vector is added with a NULL value.

**Results:** The `last` public member function returns the value of the last element in the vector.

**See Also:** `first`, `removeLast`, `WCExcept::index_range`, `WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 int occurrencesOf(const Type *) const;
```

**Semantics:** The `occurrencesOf` public member function returns the number of elements contained in the vector that are equivalent to the passed value. Note that comparisons are done on the objects pointed to, not the pointers themselves. A linear search is used by the `WCPtrOrderedVector` class to find the value. The `WCPtrSortedVector` class uses a binary search.

**Results:** The `occurrencesOf` public member function returns the number of elements equivalent to the passed value.

**See Also:** `contains`, `find`, `index`, `operator []`, `removeAll`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * & operator [](int);
 Type * const & operator [](int) const;
```

**Semantics:** `operator []` is the vector index operator. A reference to the object stored in the vector at the given index is returned. If a constant vector is indexed, a reference to a constant element is returned.

The `append`, `insert`, `insertAt` and `prepend` member functions are used to insert a new element into a vector, and the `remove`, `removeAll`, `removeAt`, `removeFirst` and `removeLast` member functions remove elements. The index operator cannot be used to change the number of entries in the vector. Searches may be performed using the `find` and `index` member functions.

If the vector is empty, one of two exceptions can be thrown. The `empty_container` exception is thrown if it is enabled. Otherwise, if the `index_range` exception is enabled, it is thrown. If neither exception is enabled, a first element of the vector is added with a NULL value. This element is added so that a reference to a valid vector element can be returned.

If the index value is negative and the `index_range` exception is enabled, the exception is thrown. An attempt to index an element with index greater than or equal to the number of entries in the vector will also cause the `index_range` exception to be thrown if enabled. If the exception is not enabled, attempting to index a negative element will index the first element in the vector, and attempting to index an element after the last entry will index the last element.

Care must be taken when using the `WCPtrSortedVector` class not to change the ordering of the vector elements. The result returned by the index operator must not be assigned to or modified in such a way that it is no longer equivalent (by `Type`'s equivalence operator) to the value inserted into the vector. Failure to comply may cause lookups to work incorrectly, since the binary search algorithm assumes elements are in sorted order.

**Results:** The `operator []` public member function returns a reference to the element at the given index. If the index is invalid, a reference to the closest valid element is returned. The result of the non-constant index operator may be assigned to.

**See Also:** `append`, `find`, `first`, `index`, `insert`, `insertAt`, `isEmpty`, `last`, `prepend`, `remove`, `removeAt`, `removeAll`, `removeFirst`, `removeLast`, `WCExcept::empty_container`, `WCExcept::index_range`

## *WCPtrSortedVector<Type>, WCPtrOrderedVector<Type>::operator =()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 WCPtrOrderedVector & WCPtrOrderedVector::operator =(const
 WCPtrOrderedVector &);
 WCPtrSortedVector & WCPtrSortedVector::operator =(const
 WCPtrSortedVector &);
```

**Semantics:** The `operator =` public member function is the assignment operator for the class. The left hand side vector is first cleared using the `clear` member function, and then the right hand side vector is copied. The left hand side vector is made to have the same length and growth amount as the right hand side (the growth amount is the second argument passed to the right hand side vector constructor). All of the vector elements and exception trap states are copied.

If the left hand side vector cannot be fully created, it will have zero length. The `out_of_memory` exception is thrown if enabled in the right hand side vector.

**Results:** The `operator =` public member function assigns the left hand side vector to be a copy of the right hand side.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcvector.h>
public:
 int WCPtrOrderedVector::operator ==(const WCPtrOrderedVector &)
const;
 int WCPtrSortedVector::operator ==(const WCPtrSortedVector &)
const;
```

**Semantics:** The operator == public member function is the equivalence operator for the class. Two vector objects are equivalent if they are the same object and share the same address.

**Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side vectors are the same object. A FALSE (zero) value is returned otherwise.

## *WCPtrOrderedVector<Type>::prepend()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int prepend(Type *);
```

**Semantics:** The `prepend` public member function inserts the passed element to be the first element in the vector. All vector elements contained in the vector are copied up one index.

This function is not provided by the `WCPtrSortedVector` class, since all elements must be inserted in sorted order by the `insert` member function.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the `prepend` fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not inserted to the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The `prepend` public member function prepends an element to the `WCPtrOrderedVector` object. A TRUE (non-zero) value is returned if the insert is successful. If the insert fails, a FALSE (zero) value is returned.

**See Also:** `append`, `insert`, `insertAt`, `WCExcept::out_of_memory`,  
`WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * remove(const Type *);
```

**Semantics:** The `remove` public member function removes the first element in the vector which is equivalent to the passed value. Note that comparisons are done on the objects pointed to, not the pointers themselves. All vector elements stored after the removed elements are copied down one index.

A linear search is used by the `WCPtrOrderedVector` class to find the element being removed. The `WCPtrSortedVector` class uses a binary search.

**Results:** The `remove` public member function removes the first element in the vector which is equivalent to the passed value. The removed pointer is returned. If the vector did not contain an equivalent value, `NULL(0)` is returned.

**See Also:** `clear`, `clearAndDestroy`, `find`, `removeAll`, `removeAt`, `removeFirst`, `removeLast`

## *WCPtrSortedVector<Type>, WCPtrOrderedVector<Type>::removeAll()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 unsigned removeAll(const Type *);
```

**Semantics:** The `removeAll` public member function removes all elements in the vector which are equivalent to the passed value. Note that comparisons are done on the objects pointed to, not the pointers themselves. All vector elements stored after the removed elements are copied down one or more indexes to take the place of the removed elements.

A linear search is used by the `WCPtrOrderedVector` class to find the elements being removed. The `WCPtrSortedVector` class uses a binary search.

**Results:** The `removeAll` public member function removes all elements in the vector which are equivalent to the passed value. The number of elements removed is returned.

**See Also:** `clear`, `clearAndDestroy`, `find`, `occurrencesOf`, `remove`, `removeAt`, `removeFirst`, `removeLast`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * removeAt(int);
```

**Semantics:** The `removeAt` public member function removes the element at the given index. All vector elements stored after the removed elements are copied down one index.

If the vector is empty and the `empty_container` exception is enabled, the exception is thrown.

If an attempt to remove an element with a negative index is made and the `index_range` exception is enabled, the exception is thrown. If the exception is not enabled, the first element is removed from the vector. Attempting to remove an element with index greater or equal to the number of entries in the vector also causes the `index_range` exception to be thrown if enabled. The last element in the vector is removed if the exception is not enabled.

**Results:** The `removeAt` public member function removes the element with the given index. If the index is invalid, the closest element to the given index is removed. The removed pointer is returned. If the vector was empty, `NULL(0)` is returned.

**See Also:** `clear`, `clearAndDestroy`, `insertAt`, `operator []`, `remove`, `removeAll`, `removeFirst`, `removeLast`

## *WCPtrSortedVector<Type>, WCPtrOrderedVector<Type>::removeFirst()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * removeFirst();
```

**Semantics:** The `removeFirst` public member function removes the first element from a vector. All other vector elements are copied down one index.

If the vector is empty and the `empty_container` exception is enabled, the exception is thrown.

**Results:** The `removeFirst` public member function removes the first element from the vector. The removed pointer is returned. If the vector was empty, `NULL(0)` is returned.

**See Also:** `clear`, `clearAndDestroy`, `first`, `remove`, `removeAt`, `removeAll`, `removeLast`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * removeLast();
```

**Semantics:** The `removeLast` public member function removes the last element from a vector. If the vector is empty and the `empty_container` exception is enabled, the exception is thrown.

**Results:** The `removeLast` public member function removes the last element from the vector. The removed pointer is returned. If the vector was empty, `NULL(0)` is returned.

**See Also:** `clear`, `clearAndDestroy`, `last`, `remove`, `removeAt`, `removeAll`, `removeFirst`

## *WCPtrSortedVector<Type>::resize(), WCPtrOrderedVector<Type>::resize()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int resize(size_t new_size);
```

**Semantics:** The `resize` public member function is used to change the vector size to be able to store *new\_size* elements. If *new\_size* is larger than the previous vector size, all elements are copied into the newly sized vector, and new elements can be added using the `append`, `insert`, `insertAt`, and `prepend` member functions. If the vector is resized to a smaller size, the first *new\_size* elements are copied (all vector elements if the vector contained *new\_size* or fewer elements). The objects pointed to by the remaining elements are not deleted.

If the `resize` cannot be performed and the `out_of_memory` exception is enabled, the exception is thrown.

**Results:** The vector is resized to *new\_size*. A TRUE value (non-zero) is returned if the `resize` is successful. A FALSE (zero) result is returned if the `resize` fails.

**See Also:** `WCExcept::out_of_memory`

**Declared:** wcvector.h

The WCPtrVector<Type> class is a templated class used to store objects in a vector. Vectors are similar to arrays, but vectors perform bounds checking and can be resized. Elements are inserted into the vector by assigning to a vector index.

The WCPtrOrderedVector and WCPtrSortedVector classes are also available. They provide a more abstract view of the vector and additional functionality, including finding and removing elements.

In the description of each member function, the text `Type` is used to indicate the template parameter defining the type pointed to by the pointers stored in the vector.

The WCExcept class is a base class of the WCPtrVector<Type> class and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCPtrVector<Type> object. No exceptions are enabled unless they are set by the exceptions member function.

### Requirements of Type

The WCPtrVector<Type> class requires nothing from `Type`.

### Public Member Functions

The following member functions are declared in the public interface:

```
WCPtrVector(size_t = 0);
WCPtrVector(size_t, const Type *);
WCPtrVector(const WCPtrVector &);
virtual ~WCPtrVector();
void clear();
void clearAndDestroy();
size_t length() const;
int resize(size_t);
```

### Public Member Operators

The following member operators are declared in the public interface:

```
Type * & operator [](int);
Type * const & operator [](int) const;
WCPtrVector & operator =(const WCPtrVector &);
int operator ==(const WCPtrVector &) const;
```

## *WCPtrVector<Type>::WCPtrVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
WCPtrVector(size_t = 0);
```

**Semantics:** The public `WCPtrVector<Type>` constructor creates a `WCPtrVector<Type>` object able to store the number of elements specified in the optional parameter, which defaults to zero. All vector elements are initialized to `NULL(0)`.

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:** The public `WCPtrVector<Type>` constructor creates an initialized `WCPtrVector<Type>` object with the specified length.

**See Also:** `WCPtrVector<Type>`, `~WCPtrVector<Type>`

**Synopsis:**

```
#include <wcvector.h>
public:
WCPtrVector(size_t, const Type *);
```

**Semantics:** The public `WCPtrVector<Type>` constructor creates a `WCPtrVector<Type>` object able to store the number of elements specified by the first parameter. All vector elements are initialized to the pointer value given by the second parameter.

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:** The public `WCPtrVector<Type>` constructor creates an initialized `WCPtrVector<Type>` object with the specified length and elements set to the given value.

**See Also:** `WCPtrVector<Type>`, `~WCPtrVector<Type>`

## *WCPtrVector<Type>::WCPtrVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
WCPtrVector(const WCPtrVector &);
```

**Semantics:** The public `WCPtrVector<Type>` constructor is the copy constructor for the `WCPtrVector<Type>` class. The new vector is created with the same length as the given vector. All of the vector elements and exception trap states are copied.

If the new vector cannot be fully created, it will have length zero. The `out_of_memory` exception is thrown if enabled in the vector being copied.

**Results:** The public `WCPtrVector<Type>` constructor creates a `WCPtrVector<Type>` object which is a copy of the passed vector.

**See Also:** `operator =, WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcvector.h>
public:
 virtual ~WCPtrVector();
```

**Semantics:** The public `~WCPtrVector<Type>` destructor is the destructor for the `WCPtrVector<Type>` class. If the vector is not length zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the vector elements are cleared using the `clear` member function. The objects which the vector elements point to are not deleted unless the `clearAndDestroy` member function is explicitly called before the destructor is called. The call to the public `~WCPtrVector<Type>` destructor is inserted implicitly by the compiler at the point where the `WCPtrVector<Type>` object goes out of scope.

**Results:** The public `~WCPtrVector<Type>` destructor destroys an `WCPtrVector<Type>` object.

**See Also:** `clear`, `clearAndDestroy`, `WCExcept::not_empty`

## *WCPtrVector<Type>::clear()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the vector so that it is of zero length. Objects pointed to by the vector elements are not deleted. The vector object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the vector to have zero length and no vector elements.

**See Also:** `~WCPtrVector<Type>`, `clearAndDestroy`, `operator =`

**Synopsis:**

```
#include <wcvector.h>
public:
void clearAndDestroy();
```

**Semantics:** The `clearAndDestroy` public member function is used to clear the vector to have zero length and delete the objects pointed to by the vector elements. The vector object is not destroyed and re-created by this function, so the vector object destructor is not invoked.

**Results:** The `clearAndDestroy` public member function clears the vector by deleting the objects pointed to by the vector elements and makes the vector zero length.

**See Also:** `clear`

## *WCPtrVector<Type>::length()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 size_t length() const;
```

**Semantics:** The `length` public member function is used to find the number of elements which can be stored in the `WCPtrVector<Type>` object.

**Results:** The `length` public member function returns the length of the vector.

**See Also:** `resize`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type * & operator [](int);
 Type * const & operator [](int) const;
```

**Semantics:** `operator []` is the vector index operator. A reference to the object stored in the vector at the given index is returned. If a constant vector is indexed, a reference to a constant element is returned. The index operator of a non-constant vector is the only way to insert an element into the vector.

If an attempt to access an element with index greater than or equal to the length of a non-constant vector is made and the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the vector is automatically resized using the `resize` member function to have length the index value plus one. New vector elements are initialized to `NULL(0)`. If the resize failed, and the `out_of_memory` exception is enabled, the exception is thrown. If the exception is not enabled and the resize failed, the last element is indexed (a new element if the vector was zero length). If a negative value is used to index the non-constant vector and the `index_range` exception is enabled, the exception is thrown. If the exception is not enabled and the vector is empty, the `resize_required` exception may be thrown.

An attempt to index an empty constant vector may cause one of two exceptions to be thrown. If the `empty_container` exception is enabled, it is thrown. Otherwise, the `index_range` exception is thrown, if enabled. If neither exception is enabled, a first vector element is added and indexed (so that a reference to a valid element can be returned).

Indexing with a negative value or a value greater than or equal to the length of a constant vector causes the `index_range` exception to be thrown, if enabled.

**Results:** The `operator []` public member function returns a reference to the element at the given index. If the index is invalid, a reference to the closest valid element is returned. The result of the non-constant index operator may be assigned to.

**See Also:** `resize`, `WCExcept::empty_container`, `WCExcept::index_range`,  
`WCExcept::out_of_memory`, `WCExcept::resize_required`

## *WCPtrVector<Type>::operator =()*

---

|                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis:</b>  | <pre>#include &lt;wcvector.h&gt; public: WCPtrVector &amp; operator =( const WCPtrVector &amp; );</pre>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>Semantics:</b> | The <code>operator =</code> public member function is the assignment operator for the <code>WCPtrVector&lt;Type&gt;</code> class. The left hand side vector is first cleared using the <code>clear</code> member function, and then the right hand side vector is copied. The left hand side vector is made to have the same length as the right hand side. All of the vector elements and exception trap states are copied.<br><br>If the left hand side vector cannot be fully created, it will have zero length. The <code>out_of_memory</code> exception is thrown if enabled in the right hand side vector. |
| <b>Results:</b>   | The <code>operator =</code> public member function assigns the left hand side vector to be a copy of the right hand side.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <b>See Also:</b>  | <code>clear</code> , <code>clearAndDestroy</code> , <code>WCExcept::out_of_memory</code>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |

**Synopsis:**

```
#include <wcvector.h>
public:
 int operator ==(const WCPtrVector &) const;
```

**Semantics:** The operator == public member function is the equivalence operator for the WCPtrVector<Type> class. Two vector objects are equivalent if they are the same object and share the same address.

**Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side vectors are the same object. A FALSE (zero) value is returned otherwise.

## *WCPtrVector<Type>::resize()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int resize(size_t new_size);
```

**Semantics:**

The `resize` public member function is used to change the vector size to be able to store *new\_size* elements. If *new\_size* is larger than the previous vector size, all elements will be copied into the newly sized vector, and new elements are initialized to `NULL(0)`. If the vector is resized to a smaller size, the first *new\_size* elements are copied. The objects pointed to by the remaining elements are not deleted.

If the `resize` cannot be performed and the `out_of_memory` exception is enabled, the exception is thrown.

**Results:**

The vector is resized to *new\_size*. A TRUE value (non-zero) is returned if the `resize` is successful. A FALSE (zero) result is returned if the `resize` fails.

**See Also:**

`WCExcept::out_of_memory`

**Declared:** wcvector.h

The WCValSortedVector<Type> and WCValOrderedVector<Type> classes are templated classes used to store objects in a vector. Ordered and Sorted vectors are powerful arrays which can be resized and provide an abstract interface to insert, find and remove elements. An ordered vector maintains the order in which elements are added, and allows more than one copy of an element that is equivalent. The sorted vector allow only one copy of an equivalent element, and inserts them in a sorted order. The sorted vector is less efficient when inserting elements, but can provide a faster retrieval time.

Elements cannot be inserted into these vectors by assigning to a vector index. Vectors automatically grow when necessary to insert an element if the `resize_required` exception is not enabled.

In the description of each member function, the text `Type` is used to indicate the template parameter defining the type of the elements stored in the vector.

Values are copied into the vector, which could be undesirable if the stored objects are complicated and copying is expensive. Value vectors should not be used to store objects of a base class if any derived types of different sizes would be stored in the vector, or if the destructor for a derived class must be called.

The WCValOrderedVector class stores elements in the order which they are inserted using the `insert`, `append`, `prepend` and `insertAt` member functions. Linear searches are performed to locate entries, and the less than operator is not required.

The WCValSortedVector class stores elements in ascending order. This requires that `Type` provides a less than operator. Insertions are more expensive than inserting or appending into an ordered vector, since entries must be moved to make room for the new element. A binary search is used to locate elements in a sorted vector, making searches quicker than in the ordered vector.

Care must be taken when using the WCValSortedVector class not to change the ordering of the vector elements. The result returned by the index operator must not be assigned to or modified in such a way that it is no longer equivalent to the value inserted into the vector. Lookups assume elements are in sorted order.

The WCValVector class is also available. It provides a resizable and boundary safe vector similar to standard arrays.

The WCExcept class is a base class of the WCValSortedVector<Type> and WCValOrderedVector<Type> classes and provides the `exceptions` member function. This member function controls the exceptions which can be thrown by the WCValSortedVector<Type> and WCValOrderedVector<Type> objects. No exceptions are enabled unless they are set by the `exceptions` member function.

### Requirements of Type

Both the WCValSortedVector<Type> and WCValOrderedVector<Type> classes require `Type` to have:

A default constructor ( `Type::Type()` ).

A well defined copy constructor ( `Type::Type( const Type & )` ).

A well defined assignment operator

## *WCValSortedVector<Type>, WCValOrderedVector<Type>*

---

```
(Type & operator =(const Type &)).
```

The following override of operator new() if Type overrides the global operator new():

```
void * operator new(size_t, void *ptr) { return(ptr); }
```

A well defined equivalence operator with constant parameters  
( int operator ==( const Type & ) const ).

Additionally the WCValSortedVector class requires Type to have:

A well defined less than operator with constant parameters  
( int operator <( const Type & ) const ).

### **Public Member Functions**

The following member functions are declared in the public interface:

```
WCValOrderedVector(size_t = WCDEFAULT_VECTOR_LENGTH, unsigned =
WCDEFAULT_VECTOR_RESIZE_GROW);
WCValOrderedVector(const WCValOrderedVector &);
virtual ~WCValOrderedVector();
WCValSortedVector(size_t = WCDEFAULT_VECTOR_LENGTH, unsigned =
WCDEFAULT_VECTOR_RESIZE_GROW);
WCValSortedVector(const WCValSortedVector &);
virtual ~WCValSortedVector();
void clear();
int contains(const Type &) const;
unsigned entries() const;
int find(const Type &, Type &) const;
Type first() const;
int index(const Type &) const;
int insert(const Type &);
int isEmpty() const;
Type last() const;
int occurrencesOf(const Type &) const;
int remove(const Type &);
unsigned removeAll(const Type &);
int removeAt(int);
int removeFirst();
int removeLast();
int resize(size_t);
```

The following public member functions are available for the WCValOrderedVector class only:

```
int append(const Type &);
int insertAt(int, const Type &);
int prepend(const Type &);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
Type & operator [](int);
const Type & operator [](int) const;
WCValOrderedVector & WCValOrderedVector::operator =(const
WCValOrderedVector &);
```

```
WCValSortedVector & WCValSortedVector::operator =(const
WCValSortedVector &);
int WCValOrderedVector::operator ==(const WCValOrderedVector &)
const;
int WCValSortedVector::operator ==(const WCValSortedVector &)
const;
```

## *WCValOrderedVector<Type>::WCValOrderedVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
WCValOrderedVector(size_t = WCDEFAULT_VECTOR_LENGTH,
unsigned = WCDEFAULT_VECTOR_RESIZE_GROW);
```

**Semantics:**

The `WCValOrderedVector<Type>` constructor creates an empty `WCValOrderedVector` object able to store the number of elements specified in the first optional parameter, which defaults to the constant `WCDEFAULT_VECTOR_LENGTH` (currently defined as 10). If the `resize_required` exception is not enabled, then the second optional parameter is used to specify the value to increase the vector size when an element is inserted into a full vector. If zero(0) is specified as the second parameter, any attempt to insert into a full vector fails. This parameter defaults to the constant `WCDEFAULT_VECTOR_RESIZE_GROW` (currently defined as 5).

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:**

The `WCValOrderedVector<Type>` constructor creates an empty initialized `WCValOrderedVector` object.

**See Also:**

`WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
WCValOrderedVector(const WCValOrderedVector &);
```

**Semantics:**

The `WCValOrderedVector<Type>` constructor is the copy constructor for the `WCValOrderedVector` class. The new vector is created with the same length and resize value as the passed vector. All of the vector elements and exception trap states are copied.

If the new vector cannot be fully created, it will have length zero. The `out_of_memory` exception is thrown if enabled in the vector being copied.

**Results:**

The `WCValOrderedVector<Type>` creates a `WCValOrderedVector` object which is a copy of the passed vector.

**See Also:**

`operator =, WCExcept::out_of_memory`

## *WCValOrderedVector<Type>::~WCValOrderedVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 virtual ~WCValOrderedVector();
```

**Semantics:**

The WCValOrderedVector<Type> destructor is the destructor for the WCValOrderedVector class. If the vector is not length zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the vector entries are cleared using the `clear` member function. The call to the WCValOrderedVector<Type> destructor is inserted implicitly by the compiler at the point where the WCValOrderedVector object goes out of scope.

**Results:**

The WCValOrderedVector<Type> destructor destroys an WCValOrderedVector object.

**See Also:**

`clear`, `WCExcept::not_empty`

**Synopsis:**

```
#include <wcvector.h>
public:
WCValSortedVector(size_t = WCDEFAULT_VECTOR_LENGTH,
unsigned = WCDEFAULT_VECTOR_RESIZE_GROW);
```

**Semantics:** The `WCValSortedVector<Type>` constructor creates an empty `WCValSortedVector` object able to store the number of elements specified in the first optional parameter, which defaults to the constant `WCDEFAULT_VECTOR_LENGTH` (currently defined as 10). If the `resize_required` exception is not enabled, then the second optional parameter is used to specify the value to increase the vector size when an element is inserted into a full vector. If zero(0) is specified as the second parameter, any attempt to insert into a full vector fails. This parameter defaults to the constant `WCDEFAULT_VECTOR_RESIZE_GROW` (currently defined as 5).

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:** The `WCValSortedVector<Type>` constructor creates an empty initialized `WCValSortedVector` object.

**See Also:** `WCExcept::resize_required`

## *WCValSortedVector<Type>::WCValSortedVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
WCValSortedVector(const WCValSortedVector &);
```

**Semantics:** The `WCValSortedVector<Type>` constructor is the copy constructor for the `WCValSortedVector` class. The new vector is created with the same length and resize value as the passed vector. All of the vector elements and exception trap states are copied.

If the new vector cannot be fully created, it will have length zero. The `out_of_memory` exception is thrown if enabled in the vector being copied.

**Results:** The `WCValSortedVector<Type>` constructor creates a `WCValSortedVector` object which is a copy of the passed vector.

**See Also:** `operator =, WCExcept::out_of_memory`

**Synopsis:**

```
#include <wcvector.h>
public:
 virtual ~WCValSortedVector();
```

**Semantics:** The `WCValSortedVector<Type>` destructor is the destructor for the `WCValSortedVector` class. If the vector is not length zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the vector entries are cleared using the `clear` member function. The call to the `WCValSortedVector<Type>` destructor is inserted implicitly by the compiler at the point where the `WCValSortedVector` object goes out of scope.

**Results:** The `WCValSortedVector<Type>` destructor destroys an `WCValSortedVector` object.

**See Also:** `clear`, `WCExcept::not_empty`

## **WCValOrderedVector<Type>::append()**

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int append(const Type &);
```

**Semantics:** The append public member function appends the passed element to be the last element in the vector. The data stored in the vector is a copy of the data passed as a parameter. This member function has the same semantics as the WCValOrderedVector::insert member function.

This function is not provided by the WCValSortedVector class, since all elements must be inserted in sorted order by the insert member function.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the append fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not appended to the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The append public member function appends an element to the WCValOrderedVector object. A TRUE (non-zero) value is returned if the append is successful. If the append fails, a FALSE (zero) value is returned.

**See Also:** `insert`, `insertAt`, `prepend`, `WCEExcept::out_of_memory`,  
`WCEExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the vector so that it contains no entries, and is zero size. Elements stored in the vector are destroyed using `Type`'s destructor. The vector object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the vector to have zero length and no entries.

**See Also:** `~WCValOrderedVector`, `operator =`

## *WCValSortedVector<Type>, WCValOrderedVector<Type>::contains()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int contains(const Type &) const;
```

**Semantics:** The `contains` public member function is used to determine if a value is contained by a vector. A linear search is used by the `WCValOrderedVector` class to find the value. The `WCValSortedVector` class uses a binary search.

**Results:** The `contains` public member function returns a TRUE (non-zero) value if the element is found in the vector. A FALSE (zero) value is returned if the vector does not contain the element.

**See Also:** `index`, `find`

**Synopsis:**

```
#include <wcvector.h>
public:
 unsigned entries() const;
```

**Semantics:** The `entries` public member function is used to find the number of elements which are stored in the vector.

**Results:** The `entries` public member function returns the number of elements in the vector.

**See Also:** `isEmpty`

## *WCValSortedVector<Type>::find(), WCValOrderedVector<Type>::find()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int find(const Type &, Type &) const;
```

**Semantics:** The `find` public member function is used to find an element equivalent to the first argument. The `WCValOrderedVector` class uses a linear search to find the element, and the `WCValSortedVector` class uses a binary search.

**Results:** If an equivalent element is found, a TRUE (non-zero) value is returned, and the second parameter is assigned the first equivalent value. A FALSE (zero) value is returned and the second parameter is unchanged if the element is not in the vector.

**See Also:** `contains`, `first`, `index`, `last`, `occurrencesOf`, `remove`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type first() const;
```

**Semantics:** The `first` public member function returns the first element in the vector. The element is not removed from the vector.

If the vector is empty, one of two exceptions can be thrown. The `empty_container` exception is thrown if it is enabled. Otherwise, if the `index_range` exception is enabled, it is thrown. If neither exception is enabled, a first element of the vector is added with a default value.

**Results:** The `first` public member function returns the value of the first element in the vector.

**See Also:** `last`, `removeFirst`, `WCExcept::index_range`, `WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 int index(const Type &) const;
```

**Semantics:** The `index` public member function is used find the index of the first element equivalent to the passed element. A linear search is used by the `WCValOrderedVector` class to find the element. The `WCValSortedVector` class uses a binary search.

**Results:** The `index` public member function returns the index of the first element equivalent to the parameter. If the passed value is not contained in the vector, negative one (-1) is returned.

**See Also:** `contains`, `find`, `insertAt`, `operator []`, `removeAt`

**Synopsis:**

```
#include <wcvector.h>
public:
 int insert(const Type &);
```

**Semantics:** The `insert` public member function inserts the value into the vector. The data stored in the vector is a copy of the data passed as a parameter.

The `WCValOrderedVector::insert` function inserts the value as the last element of the vector, and has the same semantics as the `WCValOrderedVector::append` member function.

A binary search is performed to determine where the value should be inserted for the `WCValSortedVector::insert` function. Any elements greater than the inserted value are copied up one index (using `Type`'s assignment operator), so that the new element is after all elements with value less than or equal to it.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the `insert` fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not inserted to the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The `insert` public member function inserts an element in to the vector. A TRUE (non-zero) value is returned if the insert is successful. If the insert fails, a FALSE (zero) value is returned.

**See Also:** `append`, `insertAt`, `prepend`, `WCExcept::out_of_memory`,  
`WCExcept::resize_required`

## **WCValOrderedVector<Type>::insertAt()**

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int insertAt(int, const Type &);
```

**Semantics:** The `insertAt` public member function inserts the second argument into the vector before the element at index given by the first argument. If the passed index is equal to the number of entries in the vector, the new value is appended to the vector as the last element. The data stored in the vector is a copy of the data passed as a parameter. All vector elements with indexes greater than or equal to the first parameter are copied (using `Type`'s assignment operator) up one index.

This function is not provided by the `WCValSortedVector` class, since all elements must be inserted in sorted order by the `insert` member function.

If the passed index is negative or greater than the number of entries in the vector and the `index_range` exception is enabled, the exception is thrown. If the exception is not enabled, the new element is inserted as the first element when the index is negative, or as the last element when the index is too large.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the insert fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not inserted into the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The `insertAt` public member function inserts an element into the `WCValOrderedVector` object before the element at the given index. A TRUE (non-zero) value is returned if the insert is successful. If the insert fails, a FALSE (zero) value is returned.

**See Also:** `append`, `insert`, `prepend`, `operator []`, `removeAt`, `WCExcept::index_range`, `WCExcept::out_of_memory`, `WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 int isEmpty() const;
```

**Semantics:** The `isEmpty` public member function is used to determine if a vector object has any entries contained in it.

**Results:** A TRUE value (non-zero) is returned if the vector object does not have any vector elements contained within it. A FALSE (zero) result is returned if the vector contains at least one element.

**See Also:** `entries`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type last() const;
```

**Semantics:** The `last` public member function returns the last element in the vector. The element is not removed from the vector.

If the vector is empty, one of two exceptions can be thrown. The `empty_container` exception is thrown if it is enabled. Otherwise, if the `index_range` exception is enabled, it is thrown. If neither exception is enabled, a first element of the vector is added with a default value.

**Results:** The `last` public member function returns the value of the last element in the vector.

**See Also:** `first`, `removeLast`, `WCExcept::index_range`, `WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 int occurrencesOf(const Type &) const;
```

**Semantics:**

The `occurrencesOf` public member function returns the number of elements contained in the vector that are equivalent to the passed value. A linear search is used by the `WCValOrderedVector` class to find the value. The `WCValSortedVector` class uses a binary search.

**Results:**

The `occurrencesOf` public member function returns the number of elements equivalent to the passed value.

**See Also:**

`contains`, `find`, `index`, `operator []`, `removeAll`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type & operator [](int);
 const Type & operator [](int) const;
```

**Semantics:** `operator []` is the vector index operator. A reference to the object stored in the vector at the given index is returned. If a constant vector is indexed, a reference to a constant element is returned.

The `append`, `insert`, `insertAt` and `prepend` member functions are used to insert a new element into a vector, and the `remove`, `removeAll`, `removeAt`, `removeFirst` and `removeLast` member functions remove elements. The index operator cannot be used to change the number of entries in the vector. Searches may be performed using the `find` and `index` member functions.

If the vector is empty, one of two exceptions can be thrown. The `empty_container` exception is thrown if it is enabled. Otherwise, if the `index_range` exception is enabled, it is thrown. If neither exception is enabled, a first element of the vector is added with a default value. This element is added so that a reference to a valid vector element can be returned.

If the index value is negative and the `index_range` exception is enabled, the exception is thrown. An attempt to index an element with index greater than or equal to the number of entries in the vector will also cause the `index_range` exception to be thrown if enabled. If the exception is not enabled, attempting to index a negative element will index the first element in the vector, and attempting to index an element after the last entry will index the last element.

Care must be taken when using the `WCValSortedVector` class not to change the ordering of the vector elements. The result returned by the index operator must not be assigned to or modified in such a way that it is no longer equivalent (by `Type`'s equivalence operator) to the value inserted into the vector. Failure to comply may cause lookups to work incorrectly, since the binary search algorithm assumes elements are in sorted order.

**Results:** The `operator []` public member function returns a reference to the element at the given index. If the index is invalid, a reference to the closest valid element is returned. The result of the non-constant index operator may be assigned to.

**See Also:** `append`, `find`, `first`, `index`, `insert`, `insertAt`, `isEmpty`, `last`, `prepend`, `remove`, `removeAt`, `removeAll`, `removeFirst`, `removeLast`, `WCExcept::empty_container`, `WCExcept::index_range`

**Synopsis:**

```
#include <wcvector.h>
public:
 WCValOrderedVector & WCValOrderedVector::operator =(const
 WCValOrderedVector &);
 WCValSortedVector & WCValSortedVector::operator =(const
 WCValSortedVector &);
```

**Semantics:** The `operator =` public member function is the assignment operator for the class. The left hand side vector is first cleared using the `clear` member function, and then the right hand side vector is copied. The left hand side vector is made to have the same length and growth amount as the right hand side (the growth amount is the second argument passed to the right hand side vector constructor). All of the vector elements and exception trap states are copied.

If the left hand side vector cannot be fully created, it will have zero length. The `out_of_memory` exception is thrown if enabled in the right hand side vector.

**Results:** The `operator =` public member function assigns the left hand side vector to be a copy of the right hand side.

**See Also:** `clear`, `WCExcept::out_of_memory`

## *WCValSortedVector<Type>, WCValOrderedVector<Type>::operator ==()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int WCValOrderedVector::operator ==(const WCValOrderedVector &)
const;
 int WCValSortedVector::operator ==(const WCValSortedVector &)
const;
```

**Semantics:** The `operator ==` public member function is the equivalence operator for the class. Two vector objects are equivalent if they are the same object and share the same address.

**Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side vectors are the same object. A FALSE (zero) value is returned otherwise.

**Synopsis:**

```
#include <wcvector.h>
public:
 int prepend(const Type &);
```

**Semantics:** The `prepend` public member function inserts the passed element to be the first element in the vector. The data stored in the vector is a copy of the data passed as a parameter. All vector elements contained in the vector are copied (using `Type`'s assignment operator) up one index.

This function is not provided by the `WCValSortedVector` class, since all elements must be inserted in sorted order by the `insert` member function.

Several different results can occur if the vector is not large enough for the new element. If the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the `prepend` fails if the amount the vector is to be grown (the second parameter to the constructor) is zero(0). Otherwise, the vector is automatically grown by the number of elements specified to the constructor, using the `resize` member function. If `resize` fails, the element is not inserted to the vector and the `out_of_memory` exception is thrown, if enabled.

**Results:** The `prepend` public member function prepends an element to the `WCValOrderedVector` object. A TRUE (non-zero) value is returned if the insert is successful. If the insert fails, a FALSE (zero) value is returned.

**See Also:** `append`, `insert`, `insertAt`, `WCExcept::out_of_memory`,  
`WCExcept::resize_required`

**Synopsis:**

```
#include <wcvector.h>
public:
 int remove(const Type &);
```

**Semantics:** The `remove` public member function removes the first element in the vector which is equivalent to the passed value. All vector elements stored after the removed elements are copied (using `Type`'s assignment operator) down one index.

A linear search is used by the `WCValOrderedVector` class to find the element being removed. The `WCValSortedVector` class uses a binary search.

**Results:** The `remove` public member function removes the first element in the vector which is equivalent to the passed value. A TRUE (non-zero) value is returned if an equivalent element was contained in the vector and removed. If the vector did not contain an equivalent value, a FALSE (zero) value is returned.

**See Also:** `clear`, `find`, `removeAll`, `removeAt`, `removeFirst`, `removeLast`

**Synopsis:**

```
#include <wcvector.h>
public:
 unsigned removeAll(const Type &);
```

**Semantics:** The `removeAll` public member function removes all elements in the vector which are equivalent to the passed value. All vector elements stored after the removed elements are copied (using `Type`'s assignment operator) down one or more indexes to take the place of the removed elements.

A linear search is used by the `WCValOrderedVector` class to find the elements being removed. The `WCValSortedVector` class uses a binary search.

**Results:** The `removeAll` public member function removes all elements in the vector which are equivalent to the passed value. The number of elements removed is returned.

**See Also:** `clear`, `find`, `occurrencesOf`, `remove`, `removeAt`, `removeFirst`, `removeLast`

**Synopsis:**

```
#include <wcvector.h>
public:
 int removeAt(int);
```

**Semantics:** The `removeAt` public member function removes the element at the given index. All vector elements stored after the removed elements are copied (using `Type`'s assignment operator) down one index.

If the vector is empty and the `empty_container` exception is enabled, the exception is thrown.

If an attempt to remove an element with a negative index is made and the `index_range` exception is enabled, the exception is thrown. If the exception is not enabled, the first element is removed from the vector. Attempting to remove an element with index greater or equal to the number of entries in the vector also causes the `index_range` exception to be thrown if enabled. The last element in the vector is removed if the exception is not enabled.

**Results:** The `removeAt` public member function removes the element with the given index. If the index is invalid, the closest element to the given index is removed. A TRUE (non-zero) value is returned if an element was removed. If the vector was empty, FALSE (zero) value is returned.

**See Also:** `clear`, `insertAt`, `operator []`, `remove`, `removeAll`, `removeFirst`, `removeLast`

**Synopsis:**

```
#include <wcvector.h>
public:
 int removeFirst();
```

**Semantics:** The `removeFirst` public member function removes the first element from a vector. All other vector elements are copied (using `Type`'s assignment operator) down one index.

If the vector is empty and the `empty_container` exception is enabled, the exception is thrown.

**Results:** The `removeFirst` public member function removes the first element from the vector. A TRUE (non-zero) value is returned if an element was removed. If the vector was empty, FALSE (zero) value is returned.

**See Also:** `clear`, `first`, `remove`, `removeAt`, `removeAll`, `removeLast`

## *WCValSortedVector<Type>, WCValOrderedVector<Type>::removeLast()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int removeLast();
```

**Semantics:** The `removeLast` public member function removes the last element from a vector. If the vector is empty and the `empty_container` exception is enabled, the exception is thrown.

**Results:** The `removeLast` public member function removes the last element from the vector. A TRUE (non-zero) value is returned if an element was removed. If the vector was empty, FALSE (zero) value is returned.

**See Also:** `clear`, `last`, `remove`, `removeAt`, `removeAll`, `removeFirst`

**Synopsis:**

```
#include <wcvector.h>
public:
 int resize(size_t new_size);
```

**Semantics:**

The `resize` public member function is used to change the vector size to be able to store *new\_size* elements. If *new\_size* is larger than the previous vector size, all elements are copied (using `Type`'s copy constructor) into the newly sized vector, and new elements can be added using the `append`, `insert`, `insertAt`, and `prepend` member functions. If the vector is resized to a smaller size, the first *new\_size* elements are copied (all vector elements if the vector contained *new\_size* or fewer elements). The remaining elements are destroyed using `Type`'s destructor.

If the `resize` cannot be performed and the `out_of_memory` exception is enabled, the exception is thrown.

**Results:**

The vector is resized to *new\_size*. A TRUE value (non-zero) is returned if the `resize` is successful. A FALSE (zero) result is returned if the `resize` fails.

**See Also:**

`WCExcept::out_of_memory`

## **WCValVector<Type>**

---

**Declared:** wcvector.h

The WCValVector<Type> class is a templated class used to store objects in a vector. Vectors are similar to arrays, but vectors perform bounds checking and can be resized. Elements are inserted into the vector by assigning to a vector index.

The WCValOrderedVector and WCValSortedVector classes are also available. They provide a more abstract view of the vector and additional functionality, including finding and removing elements.

Values are copied into the vector, which could be undesirable if the stored objects are complicated and copying is expensive. Value vectors should not be used to store objects of a base class if any derived types of different sizes would be stored in the vector, or if the destructor for a derived class must be called.

In the description of each member function, the text Type is used to indicate the template parameter defining the type of the elements stored in the vector.

The WCExcept class is a base class of the WCValVector<Type> class and provides the exceptions member function. This member function controls the exceptions which can be thrown by the WCValVector<Type> object. No exceptions are enabled unless they are set by the exceptions member function.

### **Requirements of Type**

The WCValVector<Type> class requires Type to have:

A default constructor ( Type::Type () ).

A well defined copy constructor ( Type::Type ( const Type & ) ).

The following override of operator new() only if Type overrides the global operator new():

```
void * operator new(size_t, void *ptr) { return(ptr); }
```

### **Public Member Functions**

The following member functions are declared in the public interface:

```
WCValVector(size_t = 0);
WCValVector(size_t, const Type &);
WCValVector(const WCValVector &);
virtual ~WCValVector();
void clear();
size_t length() const;
int resize(size_t);
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
Type & operator [](int);
const Type & operator [](int) const;
WCValVector & operator =(const WCValVector &);
int operator ==(const WCValVector &) const;
```

**Synopsis:**

```
#include <wcvector.h>
public:
WCValVector(size_t = 0);
```

**Semantics:** The public `WCValVector<Type>` constructor creates a `WCValVector<Type>` object able to store the number of elements specified in the optional parameter, which defaults to zero. All vector elements are initialized with `Type`'s default constructor.

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:** The public `WCValVector<Type>` constructor creates an initialized `WCValVector<Type>` object with the specified length.

**See Also:** `WCValVector<Type>`, `~WCValVector<Type>`

## *WCValVector<Type>::WCValVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
WCValVector(size_t, const Type &);
```

**Semantics:** The public `WCValVector<Type>` constructor creates a `WCValVector<Type>` object able to store the number of elements specified by the first parameter. All vector elements are initialized to the value of the second parameter using `Type`'s copy constructor.

If the vector object cannot be fully initialized, the vector is created with length zero.

**Results:** The public `WCValVector<Type>` constructor creates an initialized `WCValVector<Type>` object with the specified length and elements set to the given value.

**See Also:** `WCValVector<Type>`, `~WCValVector<Type>`

**Synopsis:**

```
#include <wcvector.h>
public:
WCValVector(const WCValVector &);
```

**Semantics:** The public `WCValVector<Type>` constructor is the copy constructor for the `WCValVector<Type>` class. The new vector is created with the same length as the given vector. All of the vector elements and exception trap states are copied.

If the new vector cannot be fully created, it will have length zero. The `out_of_memory` exception is thrown if enabled in the vector being copied.

**Results:** The public `WCValVector<Type>` constructor creates a `WCValVector<Type>` object which is a copy of the passed vector.

**See Also:** `operator =, WCExcept::out_of_memory`

## *WCValVector<Type>::~WCValVector()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 virtual ~WCValVector();
```

**Semantics:** The public `~WCValVector<Type>` destructor is the destructor for the `WCValVector<Type>` class. If the vector is not length zero and the `not_empty` exception is enabled, the exception is thrown. Otherwise, the vector elements are cleared using the `clear` member function. The call to the public `~WCValVector<Type>` destructor is inserted implicitly by the compiler at the point where the `WCValVector<Type>` object goes out of scope.

**Results:** The public `~WCValVector<Type>` destructor destroys an `WCValVector<Type>` object.

**See Also:** `clear`, `WCExcept::not_empty`

**Synopsis:**

```
#include <wcvector.h>
public:
void clear();
```

**Semantics:** The `clear` public member function is used to clear the vector so that it is of zero length. Elements stored in the vector are destroyed using `Type`'s destructor. The vector object is not destroyed and re-created by this function, so the object destructor is not invoked.

**Results:** The `clear` public member function clears the vector to have zero length and no vector elements.

**See Also:** `~WCValVector<Type>`, `operator =`

## *WCValVector<Type>::length()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 size_t length() const;
```

**Semantics:** The `length` public member function is used to find the number of elements which can be stored in the `WCValVector<Type>` object.

**Results:** The `length` public member function returns the length of the vector.

**See Also:** `resize`

**Synopsis:**

```
#include <wcvector.h>
public:
 Type & operator [](int);
 const Type & operator [](int) const;
```

**Semantics:** `operator []` is the vector index operator. A reference to the object stored in the vector at the given index is returned. If a constant vector is indexed, a reference to a constant element is returned. The index operator of a non-constant vector is the only way to insert an element into the vector.

If an attempt to access an element with index greater than or equal to the length of a non-constant vector is made and the `resize_required` exception is enabled, the exception is thrown. If the exception is not enabled, the vector is automatically resized using the `resize` member function to have length the index value plus one. New vector elements are initialized using `Type'`s default constructor. If the `resize` failed, and the `out_of_memory` exception is enabled, the exception is thrown. If the exception is not enabled and the `resize` failed, the last element is indexed (a new element if the vector was zero length). If a negative value is used to index the non-constant vector and the `index_range` exception is enabled, the exception is thrown. If the exception is not enabled and the vector is empty, the `resize_required` exception may be thrown.

An attempt to index an empty constant vector may cause one of two exceptions to be thrown. If the `empty_container` exception is enabled, it is thrown. Otherwise, the `index_range` exception is thrown, if enabled. If neither exception is enabled, a first vector element is added and indexed (so that a reference to a valid element can be returned).

Indexing with a negative value or a value greater than or equal to the length of a constant vector causes the `index_range` exception to be thrown, if enabled.

**Results:** The `operator []` public member function returns a reference to the element at the given index. If the index is invalid, a reference to the closest valid element is returned. The result of the non-constant index operator may be assigned to.

**See Also:** `resize`, `WCExcept::empty_container`, `WCExcept::index_range`,  
`WCExcept::out_of_memory`, `WCExcept::resize_required`

## *WCValVector<Type>::operator =()*

---

|                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis:</b>  | <pre>#include &lt;wcvector.h&gt; public:     WCValVector &amp; operator =( const WCValVector &amp; );</pre>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| <b>Semantics:</b> | The <code>operator =</code> public member function is the assignment operator for the <code>WCValVector&lt;Type&gt;</code> class. The left hand side vector is first cleared using the <code>clear</code> member function, and then the right hand side vector is copied. The left hand side vector is made to have the same length as the right hand side. All of the vector elements and exception trap states are copied.<br><br>If the left hand side vector cannot be fully created, it will have zero length. The <code>out_of_memory</code> exception is thrown if enabled in the right hand side vector. |
| <b>Results:</b>   | The <code>operator =</code> public member function assigns the left hand side vector to be a copy of the right hand side.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <b>See Also:</b>  | <code>clear</code> , <code>WCExcept::out_of_memory</code>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

**Synopsis:**

```
#include <wcvector.h>
public:
 int operator ==(const WCValVector &) const;
```

**Semantics:** The operator == public member function is the equivalence operator for the WCValVector<Type> class. Two vector objects are equivalent if they are the same object and share the same address.

**Results:** A TRUE (non-zero) value is returned if the left hand side and right hand side vectors are the same object. A FALSE (zero) value is returned otherwise.

## *WCValVector<Type>::resize()*

---

**Synopsis:**

```
#include <wcvector.h>
public:
 int resize(size_t new_size);
```

**Semantics:**

The `resize` public member function is used to change the vector size to be able to store *new\_size* elements. If *new\_size* is larger than the previous vector size, all elements will be copied (using *Type*'s copy constructor) into the newly sized vector, and new elements are initialized with *Type*'s default constructor. If the vector is resized to a smaller size, the first *new\_size* elements are copied. The remaining elements are destroyed using *Type*'s destructor.

If the `resize` cannot be performed and the `out_of_memory` exception is enabled, the exception is thrown.

**Results:**

The vector is resized to *new\_size*. A TRUE value (non-zero) is returned if the `resize` is successful. A FALSE (zero) result is returned if the `resize` fails.

**See Also:**

`WCExcept::out_of_memory`

---

# ***18 Input/Output Classes***

The input/output stream classes provide program access to the file system. In addition, various options for formatting of output and reading of input are provided.

## filebuf

---

**Declared:** fstream.h

**Derived from:** streambuf

The `filebuf` class is derived from the `streambuf` class, and provides additional functionality required to communicate with external files. Seek operations are supported when the underlying file supports seeking. Both input and output operations may be performed using a `filebuf` object, again when the underlying file supports read/write access.

`filebuf` objects are buffered by default, so the *reserve area* is allocated automatically unless one is specified when the `filebuf` object is created. The *get area* and *put area* pointers operate as if they were tied together. There is only one current position in a `filebuf` object.

The `filebuf` class allows only the *get area* or the *put area*, but not both, to be active at a time. This follows from the capability of files opened for both reading and writing to have operations of each type performed at arbitrary locations in the file. When writing is occurring, the characters are buffered in the *put area*. If a seek or read operation is done, the *put area* must be flushed before the next operation in order to ensure that the characters are written to the proper location in the file. Similarly, if reading is occurring, characters are buffered in the *get area*. If a write operation is done, the *get area* must be flushed and synchronized before the write operation in order to ensure the write occurs at the proper location in the file. If a seek operation is done, the *get area* does not have to be synchronized, but is discarded. When the *get area* is empty and a read is done, the `underflow` virtual member function reads more characters and fills the *get area* again. When the *put area* is full and a write is done, the `overflow` virtual member function writes the characters and makes the *put area* empty again.

C++ programmers who wish to use files without deriving new objects do not need to explicitly create or use a `filebuf` object.

### Public Data Members

The following data member is declared in the public interface. Its value is the default file protection that is used when creating new files. It is primarily referenced as a default argument in member functions.

```
static int const openprot;
```

### Public Member Functions

The following member functions are declared in the public interface:

```
filebuf();
filebuf(filedesc);
filebuf(filedesc, char *, int);
~filebuf();
int is_open() const;
filedesc fd() const;
filebuf *attach(filedesc);
filebuf *open(char const *,
ios::openmode,
int = filebuf::openprot);
filebuf *close();
virtual int pbackfail(int);
virtual int overflow(int = EOF);
virtual int underflow();
virtual streambuf *setbuf(char *, int);
```

```
virtual streampos seekoff(streamoff,
ios::seekdir,
ios::openmode);
virtual int sync();
```

**See Also:**      [fstreambase](#), [streambuf](#)

## **filebuf::attach()**

---

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf *filebuf::attach(filedesc hdl);
```

**Semantics:** The `attach` public member function connects an existing `filebuf` object to an open file via the file's descriptor or handle specified by `hdl`. If the `filebuf` object is already connected to a file, the `attach` public member function fails. Otherwise, the `attach` public member function extracts information from the file system to determine the capabilities of the file and hence the `filebuf` object.

**Results:** The `attach` public member function returns a pointer to the `filebuf` object on success, otherwise `NULL` is returned.

**See Also:** `filebuf`, `fd`, `open`

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf *filebuf::close();
```

**Semantics:** The `close` public member function disconnects the `filebuf` object from a connected file and closes the file. Any buffered output is flushed before the file is closed.

**Results:** The `close` public member function returns a pointer to the `filebuf` object on success, otherwise NULL is returned.

**See Also:** `filebuf`, `fd`, `is_open`

## ***filebuf::fd()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 filedesc filebuf::fd() const;
```

**Semantics:** The `fd` public member function queries the state of the `filebuf` object file handle.

**Results:** The `fd` public member function returns the file descriptor or handle of the file to which the `filebuf` object is currently connected. If the `filebuf` object is not currently connected to a file, `EOF` is returned.

**See Also:** `filebuf::attach`, `is_open`

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf::filebuf();
```

**Semantics:** This form of the public `filebuf` constructor creates a `filebuf` object that is not currently connected to any file. A call to the `fd` member function for this created `filebuf` object returns `EOF`, unless a file is connected using the `attach` member function.

**Results:** The public `filebuf` constructor produces a `filebuf` object that is not currently connected to any file.

**See Also:** `~filebuf`, `attach`, `open`

## **filebuf::filebuf()**

---

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf::filebuf(filedesc hdl);
```

**Semantics:** This form of the public `filebuf` constructor creates a `filebuf` object that is connected to an open file. The file is specified via the `hdl` parameter, which is a file descriptor or handle.

This form of the public `filebuf` constructor is similar to using the default constructor, and calling the `attach` member function. A call to the `fd` member function for this created `filebuf` object returns `hdl`.

**Results:** The public `filebuf` constructor produces a `filebuf` object that is connected to `hdl`.

**See Also:** `~filebuf`, `attach`, `open`

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf::filebuf(filedesc hdl, char *buf, int len);
```

**Semantics:** This form of the public `filebuf` constructor creates a `filebuf` object that is connected to an open file and that uses the buffer specified by `buf` and `len`. The file is specified via the `hdl` parameter, which is a file descriptor or handle. If `buf` is NULL and/or `len` is less than or equal to zero, the `filebuf` object is unbuffered, so that reading and/or writing take place one character at a time.

This form of the public `filebuf` constructor is similar to using the default constructor, and calling the `attach` and `setbuf` member functions.

**Results:** The public `filebuf` constructor constructor produces a `filebuf` object that is connected to `hdl`.

**See Also:** `~filebuf`, `attach`, `open`, `setbuf`

## ***filebuf::~filebuf()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf::~filebuf();
```

**Semantics:** The public `~filebuf` destructor closes the file if it was explicitly opened using the `open` member function. Otherwise, the destructor takes no explicit action. The `streambuf` destructor is called to destroy that portion of the `filebuf` object. The call to the public `~filebuf` destructor is inserted implicitly by the compiler at the point where the `filebuf` object goes out of scope.

**Results:** The `filebuf` object is destroyed.

**See Also:** `~filebuf`, `close`

**Synopsis:**

```
#include <fstream.h>
public:
 int filebuf::is_open();
```

**Semantics:** The `is_open` public member function queries the `filebuf` object state.

**Results:** The `is_open` public member function returns a non-zero value if the `filebuf` object is currently connected to a file. Otherwise, zero is returned.

**See Also:** `filebuf::attach`, `close`, `fd`, `open`

## **filebuf::open()**

---

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf *filebuf::open(const char *name,
 ios::openmode mode,
 int prot = filebuf::openprot);
```

**Semantics:** The open public member function is used to connect the `filebuf` object to a file specified by the *name* parameter. The file is opened using the specified *mode*. For details about the *mode* parameter, see the description of `ios::openmode`. The *prot* parameter specifies the file protection attributes to use when creating a file.

**Results:** The open public member function returns a pointer to the `filebuf` object on success, otherwise NULL is returned.

**See Also:** `filebuf`, `close`, `is_open`, `openprot`

**Synopsis:**

```
#include <fstream.h>
public:
 static int const filebuf::openprot;
```

**Semantics:** The openprot public member data is used to specify the default file protection to be used when creating new files. This value is used as the default if no user specified value is provided.

The default value is octal 0644. This is generally interpreted as follows:

- Owner: read/write
- Group: read
- World: read

Note that not all operating systems support all bits.

**See Also:** `filebuf`, `open`

## ***filebuf::overflow()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 virtual int filebuf::overflow(int ch = EOF);
```

**Semantics:** The `overflow` public virtual member function provides the output communication to the file to which the `filebuf` object is connected. Member functions in the `streambuf` class call the `overflow` public virtual member function for the derived class when the *put area* is full.

The `overflow` public virtual member function performs the following steps:

1. If no buffer is present, a buffer is allocated with the `streambuf::allocate` member function, which may call the `doallocate` virtual member function. The *put area* is then set up. If, after calling `streambuf::allocate`, no buffer is present, the `filebuf` object is unbuffered and *ch* (if not EOF) is written directly to the file without buffering, and no further action is taken.
2. If the *get area* is present, it is flushed with a call to the `sync` virtual member function. Note that the *get area* won't be present if a buffer was set up in step 1.
3. If *ch* is not EOF, it is added to the *put area*, if possible.
4. Any characters in the *put area* are written to the file.
5. The *put area* pointers are updated to reflect the new state of the *put area*. If the write did not complete, the unwritten portion of the *put area* is still present. If the *put area* was full before the write, *ch* (if not EOF) is placed at the start of the *put area*. Otherwise, the *put area* is empty.

**Results:** The `overflow` public virtual member function returns `__NOT_EOF` on success, otherwise EOF is returned.

**See Also:** `streambuf::overflow`  
`filebuf::underflow`

**Synopsis:**

```
#include <fstream.h>
public:
 virtual int filebuf::pbackfail(int ch);
```

**Semantics:** The `pbackfail` public virtual member function handles an attempt to put back a character when there is no room at the beginning of the *get area*. The `pbackfail` public virtual member function first calls the `sync` virtual member function to flush the *put area* and then it attempts to seek backwards over *ch* in the associated file.

**Results:** The `pbackfail` public virtual member function returns *ch* on success, otherwise `EOF` is returned.

**See Also:** `streambuf::pbackfail`

## **filebuf::seekoff()**

---

**Synopsis:**

```
#include <fstream.h>
public:
 virtual streampos filebuf::seekoff(streamoff offset,
 ios::seekdir dir,
 ios::openmode mode);
```

**Semantics:** The `seekoff` public virtual member function is used to position the `filebuf` object (and hence the file) to a particular offset so that subsequent input or output operations commence from that point. The offset is specified by the `offset` and `dir` parameters.

Since the *get area* and *put area* pointers are tied together for the `filebuf` object, the `mode` parameter is ignored.

Before the actual seek occurs, the *get area* and *put area* of the `filebuf` object are flushed via the `sync` virtual member function. Then, the new position in the file is calculated and the seek takes place.

The `dir` parameter may be `ios::beg`, `ios::cur`, or `ios::end` and is interpreted in conjunction with the `offset` parameter as follows:

`ios::beg` the `offset` is relative to the start and should be a positive value.  
`ios::cur` the `offset` is relative to the current position and may be positive  
    (seek towards end) or negative (seek towards start).  
`ios::end` the `offset` is relative to the end and should be a negative value.

If the `dir` parameter has any other value, or the `offset` parameter does not have an appropriate sign, the `seekoff` public virtual member function fails.

**Results:** The `seekoff` public virtual member function returns the new position in the file on success, otherwise EOF is returned.

**See Also:** `streambuf::seekoff`

**Synopsis:**

```
#include <fstream.h>
public:
 virtual streambuf *filebuf::setbuf(char *buf, int len);
```

**Semantics:**

The `setbuf` public virtual member function is used to offer a buffer, specified by `buf` and `len` to the `filebuf` object. If the `buf` parameter is `NULL` or the `len` is less than or equal to zero, the request is to make the `filebuf` object unbuffered.

If the `filebuf` object is already connected to a file and has a buffer, the offer is rejected. In other words, a call to the `setbuf` public virtual member function after the `filebuf` object has started to be used usually fails because the `filebuf` object has set up a buffer.

If the request is to make the `filebuf` object unbuffered, the offer succeeds.

If the `buf` is too small (less than five characters), the offer is rejected. Five characters are required to support the default putback area.

Otherwise, the `buf` is acceptable and the offer succeeds.

If the offer succeeds, the `streambuf::setb` member function is called to set up the pointers to the buffer. The `streambuf::setb` member function releases the old buffer (if present), depending on how that buffer was allocated.

Calls to the `setbuf` public virtual member function are usually made by a class derived from the `fstream` class, not directly by a user program.

**Results:**

The `setbuf` public virtual member function returns a pointer to the `filebuf` object on success, otherwise `NULL` is returned.

**See Also:**

`streambuf::setbuf`

## ***filebuf::sync()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 virtual int filebuf::sync();
```

**Semantics:** The `sync` public virtual member function synchronizes the `filebuf` object with the external file or device. If the *put area* contains characters it is flushed. This leaves the file positioned after the last written character. If the *get area* contains buffered (unread) characters, file is backed up to be positioned after the last read character.

Note that the *get area* and *put area* never both contain characters.

**Results:** The `sync` public virtual member function returns `__NOT_EOF` on success, otherwise `EOF` is returned.

**See Also:** `streambuf::sync`

**Synopsis:**

```
#include <fstream.h>
public:
 virtual int filebuf::underflow();
```

**Semantics:** The `underflow` public virtual member function provides the input communication from the file to which the `filebuf` object is connected. Member functions in the `streambuf` class call the `underflow` public virtual member function for the derived class when the *get area* is empty.

The `underflow` public virtual member function performs the following steps:

1. If no *reserve area* is present, a buffer is allocated with the `streambuf::allocate` member function, which may call the `doallocate` virtual member function. If, after calling `allocate`, no *reserve area* is present, the `filebuf` object is unbuffered and a one-character *reserve area* (plus putback area) is set up to do unbuffered input. This buffer is embedded in the `filebuf` object. The *get area* is set up as empty.
2. If the *put area* is present, it is flushed using the `sync` virtual member function.
3. The unused part of the *get area* is used to read characters from the file connected to the `filebuf` object. The *get area* pointers are then set up to reflect the new *get area*.

**Results:** The `underflow` public virtual member function returns the first unread character of the *get area*, on success, otherwise EOF is returned. Note that the *get pointer* is not advanced on success.

**See Also:** `streambuf::underflow`  
`filebuf::overflow`

## ***fstream***

---

**Declared:** fstream.h

**Derived from:** fstreambase, iostream

The `fstream` class is used to access files for reading and writing. The file can be opened and closed, and read, write and seek operations can be performed.

The `fstream` class provides very little of its own functionality. It is derived from both the `fstreambase` and `iostream` classes. The `fstream` constructors, destructor and member function provide simplified access to the appropriate equivalents in the base classes.

Of the available I/O stream classes, creating an `fstream` object is the preferred method of accessing a file for both input and output.

### **Public Member Functions**

The following public member functions are declared:

```
fstream();
fstream(char const *,
ios::openmode = ios::in|ios::out,
int = filebuf::openprot);
fstream(filedesc);
fstream(filedesc, char *, int);
~fstream();
void open(char const *,
ios::openmode = ios::in|ios::out,
int = filebuf::openprot);
```

**See Also:** fstreambase, ifstream, iostream, ofstream

**Synopsis:**

```
#include <fstream.h>
public:
 fstream::fstream();
```

**Semantics:** This form of the public `fstream` constructor creates an `fstream` object that is not connected to a file. The `open` or `attach` member functions should be used to connect the `fstream` object to a file.

**Results:** The public `fstream` constructor produces an `fstream` object that is not connected to a file.

**See Also:** `~fstream`, `open`, `fstreambase::attach`

## ***fstream::fstream()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 fstream::fstream(const char *name,
 ios::openmode mode = ios::in|ios::out,
 int prot = filebuf::openprot);
```

**Semantics:** This form of the public `fstream` constructor creates an `fstream` object that is connected to the file specified by the *name* parameter, using the specified *mode* and *prot* parameters. The connection is made via the C library `open` function.

**Results:** The public `fstream` constructor produces an `fstream` object that is connected to the file specified by *name*. If the open fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:** `~fstream`, `open`, `openmode`, `openprot`

**Synopsis:**

```
#include <fstream.h>
public:
 fstream::fstream(filedesc hdl);
```

**Semantics:** This form of the public `fstream` constructor creates an `fstream` object that is attached to the file specified by the `hdl` parameter.

**Results:** The public `fstream` constructor produces an `fstream` object that is attached to `hdl`. If the attach fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:** `~fstream`, `fstreambase::attach`, `fstreambase::fd`

## ***fstream::fstream()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 fstream::fstream(filedesc hdl, char *buf, int len);
```

**Semantics:** This form of the public `fstream` constructor creates an `fstream` object that is connected to the file specified by the *hdl* parameter. The buffer specified by the *buf* and *len* parameters is offered to the associated `filebuf` object via the `setbuf` member function. If the *buf* parameter is `NULL` or the *len* is less than or equal to zero, the `filebuf` is unbuffered, so that each read or write operation reads or writes a single character at a time.

**Results:** The public `fstream` constructor produces an `fstream` object that is attached to *hdl*. If the connection to *hdl* fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object. If the `setbuf` fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `~fstream`, `filebuf::setbuf`, `fstreambase::attach`

**Synopsis:**

```
#include <fstream.h>
public:
fstream::~fstream();
```

**Semantics:** The public `~fstream` destructor does not do anything explicit. The call to the public `~fstream` destructor is inserted implicitly by the compiler at the point where the `fstream` object goes out of scope.

**Results:** The public `~fstream` destructor destroys the `fstream` object.

**See Also:** `fstream`

## ***fstream::open()***

---

**Synopsis:**

```
#include <fstream.h>
public:
void fstream::open(const char *name,
ios::openmode mode = ios::in|ios::out,
int prot = filebuf::openprot);
```

**Semantics:** The open public member function connects the `fstream` object to the file specified by the *name* parameter, using the specified *mode* and *prot* parameters. The *mode* parameter is optional and usually is not specified unless additional bits (such as `ios::binary` or `ios::text`) are to be specified. The connection is made via the C library `open` function.

**Results:** If the open fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `fstreambase::attach`, `fstreambase::close`, `fstreambase::fd`,  
`fstreambase::is_open`  
`fstream::openmode`, `openprot`

**Declared:** fstream.h

**Derived from:** ios

**Derived by:** ifstream, ofstream, fstream

The **fstreambase** class is a base class that provides common functionality for the three file-based classes, ifstream, ofstream and fstream. The **fstreambase** class is derived from the **ios** class, providing the stream state information, plus it provides member functions for opening and closing files. The actual file manipulation work is performed by the **filebuf** class.

It is not intended that **fstreambase** objects be created. Instead, the user should create an ifstream, ofstream or fstream object.

### **Protected Member Functions**

The following member functions are declared in the protected interface:

```
fstreambase();
fstreambase(char const *,
ios::openmode,
int = filebuf::openprot);
fstreambase(filedesc);
fstreambase(filedesc, char *, int);
~fstreambase();
```

### **Public Member Functions**

The following member functions are declared in the public interface:

```
void attach(filedesc);
void close();
filedesc fd() const;
int is_open() const;
void open(char const *,
ios::openmode,
int = filebuf::openprot);
filebuf *rdbuf() const;
void setbuf(char *, int);
```

**See Also:** filebuf, fstream, ifstream, ofstream

## ***fstreambase::attach()***

---

**Synopsis:**

```
#include <fstream.h>
public:
void fstreambase::attach(filedesc hdl);
```

**Semantics:** The `attach` public member function connects the `fstreambase` object to the file specified by the `hdl` parameter.

**Results:** If the `attach` public member function fails, `ios::failbit` bit is set in the error state in the inherited `ios` object. The error state in the inherited `ios` object is cleared on success.

**See Also:** `fstreambase::fd`, `is_open`, `open`

**Synopsis:**

```
#include <fstream.h>
public:
void fstreambase::close();
```

**Semantics:** The `close` public member function disconnects the `fstreambase` object from the file with which it is associated. If the `fstreambase` object is not associated with a file, the `close` public member function fails.

**Results:** If the `close` public member function fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `fstreambase::fd`, `is_open`, `open`

## ***fstreambase::fstreambase()***

---

**Synopsis:**

```
#include <fstream.h>
protected:
fstreambase::fstreambase();
```

**Semantics:** The protected `fstreambase` constructor creates an `fstreambase` object that is initialized, but not connected to anything. The `open` or `attach` member function should be used to connect the `fstreambase` object to a file.

**Results:** The protected `fstreambase` constructor produces an `fstreambase` object.

**See Also:** `~fstreambase`, `attach`, `open`

**Synopsis:**

```
#include <fstream.h>
protected:
fstreambase::fstreambase(char const *name,
ios::openmode mode,
int prot = filebuf::openprot);
```

**Semantics:** This protected `fstreambase` constructor creates an `fstreambase` object that is initialized and connected to the file indicated by *name* using the specified *mode* and *prot*. The `fstreambase` object is connected to the specified file via the `open` C library function.

**Results:** The protected `fstreambase` constructor produces an `fstreambase` object. If the call to `open` for the file fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object

.

**See Also:** `~fstreambase`, `open`, `openmode`, `openprot`

## ***fstreambase::fstreambase()***

---

**Synopsis:**

```
#include <fstream.h>
protected:
 fstreambase::fstreambase(filedesc hdl);
```

**Semantics:** This protected `fstreambase` constructor creates an `fstreambase` object that is initialized and connected to the open file specified by the `hdl` parameter.

**Results:** The protected `fstreambase` constructor produces an `fstreambase` object. If the attach to the file fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:** `~fstreambase`, `attach`

**Synopsis:**

```
#include <fstream.h>
protected:
 fstreambase::fstreambase(filedesc hdl, char *buf, int len);
```

**Semantics:** This protected `fstreambase` constructor creates an `fstreambase` object that is initialized and connected to the open file specified by the *hdl* parameter. The buffer, specified by the *buf* and *len* parameters, is offered via the `setbuf` virtual member function to be used as the *reserve area* for the `filebuf` associated with the `fstreambase` object.

**Results:** The protected `fstreambase` constructor produces an `fstreambase` object. If the attach to the file fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:** `~fstreambase`, `attach`, `setbuf`

## ***fstreambase::~fstreambase()***

---

**Synopsis:**

```
#include <fstream.h>
protected:
fstreambase::~fstreambase();
```

**Semantics:** The protected ~fstreambase destructor does not do anything explicit. The filebuf object associated with the fstreambase object is embedded within the fstreambase object, so the filebuf destructor is called. The ios destructor is called for that portion of the fstreambase object. The call to the protected ~fstreambase destructor is inserted implicitly by the compiler at the point where the fstreambase object goes out of scope.

**Results:** The fstreambase object is destroyed.

**See Also:** fstreambase, close

**Synopsis:**

```
#include <fstream.h>
public:
 int fstreambase::is_open() const;
```

**Semantics:** The `is_open` public member function queries the current state of the file associated with the `fstreambase` object. Calling the `is_open` public member function is equivalent to calling the `fd` member function and testing for EOF.

**Results:** The `is_open` public member function returns a non-zero value if the `fstreambase` object is currently connected to a file, otherwise zero is returned.

**See Also:** `fstreambase::attach`, `fd`, `open`

## ***fstreambase::fd()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 filedesc fstreambase::fd() const;
```

**Semantics:** The `fd` public member function returns the file descriptor for the file to which the `fstreambase` object is connected.

**Results:** The `fd` public member function returns the file descriptor for the file to which the `fstreambase` object is connected. If the `fstreambase` object is not currently connected to a file, EOF is returned.

**See Also:** `fstreambase::attach`, `is_open`, `open`

**Synopsis:**

```
#include <fstream.h>
public:
void fstreambase::open(const char *name,
ios::openmode mode,
int prot = filebuf::openprot);
```

**Semantics:** The open public member function connects the `fstreambase` object to the file specified by *name*, using the specified *mode* and *prot*. The connection is made via the C library `open` function.

**Results:** If the open fails, `ios::failbit` is set in the error state in the inherited `ios` object. The error state in the inherited `ios` object is cleared on success.

**See Also:** `fstreambase::attach`, `close`, `fd`, `is_open`, `openmode`, `openprot`

## ***fstreambase::rdbuf()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 filebuf *fstreambase::rdbuf() const;
```

**Semantics:** The `rdbuf` public member function returns the address of the `filebuf` object currently associated with the `fstreambase` object.

**Results:** The `rdbuf` public member function returns a pointer to the `filebuf` object currently associated with the `fstreambase` object. If there is no associated `filebuf`, `NULL` is returned.

**See Also:** `ios::rdbuf`

**Synopsis:**

```
#include <fstream.h>
public:
void fstreambase::setbuf(char *buf, int len);
```

**Semantics:** The `setbuf` public member function offers the specified buffer to the `filebuf` object associated with the `fstreambase` object. The `filebuf` may or may not reject the offer, depending upon its state.

**Results:** If the offer is rejected, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `filebuf::setbuf`

## ***ifstream***

---

**Declared:** fstream.h

**Derived from:** fstreambase, istream

The `ifstream` class is used to access existing files for reading. Such files can be opened and closed, and read and seek operations can be performed.

The `ifstream` class provides very little of its own functionality. Derived from both the `fstreambase` and `istream` classes, its constructors, destructor and member functions provide simplified access to the appropriate equivalents in those base classes.

Of the available I/O stream classes, creating an `ifstream` object is the preferred method of accessing a file for input only operations.

### **Public Member Functions**

The following public member functions are declared:

```
ifstream();
ifstream(char const *,
ios::openmode = ios::in,
int = filebuf::openprot);
ifstream(filedesc);
ifstream(filedesc, char *, int);
~ifstream();
void open(char const *,
ios::openmode = ios::in,
int = filebuf::openprot);
```

**See Also:** fstream, fstreambase, istream, ofstream

**Synopsis:**

```
#include <fstream.h>
public:
 ifstream::ifstream();
```

**Semantics:** This form of the public `ifstream` constructor creates an `ifstream` object that is not connected to a file. The `open` or `attach` member functions should be used to connect the `ifstream` object to a file.

**Results:** The public `ifstream` constructor produces an `ifstream` object that is not connected to a file.

**See Also:** `~ifstream`, `open`, `fstreambase::attach`

## ***ifstream::ifstream()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 ifstream::ifstream(const char *name,
 ios::openmode mode = ios::in,
 int prot = filebuf::openprot);
```

**Semantics:** This form of the public `ifstream` constructor creates an `ifstream` object that is connected to the file specified by the *name* parameter, using the specified *mode* and *prot* parameters. The connection is made via the C library `open` function.

**Results:** The public `ifstream` constructor produces an `ifstream` object that is connected to the file specified by *name*. If the `open` fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:** `~ifstream`, `open`, `openmode`, `openprot`, `fstreambase::attach`, `fstreambase::fd`, `fstreambase::is_open`

**Synopsis:**

```
#include <fstream.h>
public:
 ifstream::ifstream(filedesc hdl);
```

**Semantics:** This form of the public `ifstream` constructor creates an `ifstream` object that is attached to the file specified by the `hdl` parameter.

**Results:** The public `ifstream` constructor produces an `ifstream` object that is attached to `hdl`. If the attach fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:**

- `fstreambase::attach`
- `~ifstream`, `open`

## ***ifstream::ifstream()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 ifstream::ifstream(filedesc hdl, char *buf, int len);
```

**Semantics:** This form of the public `ifstream` constructor creates an `ifstream` object that is connected to the file specified by the `hdl` parameter. The buffer specified by the `buf` and `len` parameters is offered to the associated `filebuf` object via the `setbuf` member function. If the `buf` parameter is `NULL` or the `len` is less than or equal to zero, the `filebuf` is unbuffered, so that each read or write operation reads or writes a single character at a time.

**Results:** The public `ifstream` constructor produces an `ifstream` object that is attached to `hdl`. If the connection to `hdl` fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object. If the `setbuf` fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `fstreambase::attach`, `fstreambase::setbuf`  
`~ifstream`, `open`

**Synopsis:**

```
#include <fstream.h>
public:
ifstream::~ifstream();
```

**Semantics:** The public `~ifstream` destructor does not do anything explicit. The call to the public `~ifstream` destructor is inserted implicitly by the compiler at the point where the `ifstream` object goes out of scope.

**Results:** The public `~ifstream` destructor destroys the `ifstream` object.

**See Also:** `ifstream`

## ***ifstream::open()***

---

**Synopsis:**

```
#include <fstream.h>
public:
void ifstream::open(const char *name,
ios::openmode mode = ios::in,
int prot = filebuf::openprot);
```

**Semantics:** The open public member function connects the `ifstream` object to the file specified by the `name` parameter, using the specified `mode` and `prot` parameters. The `mode` parameter is optional and usually is not specified unless additional bits (such as `ios::binary` or `ios::text`) are to be specified. The connection is made via the C library `open` function.

**Results:** If the open fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `fstreambase::attach`, `fstreambase::close`, `fstreambase::fd`,  
`fstreambase::is_open`  
`ifstream::openmode`, `openprot`

**Declared:** iostream.h

**Derived by:** istream, ostream

The `ios` class is used to group together common functionality needed for other derived stream classes. It is not intended that objects of type `ios` be created.

This class maintains state information about the stream. (the `ios` name can be thought of as a short-form for I/O State). Error flags, formatting flags, and values and the connection to the buffers used for the input and output are all maintained by the `ios` class. No information about the buffer itself is stored in an `ios` object, merely the pointer to the buffer information.

### Protected Member Functions

The following member functions are declared in the protected interface:

```
ios();
void init(streambuf *);
void setstate(ios::iostate);
```

### Public Enumerations

The following enumeration typedefs are declared in the public interface:

```
typedef int iostate;
typedef long fmtflags;
typedef int openmode;
typedef int seekdir;
```

### Public Member Functions

The following member functions are declared in the public interface:

```
ios(streambuf *);
virtual ~ios();
ostream *tie() const;
ostream *tie(ostream *);
streambuf *rdbuf() const;
ios::iostate rdstate() const;
ios::iostate clear(ios::iostate = 0);
int good() const;
int bad() const;
int fail() const;
int eof() const;
ios::iostate exceptions(ios::iostate);
ios::iostate exceptions() const;
ios::fmtflags setf(ios::fmtflags, ios::fmtflags);
ios::fmtflags setf(ios::fmtflags);
ios::fmtflags unsetf(ios::fmtflags);
ios::fmtflags flags(ios::fmtflags);
ios::fmtflags flags() const;
char fill(char);
char fill() const;
int precision(int);
int precision() const;
int width(int);
int width() const;
```

```
long &iword(int);
void *pword(int);
static void sync_with_stdio();
static ios::fmtflags bitalloc();
static int xalloc();
```

### **Public Member Operators**

The following member operators are declared in the public interface:

```
operator void *() const;
int operator !() const;
```

**See Also:** [iostream](#), [istream](#), [ostream](#), [streambuf](#)

**Synopsis:**

```
#include <iostream.h>
public:
 int ios::bad() const;
```

**Semantics:** The `bad` public member function queries the state of the `ios` object.

**Results:** The `bad` public member function returns a non-zero value if `ios::badbit` is set in the error state in the inherited `ios` object, otherwise zero is returned.

**See Also:** `ios::clear`, `eof`, `fail`, `good`, `iostate`, `operator !`, `operator void *`, `rdstate`, `setstate`

## ***ios::bitalloc()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 static ios::fmtflags ios::bitalloc();
```

**Semantics:** The `bitalloc` public static member function is used to allocate a new `ios::fmtflags` bit for use by user derived classes.

Because the `bitalloc` public static member function manipulates `static` member data, its behavior is not tied to any one object but affects the entire class of objects. The value that is returned by the `bitalloc` public static member function is valid for all objects of all classes derived from the `ios` class. No subsequent call to the `bitalloc` public static member function will return the same value as a previous call.

The bit value allocated may be used with the member functions that query and affect `ios::fmtflags`. In particular, the bit can be set with the `setf` or `flags` member functions or the `setiosflags` manipulator, and reset with the `unsetf` or `flags` member functions or the `resetiosflags` manipulator.

There are two constants defined in `<iostream.h>` which indicate the number of bits available when a program starts. `_LAST_FORMAT_FLAG` indicates the last bit used by the built-in format flags described by `ios::fmtflags`. `_LAST_FLAG_BIT` indicates the last bit that is available for the `bitalloc` public static member function to allocate. The difference between the bit positions indicates how many bits are available.

**Results:** The `bitalloc` public static member function returns the next available `ios::fmtflags` bit for use by user derived classes. If no more bits are available, zero is returned.

**See Also:** `ios::fmtflags`

**Synopsis:**

```
#include <iostream.h>
public:
 iostate ios::clear(ios::iostate flags = 0);
```

**Semantics:** The `clear` public member function is used to change the current value of `ios::iostate` in the `ios` object. `ios::iostate` is cleared, all bits specified in `flags` are set.

**Results:** The `clear` public member function returns the previous value of `ios::iostate`.

**See Also:** `ios::bad`, `eof`, `fail`, `good`, `iostate`, `operator !`, `operator void *`, `rdstate`, `setstate`

## *ios::eof()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 int ios::eof() const;
```

**Semantics:** The `eof` public member function queries the state of the `ios` object.

**Results:** The `eof` public member function returns a non-zero value if `ios::eofbit` is set in the error state in the inherited `ios` object, otherwise zero is returned.

**See Also:** `ios::bad`, `clear`, `fail`, `good`, `iostate`, `rdstate`, `setstate`

**Synopsis:**

```
#include <iostream.h>
public:
 ios::iostate ios::exceptions() const;
 ios::iostate ios::exceptions(int enable);
```

**Semantics:** The `exceptions` public member function queries and/or sets the bits that control which exceptions are enabled. `ios::iostate` within the `ios` object is used to enable and disable exceptions.

When a condition arises that sets a bit in `ios::iostate`, a check is made to see if the same bit is also set in the exception bits. If so, an exception is thrown. Otherwise, no exception is thrown.

The first form of the `exceptions` public member function looks up the current setting of the exception bits. The bit values are those described by `ios::iostate`.

The second form of the `exceptions` public member function sets the exception bits to those specified in the `enable` parameter, and returns the current settings.

**Results:** The `exceptions` public member function returns the previous setting of the exception bits.

**See Also:** `ios::clear`, `iostate`, `rdstate`, `setstate`

## ***ios::fail()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 int ios::fail() const;
```

**Semantics:** The `fail` public member function queries the state of the `ios` object.

**Results:** The `fail` public member function returns a non-zero value if `ios::failbit` or `ios::badbit` is set in the error state in the inherited `ios` object, otherwise zero is returned.

**See Also:** `ios::bad`, `clear`, `eof`, `good`, `iostate`, `operator !`, `operator void *`, `rdstate`, `setstate`

**Synopsis:**

```
#include <iostream.h>
public:
char ios::fill() const;
char ios::fill(char fillchar);
```

**Semantics:** The `fill` public member function queries and/or sets the *fill character* used when the size of a formatted object is smaller than the *format width* specified.

The first form of the `fill` public member function looks up the current value of the *fill character*.

The second form of the `fill` public member function sets the *fill character* to `fillchar`.

By default, the *fill character* is a space.

**Results:** The `fill` public member function returns the previous value of the *fill character*.

**See Also:** `ios::fmtflags`, manipulator `setfill`

## ***ios::flags()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 ios::fmtflags ios::flags() const;
 ios::fmtflags ios::flags(ios::fmtflags setbits);
```

**Semantics:** The `flags` public member function is used to query and/or set the value of `ios::fmtflags` in the `ios` object.

The first form of the `flags` public member function looks up the current `ios::fmtflags` value.

The second form of the `flags` public member function sets `ios::fmtflags` to the value specified in the `setbits` parameter.

Note that the `setf` public member function only turns bits on, while the `flags` public member function turns some bits on and some bits off.

**Results:** The `flags` public member function returns the previous `ios::fmtflags` value.

**See Also:** `ios::fmtflags`, `setf`, `unsetf`, manipulator `dec`, manipulator `hex`, manipulator `oct`, manipulator `resetiosflags`, manipulator `setbase`, manipulator `setiosflags`

**Synopsis:**

```
#include <iostream.h>
public:
enum fmt_flags {
 skipws = 0x0001, // skip whitespace
 left = 0x0002, // align field to left edge
 right = 0x0004, // align field to right edge
 internal = 0x0008, // sign at left, value at right
 dec = 0x0010, // decimal conversion for integers
 oct = 0x0020, // octal conversion for integers
 hex = 0x0040, // hexadecimal conversion for integers
 showbase = 0x0080, // show dec/octal/hex base on output
 showpoint = 0x0100, // show decimal and digits on output
 uppercase = 0x0200, // use uppercase for format characters
 showpos = 0x0400, // use + for output positive numbers
 scientific = 0x0800, // use scientific notation for output
 fixed = 0x1000, // use floating notation for output
 unitbuf = 0x2000, // flush stream after output
 stdio = 0x4000, // flush stdout/stderr after output

 basefield = dec | oct | hex,
 adjustfield= left | right | internal,
 floatfield = scientific | fixed
};
typedef long fmtflags;
```

**Semantics:** The type `ios::fmt_flags` is a set of bits representing methods of formatting objects written to the stream and interpreting objects read from the stream. The `ios::fmtflags` member typedef represents the same set of bits, but uses a `long` to represent the values, thereby avoiding problems made possible by the compiler's ability to use smaller types for enumerations. All uses of these bits should use the `ios::fmtflags` member typedef.

The bit values defined by the `ios::fmtflags` member typedef are set and read by the member functions `setf`, `unsetf` and `flags`, as well as the manipulators `setiosflags` and `resetiosflags`.

Because one field is used to store all of these bits, there are three special values used to mask various groups of bits. These values are named `ios::basefield`, `ios::adjustfield` and `ios::floatfield`, and are discussed with the bits that they are used to mask.

`ios::skipws` controls whether or not whitespace characters are automatically skipped when using an operator `>>` extractor. If `ios::skipws` is on, any use of the operator `>>` extractor skips whitespace characters before inputting the next item. Otherwise, skipping of whitespace characters must be handled by the program.

`ios::left`, `ios::right` and `ios::internal` control the alignment of items written using an operator `<<` inserter. These bits are usually used in conjunction with the *format width* and *fill character*.

`ios::adjustfield` can be used to mask the alignment bits returned by the `setf`, `unsetf` and `flags` member functions, and for setting new values to ensure that no other bits are accidentally affected.

When the item to be written is smaller than the *format width* specified, *fill characters* are written to occupy the additional space. If `ios::left` is in effect, the item is written in the left portion of the available space, and *fill characters* are written in the right portion. If `ios::right` is in effect, the item is written in the right portion of the available space, and *fill characters* are written in the left

portion. If `ios::internal` is in effect, any sign character or base indicator is written in the left portion, the digits are written in the right portion, and *fill characters* are written in between.

If no alignment is specified, `ios::right` is assumed.

If the item to be written is as big as or bigger than the *format width* specified, no *fill characters* are written and the alignment is ignored.

`ios::dec`, `ios::oct` and `ios::hex` control the base used to format integers being written to the stream, and also control the interpretation of integers being read from the stream.

`ios::basefield` can be used to mask the base bits returned by the member functions `setf`, `unsetf` and `flags`, and for setting new values to ensure that no other bits are accidentally affected.

When an integer is being read from the stream, these bits control the base used for the interpretation of the digits. If none of these bits is set, a number that starts with `0x` or `0X` is interpreted as hexadecimal (digits 0123456789, plus the letters `abcdef` or `ABCDEF`), a number that starts with `0` (zero) is interpreted as octal (digits 01234567), otherwise the number is interpreted as decimal (digits 0123456789). If one of the bits is set, then the prefix is not necessary and the number is interpreted according to the bit.

When any one of the integer types is being written to the stream, it can be written in decimal, octal or hexadecimal. If none of these bits is set, `ios::dec` is assumed.

If `ios::dec` is set (or assumed), the integer is written in decimal (digits 0123456789). No prefix is included.

If `ios::oct` is set, the integer is written in octal (digits 01234567). No sign character is written, as the number is treated as an unsigned quantity upon conversion to octal.

If `ios::hex` is set, the integer is written in hexadecimal (digits 0123456789, plus the letters `abcdef` or `ABCDEF`, depending on the setting of `ios::uppercase`). No sign character is written, as the number is treated as an unsigned quantity upon conversion to hexadecimal.

`ios::showbase` controls whether or not integers written to the stream in octal or hexadecimal form have a prefix that indicates the base of the number. If the bit is set, decimal numbers are written without a prefix, octal numbers are written with the prefix `0` (zero) and hexadecimal numbers are written with the prefix `0x` or `0X` depending on the setting of `ios::uppercase`. If the `ios::showbase` is not set, no prefixes are written.

`ios::showpoint` is used to control whether or not the decimal point and trailing zeroes are trimmed when floating-point numbers are written to the stream. If the bit is set, no trimming is done, causing the number to appear with the specified *format precision*. If the bit is not set, any trailing zeroes after the decimal point are trimmed, and if not followed by any digits, the decimal point is removed as well.

`ios::uppercase` is used to force to upper-case all letters used in formatting numbers, including the letter-digits `abcdef`, the `x` hexadecimal prefix, and the `e` used for the exponents in floating-point numbers.

`ios::showpos` controls whether or not a `+` is added to the front of positive integers being written to the stream. If the bit is set, the number is positive and the number is being written in decimal, a `+` is written before the first digit.

`ios::scientific` and `ios::fixed` controls the form used for writing floating-point numbers to the stream. Floating-point numbers can be written in scientific notation (also called exponential notation) or in fixed-point notation.

`ios::floatfield` can be used to mask the floating-format bits returned by the member functions `setf`, `unsetf` and `flags`, and for setting new values to ensure that no other bits are accidentally affected.

If `ios::scientific` is set, the floating-point number is written with a leading `-` sign (for negative numbers), a digit, a decimal point, more digits, an `e` (or `E` if `ios::uppercase` is set), a `+` or `-` sign, and two or three digits representing the exponent. The digit before the decimal is not zero unless the number is zero. The total number of digits before and after the decimal is equal to the specified *format precision*. If `ios::showpoint` is not set, trimming of the decimal and digits following the decimal may occur.

If `ios::fixed` is set, the floating-point number is written with a `-` sign (for negative numbers), at least one digit, the decimal point, and as many digits following the decimal as specified by the *format precision*. If `ios::showpoint` is not set, trimming of the decimal and digits following the decimal may occur.

If neither `ios::scientific` nor `ios::fixed` is specified, the floating-point number is formatted using scientific notation provided one or both of the following conditions are met:

- the exponent is less than `-4`, or,
- the exponent is greater than the *format precision*.

Otherwise, fixed-point notation is used.

`ios::unitbuf` controls whether or not the stream is flushed after each item is written. If the bit is set, every item that is written to the stream is followed by a flush operation, which ensures that the I/O stream buffer associated with the stream is kept empty, immediately transferring the data to its final destination.

`ios::stdio` controls whether or not the stream is synchronized after each item is written. If the bit is set, every item that is written to the stream causes the stream to be synchronized, which means any input or output buffers are flushed so that an I/O operation performed using C (not C++) I/O behaves in an understandable way. If the output buffer was not flushed, writing using C++ and then C I/O functions could cause the output from the C functions to appear before the output from the C++ functions, since the characters might be sitting in the C++ output buffer. Similarly, after the C output operations are done, a call should be made to the C library `fflush` function on the appropriate stream before resuming C++ output operations.

**See Also:** `ios::flags`, `setf`, `unsetf`, manipulator `dec`, manipulator `hex`, manipulator `oct`, manipulator `resetiosflags`, manipulator `setbase`, manipulator `setiosflags`

## *ios::good()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 int ios::good() const;
```

**Semantics:** The `good` public member function queries the state of the `ios` object.

**Results:** The `good` public member function returns a non-zero value if none of `ios::iostate` is clear, otherwise zero is returned.

**See Also:** `ios::bad`, `clear`, `eof`, `fail`, `iostate`, `rdstate`, `setstate`

**Synopsis:**

```
#include <iostream.h>
protected:
void ios::init(streambuf *sb);
```

**Semantics:** The `init` public protected member function is used by derived classes to explicitly initialize the `ios` portion of the derived object, and to associate a `streambuf` with the `ios` object. The `init` public protected member function performs the following steps:

1. The default *fill character* is set to a space.
2. The *format precision* is set to six.
3. The `streambuf` pointer (returned by the `rdbuf` member function) is set to `sb`.
4. The remaining fields of the `ios` object are initialized to zero.

**Results:** If `sb` is NULL the `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** `ios`, `rdbuf`

## *ios::ios()*

---

**Synopsis:**

```
#include <iostream.h>
protected:
ios::ios();
```

**Semantics:** This form of the protected `ios` constructor creates a default `ios` object that is initialized, but does not have an associated `streambuf`. Initialization of an `ios` object is handled by the `init` protected member function.

**Results:** This protected `ios` constructor creates an `ios` object and sets `ios::badbit` in the error state in the inherited `ios` object.

**See Also:** `~ios`, `init`

**Synopsis:**

```
#include <iostream.h>
public:
ios::ios(streambuf *sb);
```

**Semantics:** This form of the public `ios` constructor creates an `ios` object that is initialized and has an associated `streambuf`. Initialization of an `ios` object is handled by the `init` protected member function. Once the `init` protected member function is completed, the `ios` object's `streambuf` pointer is set to `sb`. If `sb` is not `NULL`, `ios::badbit` is cleared from the error state in the inherited `ios` object.

**Results:** This public `ios` constructor creates an `ios` object and, if `sb` is `NULL`, sets `ios::badbit` in the error state in the inherited `ios` object.

**See Also:** `~ios`, `init`

## *ios::~ios()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 virtual ios::~ios();
```

**Semantics:** The public virtual `~ios` destructor destroys an `ios` object. The call to the public virtual `~ios` destructor is inserted implicitly by the compiler at the point where the `ios` object goes out of scope.

**Results:** The `ios` object is destroyed.

**See Also:** `ios`

**Synopsis:**

```
#include <iostream.h>
public:
enum io_state {
goodbit = 0x00, // no errors
badbit = 0x01, // operation failed, may not proceed
failbit = 0x02, // operation failed, may proceed
eofbit = 0x04 // end of file encountered
};
typedef int iostate;
```

**Semantics:** The type `ios::io_state` is a set of bits representing the current state of the stream. The `ios::iostate` member typedef represents the same set of bits, but uses an `int` to represent the values, thereby avoiding problems made possible by the compiler's ability to use smaller types for enumerations. All uses of these bits should use the `ios::iostate` member typedef.

The bit values defined by the `ios::iostate` member typedef can be read and set by the member functions `rdstate` and `clear`, and can be used to control exception handling with the member function `exceptions`.

`ios::badbit` represents the state where the stream is no longer usable because of some error condition.

`ios::failbit` represents the state where the previous operation on the stream failed, but the stream is still usable. Subsequent operations on the stream are possible, but the state must be cleared using the `clear` member function.

`ios::eofbit` represents the state where the end-of-file condition has been encountered. The stream may still be used, but the state must be cleared using the `clear` member function.

Even though `ios::goodbit` is not a bit value (because its value is zero, which has no bits on), it is provided for completeness.

**See Also:** `ios::bad`, `clear`, `eof`, `fail`, `good`, `operator !`, `operator void *`, `rdstate`, `setstate`

## *ios::iword()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 long &ios::iword(int index);
```

**Semantics:** The `iword` public member function creates a reference to a `long int`, which may be used to store and retrieve any suitable integer value. The `index` parameter specifies which `long int` is to be referenced and must be obtained from a call to the `xalloc` static member function.

Note that the `iword` and `pword` public member functions return references to the same storage with a different type. Therefore, each `index` obtained from the `xalloc` static member function can be used only for an integer or a pointer, not both.

Since the `iword` public member function returns a reference and the `ios` class cannot predict how many such items will be required by a program, it should be assumed that each call to the `xalloc` static member function invalidates all previous references returned by the `iword` public member function. Therefore, the `iword` public member function should be called each time the reference is needed.

**Results:** The `iword` public member function returns a reference to a `long int`.

**See Also:** `ios::pword`, `xalloc`

---

**Synopsis:**

```
#include <iostream.h>
public:
enum open_mode {
 in = 0x0001, // open for input
 out = 0x0002, // open for output
 atend = 0x0004, // seek to end after opening
 append = 0x0008, // open for output, append to the end
 truncate = 0x0010, // discard contents after opening
 nocreate = 0x0020, // open only an existing file
 noreplace = 0x0040, // open only a new file
 text = 0x0080, // open as text file
 binary = 0x0100, // open as binary file

 app = append, // synonym
 ate = atend, // synonym
 trunc = truncate // synonym
};
typedef int openmode;
```

**Semantics:** The type `ios::open_mode` is a set of bits representing ways of opening a stream. The `ios::openmode` member `typedef` represents the same set of bits, but uses an `int` to represent the values, thereby avoiding problems made possible by the compiler's ability to use smaller types for enumerations. All uses of these bits should use the `ios::openmode` member `typedef`.

The bit values defined by `ios::openmode` member `typedef` can be specified in the constructors for stream objects, as well as in various member functions.

`ios::in` is specified in a stream for which input operations may be performed. `ios::out` is specified in a stream for which output operations may be performed. A stream for which only `ios::in` is specified is referred to as an *input* stream. A stream for which only `ios::out` is specified is referred to as an *output* stream. A stream where both `ios::in` and `ios::out` are specified is referred to as an *input/output* stream.

`ios::atend` and `ios::ate` are equivalent, and either one is specified for streams that are to be positioned to the end before the first operation takes place. `ios::ate` is provided for historical purposes and compatibility with other implementations of I/O streams. Note that this bit positions the stream to the end exactly once, when the stream is opened.

`ios::append` and `ios::app` are equivalent, and either one is specified for streams that are to be positioned to the end before any and all output operations take place. `ios::app` is provided for historical purposes and compatibility with other implementations of I/O streams. Note that this bit causes the stream to be positioned to the end before each output operation, while `ios::atend` causes the stream to be positioned to the end only when first opened.

`ios::truncate` and `ios::trunc` are equivalent, and either one is specified for streams that are to be truncated to zero length before the first operation takes place. `ios::trunc` is provided for historical purposes and compatibility with other implementations of I/O streams.

`ios::nocode` is specified if the file must exist before it is opened. If the file does not exist, an error occurs.

`ios::noreplace` is specified if the file must not exist before it is opened. That is, the file must be a new file. If the file exists, an error occurs.

`ios::text` is specified if the file is to be treated as a *text* file. A text file is divided into records, and each record is terminated by a *new-line* character, usually represented as '`\n`'. The new-line character is translated into a form that is compatible with the underlying file system's concept of text files. This conversion happens automatically whenever the new-line is written to the file, and the inverse conversion (to the new-line character) happens automatically whenever the end of a record is read from the file system.

`ios::binary` is specified if the file is to be treated as a *binary* file. Binary files are streams of characters. No character has a special meaning. No grouping of characters into records is apparent to the program, although the underlying file system may cause such a grouping to occur.

The following default behaviors are defined:

If `ios::out` is specified and none of `ios::in`, `ios::append` or `ios::atend` are specified, `ios::truncate` is assumed.

If `ios::append` is specified, `ios::out` is assumed.

If `ios::truncate` is specified, `ios::out` is assumed.

If neither `ios::text` nor `ios::binary` is specified, `ios::text` is assumed.

**Synopsis:**

```
#include <iostream.h>
public:
 int ios::operator !() const;
```

**Semantics:** The operator ! public member function tests the error state in the inherited `ios` object of the `ios` object.

**Results:** The operator ! public member function returns a non-zero value if either of `ios::failbit` or `ios::badbit` bits are set in the error state in the inherited `ios` object, otherwise zero is returned.

**See Also:** `ios::bad`, `clear`, `fail`, `good`, `iostate`, `operator void *`, `rdstate`, `setstate`

## *ios::operator void \*()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 ios::operator void *() const;
```

**Semantics:** The `operator void *` public member function converts the `ios` object into a pointer to `void`. The actual pointer value returned is meaningless and intended only for comparison with `NULL` to determine the error state in the inherited `ios` object of the `ios` object.

**Results:** The `operator void *` public member function returns a `NULL` pointer if either of `ios::failbit` or `ios::badbit` bits are set in the error state in the inherited `ios` object, otherwise a non-`NULL` pointer is returned.

**See Also:** `ios::bad`, `clear`, `fail`, `good`, `iostate`, `operator !`, `rdstate`, `setstate`

**Synopsis:**

```
#include <iostream.h>
public:
 int ios::precision() const;
 int ios::precision(int prec);
```

**Semantics:** The `precision` public member function is used to query and/or set the *format precision*. The *format precision* is used to control the number of digits of precision used when formatting floating-point numbers. For scientific notation, the *format precision* describes the total number of digits before and after the decimal point, but not including the exponent. For fixed-point notation, the *format precision* describes the number of digits after the decimal point.

The first form of the `precision` public member function looks up the current *format precision*.

The second form of the `precision` public member function sets the *format precision* to `prec`.

By default, the *format precision* is six. If `prec` is specified to be less than zero, the *format precision* is set to six. Otherwise, the specified *format precision* is used. For scientific notation, a *format precision* of zero is treated as a precision of one.

**Results:** The `precision` public member function returns the previous *format precision* setting.

**See Also:** `ios::fmtflags`, manipulator `setprec`

## *ios::pword()*

---

**Synopsis:**

```
#include <iostream.h>
public:
void * &ios::pword(int index);
```

**Semantics:** The `pword` public member function creates a reference to a `void` pointer, which may be used to store and retrieve any suitable pointer value. The `index` parameter specifies which `void` pointer is to be referenced and must be obtained from a call to the `xalloc` static member function.

Note that the `iword` and `pword` public member functions return references to the same storage with a different type. Therefore, each `index` obtained from the `xalloc` static member function can be used only for an integer or a pointer, not both.

Since the `pword` public member function returns a reference and the `ios` class cannot predict how many such items will be required by a program, it should be assumed that each call to the `xalloc` static member function invalidates all previous references returned by the `pword` public member function. Therefore, the `pword` public member function should be called each time the reference is needed.

**Results:** The `pword` public member function returns a reference to a `void` pointer.

**See Also:** `ios::iword`, `xalloc`

**Synopsis:**

```
#include <iostream.h>
public:
 streambuf *ios::rdbuf() const;
```

**Semantics:** The `rdbuf` public member function looks up the pointer to the `streambuf` object which maintains the buffer associated with the `ios` object.

**Results:** The `rdbuf` public member function returns the pointer to the `streambuf` object associated with the `ios` object. If there is no associated `streambuf` object, `NULL` is returned.

## ***ios::rdstate()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 iostate ios::rdstate() const;
```

**Semantics:** The `rdstate` public member function is used to query the current value of `ios::iostate` in the `ios` object without modifying it.

**Results:** The `rdstate` public member function returns the current value of `ios::iostate`.

**See Also:** `ios::bad`, `clear`, `eof`, `fail`, `good`, `iostate`, `operator !`, `operator void *`, `setstate`

**Synopsis:**

```
#include <iostream.h>
public:
enum seek_dir {
beg, // seek from beginning
cur, // seek from current position
end // seek from end
};
typedef int seekdir;
```

**Semantics:** The type `ios::seek_dir` is a set of bits representing different methods of seeking within a stream. The `ios::seekdir` member typedef represents the same set of bits, but uses an `int` to represent the values, thereby avoiding problems made possible by the compiler's ability to use smaller types for enumerations. All uses of these bits should use the `ios::seekdir` member typedef.

The bit values defined by `ios::seekdir` member typedef are used by the member functions `seekg` and `seekp`, as well the `seekoff` and `seekpos` member functions in classes derived from the `streambuf` class.

`ios::beg` causes the seek offset to be interpreted as an offset from the beginning of the stream. The offset is specified as a positive value.

`ios::cur` causes the seek offset to be interpreted as an offset from the current position of the stream. If the offset is a negative value, the seek is towards the start of the stream. Otherwise, the seek is towards the end of the stream.

`ios::end` causes the seek offset to be interpreted as an offset from the end of the stream. The offset is specified as a negative value.

## *ios::setf()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 ios::fmtflags ios::setf(ios::fmtflags onbits);
 ios::fmtflags ios::setf(ios::fmtflags setbits,
 ios::fmtflags mask);
```

**Semantics:** The `setf` public member function is used to set bits in `ios::fmtflags` in the `ios` object.

The first form is used to turn on the bits that are on in the *onbits* parameter. ( *onbits* is or'ed into `ios::fmtflags`).

The second form is used to turn off the bits specified in the *mask* parameter and turn on the bits specified in the *setbits* parameter. This form is particularly useful for setting the bits described by the `ios::basefield`, `ios::adjustfield` and `ios::floatfield` values, where only one bit should be on at a time.

**Results:** Both forms of the `setf` public member function return the previous `ios::fmtflags` value.

**See Also:** `ios::fmtflags`, `setf`, `unsetf`, manipulator `dec`, manipulator `hex`, manipulator `oct`, manipulator `setbase`, manipulator `setiosflags`, manipulator `resetiosflags`

**Synopsis:**

```
#include <iostream.h>
protected:
void ios::setstate(int or_bits);
```

**Semantics:** The `setstate` protected member function is provided as a convenience for classes derived from the `ios` class. It turns on the error state in the inherited `ios` object bits that are set in the `or_bits` parameter, and leaves the other error state in the inherited `ios` object bits unchanged.

**Results:** The `setstate` protected member function sets the bits specified by `or_bits` in the error state in the inherited `ios` object.

**See Also:** `ios::bad`, `clear`, `eof`, `fail`, `good`, `iostate`, `operator !`, `operator void *`,  
`rdstate`

## *ios::sync\_with\_stdio()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 static void ios::sync_with_stdio();
```

**Semantics:** The `sync_with_stdio` public static member function is obsolete. It is provided for compatibility.

**Results:** The `sync_with_stdio` public static member function has no return value.

**Synopsis:**

```
#include <iostream.h>
public:
ostream *ios::tie() const;
ostream *ios::tie(ostream *ostrm);
```

**Semantics:** The `tie` public member function is used to query and/or set up a connection between the `ios` object and another stream. The connection causes the output stream specified by `ostrm` to be flushed whenever the `ios` object is about to read characters from a device or is about to write characters to an output buffer or device.

The first form of the `tie` public member function is used to query the current tie.

The second form of the `tie` public member function is used to set the tied stream to `ostrm`.

Normally, the predefined streams `cin` and `cerr` set up ties to `cout` so that any input from the terminal flushes any buffered output, and any writes to `cerr` flush `cout` before the characters are written. `cout` does not set up a tie to `cerr` because `cerr` has the flag `ios::unitbuf` set, so it flushes itself after every write operation.

**Results:** Both forms of the `tie` public member function return the previous tie value.

**See Also:** `ios::fmtflags`

## ***ios::unsetf()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 ios::fmtflags ios::unsetf(ios::fmtflags offbits);
```

**Semantics:** The `unsetf` public member function is used to turn off bits in `ios::fmtflags` that are set in the `offbits` parameter. All other bits in `ios::fmtflags` are unchanged.

**Results:** The `unsetf` public member function returns the old `ios::fmtflags` value.

**See Also:** `ios::fmtflags`, `setf`, `unsetf`, manipulator `dec`, manipulator `hex`, manipulator `oct`, manipulator `setbase`, manipulator `setiosflags`, manipulator `resetiosflags`

**Synopsis:**

```
#include <iostream.h>
public:
 int ios::width() const;
 int ios::width(int wid);
```

**Semantics:** The `width` public member function is used to query and/or set the *format width* used to format the next item. A *format width* of zero indicates that the item is to be written using exactly the number of positions required. Other values indicate that the item must occupy at least that many positions. If the formatted item is larger than the specified *format width*, the *format width* is ignored and the item is formatted using the required number of positions.

The first form of the `width` public member function is used to query the *format width* that is to be used for the next item.

The second form of the `width` public member function is used to set the *format width* to `wid` for the next item to be formatted.

After an item has been formatted, the *format width* is reset to zero. Therefore, any non-zero *format width* must be set before each item that is to be formatted.

**Results:** The `width` public member function returns the previous *format width*.

**See Also:** `ios::fmtflags`, manipulator `setw`, manipulator `setwidth`

## *ios::xalloc()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 static int ios::xalloc();
```

**Semantics:** The `xalloc` public static member function returns an index into an array of items that the program may use for any purpose. Each item can be either a `long int` or a pointer to `void`. The index can be used with the `iword` and `pword` member functions.

Because the `xalloc` public static member function manipulates `static` member data, its behavior is not tied to any one object but affects the entire class of objects. The value that is returned by the `xalloc` public static member function is valid for all objects of all classes derived from the `ios` class. No subsequent call to the `xalloc` public static member function will return the same value as a previous call.

**Results:** The `xalloc` public static member function returns an index for use with the `iword` and `pword` member functions.

**See Also:** `ios::iword`, `pword`

**Declared:** `iostream.h`

**Derived from:** `istream, ostream`

**Derived by:** `fstream, strstream`

The `iostream` class supports reading and writing of characters from and to the standard input/output devices, usually the keyboard and screen. The `iostream` class provides formatted conversion of characters to and from other types (e.g. integers and floating-point numbers). The associated `streambuf` class provides the methods for communicating with the actual device, while the `iostream` class provides the interpretation of the characters.

Generally, an `iostream` object won't be created by a program, since there is no mechanism at this level to "open" a device. No instance of an `iostream` object is created by default, since it is usually not possible to perform both input and output on the standard input/output devices. The `iostream` class is provided as a base class for other derived classes that can provide both input and output capabilities through the same object. The `fstream` and `strstream` classes are examples of classes derived from the `iostream` class.

### **Protected Member Functions**

The following protected member functions are declared:

```
iostream();
```

### **Public Member Functions**

The following public member functions are declared:

```
iostream(ios const &);
iostream(streambuf *);
virtual ~iostream();
```

### **Public Member Operators**

The following public member operators are declared:

```
iostream & operator =(streambuf *);
iostream & operator =(ios const &);
```

**See Also:** `ios, istream, ostream`

## *iostream::iostream()*

---

**Synopsis:**

```
#include <iostream.h>
protected:
 iostream::iostream();
```

**Semantics:** This form of the protected `iostream` constructor creates an `iostream` object without an attached `streambuf` object.

This form of the protected `iostream` constructor is only used implicitly by the compiler when it generates a constructor for a derived class.

**Results:** The protected `iostream` constructor produces an initialized `iostream` object. `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** [~iostream](#)

**Synopsis:**

```
#include <iostream.h>
public:
 iostream::iostream(ios const &strm);
```

**Semantics:** This form of the public `iostream` constructor creates an `iostream` object associated with the `streambuf` object currently associated with the `strm` parameter. The `iostream` object is initialized and will use the `strm` `streambuf` object for subsequent operations. `strm` will continue to use the `streambuf` object.

**Results:** The public `iostream` constructor produces an initialized `iostream` object. If there is no `streambuf` object currently associated with the `strm` parameter, `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** `~iostream`

## *iostream::iostream()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 iostream::iostream(streambuf *sb);
```

**Semantics:** This form of the public `iostream` constructor creates an `iostream` object with an attached `streambuf` object.

Since a user program usually will not create an `iostream` object, this form of the public `iostream` constructor is unlikely to be explicitly used, except in the member initializer list for the constructor of a derived class. The `sb` parameter is a pointer to a `streambuf` object, which should be connected to the source and sink of characters for the stream.

**Results:** The public `iostream` constructor produces an initialized `iostream` object. If the `sb` parameter is `NULL`, `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** [~iostream](#)

**Synopsis:**

```
#include <iostream.h>
public:
 virtual iostream::~iostream();
```

**Semantics:** The public `~iostream` destructor does not do anything explicit. The `ios` destructor is called for that portion of the `iostream` object. The call to the public `~iostream` destructor is inserted implicitly by the compiler at the point where the `iostream` object goes out of scope.

**Results:** The `iostream` object is destroyed.

**See Also:** `iostream`

## *iostream::operator =()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 iostream &iostream::operator =(streambuf *sb);
```

**Semantics:** This form of the `operator =` public member function initializes the target `iostream` object and sets up an association between the `iostream` object and the `streambuf` object specified by the `sb` parameter.

**Results:** The `operator =` public member function returns a reference to the `iostream` object that is the target of the assignment. If the `sb` parameter is `NULL`, `ios::badbit` is set in the error state in the inherited `ios` object.

**Synopsis:**

```
#include <iostream.h>
public:
 iostream &iostream::operator =(const ios &strm);
```

**Semantics:** This form of the `operator =` public member function initializes the `iostream` object and sets up an association between the `iostream` object and the `streambuf` object currently associated with the `strm` parameter.

**Results:** The `operator =` public member function returns a reference to the `iostream` object that is the target of the assignment. If there is no `streambuf` object currently associated with the `strm` parameter, `ios::badbit` is set in the error state in the inherited `ios` object.

## ***istream***

---

**Declared:** iostream.h

**Derived from:** ios

**Derived by:** iostream, ifstream, istrstream

The `istream` class supports reading characters from a class derived from `streambuf`, and provides formatted conversion of characters into other types (such as integers and floating-point numbers). The `streambuf` class provides the methods for communicating with the external device (keyboard, disk), while the `istream` class provides the interpretation of the resulting characters.

Generally, an `istream` object won't be explicitly created by a program, since there is no mechanism at this level to open a device. The only default `istream` object in a program is `cin`, which reads from standard input (usually the keyboard).

The `istream` class supports two basic concepts of input: formatted and unformatted. The overloaded operator `>>` member functions are called *extractors* and they provide the support for formatted input. The rest of the member functions deal with unformatted input, managing the state of the `ios` object and providing a friendlier interface to the associated `streambuf` object.

### **Protected Member Functions**

The following protected member functions are declared:

```
istream();
eatwhite();
```

### **Public Member Functions**

The following public member functions are declared:

```
istream(istream const &);
istream(streambuf *);
virtual ~istream();
int ipfx(int = 0);
void isfx();
int get();
istream &get(char *, int, char = '\n');
istream &get(signed char *, int, char = '\n');
istream &get(unsigned char *, int, char = '\n');
istream &get(char &);
istream &get(signed char &);
istream &get(unsigned char &);
istream &get(streambuf &, char = '\n');
istream &getline(char *, int, char = '\n');
istream &getline(signed char *, int, char = '\n');
istream &getline(unsigned char *, int, char = '\n');
istream &ignore(int = 1, int = EOF);
istream &read(char *, int);
istream &read(signed char *, int);
istream &read(unsigned char *, int);
istream &seekg(streampos);
istream &seekg(streamoff, ios::seekdir);
istream &putback(char);
streampos tellg();
int gcount() const;
```

```
int peek();
int sync();
```

### Public Member Operators

The following public member operators are declared:

```
istream &operator =(streambuf *);
istream &operator =(istream const &);
istream &operator >>(char *);
istream &operator >>(signed char *);
istream &operator >>(unsigned char *);
istream &operator >>(char &);
istream &operator >>(signed char &);
istream &operator >>(unsigned char &);
istream &operator >>(signed short &);
istream &operator >>(unsigned short &);
istream &operator >>(signed int &);
istream &operator >>(unsigned int &);
istream &operator >>(signed long &);
istream &operator >>(unsigned long &);
istream &operator >>(float &);
istream &operator >>(double &);
istream &operator >>(long double &);
istream &operator >>(streambuf &);
istream &operator >>(istream &(*)(istream &));
istream &operator >>(ios &(*)(ios &));
```

**See Also:**    `ios`, `iostream`, `ostream`

## ***istream::eatwhite()***

---

**Synopsis:**

```
#include <iostream.h>
protected:
void istream::eatwhite();
```

**Semantics:** The `eatwhite` protected member function extracts and discards whitespace characters from the `istream` object, until a non-whitespace character is found. The non-whitespace character is not extracted.

**Results:** The `eatwhite` protected member function sets `ios::eofbit` in the error state in the inherited `ios` object if end-of-file is encountered as the first character while extracting whitespace characters.

**See Also:** `istream::ignore`, `ios::fmtflags`

**Synopsis:**

```
#include <iostream.h>
public:
 int istream::gcount() const;
```

**Semantics:** The `gcount` public member function determines the number of characters extracted by the last unformatted input member function.

**Results:** The `gcount` public member function returns the number of characters extracted by the last unformatted input member function.

**See Also:** `istream::get`, `getline`, `read`

## ***istream::get()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 int istream::get();
```

**Semantics:** This form of the `get` public member function performs an unformatted read of a single character from the `istream` object.

**Results:** This form of the `get` public member function returns the character read from the `istream` object. If the `istream` object is positioned at end-of-file before the read, EOF is returned and `ios::eofbit` bit is set in the error state in the inherited `ios` object. `ios::failbit` bit is not set by this form of the `get` public member function.

**See Also:** `istream::putback`

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::get(char &ch);
 istream &istream::get(signed char &ch);
 istream &istream::get(unsigned char &ch);
```

**Semantics:** These forms of the `get` public member function perform an unformatted read of a single character from the `istream` object and store the character in the `ch` parameter.

**Results:** These forms of the `get` public member function return a reference to the `istream` object. `ios::eofbit` is set in the error state in the inherited `ios` object if the `istream` object is positioned at end-of-file before the attempt to read the character. `ios::failbit` is set in the error state in the inherited `ios` object if no character is read.

**See Also:** `istream::read`, `operator >>`

## ***istream::get()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::get(char *buf, int len,
 char delim = '\n');
 istream &istream::get(signed char *buf, int len,
 char delim = '\n');
 istream &istream::get(unsigned char *buf, int len,
 char delim = '\n');
```

**Semantics:** These forms of the `get` public member function perform an unformatted read of at most `len - 1` characters from the `istream` object and store them starting at the memory location specified by the `buf` parameter. If the character specified by the `delim` parameter is encountered in the `istream` object before `len - 1` characters have been read, the read terminates without extracting the delimiting character.

After the read terminates, whether or not an error occurred, a null character is stored in `buf` following the last character read from the `istream` object.

If the `delim` parameter is not specified, the new-line character is assumed.

**Results:** These forms of the `get` public member function return a reference to the `istream` object. If end-of-file is encountered as the first character, `ios::eofbit` is set in the error state in the inherited `ios` object. If no characters are stored into `buf`, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `istream::getline`, `read`, `operator >>`

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::get(streambuf &sb, char delim = '\n');
```

**Semantics:**

This form of the `get` public member function performs an unformatted read of characters from the `istream` object and transfers them to the `streambuf` object specified in the `sb` parameter. The transfer stops if end-of-file is encountered, the delimiting character specified in the `delim` parameter is found, or if the store into the `sb` parameter fails. If the `delim` character is found, it is not extracted from the `istream` object and is not transferred to the `sb` object.

If the `delim` parameter is not specified, the new-line character is assumed.

**Results:**

The `get` public member function returns a reference to the `istream` object. `ios::failbit` is set in the error state in the inherited `ios` object if the store into the `streambuf` object fails.

**See Also:**

`istream::getline`, `read`, `operator >>`

## ***istream::getline()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::getline(char *buf, int len,
 char delim = '\n');
 istream &istream::getline(signed char *buf, int len,
 char delim = '\n');
 istream &istream::getline(unsigned char *buf, int len,
 char delim = '\n');
```

**Semantics:**

The `getline` public member function performs an unformatted read of at most *len* - 1 characters from the `istream` object and stores them starting at the memory location specified by the `buf` parameter. If the delimiting character, specified by the `delim` parameter, is encountered in the `istream` object before *len* - 1 characters have been read, the read terminates after extracting the `delim` character.

If *len* - 1 characters have been read and the next character is the `delim` character, it is not extracted.

After the read terminates, whether or not an error occurred, a null character is stored in the buffer following the last character read from the `istream` object.

If the `delim` parameter is not specified, the new-line character is assumed.

**Results:**

The `getline` public member function returns a reference to the `istream` object. If end-of-file is encountered as the first character, `ios::eofbit` is set in the error state in the inherited `ios` object. If end-of-file is encountered before *len* characters are transferred or the `delim` character is reached, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:**

`istream::get`, `read`, `operator >>`

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::ignore(int num = 1, int delim = EOF);
```

**Semantics:**

The `ignore` public member function extracts and discards up to *num* characters from the `istream` object. If the *num* parameter is not specified, the `ignore` public member function extracts and discards one character. If the *delim* parameter is not EOF and it is encountered before *num* characters have been extracted, the extraction ceases after discarding the delimiting character. The extraction stops if end-of-file is encountered.

If the *num* parameter is specified as a negative number, no limit is imposed on the number of characters extracted and discarded. The operation continues until the delimiting character is found and discarded, or until end-of-file. This behavior is a WATCOM extension.

**Results:**

The `ignore` public member function returns a reference to the `istream` object. If end-of-file is encountered as the first character, `ios::eofbit` is set in the error state in the inherited `ios` object.

**See Also:**

`istream::eatwhite`

## ***istream::ipfx()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 int istream::ipfx(int noskipws = 0);
```

**Semantics:** The `ipfx` public member function is a prefix function executed before each of the formatted and unformatted read operations. If any bits are set in `ios::iostate`, the `ipfx` public member function immediately returns 0, indicating that the prefix function failed. Failure in the prefix function causes the input operation to fail.

If the `noskipws` parameter is 0 or unspecified and the `ios::skipws` bit is on in `ios::fmtflags`, whitespace characters are discarded and the `istream` object is positioned so that the next character read is the first character after the discarded whitespace. Otherwise, no whitespace skipping takes place.

The formatted input functions that read specific types of objects (such as integers and floating-point numbers) call the `ipfx` public member function with the `noskipws` parameter set to zero, allowing leading whitespaces to be discarded if the `ios::skipws` bit is on in `ios::fmtflags`. The unformatted input functions that read characters without interpretation call the `ipfx` public member function with a the `noskipws` parameter set to 1 so that no whitespace characters are discarded.

If the `istream` object is tied to an output stream, the output stream is flushed.

**Results:** If the `istream` object is not in an error state in the inherited `ios` object when the above processing is completed, the `ipfx` public member function returns a non-zero value to indicate success. Otherwise, zero is returned to indicate failure.

**See Also:** `istream::isfx`

**Synopsis:**

```
#include <iostream.h>
public:
void istream::isfx();
```

**Semantics:** The `isfx` public member function is a suffix function executed just before the end of each of the formatted and unformatted read operations.

As currently implemented, the `isfx` public member function does not do anything.

**See Also:** `istream::ipfx`

## *istream::istream()*

---

**Synopsis:**

```
#include <iostream.h>
protected:
istream::istream();
```

**Semantics:** This form of the protected *istream* constructor creates an *istream* object without an associated *streambuf* object.

This form of the protected *istream* constructor is only used implicitly by the compiler when it generates a constructor for a derived class.

**Results:** This form of the protected *istream* constructor creates an initialized *istream* object. *ios::badbit* is set in the error state in the inherited *ios* object.

**See Also:** [~istream](#)

**Synopsis:**

```
#include <iostream.h>
public:
 istream::istream(istream const &istrm);
```

**Semantics:** This form of the public `istream` constructor creates an `istream` object associated with the `streambuf` object currently associated with the `istrm` parameter. The `istream` object is initialized and will use the `istrm` `streambuf` object for subsequent operations. `istrm` will continue to use the `streambuf` object.

**Results:** This form of the public `istream` constructor creates an initialized `istream` object. If there is no `streambuf` object currently associated with the `istrm` parameter, `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** `~istream`

## ***istream::istream()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream::istream(streambuf *sb);
```

**Semantics:** This form of the public `istream` constructor creates an `istream` object with an associated `streambuf` object specified by the `sb` parameter.

This function is likely to be used for the creation of an `istream` object that is associated with the same `streambuf` object as another `istream` object.

**Results:** This form of the public `istream` constructor creates an initialized `istream` object. If the `sb` parameter is NULL, `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** `~istream`

**Synopsis:**

```
#include <iostream.h>
public:
 virtual istream::~istream();
```

**Semantics:** The public virtual `~istream` destructor does not do anything explicit. The `ios` destructor is called for that portion of the `istream` object. The call to the public virtual `~istream` destructor is inserted implicitly by the compiler at the point where the `istream` object goes out of scope.

**Results:** The `istream` object is destroyed.

**See Also:** `istream`

## *istream::operator =()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator =(streambuf *sb);
```

**Semantics:** This form of the `operator =` public member function is used to associate a `streambuf` object, specified by the `sb` parameter, with an existing `istream` object. The `istream` object is initialized and will use the specified `streambuf` object for subsequent operations.

**Results:** This form of the `operator =` public member function returns a reference to the `istream` object that is the target of the assignment. If the `sb` parameter is `NULL`, `ios::badbit` is set in the error state in the inherited `ios` object.

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator =(istream const &istrm);
```

**Semantics:** This form of the `operator =` public member function is used to associate the `istream` object with the `streambuf` object currently associated with the `istrm` parameter. The `istream` object is initialized and will use the `istrm`'s `streambuf` object for subsequent operations. The `istrm` object will continue to use the `streambuf` object.

**Results:** This form of the `operator =` public member function returns a reference to the `istream` object that is the target of the assignment. If there is no `streambuf` object currently associated with the `istrm` parameter, `ios::badbit` is set in the error state in the inherited `ios` object.

## *istream::operator >>()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator >>(char *buf);
 istream &istream::operator >>(signed char *buf);
 istream &istream::operator >>(unsigned char *buf);
```

**Semantics:** These forms of the `operator >>` public member function perform a formatted read of characters from the `istream` object and place them in the buffer specified by the `buf` parameter. Characters are read until a whitespace character is found or the maximum size has been read. If a whitespace character is found, it is not transferred to the buffer and remains in the `istream` object.

If a non-zero *format width* has been specified, it is interpreted as the maximum number of characters that may be placed in `buf`. No more than *format width*-1 characters are read from the `istream` object and transferred to `buf`. If *format width* is zero, characters are transferred until a whitespace character is found.

Since these forms of the `operator >>` public member function use *format width*, it is reset to zero after each use. It must be set before each input operation that requires a non-zero *format width*.

A null character is added following the last transferred character, even if the transfer fails because of an error.

**Results:** These forms of the `operator >>` public member function return a reference to the `istream` object so that further extraction operations may be specified in the same statement. If no characters are transferred to `buf`, `ios::failbit` is set in the error state in the inherited `ios` object. If the first character read yielded end-of-file, `ios::eofbit` is set in the error state in the inherited `ios` object.

**See Also:** `istream::get`, `getline`, `read`

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator >>(char &ch);
 istream &istream::operator >>(signed char &ch);
 istream &istream::operator >>(unsigned char &ch);
```

**Semantics:** These forms of the `operator >>` public member function perform a formatted read of a single character from the `istream` object and place it in the `ch` parameter.

**Results:** These forms of the `operator >>` public member function return a reference to the `istream` object so that further extraction operations may be specified in the same statement. If the character read yielded end-of-file, `ios::eofbit` is set in the error state in the inherited `ios` object.

**See Also:** `istream::get`

## *istream::operator >>()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator >>(signed int &num);
 istream &istream::operator >>(unsigned int &num);
 istream &istream::operator >>(signed long &num);
 istream &istream::operator >>(unsigned long &num);
 istream &istream::operator >>(signed short &num);
 istream &istream::operator >>(unsigned short &num);
```

**Semantics:**

These forms the `operator >>` public member function perform a formatted read of an integral value from the `istream` object and place it in the `num` parameter.

The number may be preceded by a + or - sign.

If `ios::dec` is the only bit set in the `ios::basefield` bits of `ios::fmtflags`, the number is interpreted as a decimal (base 10) integer, composed of the digits 0123456789.

If `ios::oct` is the only bit set in the `ios::basefield` bits of `ios::fmtflags`, the number is interpreted as an octal (base 8) integer, composed of the digits 01234567.

If `ios::hex` is the only bit set in the `ios::basefield` bits of `ios::fmtflags`, the number is interpreted as a hexadecimal (base 16) integer, composed of the digits 0123456789 and the letters abcdef or ABCDEF.

If no bits are set in the `ios::basefield` bits of `ios::fmtflags`, the operator looks for a prefix to determine the base of the number. If the first two characters are 0x or 0X, the number is interpreted as a hexadecimal number. If the first character is a 0 (and the second is not an x or X), the number is interpreted as an octal integer. Otherwise, no prefix is expected and the number is interpreted as a decimal integer.

If more than one bit is set in the `ios::basefield` bits of `ios::fmtflags`, the number is interpreted as a decimal integer.

**Results:**

These forms of the `operator >>` public member function return a reference to the `istream` object so that further extraction operations may be specified in the same statement. If end-of-file is encountered as the first character, `ios::eofbit` is set in the error state in the inherited `ios` object. If an overflow occurs while converting to the required integer type, the `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:**

`ios::fmtflags`

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator >>(float &num);
 istream &istream::operator >>(double &num);
 istream &istream::operator >>(long double &num);
```

**Semantics:** These forms of the `operator >>` public member function perform a formatted read of a floating-point value from the `istream` object and place it in the `num` parameter.

The floating-point value may be specified in any form that is acceptable to the C++ compiler.

**Results:** These forms of the `operator >>` public member function return a reference to the `istream` object so that further extraction operations may be specified in the same statement. If end-of-file is encountered as the first character, `ios::eofbit` is set in the error state in the inherited `ios` object. If an overflow occurs while converting to the required type, the `ios::failbit` is set in the error state in the inherited `ios` object.

## *istream::operator >>()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator >>(streambuf &sb);
```

**Semantics:** This form of the `operator >>` public member function transfers all the characters from the `istream` object into the `sb` parameter. Reading continues until end-of-file is encountered.

**Results:** This form of the `operator >>` public member function return a reference to the `istream` object so that further extraction operations may be specified in the same statement.

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::operator >>(istream &(*fn)(istream &));
 istream &istream::operator >>(ios &(*fn)(ios &));
```

**Semantics:** These forms of the `operator >>` public member function are used to implement the non-parameterized manipulators for the `istream` class. The function specified by the `fn` parameter is called with the `istream` object as its parameter.

**Results:** These forms of the `operator >>` public member function return a reference to the `istream` object so that further extraction operations may be specified in the same statement.

## *istream::peek()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 int istream::peek();
```

**Semantics:** The `peek` public member function looks up the next character to be extracted from the `istream` object, without extracting the character.

**Results:** The `peek` public member function returns the next character to be extracted from the `istream` object. If the `istream` object is positioned at end-of-file, EOF is returned.

**See Also:** `istream::get`

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::putback(char ch);
```

**Semantics:** The putback public member function attempts to put the extracted character specified by the *ch* parameter back into the *istream* object. The *ch* character must be the same as the character before the current position of the *istream* object, usually the last character extracted from the stream. If it is not the same character, the result of the next character extraction is undefined.

The number of characters that can be put back is defined by the *istream* object, but is usually at least 4. Depending on the status of the buffers used for input, it may be possible to put back more than 4 characters.

**Results:** The putback public member function returns a reference to the *istream* object. If the putback public member function is unable to put back the *ch* parameter, *ios::failbit* is set in the error state in the inherited *ios* object.

**See Also:** *istream::get*

## ***istream::read()***

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::read(char *buf, int len);
 istream &istream::read(signed char *buf, int len);
 istream &istream::read(unsigned char *buf, int len);
```

**Semantics:** The `read` public member function performs an unformatted read of at most *len* characters from the `istream` object and stores them in the memory locations starting at *buf*. If end-of-file is encountered before *len* characters have been transferred, the transfer stops and `ios::failbit` is set in the error state in the inherited `ios` object.

The number of characters extracted can be determined with the `gcount` member function.

**Results:** The `read` public member function returns a reference to the `istream` object. If end-of-file is encountered as the first character, `ios::eofbit` is set in the error state in the inherited `ios` object. If end-of-file is encountered before *len* characters are transferred, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `istream::gcount`, `get`, `getline`

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::seekg(streampos pos);
```

**Semantics:** The `seekg` public member function positions the `istream` object to the position specified by the `pos` parameter so that the next input operation commences from that position.

**Results:** The `seekg` public member function returns a reference to the `istream` object. If the seek operation fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `istream::tellg`, `ostream::tellp`, `ostream::seekp`

## *istream::seekg()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 istream &istream::seekg(streamoff offset, ios::seekdir dir);
```

**Semantics:** The `seekg` public member function positions the `istream` object to the specified position so that the next input operation commences from that position.

The `dir` parameter may be `ios::beg`, `ios::cur`, or `ios::end` and is interpreted in conjunction with the `offset` parameter as follows:

`ios::beg` the `offset` is relative to the start and should be a positive value.  
`ios::cur` the `offset` is relative to the current position and may be positive  
    (seek towards end) or negative (seek towards start).  
`ios::end` the `offset` is relative to the end and should be a negative value.

If the `dir` parameter has any other value, or the `offset` parameter does not have an appropriate sign, the `seekg` public member function fails.

**Results:** The `seekg` public member function returns a reference to the `istream` object. If the seek operation fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `ostream::tellp`, `ostream::seekp`  
`istream::telli`

**Synopsis:**

```
#include <iostream.h>
public:
 int istream::sync();
```

**Semantics:** The `sync` public member function synchronizes the input buffer and the `istream` object with whatever source of characters is being used. The `sync` public member function uses the `streambuf` class's `sync` virtual member function to carry out the synchronization. The specific behavior is dependent on what type of `streambuf` derived object is associated with the `istream` object.

**Results:** The `sync` public member function returns `__NOT_EOF` on success, otherwise `EOF` is returned.

## ***istream::tellg()***

---

**Synopsis:**

```
#include <iostream.h>
public:
streampos istream::tellg();
```

**Semantics:** The `tellg` public member function determines the position in the `istream` object of the next character available for reading. The first character in an `istream` object is at offset zero.

**Results:** The `tellg` public member function returns the position of the next character available for reading.

**See Also:** `ostream::tellp`, `ostream::seekp`  
`istream::seekg`

**Declared:** strstrea.h

**Derived from:** strstreambase, istream

The *istrstream* class is used to create and read from string stream objects.

The *istrstream* class provides little of its own functionality. Derived from the *strstreambase* and *istream* classes, its constructors and destructor provide simplified access to the appropriate equivalents in those base classes.

Of the available I/O stream classes, creating an *istrstream* object is the preferred method of performing read operations from a string stream.

### Public Member Functions

The following member functions are declared in the public interface:

```
istrstream(char *);
istrstream(signed char *);
istrstream(unsigned char *);
istrstream(char *, int);
istrstream(signed char *, int);
istrstream(unsigned char *, int);
~istrstream();
```

**See Also:** *istream*, *ostrstream*, *strstream*, *strstreambase*

## *istrstream*::*istrstream()*

---

**Synopsis:**

```
#include <strstrea.h>
public:
 istrstream::istrstream(char *str);
 istrstream::istrstream(signed char *str);
 istrstream::istrstream(unsigned char *str);
```

**Semantics:** This form of the public *istrstream* constructor creates an *istrstream* object consisting of the null terminated C string specified by the *str* parameter. The inherited *istream* member functions can be used to read from the *istrstream* object.

**Results:** This form of the public *istrstream* constructor creates an initialized *istrstream* object.

**See Also:** [~istrstream](#)

**Synopsis:**

```
#include <strstrea.h>
public:
 istrstream::istrstream(char *str, int len);
 istrstream::istrstream(signed char *str, int len);
 istrstream::istrstream(unsigned char *str, int len);
```

**Semantics:** This form of the public `istrstream` constructor creates an `istrstream` object consisting of the characters starting at `str` and ending at `str + len - 1`. The inherited `istream` member functions can be used to read from the `istrstream` object.

**Results:** This form of the public `istrstream` constructor creates an initialized `istrstream` object.

**See Also:** `~istrstream`

## *istrstream*::~*istrstream*()

---

**Synopsis:**

```
#include <strstrea.h>
public:
 istrstream::~istrstream();
```

**Semantics:** The public ~*istrstream* destructor does not do anything explicit. The call to the public ~*istrstream* destructor is inserted implicitly by the compiler at the point where the *istrstream* object goes out of scope.

**Results:** The *istrstream* object is destroyed.

**See Also:** *istrstream*

**Declared:** `iostream.h` and `iomanip.h`

Manipulators are designed to be inserted into or extracted from a stream. Manipulators come in two forms, non-parameterized and parameterized. The non-parameterized manipulators are simpler and are declared in `<iostream.h>`. The parameterized manipulators require more complexity and are declared in `<iomanip.h>`.

`<iomanip.h>` defines two macros `SMANIP_define` and `SMANIP_make` to implement parameterized manipulators. The workings of the `SMANIP_define` and `SMANIP_make` macros are disclosed in the header file and are not discussed here.

### **Non-parameterized Manipulators**

The following non-parameterized manipulators are declared in `<iostream.h>`:

```
ios &dec(ios &);
ios &hex(ios &);
ios &oct(ios &);
istream &ws(istream &);
ostream &endl(ostream &);
ostream &ends(ostream &);
ostream &flush(ostream &);
```

### **Parameterized Manipulators**

The following parameterized manipulators are declared in `<iomanip.h>`:

```
SMANIP_define(long) resetiosflags(long);
SMANIP_define(int) setbase(int);
SMANIP_define(int) setfill(int);
SMANIP_define(long) setiosflags(long);
SMANIP_define(int) setprecision(int);
SMANIP_define(int) setw(int);
SMANIP_define(int) setwidth(int);
```

## ***manipulator dec()***

---

**Synopsis:**      `#include <iostream.h>  
ios &dec( ios &strm );`

**Semantics:**    The `dec` manipulator sets the `ios::basefield` bits for decimal formatting in `ios::fmtflags` in the *strm* `ios` object.

**See Also:**      `ios::fmtflags`

**Synopsis:**    `#include <iostream.h>  
ostream &endl( ostream &ostrm );`

**Semantics:**    The `endl` manipulator writes a new-line character to the stream specified by the *ostrm* parameter and performs a flush.

**See Also:**    `ostream::flush`

## ***manipulator ends()***

---

**Synopsis:**    `#include <iostream.h>`  
              `ostream &ends( ostream &ostrm );`

**Semantics:**    The `ends` manipulator writes a null character to the stream specified by the *ostrm* parameter.

**Synopsis:**    `#include <iostream.h>  
ostream &flush( ostream &ostrm );`

**Semantics:**    The `flush` manipulator flushes the stream specified by the `ostrm` parameter. The flush is performed in the same manner as the `flush` member function.

**See Also:**    `ostream::flush`

## ***manipulator hex()***

---

**Synopsis:**     `#include <iostream.h>`  
              `ios &hex( ios &strm );`

**Semantics:**   The `hex` manipulator sets the `ios::basefield` bits for hexadecimal formatting in `ios::fmtflags` in the *strm* `ios` object.

**See Also:**      `ios::fmtflags`

**Synopsis:**    `#include <iostream.h>  
ios &oct( ios &strm );`

**Semantics:**    The `oct` manipulator sets the `ios::basefield` bits for octal formatting in `ios::fmtflags` in the *strm* `ios` object.

**See Also:**    `ios::fmtflags`

## *manipulator resetiosflags()*

---

**Synopsis:**    `#include <iomanip.h>`  
              `SMANIP_define( long ) resetiosflags( long flags )`

**Semantics:**    The `resetiosflags` manipulator turns off the bits in `ios::fmtflags` that correspond to the bits that are on in the `flags` parameter. No other bits are affected.

**See Also:**    `ios::flags`, `ios::fmtflags`, `ios::setf`, `ios::unsetf`

**Synopsis:** #include <iomanip.h>  
SMANIP\_define( int ) setbase( int base );

**Semantics:** The `setbase` manipulator sets the `ios::basefield` bits in `ios::fmtflags` to the value specified by the *base* parameter within the stream that the `setbase` manipulator is operating upon.

**See Also:** `ios::fmtflags`

## ***manipulator setfill()***

---

**Synopsis:**     `#include <iomanip.h>`  
                `SMANIP_define( int ) setfill( int fill )`

**Semantics:**   The `setfill` manipulator sets the *fill character* to the value specified by the *fill* parameter within the stream that the `setfill` manipulator is operating upon.

**See Also:**      `ios::fill`

**Synopsis:** #include <iomanip.h>  
SMANIP\_define( long ) setiosflags( long flags );

**Semantics:** The `setiosflags` manipulator turns on the bits in `ios::fmtflags` that correspond to the bits that are on in the `flags` parameter. No other bits are affected.

**See Also:** `ios::flags`, `ios::fmtflags`, `ios::setf`, `ios::unsetf`

## *manipulator setprecision()*

---

- Synopsis:**    `#include <iomanip.h>`  
              `SMANIP_define( int ) setprecision( int prec );`
- Semantics:**    The `setprecision` manipulator sets the *format precision* to the value specified by the *prec* parameter within the stream that the `setprecision` manipulator is operating upon.
- See Also:**    `ios::precision`

**Synopsis:**    `#include <iomanip.h>`  
              `SMANIP_define( int ) setw( int wid );`

**Semantics:**    The `setw` manipulator sets the *format width* to the value specified by the *wid* parameter within the stream that the `setw` manipulator is operating upon.

**See Also:**    `ios::width`, manipulator `setwidth`

## ***manipulator setwidth()***

---

**Synopsis:**      `#include <iomanip.h>`  
                  `SMANIP_define( int ) setwidth( int wid );`

**Semantics:**    The `setwidth` manipulator sets the *format width* to the value specified by the *wid* parameter within the stream that the `setwidth` manipulator is operating upon.

This function is a WATCOM extension.

**See Also:**      `ios::width`, manipulator `setw`

**Synopsis:**    `#include <iostream.h>  
istream &ws( istream &istrm );`

**Semantics:**    The ws manipulator extracts and discards whitespace characters from the *istrm* parameter, leaving the stream positioned at the next non-whitespace character.

The ws manipulator is needed particularly when the `ios::skipws` bit is not set in `ios::fmtflags` in the *istrm* object. In this case, whitespace characters must be explicitly removed from the stream, since the formatted input operations will not automatically remove them.

**See Also:**    `istream::eatwhite`, `istream::ignore`

## ***ofstream***

---

**Declared:** fstream.h

**Derived from:** fstreambase, ostream

The `ofstream` class is used to create new files or access existing files for writing. The file can be opened and closed, and write and seek operations can be performed.

The `ofstream` class provides very little of its own functionality. Derived from both the `fstreambase` and `ostream` classes, its constructors, destructor and member function provide simplified access to the appropriate equivalents in those base classes.

Of the available I/O stream classes, creating an `ofstream` object is the preferred method of accessing a file for output operations.

### **Public Member Functions**

The following public member functions are declared:

```
ofstream();
ofstream(char const *,
ios::openmode = ios::out,
int = filebuf::openprot);
ofstream(filedesc);
ofstream(filedesc, char *, int);
~ofstream();
void open(char const *,
ios::openmode = ios::out,
int = filebuf::openprot);
```

**See Also:** fstream, fstreambase, ifstream, ostream

**Synopsis:**

```
#include <fstream.h>
public:
ofstream::ofstream();
```

**Semantics:** This form of the public `ofstream` constructor creates an `ofstream` object that is not connected to a file. The `open` or `attach` member functions should be used to connect the `ofstream` object to a file.

**Results:** The public `ofstream` constructor produces an `ofstream` object that is not connected to a file.

**See Also:** `~ofstream`

## ***ofstream::ofstream()***

---

**Synopsis:**

```
#include <fstream.h>
public:
 ofstream::ofstream(const char *name,
 ios::openmode mode = ios::out,
 int prot = filebuf::openprot);
```

**Semantics:** This form of the public `ofstream` constructor creates an `ofstream` object that is connected to the file specified by the *name* parameter, using the specified *mode* and *prot* parameters. The connection is made via the C library `open` function.

**Results:** The public `ofstream` constructor produces an `ofstream` object that is connected to the file specified by *name*. If the `open` fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:** `~ofstream`, `open`, `fstreambase::close`, `openmode`, `openprot`

**Synopsis:**

```
#include <fstream.h>
public:
ofstream::ofstream(filedesc hdl);
```

**Semantics:** This form of the public `ofstream` constructor creates an `ofstream` object that is attached to the file specified by the `hdl` parameter.

**Results:** The public `ofstream` constructor produces an `ofstream` object that is attached to `hdl`. If the attach fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object.

**See Also:** `~ofstream`, `fstreambase::attach`, `fstreambase::fd`

## ***ofstream::ofstream()***

---

**Synopsis:**

```
#include <fstream.h>
public:
ofstream::ofstream(filedesc hdl, char *buf, int len);
```

**Semantics:** This form of the public `ofstream` constructor creates an `ofstream` object that is connected to the file specified by the *hdl* parameter. The buffer specified by the *buf* and *len* parameters is offered to the associated `filebuf` object via the `setbuf` member function. If the *buf* parameter is `NULL` or the *len* is less than or equal to zero, the `filebuf` is unbuffered, so that each read or write operation reads or writes a single character at a time.

**Results:** The public `ofstream` constructor produces an `ofstream` object that is attached to *hdl*. If the connection to *hdl* fails, `ios::failbit` and `ios::badbit` are set in the error state in the inherited `ios` object. If the `setbuf` fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `~ofstream`, `fstreambase::attach`, `fstreambase::fd`, `fstreambase::setbuf`

**Synopsis:**

```
#include <fstream.h>
public:
ofstream::~ofstream();
```

**Semantics:** The public `~ofstream` destructor does not do anything explicit. The call to the public `~ofstream` destructor is inserted implicitly by the compiler at the point where the `ofstream` object goes out of scope.

**Results:** The public `~ofstream` destructor destroys the `ofstream` object.

**See Also:** `ofstream`

## ***ofstream::open()***

---

**Synopsis:**

```
#include <fstream.h>
public:
void ofstream::open(const char *name,
ios::openmode mode = ios::out,
int prot = filebuf::openprot);
```

**Semantics:** The open public member function connects the `ofstream` object to the file specified by the *name* parameter, using the specified *mode* and *prot* parameters. The *mode* parameter is optional and usually is not specified unless additional bits (such as `ios::binary` or `ios::text`) are to be specified. The connection is made via the C library `open` function.

**Results:** If the open fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `ofstream`, `openmode`, `openprot`, `fstreambase::attach`, `fstreambase::close`, `fstreambase::fd`, `fstreambase::is_open`

**Declared:** iostream.h

**Derived from:** ios

**Derived by:** iostream, ofstream, ostrstream

The ostream class supports writing characters to a class derived from the streambuf class, and provides formatted conversion of types (such as integers and floating-point numbers) into characters. The class derived from the streambuf class provides the methods for communicating with the external device (screen, disk), while the ostream class provides the conversion of the types into characters.

Generally, ostream objects won't be explicitly created by a program, since there is no mechanism at this level to open a device. The only default ostream objects in a program are cout, cerr, and clog which write to the standard output and error devices (usually the screen).

The ostream class supports two basic concepts of output: formatted and unformatted. The overloaded operator << member functions are called *inserters* and they provide the support for formatted output. The rest of the member functions deal with unformatted output, managing the state of the ios object and providing a friendlier interface to the associated streambuf object.

### Protected Member Functions

The following protected member functions are declared:

```
ostream();
```

### Public Member Functions

The following public member functions are declared:

```
ostream(ostream const &);
ostream(streambuf *);
virtual ~ostream();
ostream &flush();
int opfx();
void osfx();
ostream &put(char);
ostream &put(signed char);
ostream &put(unsigned char);
ostream &seekp(streampos);
ostream &seekp(streamoff, ios::seekdir);
streampos tellp();
ostream &write(char const *, int);
ostream &write(signed char const *, int);
ostream &write(unsigned char const *, int);
```

### Public Member Operators

The following public member operators are declared:

```
ostream &operator =(streambuf *);
ostream &operator =(ostream const &);
ostream &operator <<(char);
ostream &operator <<(signed char);
ostream &operator <<(unsigned char);
```

```
ostream &operator <<(signed short);
ostream &operator <<(unsigned short);
ostream &operator <<(signed int);
ostream &operator <<(unsigned int);
ostream &operator <<(signed long);
ostream &operator <<(unsigned long);
ostream &operator <<(float);
ostream &operator <<(double);
ostream &operator <<(long double);
ostream &operator <<(void *);
ostream &operator <<(streambuf &);
ostream &operator <<(char const *);
ostream &operator <<(signed char const *);
ostream &operator <<(unsigned char const *);
ostream &operator <<(ostream &(*)(ostream &));
ostream &operator <<(ios &(*)(ios &));
```

**See Also:**    `ios`, `iostream`, `istream`

**Synopsis:**

```
#include <iostream.h>
public:
 ostream & ostream::flush();
```

**Semantics:** The `flush` public member function causes the `ostream` object's buffers to be flushed, forcing the contents to be written to the actual device connected to the `ostream` object.

**Results:** The `flush` public member function returns a reference to the `ostream` object. On failure, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `ostream::osfx`

## *ostream::operator <<()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 ostream &ostream::operator <<(char ch);
 ostream &ostream::operator <<(signed char ch);
 ostream &ostream::operator <<(unsigned char ch);
```

**Semantics:** These forms of the operator `<<` public member function write the *ch* character into the `ostream` object.

**Results:** These forms of the operator `<<` public member function return a reference to the `ostream` object so that further insertion operations may be specified in the same statement. `ios::failbit` is set in the error state in the inherited `ios` object if an error occurs.

**See Also:** `ostream::put`

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::operator <<(char const *str);
ostream &ostream::operator <<(signed char const *str);
ostream &ostream::operator <<(unsigned char const *str);
```

**Semantics:** These forms of the `operator <<` public member function perform a formatted write of the contents of the C string specified by the *str* parameter to the `ostream` object. The characters from *str* are transferred up to, but not including the terminating null character.

**Results:** These forms of the `operator <<` public member function return a reference to the `ostream` object so that further insertion operations may be specified in the same statement. `ios::failbit` is set in the error state in the inherited `ios` object if an error occurs.

## *ostream::operator <<()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 ostream &ostream::operator << (signed int num);
 ostream &ostream::operator << (unsigned int num);
 ostream &ostream::operator << (signed long num);
 ostream &ostream::operator << (unsigned long num);
 ostream &ostream::operator << (signed short num);
 ostream &ostream::operator << (unsigned short num);
```

**Semantics:**

These forms of the operator `<<` public member function perform a formatted write of the integral value specified by the *num* parameter to the *ostream* object. The integer value is converted to a string of characters which are written to the *ostream* object. *num* is converted to a base representation depending on the setting of the `ios::basefield` bits in `ios::fmtflags`. If the `ios::oct` bit is the only bit on, the conversion is to an octal (base 8) representation. If the `ios::hex` bit is the only bit on, the conversion is to a hexadecimal (base 16) representation. Otherwise, the conversion is to a decimal (base 10) representation.

For decimal conversions only, a sign may be written in front of the number. If the number is negative, a `-` minus sign is written. If the number is positive and the `ios::showpos` bit is on in `ios::fmtflags`, a `+` plus sign is written. No sign is written for a value of zero.

If the `ios::showbase` bit is on in `ios::fmtflags`, and the conversion is to octal or hexadecimal, the base indicator is written next. The base indicator for a conversion to octal is a zero. The base indicator for a conversion to hexadecimal is `0x` or `0X`, depending on the setting of the `ios::uppercase` bit in `ios::fmtflags`.

If the value being written is zero, the conversion is to octal, and the `ios::showbase` bit is on, nothing further is written since a single zero is sufficient.

The value of *num* is then converted to characters. For conversions to decimal, the magnitude of the number is converted to a string of decimal digits `0123456789`. For conversions to octal, the number is treated as an unsigned quantity and converted to a string of octal digits `01234567`. For conversions to hexadecimal, the number is treated as an unsigned quantity and converted to a string of hexadecimal digits `0123456789` and the letters `abcdef` or `ABCDEF`, depending on the setting of the `ios::uppercase` in `ios::fmtflags`. The string resulting from the conversion is then written to the *ostream* object.

If the `ios::internal` bit is set in `ios::fmtflags` and padding is required, the padding characters are written after the sign and/or base indicator (if present) and before the digits.

**Results:**

These forms of the operator `<<` public member function return a reference to the *ostream* object so that further insertion operations may be specified in the same statement. `ios::failbit` is set in the error state in the inherited *ios* object if an error occurs.

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::operator <<(float num);
ostream &ostream::operator <<(double num);
ostream &ostream::operator <<(long double num);
```

**Semantics:**

These forms of the operator `<<` public member function perform a formatted write of the floating-point value specified by the *num* parameter to the *ostream* object. The number is converted to either scientific (exponential) form or fixed-point form, depending on the setting of the *ios::floatfield* bits in *ios::fmtflags*. If *ios::scientific* is the only bit set, the conversion is to scientific form. If *ios::fixed* is the only bit set, the conversion is to fixed-point form. Otherwise (neither or both bits set), the value of the number determines the conversion used. If the exponent is less than -4 or is greater than or equal to the *format precision*, the scientific form is used. Otherwise, the fixed-point form is used.

Scientific form consists of a minus sign (for negative numbers), one digit, a decimal point, *format precision*-1 digits, an e or E (depending on the setting of the *ios::uppercase* bit), a minus sign (for negative exponents) or a plus sign (for zero or positive exponents), and two or three digits for the exponent. The digit before the decimal is not zero, unless the number is zero. If the *format precision* is zero (or one), no digits are written following the decimal point.

Fixed-point form consists of a minus sign (for negative numbers), one or more digits, a decimal point, and *format precision* digits.

If the *ios::showpoint* bit is not set in *ios::fmtflags*, trailing zeroes are trimmed after the decimal point (and before the exponent for scientific form), and if no digits remain after the decimal point, the decimal point is discarded as well.

If the *ios::internal* bit is set in *ios::fmtflags* and padding is required, the padding characters are written after the sign (if present) and before the digits.

**Results:**

These forms of the operator `<<` public member function return a reference to the *ostream* object so that further insertion operations may be specified in the same statement. *ios::failbit* is set in the error state in the inherited *ios* object if an error occurs.

## *ostream::operator <<()*

---

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::operator <<(void *ptr);
```

**Semantics:** This form of the `operator <<` public member function performs a formatted write of the pointer value specified by the `ptr` parameter to the `ostream` object. The `ptr` parameter is converted to an implementation-defined string of characters and written to the `ostream` object. With the Open Watcom C++ implementation, the string starts with `0x` or `0X` (depending on the setting of the `ios::uppercase` bit), followed by 4 hexadecimal digits for 16-bit pointers and 8 hexadecimal digits for 32-bit pointers. Leading zeroes are added to ensure the correct number of digits are written. For far pointers, 4 additional hexadecimal digits and a colon are inserted immediately after the `0x` prefix.

**Results:** This form of the `operator <<` public member function returns a reference to the `ostream` object so that further insertion operations may be specified in the same statement. `ios::failbit` is set in the error state in the inherited `ios` object if an error occurs during the write.

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::operator <<(streambuf &sb);
```

**Semantics:** This form of the `operator <<` public member function transfers the contents of the *sb* `streambuf` object to the `ostream` object. Reading from the `streambuf` object stops when the read fails. No padding with the *fill character* takes place on output to the `ostream` object.

**Results:** This form of the `operator <<` public member function returns a reference to the `ostream` object so that further insertion operations may be specified in the same statement. `ios::failbit` is set in the error state in the inherited `ios` object if an error occurs.

## *ostream::operator <<()*

---

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::operator <<(ostream &(*fn)(ostream &));
ostream &ostream::operator <<(ios &(*fn)(ios &));
```

**Semantics:** These forms of the `operator <<` public member function are used to implement the non-parameterized manipulators for the `ostream` class. The function specified by the *fn* parameter is called with the `ostream` object as its parameter.

**Results:** These forms of the `operator <<` public member function return a reference to the `ostream` object so that further insertions operations may be specified in the same statement.

**Synopsis:**

```
#include <iostream.h>
public:
ostream & ostream::operator =(streambuf *sb);
```

**Semantics:** This form of the `operator =` public member function is used to associate a `streambuf` object, specified by the `sb` parameter, with an existing `ostream` object. The `ostream` object is initialized and will use the specified `streambuf` object for subsequent operations.

**Results:** This form of the `operator =` public member function returns a reference to the `ostream` object that is the target of the assignment. If the `sb` parameter is `NULL`, `ios::badbit` is set in the error state in the inherited `ios` object.

## *ostream::operator =()*

---

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::operator =(const ostream &ostrm);
```

**Semantics:** This form of the `operator =` public member function is used to associate the `ostream` object with the `streambuf` object currently associated with the `ostrm` parameter. The `ostream` object is initialized and will use the `ostrm`'s `streambuf` object for subsequent operations. The `ostrm` object will continue to use the `streambuf` object.

**Results:** This form of the `operator =` public member function returns a reference to the `ostream` object that is the target of the assignment. If there is no `streambuf` object currently associated with the `ostrm` parameter, `ios::badbit` is set in the error state in the inherited `ios` object.

**Synopsis:**

```
#include <iostream.h>
public:
 int ostream::opfx();
```

**Semantics:** If `opfx` public member function is a prefix function executed before each of the formatted and unformatted output operations. If any bits are set in `ios::iostate`, the `opfx` public member function immediately returns zero, indicating that the prefix function failed. Failure in the prefix function causes the output operation to fail.

If the `ostream` object is tied to another `ostream` object, the other `ostream` object is flushed.

**Results:** The `opfx` public member function returns a non-zero value on success, otherwise zero is returned.

**See Also:** `ostream::osfx`, `flush`, `ios::tie`

## *ostream::osfx()*

---

**Synopsis:**

```
#include <iostream.h>
public:
void ostream::osfx();
```

**Semantics:** The `osfx` public member function is a suffix function executed at the end of each of the formatted and unformatted output operations.

If the `ios::unitbuf` bit is set in `ios::fmtflags`, the `flush` member function is called. If the `ios::stdio` bit is set in `ios::fmtflags`, the C library `fflush` function is invoked on the `stdout` and `stderr` file streams.

**See Also:** `ostream::osfx`, `flush`

**Synopsis:**

```
#include <iostream.h>
protected:
ostream::ostream();
```

**Semantics:** This form of the protected `ostream` constructor creates an `ostream` object without an attached `streambuf` object.

This form of the protected `ostream` constructor is only used implicitly by the compiler when it generates a constructor for a derived class.

**Results:** This form of the protected `ostream` constructor creates an initialized `ostream` object. `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** `~ostream`

## *ostream::ostream()*

---

**Synopsis:**

```
#include <iostream.h>
public:
ostream::ostream(ostream const &ostrm);
```

**Semantics:** This form of the public `ostream` constructor creates an `ostream` object associated with the `streambuf` object currently associated with the `ostrm` parameter. The `ostream` object is initialized and will use the `ostrm`'s `streambuf` object for subsequent operations. The `ostrm` object will continue to use the `streambuf` object.

**Results:** This form of the public `ostream` constructor creates an initialized `ostream` object. If there is no `streambuf` object currently associated with the `ostrm` parameter, `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** `~ostream`

**Synopsis:**

```
#include <iostream.h>
public:
ostream::ostream(streambuf *sb);
```

**Semantics:** This form of the public `ostream` constructor creates an `ostream` object with an associated `streambuf` object specified by the `sb` parameter.

This function is likely to be used for the creation of an `ostream` object that is associated with the same `streambuf` object as another `ostream` object.

**Results:** This form of the public `ostream` constructor creates an initialized `ostream` object. If the `sb` parameter is NULL, `ios::badbit` is set in the error state in the inherited `ios` object.

**See Also:** `~ostream`

## *ostream::~ostream()*

---

**Synopsis:**

```
#include <iostream.h>
public:
 virtual ostream::~ostream();
```

**Semantics:** The public virtual `~ostream` destructor does not do anything explicit. The `ios` destructor is called for that portion of the `ostream` object. The call to the public virtual `~ostream` destructor is inserted implicitly by the compiler at the point where the `ostream` object goes out of scope.

**Results:** The `ostream` object is destroyed.

**See Also:** `ostream`

**Synopsis:**

```
#include <iostream.h>
public:
 ostream &ostream::put(char ch);
 ostream &ostream::put(signed char ch);
 ostream &ostream::put(unsigned char ch);
```

**Semantics:** These forms of the `put` public member function write the `ch` character to the `ostream` object.

**Results:** These forms of the `put` public member function return a reference to the `ostream` object. If an error occurs, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `ostream::operator <<, write`

## ***ostream::seekp()***

---

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::seekp(streampos pos);
```

**Semantics:** This form of the `seekp` public member function positions the `ostream` object to the position specified by the `pos` parameter so that the next output operation commences from that position.

The `pos` value is an absolute position within the stream. It may be obtained via a call to the `tellp` member function.

**Results:** This form of the `seekp` public member function returns a reference to the `ostream` object. If the seek operation fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `ostream::tellp`, `istream::tellg`, `istream::seekg`

**Synopsis:**

```
#include <iostream.h>
public:
ostream & ostream::seekp(streamoff offset, ios::seekdir dir);
```

**Semantics:** This form of the `seekp` public member function positions the `ostream` object to the specified position so that the next output operation commences from that position.

The `dir` parameter may be `ios::beg`, `ios::cur`, or `ios::end` and is interpreted in conjunction with the `offset` parameter as follows:

`ios::beg` the `offset` is relative to the start and should be a positive value.  
`ios::cur` the `offset` is relative to the current position and may be positive  
    (seek towards end) or negative (seek towards start).  
`ios::end` the `offset` is relative to the end and should be a negative value.

If the `dir` parameter has any other value, or the `offset` parameter does not have an appropriate sign, the `seekp` public member function fails.

**Results:** This form of the `seekp` public member function returns a reference to the `ostream` object. If the seek operation fails, `ios::failbit` is set in the error state in the inherited `ios` object.

**See Also:** `ostream::tellp`, `istream::tellg`, `istream::seekg`

## *ostream::tellp()*

---

**Synopsis:**

```
#include <iostream.h>
public:
streampos ostream::tellp();
```

**Semantics:** The `tellp` public member function returns the position in the `ostream` object at which the next character will be written. The first character in an `ostream` object is at offset zero.

**Results:** The `tellp` public member function returns the position in the `ostream` object at which the next character will be written.

**See Also:** `ostream::seekp`, `istream::tellg`, `istream::seekg`

**Synopsis:**

```
#include <iostream.h>
public:
ostream &ostream::write(char const *buf, int len);
ostream &ostream::write(signed char const *buf, int len);
ostream &ostream::write(unsigned char const *buf, int len);
```

**Semantics:** The `write` public member function performs an unformatted write of the characters specified by the `buf` and `len` parameters into the `ostream` object.

**Results:** These member functions return a reference to the `ostream` object. If an error occurs, `ios::failbit` is set in the error state in the inherited `ios` object.

## ***ostrstream***

---

**Declared:** strstrea.h

**Derived from:** strstreambase, ostream

The `ostrstream` class is used to create and write to string stream objects.

The `ostrstream` class provides little of its own functionality. Derived from the `strstreambase` and `ostream` classes, its constructors and destructor provide simplified access to the appropriate equivalents in those base classes. The member functions provide specialized access to the string stream object.

Of the available I/O stream classes, creating an `ostrstream` object is the preferred method of performing write operations to a string stream.

### **Public Member Functions**

The following member functions are declared in the public interface:

```
ostrstream();
ostrstream(char *, int, ios::openmode = ios::out);
ostrstream(signed char *, int, ios::openmode = ios::out);
ostrstream(unsigned char *, int, ios::openmode = ios::out);
~ostrstream();
int pcount() const;
char *str();
```

**See Also:** istrstream, ostream, ostrstream, strstreambase

**Synopsis:**

```
#include <strstrea.h>
public:
ostrstream::ostrstream();
```

**Semantics:** This form of the public `ostrstream` constructor creates an empty `ostrstream` object. Dynamic allocation is used. The inherited stream member functions can be used to access the `ostrstream` object.

**Results:** This form of the public `ostrstream` constructor creates an initialized, empty `ostrstream` object.

**See Also:** `~ostrstream`

## *ostrstream::ostrstream()*

---

**Synopsis:**

```
#include <strstrea.h>
public:
 ostrstream::ostrstream(char *str,
 int len,
 ios::openmode mode = ios::out);
 ostrstream::ostrstream(signed char *str,
 int len,
 ios::openmode mode = ios::out);
 ostrstream::ostrstream(unsigned char *str,
 int len,
 ios::openmode mode = ios::out);
```

**Semantics:** These forms of the public `ostrstream` constructor create an initialized `ostrstream` object. Dynamic allocation is not used. The buffer is specified by the `str` and `len` parameters. If the `ios::append` or `ios::atend` bits are set in the `mode` parameter, the `str` parameter is assumed to contain a C string terminated by a null character, and writing commences at the null character. Otherwise, writing commences at `str`.

**Results:** This form of the public `ostrstream` constructor creates an initialized `ostrstream` object.

**See Also:** `~ostrstream`

**Synopsis:**

```
#include <strstrea.h>
public:
ostrstream::~ostrstream();
```

**Semantics:** The public `~ostrstream` destructor does not do anything explicit. The call to the public `~ostrstream` destructor is inserted implicitly by the compiler at the point where the `ostrstream` object goes out of scope.

**Results:** The `ostrstream` object is destroyed.

**See Also:** `ostrstream`

## *ostrstream::pcount()*

---

**Synopsis:**

```
#include <strstrea.h>
public:
 int ostrstream::pcount() const;
```

**Semantics:** The pcount public member function computes the number of characters that have been written to the `ostrstream` object. This value is particularly useful if the `ostrstream` object does not contain a C string (terminated by a null character), so that the number of characters cannot be determined with the C library `strlen` function. If the `ostrstream` object was created by appending to a C string in a static buffer, the length of the original string is included in the character count.

**Results:** The pcount public member function returns the number of characters contained in the `ostrstream` object.

**Synopsis:**

```
#include <strstrea.h>
public:
char *ostrstream::str();
```

**Semantics:** The `str` public member function creates a pointer to the buffer being used by the `ostrstream` object. If the `ostrstream` object was created without dynamic allocation (static mode), the pointer is the same as the buffer pointer passed in the constructor.

For `ostrstream` objects using dynamic allocation, the `str` public member function makes an implicit call to the `strstreibuf::freeze` member function. If nothing has been written to the `ostrstream` object, the returned pointer will be `NULL`.

Note that the buffer does not necessarily end with a null character. If the pointer returned by the `str` public member function is to be interpreted as a C string, it is the program's responsibility to ensure that the null character is present.

**Results:** The `str` public member function returns a pointer to the buffer being used by the `ostrstream` object

## ***stdiobuf***

---

**Declared:** stdiobuf.h

**Derived from:** streambuf

The `stdiobuf` class specializes the `streambuf` class and is used to implement the standard input/output buffering required for the `cin`, `cout`, `cerr` and `clog` predefined objects.

The `stdiobuf` class behaves in a similar way to the `filebuf` class, but does not need to switch between the *get area* and *put area*, since no `stdiobuf` object can be created for both reading and writing. When the *get area* is empty and a read is done, the `underflow` virtual member function reads more characters and fills the *get area* again. When the *put area* is full and a write is done, the `overflow` virtual member function writes the characters and makes the *put area* empty again.

C++ programmers who wish to use the standard input/output streams without deriving new objects do not need to explicitly create or use a `stdiobuf` object.

### **Public Member Functions**

The following member functions are declared in the public interface:

```
stdiobuf();
stdiobuf(FILE *);
~stdiobuf();
virtual int overflow(int = EOF);
virtual int underflow();
virtual int sync();
```

**See Also:** streambuf, ios

**Synopsis:**

```
#include <stdiobuf.h>
public:
 virtual int stdiobuf::overflow(int ch = EOF);
```

**Semantics:** The `overflow` public virtual member function provides the output communication to the standard output and standard error devices to which the `stdiobuf` object is connected. Member functions in the `streambuf` class call the `overflow` public virtual member function for the derived class when the *put area* is full.

The `overflow` public virtual member function performs the following steps:

1. If no buffer is present, a buffer is allocated with the `streambuf::allocate` member function, which may call the `doallocate` virtual member function. The *put area* is then set up. If, after calling `streambuf::allocate`, no buffer is present, the `stdiobuf` object is unbuffered and *ch* (if not EOF) is written directly to the file without buffering, and no further action is taken.
2. If the *get area* is present, it is flushed with a call to the `sync` virtual member function. Note that the *get area* won't be present if a buffer was set up in step 1.
3. If *ch* is not EOF, it is added to the *put area*, if possible.
4. Any characters in the *put area* are written to the file.
5. The *put area* pointers are updated to reflect the new state of the *put area*. If the write did not complete, the unwritten portion of the *put area* is still present. If the *put area* was full before the write, *ch* (if not EOF) is placed at the start of the *put area*. Otherwise, the *put area* is empty.

**Results:** The `overflow` public virtual member function returns `__NOT_EOF` on success, otherwise EOF is returned.

**See Also:** `stdiobuf::underflow`, `streambuf::overflow`

## ***stdiobuf::stdiobuf()***

---

**Synopsis:**

```
#include <stdiobuf.h>
public:
 stdiobuf::stdiobuf();
```

**Semantics:** This form of the public `stdiobuf` constructor creates a `stdiobuf` object that is initialized but not yet connected to a file.

**Results:** This form of the public `stdiobuf` constructor creates a `stdiobuf` object.

**See Also:** `~stdiobuf`

**Synopsis:**

```
#include <stdiobuf.h>
public:
 stdiobuf::stdiobuf(FILE *fptr);
```

**Semantics:** This form of the public `stdiobuf` constructor creates a `stdiobuf` object that is initialized and connected to a C library `FILE` stream. Usually, one of `stdin`, `stdout` or `stderr` is specified for the `fptr` parameter.

**Results:** This form of the public `stdiobuf` constructor creates a `stdiobuf` object that is initialized and connected to a C library `FILE` stream.

**See Also:** `~stdiobuf`

## ***stdiobuf::~stdiobuf()***

---

**Synopsis:**

```
#include <stdiobuf.h>
public:
 stdiobuf::~stdiobuf();
```

**Semantics:** The public ~stdiobuf destructor does not do anything explicit. The streambuf destructor is called for that portion of the stdiobuf object. The call to the public ~stdiobuf destructor is inserted implicitly by the compiler at the point where the stdiobuf object goes out of scope.

**Results:** The stdiobuf object is destroyed.

**See Also:** stdiobuf

**Synopsis:**

```
#include <stdiobuf.h>
public:
 virtual int stdiobuf::sync();
```

**Semantics:** The `sync` public virtual member function synchronizes the `stdiobuf` object with the associated device. If the *put area* contains characters, it is flushed. If the *get area* contains buffered characters, the `sync` public virtual member function fails.

**Results:** The `sync` public virtual member function returns `__NOT_EOF` on success, otherwise, `EOF` is returned.

**See Also:** `streambuf::sync`

## ***stdiobuf::underflow()***

---

**Synopsis:**

```
#include <stdiobuf.h>
public:
 virtual int stdiobuf::underflow();
```

**Semantics:** The `underflow` public virtual member function provides the input communication from the standard input device to which the `stdiobuf` object is connected. Member functions in the `streambuf` class call the `underflow` public virtual member function for the derived class when the *get area* is empty.

The `underflow` public virtual member function performs the following steps:

1. If no *reserve area* is present, a buffer is allocated with the `streambuf::allocate` member function, which may call the `doallocate` virtual member function. If, after calling `allocate`, no *reserve area* is present, the `stdiobuf` object is unbuffered and a one-character *reserve area* (plus putback area) is set up to do unbuffered input. This buffer is embedded in the `stdiobuf` object. The *get area* is set up as empty.
2. The unused part of the *get area* is used to read characters from the file connected to the `stdiobuf` object. The *get area* pointers are then set up to reflect the new *get area*.

**Results:** The `underflow` public virtual member function returns the first unread character of the *get area*, on success, otherwise EOF is returned. Note that the *get pointer* is not advanced on success.

**See Also:** `stdiobuf::overflow`, `streambuf::underflow`

**Declared:** streambu.h

**Derived by:** filebuf, stdiobuf, strstreambuf

The `streambuf` class is responsible for maintaining the buffer used to create an efficient implementation of the stream classes. Through its pure virtual functions, it is also responsible for the actual communication with the device associated with the stream.

The `streambuf` class is abstract, due to the presence of pure virtual member functions. Abstract classes may not be instantiated, only inherited. Hence, `streambuf` objects will not be created by user programs.

Stream objects maintain a pointer to an associated `streambuf` object and present the interface that the user deals with most often. Whenever a stream member function wishes to read or write characters, it uses the `rdbuf` member function to access the associated `streambuf` object and its member functions. Through judicious use of inline functions, most reads and writes of characters access the buffer directly without even doing a function call. Whenever the buffer gets filled (writing) or exhausted (reading), these inline functions invoke the function required to rectify the situation so that the proper action can take place.

A `streambuf` object can be unbuffered, but most often has one buffer which can be used for both input and output operations. The buffer (called the *reserve area*) is divided into two areas, called the *get area* and the *put area*. For a `streambuf` object being used exclusively to write, the *get area* is empty or not present. Likewise, a `streambuf` object being used exclusively for reading has an empty or non-existent *put area*.

The use of the *get area* and *put area* differs among the various classes derived from the `streambuf` class.

The `filebuf` class allows only the *get area* or the *put area*, but not both, to be active at a time. This follows from the capability of files opened for both reading and writing to have operations of each type performed at arbitrary locations in the file. When writing is occurring, the characters are buffered in the *put area*. If a seek or read operation is done, the *put area* must be flushed before the next operation in order to ensure that the characters are written to the proper location in the file. Similarly, if reading is occurring, characters are buffered in the *get area*. If a write operation is done, the *get area* must be flushed and synchronized before the write operation in order to ensure the write occurs at the proper location in the file. If a seek operation is done, the *get area* does not have to be synchronized, but is discarded. When the *get area* is empty and a read is done, the `underflow` virtual member function reads more characters and fills the *get area* again. When the *put area* is full and a write is done, the `overflow` virtual member function writes the characters and makes the *put area* empty again.

The `stdiobuf` class behaves in a similar way to the `filebuf` class, but does not need to switch between the *get area* and *put area*, since no `stdiobuf` object can be created for both reading and writing. When the *get area* is empty and a read is done, the `underflow` virtual member function reads more characters and fills the *get area* again. When the *put area* is full and a write is done, the `overflow` virtual member function writes the characters and makes the *put area* empty again.

The `strstreambuf` class differs quite markedly from the `filebuf` and `stdiobuf` classes. Since there is no actual source or destination for the characters in `strstream` objects, the buffer itself takes on that role. When writing is occurring and the *put area* is full, the `overflow` virtual member function reallocates the buffer to a larger size (if possible), the *put area* is extended and the writing continues. If reading is occurring and the *get area* is empty, the `underflow` virtual member function checks to see if the *put area* is present and not empty. If so, the *get area* is extended to overlap the *put area*.

The *reserve area* is marked by two pointer values. The `base` member function returns the pointer to the start of the buffer. The `ebuf` member function returns the pointer to the end of the buffer (last character + 1). The `setb` protected member function is used to set both pointers.

Within the *reserve area*, the *get area* is marked by three pointer values. The `eback` member function returns a pointer to the start of the *get area*. The `egptr` member function returns a pointer to the end of the *get area* (last character + 1). The `gptr` member function returns the *get pointer*. The *get pointer* is a pointer to the next character to be extracted from the *get area*. Characters before the *get pointer* have already been consumed by the program, while characters at and after the *get pointer* have been read from their source and are buffered and waiting to be read by the program. The `setg` member function is used to set all three pointer values. If any of these pointers are `NULL`, there is no *get area*.

Also within the *reserve area*, the *put area* is marked by three pointer values. The `pbase` member function returns a pointer to the start of the *put area*. The `eptr` member function returns a pointer to the end of the *put area* (last character + 1). The `pptr` member function returns the *put pointer*. The *put pointer* is a pointer to the next available position into which a character may be stored. Characters before the *put pointer* are buffered and waiting to be written to their final destination, while character positions at and after the *put pointer* have yet to be written by the program. The `setp` member function is used to set all three pointer values. If any of these pointers are `NULL`, there is no *put area*.

Unbuffered I/O is also possible. If unbuffered, the `overflow` virtual member function is used to write single characters directly to their final destination without using the *put area*. Similarly, the `underflow` virtual member function is used to read single characters directly from their source without using the *get area*.

### Protected Member Functions

The following member functions are declared in the protected interface:

```
streambuf();
streambuf(char *, int);
virtual ~streambuf();
int allocate();
char *base() const;
char *ebuf() const;
int blen() const;
void setb(char *, char *, int);
char *eback() const;
char *gptr() const;
char *egptr() const;
void gbump(streamoff);
void setg(char *, char *, char *);
char *pbase() const;
char *pptr() const;
char *eptr() const;
void pbump(streamoff);
void setp(char *, char *);
int unbuffered(int);
int unbuffered() const;
virtual int doallocate();
```

### Public Member Functions

The following member functions are declared in the public interface:

```
int in_avail() const;
```

```
int out_waiting() const;
int snextc();
int sgetn(char *, int);
int speekc();
int sgetc();
int sgetchar();
int sbumpc();
void stoss();
int sputbackc(char);
int sputc(int);
int sputn(char const *, int);
void dbp();

virtual int do_sgetn(char *, int);
virtual int do_sputn(char const *, int);
virtual int pbackfail(int);
virtual int overflow(int = EOF) = 0;
virtual int underflow() = 0;
virtual streambuf *setbuf(char *, int);
virtual streampos seekoff(streamoff, ios::seekdir,
ios::openmode = ios::in|ios::out);
virtual streampos seekpos(streampos,
ios::openmode = ios::in|ios::out);
virtual int sync();
```

**See Also:** filebuf, stdiobuf, strstreambuf

## ***streambuf::allocate()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
 int streambuf::allocate();
```

**Semantics:** The `allocate` protected member function works in tandem with the `doallocate` protected virtual member function to manage allocation of the `streambuf` object *reserve area*. Classes derived from the `streambuf` class should call the `allocate` protected member function, rather than the `doallocate` protected virtual member function. The `allocate` protected member function determines whether or not the `streambuf` object is allowed to allocate a buffer for use as the *reserve area*. If a *reserve area* already exists or if the `streambuf` object unbuffering state is non-zero, the `allocate` protected member function fails. Otherwise, it calls the `doallocate` protected virtual member function.

**Results:** The `allocate` protected member function returns `__NOT_EOF` on success, otherwise `EOF` is returned.

**See Also:** `streambuf::doallocate`, `underflow`, `overflow`

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::base() const;
```

**Semantics:** The base protected member function returns a pointer to the start of the *reserve area* that the streambuf object is using.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

`base()` start of the *reserve area*.  
`ebuf()` end of the *reserve area*.  
`blen()` length of the *reserve area*.

`eback()` start of the *get area*.  
`gptr()` the *get pointer*.  
`egptr()` end of the *get area*.

`pbase()` start of the *put area*.  
`pptr()` the *put pointer*.  
`eptr()` end of the *put area*.

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The base protected member function returns a pointer to the start of the *reserve area* that the streambuf object is using. If the streambuf object currently does not have a *reserve area*, NULL is returned.

**See Also:** `streambuf::blen`, `ebuf`, `setb`

## ***streambuf::blen()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
 int streambuf::blen() const;
```

**Semantics:** The `blen` protected member function reports the length of the *reserve area* that the `streambuf` object is using.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

`base()` start of the *reserve area*.  
`ebuf()` end of the *reserve area*.  
`blen()` length of the *reserve area*.

`eback()` start of the *get area*.  
`gptr()` the *get pointer*.  
`egptr()` end of the *get area*.

`pbase()` start of the *put area*.  
`pptr()` the *put pointer*.  
`eptr()` end of the *put area*.

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The `blen` protected member function returns the length of the *reserve area* that the `streambuf` object is using. If the `streambuf` object currently does not have a *reserve area*, zero is returned.

**See Also:** `streambuf::base`, `ebuf`, `setb`

**Synopsis:**

```
#include <streambu.h>
public:
void streambuf::dbp();
```

**Semantics:** The `dbp` public member function dumps information about the `streambuf` object directly to `stdout`, and is used for debugging classes derived from the `streambuf` class.

The following is an example of what the `dbp` public member function dumps:

```
STREAMBUF Debug Info:
this = 00030679, unbuffered = 0, delete_reserve = 1
base = 00070010, ebuf = 00070094
eback = 00000000, gptr = 00000000, egptr = 00000000
pbase = 00070010, pptr = 00070010, epptr = 00070094
```

## ***streambuf::do\_sgetn()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 virtual int do_sgetn(char *buf, int len);
```

**Semantics:** The `do_sgetn` public virtual member function works in tandem with the `sgetn` member function to transfer `len` characters from the *get area* into `buf`.

Classes derived from the `streambuf` class should call the `sgetn` member function, rather than the `do_sgetn` public virtual member function.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class that implement the `do_sgetn` public virtual member function should support copying up to `len` characters from the source through the *get area* and into `buf`.

**Default Implementation:**

The default `do_sgetn` public virtual member function provided with the `streambuf` class calls the `underflow` virtual member function to fetch more characters and then copies the characters from the *get area* into `buf`.

**Results:** The `do_sgetn` public virtual member function returns the number of characters successfully transferred.

**See Also:** `streambuf::sgetn`

**Synopsis:**

```
#include <streambu.h>
public:
 virtual int do_sputn(char const *buf, int len);
```

**Semantics:**

The `do_sputn` public virtual member function works in tandem with the `sputn` member function to transfer `len` characters from `buf` to the end of the *put area* and advances the *put pointer*.

Classes derived from the `streambuf` class should call the `sputn` member function, rather than the `do_sputn` public virtual member function.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class that implement the `do_sputn` public virtual member function should support copying up to `len` characters from `buf` through the *put area* and out to the destination device.

**Default Implementation:**

The default `do_sputn` public virtual member function provided with the `streambuf` class calls the `overflow` virtual member function to flush the *put area* and then copies the rest of the characters from `buf` into the *put area*.

**Results:**

The `do_sputn` public virtual member function returns the number of characters successfully written. If an error occurs, this number may be less than `len`.

**See Also:**

`streambuf::sputn`

## ***streambuf::doallocate()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
 virtual int streambuf::doallocate();
```

**Semantics:** The `doallocate` protected virtual member function manages allocation of the `streambuf` object's *reserve area* in tandem with the `allocate` protected member function.

Classes derived from the `streambuf` class should call the `allocate` protected member function rather than the `doallocate` protected virtual member function.

The `doallocate` protected virtual member function does the actual memory allocation, and can be defined for each class derived from the `streambuf` class.

### **Derived Implementation Protocol:**

Classes derived from the `streambuf` class should implement the `doallocate` protected virtual member function such that it does the following:

1. attempts to allocate an area of memory,
2. calls the `setb` protected member function to initialize the *reserve area* pointers,
3. performs any class specific operations required.

### **Default Implementation:**

The default `doallocate` protected virtual member function provided with the `streambuf` class attempts to allocate a buffer area with the `operator new` intrinsic function. It then calls the `setb` protected member function to set up the pointers to the *reserve area*.

**Results:** The `doallocate` protected virtual member function returns `__NOT_EOF` on success, otherwise `EOF` is returned.

**See Also:** `streambuf::allocate`

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::eback() const;
```

**Semantics:** The `eback` protected member function returns a pointer to the start of the *get area* within the *reserve area* used by the `streambuf` object.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

`base()` start of the *reserve area*.  
`ebuf()` end of the *reserve area*.  
`blen()` length of the *reserve area*.

`eback()` start of the *get area*.  
`gptr()` the *get pointer*.  
`egptr()` end of the *get area*.

`pbase()` start of the *put area*.  
`pptr()` the *put pointer*.  
`eptr()` end of the *put area*.

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The `eback` protected member function returns a pointer to the start of the *get area*. If the `streambuf` object currently does not have a *get area*, `NULL` is returned.

**See Also:** `streambuf::egptr`, `gptr`, `setg`

## **streambuf::ebuf()**

---

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::ebuf() const;
```

**Semantics:** The `ebuf` protected member function returns a pointer to the end of the *reserve area* that the `streambuf` object is using. The character pointed at is actually the first character past the end of the *reserve area*.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

`base ()` start of the *reserve area*.  
`ebuf ()` end of the *reserve area*.  
`blen ()` length of the *reserve area*.

`eback ()` start of the *get area*.  
`gptr ()` the *get pointer*.  
`egptr ()` end of the *get area*.

`pbase ()` start of the *put area*.  
`pptr ()` the *put pointer*.  
`eptr ()` end of the *put area*.

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The `ebuf` protected member function returns a pointer to the end of the *reserve area*. If the `streambuf` object currently does not have a *reserve area*, NULL is returned.

**See Also:** `streambuf::base`, `blen`, `setb`

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::egptr() const;
```

**Semantics:** The `egptr` protected member function returns a pointer to the end of the *get area* within the *reserve area* used by the `streambuf` object. The character pointed at is actually the first character past the end of the *get area*.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

`base ()` start of the *reserve area*.

`ebuf ()` end of the *reserve area*.

`blen ()` length of the *reserve area*.

`eback ()` start of the *get area*.

`gptr ()` the *get pointer*.

`egptr ()` end of the *get area*.

`pbase ()` start of the *put area*.

`pptr ()` the *put pointer*.

`eptr ()` end of the *put area*.

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The `egptr` protected member function returns a pointer to the end of the *get area*. If the `streambuf` object currently does not have a *get area*, NULL is returned.

**See Also:** `streambuf::eback`, `gptr`, `setg`

## **streambuf::eptr()**

---

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::eptr() const;
```

**Semantics:** The `eptr` protected member function returns a pointer to the end of the *put area* within the *reserve area* used by the `streambuf` object. The character pointed at is actually the first character past the end of the *put area*.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

`base ()` start of the *reserve area*.

`ebuf ()` end of the *reserve area*.

`blen ()` length of the *reserve area*.

`eback ()` start of the *get area*.

`gptr ()` the *get pointer*.

`egptr ()` end of the *get area*.

`pbase ()` start of the *put area*.

`pptr ()` the *put pointer*.

`eptr ()` end of the *put area*.

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The `eptr` protected member function returns a pointer to the end of the *put area*. If the `streambuf` object currently does not have a *put area*, `NULL` is returned.

**See Also:** `streambuf::pbase`, `pptr`, `setp`

**Synopsis:**

```
#include <streambu.h>
protected:
void streambuf::gbump(streamoff offset);
```

**Semantics:** The `gbump` protected member function increments the *get pointer* by the specified *offset*, without regard for the boundaries of the *get area*. The *offset* parameter may be positive or negative.

**Results:** The `gbump` protected member function returns nothing.

**See Also:** `streambuf::gptr`, `pbump`, `sbumpc`, `sputbackc`

## **streambuf::gptr()**

---

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::gptr() const;
```

**Semantics:** The `gptr` protected member function returns a pointer to the next available character in the *get area* within the *reserve area* used by the `streambuf` object. This pointer is called the *get pointer*.

If the *get pointer* points beyond the end of the *get area*, all characters in the *get area* have been read by the program and a subsequent read causes the `underflow` virtual member function to be called to fetch more characters from the source to which the `streambuf` object is attached.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

|                       |                                     |
|-----------------------|-------------------------------------|
| <code>base ()</code>  | start of the <i>reserve area</i> .  |
| <code>ebuf ()</code>  | end of the <i>reserve area</i> .    |
| <code>blen ()</code>  | length of the <i>reserve area</i> . |
| <br>                  |                                     |
| <code>eback ()</code> | start of the <i>get area</i> .      |
| <code>gptr ()</code>  | the <i>get pointer</i> .            |
| <code>egptr ()</code> | end of the <i>get area</i> .        |
| <br>                  |                                     |
| <code>pbase ()</code> | start of the <i>put area</i> .      |
| <code>pptr ()</code>  | the <i>put pointer</i> .            |
| <code>epptr ()</code> | end of the <i>put area</i> .        |

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `epptr` is unused buffer area.

**Results:** The `gptr` protected member function returns a pointer to the next available character in the *get area*. If the `streambuf` object currently does not have a *get area*, NULL is returned.

**See Also:** `streambuf::eback`, `egptr`, `setg`

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::in_avail() const;
```

**Semantics:** The `in_avail` public member function computes the number of input characters buffered in the *get area* that have not yet been read by the program. These characters can be read with a guarantee that no errors will occur.

**Results:** The `in_avail` public member function returns the number of buffered input characters.

**See Also:** `streambuf::egptr`, `gptr`

## ***streambuf::out\_waiting()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::out_waiting() const;
```

**Semantics:** The *out\_waiting* public member function computes the number of characters that have been buffered in the *put area* and not yet been written to the output device.

**Results:** The *out\_waiting* public member function returns the number of buffered output characters.

**See Also:** `streambuf::pbase`, `pptr`

**Synopsis:**

```
#include <streambuf.h>
public:
 virtual int streambuf::overflow(int ch = EOF) = 0;
```

**Semantics:** The `overflow` public virtual member function is used to flush the *put area* when it is full.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class should implement the `overflow` public virtual member function so that it performs the following:

1. if no *reserve area* is present and the `streambuf` object is not unbuffered, allocate a *reserve area* using the `allocate` member function and set up the *reserve area* pointers using the `setb` protected member function,
2. flush any other uses of the *reserve area*,
3. write any characters in the *put area* to the `streambuf` object's destination,
4. set up the *put area* pointers to reflect the characters that were written,
5. return `__NOT_EOF` on success, otherwise return `EOF`.

**Default Implementation:**

There is no default `streambuf` class implementation of the `overflow` public virtual member function. The `overflow` public virtual member function must be defined for all classes derived from the `streambuf` class.

**Results:** The `overflow` public virtual member function returns `__NOT_EOF` on success, otherwise `EOF` is returned.

**See Also:** `filebuf::overflow`, `stdiobuf::overflow`, `strstreambuf::overflow`

## ***streambuf::pbackfail()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 virtual int streambuf::pbackfail(int ch);
```

**Semantics:** The `pbackfail` public virtual member function is called by the `sputbackc` member function when the *get pointer* is at the beginning of the *get area*, and so there is no place to put the *ch* parameter.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class should implement the `pbackfail` public virtual member function such that it attempts to put *ch* back into the source of the stream.

**Default Implementation:**

The default `streambuf` class implementation of the `pbackfail` public virtual member function is to return EOF.

**Results:** If the `pbackfail` public virtual member function succeeds, it returns *ch*. Otherwise, EOF is returned.

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::pbase() const;
```

**Semantics:** The pbase protected member function returns a pointer to the start of the *put area* within the *reserve area* used by the streambuf object.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

`base()` start of the *reserve area*.  
`ebuf()` end of the *reserve area*.  
`blen()` length of the *reserve area*.

`eback()` start of the *get area*.  
`gptr()` the *get pointer*.  
`egptr()` end of the *get area*.

`pbase()` start of the *put area*.  
`pptr()` the *put pointer*.  
`eptr()` end of the *put area*.

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The pbase protected member function returns a pointer to the start of the *put area*. If the streambuf object currently does not have a *put area*, NULL is returned.

**See Also:** `streambuf::eptr`, `pptr`, `setp`

## ***streambuf::pbump()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
void streambuf::pbump(streamoff offset);
```

**Semantics:** The pbump protected member function increments the *put pointer* by the specified *offset*, without regard for the boundaries of the *put area*. The *offset* parameter may be positive or negative.

**Results:** The pbump protected member function returns nothing.

**See Also:** `streambuf::gbump`, `pbase`, `pptr`

**Synopsis:**

```
#include <streambu.h>
protected:
char *streambuf::pptr() const;
```

**Semantics:** The `pptr` protected member function returns a pointer to the next available space in the *put area* within the *reserve area* used by the `streambuf` object. This pointer is called the *put pointer*.

If the *put pointer* points beyond the end of the *put area*, the *put area* is full and a subsequent write causes the `overflow` virtual member function to be called to empty the *put area* to the device to which the `streambuf` object is attached.

The *reserve area*, *get area*, and *put area* pointer functions return the following values:

|                       |                                     |
|-----------------------|-------------------------------------|
| <code>base ()</code>  | start of the <i>reserve area</i> .  |
| <code>eback ()</code> | end of the <i>get area</i> .        |
| <code>ebuf ()</code>  | the <i>get pointer</i> .            |
| <code>blen ()</code>  | length of the <i>reserve area</i> . |
| <code>egptr ()</code> | end of the <i>get area</i> .        |
| <code>pbase ()</code> | start of the <i>put area</i> .      |
| <code>pptr ()</code>  | the <i>put pointer</i> .            |
| <code>eptr ()</code>  | end of the <i>put area</i> .        |

From `eback` to `gptr` are characters buffered and read. From `gptr` to `egptr` are characters buffered but not yet read. From `pbase` to `pptr` are characters buffered and not yet written. From `pptr` to `eptr` is unused buffer area.

**Results:** The `pptr` protected member function returns a pointer to the next available space in the *put area*. If the `streambuf` object currently does not have a *put area*, `NULL` is returned.

**See Also:** `streambuf::eptr`, `pbase`, `setp`

## ***streambuf::sbumpc()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::sbumpc();
```

**Semantics:** The `sbumpc` public member function extracts the next available character from the *get area* and advances the *get pointer*. If no character is available, it calls the `underflow` virtual member function to fetch more characters from the source into the *get area*.

Due to the `sbumpc` member functions's awkward name, the `sgetchar` member function was added to take its place in the WATCOM implementation.

**Results:** The `sbumpc` public member function returns the next available character in the *get area*. If no character is available, EOF is returned.

**See Also:** `streambuf::gbump`, `sgetc`, `sgetchar`, `sgetn`, `snextc`, `sputbackc`

**Synopsis:**

```
#include <streambu.h>
public:
 virtual streampos streambuf::seekoff(streamoff offset,
 ios::seekdir dir,
 ios::openmode mode);
```

**Semantics:** The `seekoff` public virtual member function is used for positioning to a relative location within the `streambuf` object, and hence within the device that is connected to the `streambuf` object. The `offset` and `dir` parameters specify the relative change in position. The `mode` parameter controls whether the *get pointer* and/or the *put pointer* are repositioned.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class should implement the `seekoff` virtual member function so that it uses its parameters in the following way.

The `mode` parameter may be `ios::in`, `ios::out`, or `ios::in|ios::out` and should be interpreted as follows, provided the interpretation is meaningful:

|                               |                                                                         |
|-------------------------------|-------------------------------------------------------------------------|
| <code>ios::in</code>          | the <i>get pointer</i> should be moved.                                 |
| <code>ios::out</code>         | the <i>put pointer</i> should be moved.                                 |
| <code>ios::in ios::out</code> | both the <i>get pointer</i> and the <i>put pointer</i> should be moved. |

If `mode` has any other value, the `seekoff` public virtual member function fails.

The `dir` parameter may be `ios::beg`, `ios::cur`, or `ios::end` and is interpreted in conjunction with the `offset` parameter as follows:

`ios::beg` the `offset` is relative to the start and should be a positive value.  
`ios::cur` the `offset` is relative to the current position and may be positive  
    (seek towards end) or negative (seek towards start).  
`ios::end` the `offset` is relative to the end and should be a negative value.

If the `dir` parameter has any other value, or the `offset` parameter does not have an appropriate sign, the `seekoff` public virtual member function fails.

**Default Implementation:**

The default implementation of the `seekoff` public virtual member function provided by the `streambuf` class returns EOF.

**Results:** The `seekoff` public virtual member function returns the new position in the stream on success, otherwise EOF is returned.

**See Also:** `streambuf::seekpos`

## ***streambuf::seekpos()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 virtual streampos streambuf::seekpos(streampos pos,
 ios::openmode mode = ios::in|ios::out);
```

**Semantics:** The `seekpos` public virtual member function is used for positioning to an absolute location within the `streambuf` object, and hence within the device that is connected to the `streambuf` object. The `pos` parameter specifies the absolute position. The `mode` parameter controls whether the *get pointer* and/or the *put pointer* are repositioned.

### **Derived Implementation Protocol:**

Classes derived from the `streambuf` class should implement the `seekpos` public virtual member function so that it uses its parameters in the following way.

The `mode` parameter may be `ios::in`, `ios::out`, or `ios::in|ios::out` and should be interpreted as follows, provided the interpretation is meaningful:

|                               |                                                                         |
|-------------------------------|-------------------------------------------------------------------------|
| <code>ios::in</code>          | the <i>get pointer</i> should be moved.                                 |
| <code>ios::out</code>         | the <i>put pointer</i> should be moved.                                 |
| <code>ios::in ios::out</code> | both the <i>get pointer</i> and the <i>put pointer</i> should be moved. |

If `mode` has any other value, the `seekpos` public virtual member function fails.

In general the `seekpos` public virtual member function is equivalent to calling the `seekoff` virtual member function with the offset set to `pos`, the direction set to `ios::beg` and the mode set to `mode`.

### **Default Implementation:**

The default implementation of the `seekpos` public virtual member function provided by the `streambuf` class calls the `seekoff` virtual member function with the offset set to `pos`, the direction set to `ios::beg`, and the mode set to `mode`.

**Results:** The `seekpos` public virtual member function returns the new position in the stream on success, otherwise EOF is returned.

**See Also:** `streambuf::seekoff`

**Synopsis:**

```
#include <streambu.h>
protected:
void streambuf::setb(char *base, char *ebuf, int autodel);
```

**Semantics:**

The *setb* protected member function is used to set the pointers to the *reserve area* that the *streambuf* object is using.

The *base* parameter is a pointer to the start of the *reserve area* and corresponds to the value that the *base* member function returns.

The *ebuf* parameter is a pointer to the end of the *reserve area* and corresponds to the value that the *ebuf* member function returns.

The *autodel* parameter indicates whether or not the *streambuf* object can free the *reserve area* when the *streambuf* object is destroyed or when a new *reserve area* is set up in a subsequent call to the *setb* protected member function. If the *autodel* parameter is non-zero, the *streambuf* object can delete the *reserve area*, using the *operator delete* intrinsic function. Otherwise, a zero value indicates that the buffer will be deleted elsewhere.

If either of the *base* or *ebuf* parameters are `NULL` or if *ebuf*  $\leq$  *base*, the *streambuf* object does not have a buffer and input/output operations are unbuffered, unless another buffer is set up.

Note that the *setb* protected member function is used to set the *reserve area* pointers, while the *setbuf* protected member function is used to offer a buffer to the *streambuf* object.

**See Also:**

*streambuf::base*, *blen*, *ebuf*, *setbuf*

## ***streambuf::setbuf()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 virtual streambuf *streambuf::setbuf(char *buf, int len);
```

**Semantics:** The `setbuf` public virtual member function is used to offer a buffer specified by the `buf` and `len` parameters to the `streambuf` object for use as its *reserve area*. Note that the `setbuf` public virtual member function is used to offer a buffer, while the `setb` protected member function is used to set the *reserve area* pointers once a buffer has been accepted.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class may implement the `setbuf` public virtual member function if the default behavior is not suitable.

Derived classes that provide their own implementations of the `setbuf` public virtual member function may accept or reject the offered buffer. Often, if a buffer is already allocated, the offered buffer is rejected, as it may be difficult to transfer the information from the current buffer.

**Default Implementation:**

The default `setbuf` public virtual member function provided by the `streambuf` class rejects the buffer if one is already present.

If no buffer is present and either `buf` is `NULL` or `len` is zero, the offer is accepted and the `streambuf` object is unbuffered.

Otherwise, no buffer is present and one is specified. If `len` is less than five characters the buffer is too small and it is rejected. Otherwise, the buffer is accepted.

**Results:** The `setbuf` public virtual member function returns the address of the `streambuf` object if the offered buffer is accepted, otherwise `NULL` is returned.

**See Also:** `streambuf::setb`

**Synopsis:**

```
#include <streambuf.h>
protected:
void streambuf::setg(char *eback, char *gptr, char *egptr);
```

**Semantics:** The `setg` protected member function is used to set the three *get area* pointers.

The `eback` parameter is a pointer to the start of the *get area* and corresponds to the value that the `eback` member function returns.

The `gptr` parameter is a pointer to the first available character in the *get area*, that is, the *get pointer*, and usually is greater than the `eback` parameter in order to accommodate a putback area. The `gptr` parameter corresponds to the value that the `gptr` member function returns.

The `egptr` parameter is a pointer to the end of the *get area* and corresponds to the value that the `egptr` member function returns.

If any of the three parameters are `NULL`, there is no *get area*.

**See Also:** `streambuf::eback`, `egptr`, `gptr`

## ***streambuf::setp()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
void streambuf::setp(char *pbase, char *epptr);
```

**Semantics:** The `setp` protected member function is used to set the three *put area* pointers.

The `pbase` parameter is a pointer to the start of the *put area* and corresponds to the value that the `pbase` member function returns.

The `epptr` parameter is a pointer to the end of the *put area* and corresponds to the value that the `epptr` member function returns.

The *put pointer* is set to the `pbase` parameter value and corresponds to the value that the `pptr` member function returns.

If either parameter is NULL, there is no *put area*.

**See Also:** `streambuf::epptr`, `pbase`, `pptr`

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::sgetc();
```

**Semantics:** The `sgetc` public member function returns the next available character in the *get area*. The *get pointer* is not advanced. If the *get area* is empty, the `underflow` virtual member function is called to fetch more characters from the source into the *get area*.

Due to the `sgetc` member function's confusing name (the C library `getc` function does advance the pointer), the `speekc` member function was added to take its place in the WATCOM implementation.

**Results:** The `sgetc` public member function returns the next available character in the *get area*. If no character is available, EOF is returned.

**See Also:** `streambuf::sbumpc`, `sgetchar`, `sgetn`, `snextc`, `speekc`

## ***streambuf::sgetchar()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::sgetchar();
```

**Semantics:** The `sgetchar` public member function extracts the next available character from the *get area* and advances the *get pointer*. If no character is available, it calls the `underflow` virtual member function to fetch more characters from the source into the *get area*.

Due to the `sbumpc` member functions's awkward name, the `sgetchar` member function was added to take its place in the WATCOM implementation.

**Results:** The `sgetchar` public member function returns the next available character in the *get area*. If no character is available, EOF is returned.

**See Also:** `streambuf::gbump`, `sgetc`, `sgetchar`, `sgetn`, `snextc`, `speekc`, `sputbackc`

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::sgetn(char *buf, int len);
```

**Semantics:** The `sgetn` public member function transfers up to `len` characters from the *get area* into `buf`. If there are not enough characters in the *get area*, the `do_sgetn` virtual member function is called to fetch more.

Classes derived from the `streambuf` class should call the `sgetn` public member function, rather than the `do_sgetn` virtual member function.

**Results:** The `sgetn` public member function returns the number of characters transferred from the *get area* into `buf`.

**See Also:** `streambuf::do_sgetn`, `sbumpc`, `sgetc`, `sgetchar`, `speekc`

## ***streambuf::snextc()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::snextc();
```

**Semantics:** The `snextc` public member function advances the *get pointer* and then returns the character following the *get pointer*. The *get pointer* is left pointing at the returned character.

If the *get pointer* cannot be advanced, the `underflow` virtual member function is called to fetch more characters from the source into the *get area*.

**Results:** The `snextc` public member function advances the *get pointer* and returns the next available character in the *get area*. If there is no next available character, EOF is returned.

**See Also:** `streambuf::sbumpc`, `sgetc`, `sgetchar`, `sgetn`, `speekc`

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::speekc();
```

**Semantics:** The `speekc` public member function returns the next available character in the *get area*. The *get pointer* is not advanced. If the *get area* is empty, the `underflow` virtual member function is called to fetch more characters from the source into the *get area*.

Due to the `sgetc` member function's confusing name (the C library `getc` function does advance the pointer), the `speekc` member function was added to take its place in the WATCOM implementation.

**Results:** The `speekc` public member function returns the next available character in the *get area*. If no character is available, EOF is returned.

**See Also:** `streambuf::sbumpc`, `sgetc`, `sgetchar`, `sgetn`, `snextc`

## ***streambuf::sputbackc()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::sputbackc(char ch);
```

**Semantics:** The `sputbackc` public member function is used to put a character back into the *get area*. The *ch* character specified must be the same as the character before the *get pointer*, otherwise the behavior is undefined. The *get pointer* is backed up by one position. At least four characters may be put back without any intervening reads.

**Results:** The `sputbackc` public member function returns *ch* on success, otherwise `EOF` is returned.

**See Also:** `streambuf::gbump`, `sbumpc`, `sgetchar`

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::sputc(int ch);
```

**Semantics:** The `sputc` public member function adds the character `ch` to the end of the *put area* and advances the *put pointer*. If the *put area* is full before the character is added, the `overflow` virtual member function is called to empty the *put area* and write the character.

**Results:** The `sputc` public member function returns `ch` on success, otherwise `EOF` is returned.

**See Also:** `streambuf::sgetc`, `sputn`

## ***streambuf::sputn()***

---

**Synopsis:**

```
#include <streambu.h>
public:
 int streambuf::sputn(char const *buf, int len);
```

**Semantics:** The `sputn` public member function transfers up to `len` characters from `buf` to the end of the *put area* and advance the *put pointer*. If the *put area* is full or becomes full and more characters are to be written, the `do_sputn` virtual member function is called to empty the *put area* and finish writing the characters.

Classes derived from the `streambuf` class should call the `sputn` public member function, rather than the `do_sputn` virtual member function.

**Results:** The `sputn` public member function returns the number of characters successfully written. If an error occurs, this number may be less than `len`.

**See Also:** `streambuf::do_sputn`, `sputc`

**Synopsis:**

```
#include <streambu.h>
public:
void streambuf::stossc();
```

**Semantics:** The `stossc` public member function advances the *get pointer* by one without returning a character. If the *get area* is empty, the `underflow` virtual member function is called to fetch more characters and then the *get pointer* is advanced.

**See Also:** `streambuf::gbump`, `sbumpc`, `sgetchar`, `snextc`

## ***streambuf::streambuf()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
 streambuf::streambuf();
```

**Semantics:** This form of the protected `streambuf` constructor creates an empty `streambuf` object with all fields initialized to zero. No *reserve area* is yet allocated, but the `streambuf` object is buffered unless a subsequent call to the `setbuf` or `unbuffered` member functions dictate otherwise.

**Results:** This form of the protected `streambuf` constructor creates an initialized `streambuf` object with no associated *reserve area*.

**See Also:** `~streambuf`

**Synopsis:**

```
#include <streambu.h>
protected:
 streambuf::streambuf(char *buf, int len);
```

**Semantics:** This form of the protected `streambuf` constructor creates an empty `streambuf` object with all fields initialized to zero. The `buf` and `len` parameters are passed to the `setbuf` member function, which sets up the buffer (if specified), or makes the `streambuf` object unbuffered (if the `buf` parameter is `NULL` or the `len` parameter is not positive).

**Results:** This form of the protected `streambuf` constructor creates an initialized `streambuf` object with an associated *reserve area*.

**See Also:** `~streambuf`, `setbuf`

## ***streambuf::~streambuf()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
 virtual streambuf::~streambuf();
```

**Semantics:** The `streambuf` object is destroyed. If the buffer was allocated by the `streambuf` object, it is freed. Otherwise, the buffer is not freed and must be freed by the user of the `streambuf` object. The call to the protected `~streambuf` destructor is inserted implicitly by the compiler at the point where the `streambuf` object goes out of scope.

**Results:** The `streambuf` object is destroyed.

**See Also:** `streambuf`

**Synopsis:**

```
#include <streambu.h>
public:
 virtual int streambuf::sync();
```

**Semantics:** The `sync` public virtual member function is used to synchronize the `streambuf` object's *get area* and *put area* with the associated device.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class should implement the `sync` public virtual member function such that it attempts to perform the following:

1. flush the *put area*,
2. discard the contents of the *get area* and reposition the stream device so that the discarded characters may be read again.

**Default Implementation:**

The default implementation of the `sync` public virtual member function provided by the `streambuf` class takes no action. It succeeds if the *get area* and the *put area* are empty, otherwise it fails.

**Results:** The `sync` public virtual member function returns `__NOT_EOF` on success, otherwise `EOF` is returned.

## ***streambuf::unbuffered()***

---

**Synopsis:**

```
#include <streambu.h>
protected:
 int ios::unbuffered() const;
 int ios::unbuffered(int unbuf);
```

**Semantics:** The `unbuffered` protected member function is used to query and/or set the unbuffering state of the `streambuf` object. A non-zero unbuffered state indicates that the `streambuf` object is unbuffered. An unbuffered state of zero indicates that the `streambuf` object is buffered.

The first form of the `unbuffered` protected member function is used to query the current unbuffering state.

The second form of the `unbuffered` protected member function is used to set the unbuffering state to *unbuf*.

Note that the unbuffering state only affects the `allocate` protected member function, which does nothing if the unbuffering state is non-zero. Setting the unbuffering state to a non-zero value does not mean that future I/O operations will be unbuffered.

To determine if current I/O operations are unbuffered, use the `base` protected member function. A return value of `NULL` from the `base` protected member function indicates that unbuffered I/O operations will be used.

**Results:** The `unbuffered` protected member function returns the previous unbuffered state.

**See Also:** `streambuf::allocate`, `pbase`, `setbuf`

**Synopsis:**

```
#include <streambuf.h>
public:
 virtual int streambuf::underflow() = 0;
```

**Semantics:** The `underflow` public virtual member function is used to fill the *get area* when it is empty.

**Derived Implementation Protocol:**

Classes derived from the `streambuf` class should implement the `underflow` public virtual member function so that it performs the following:

1. if no *reserve area* is present and the `streambuf` object is buffered, allocate the *reserve area* using the `allocate` member function and set up the *reserve area* pointers using the `setb` protected member function,
2. flush any other uses of the *reserve area*,
3. read some characters from the `streambuf` object's source into the *get area*,
4. set up the *get area* pointers to reflect the characters that were read,
5. return the first character of the *get area*, or `EOF` if no characters could be read.

**Default Implementation:**

There is no default `streambuf` class implementation of the `underflow` public virtual member function. The `underflow` public virtual member function must be defined for all classes derived from the `streambuf` class.

**Results:** The `underflow` public virtual member function returns the first character read into the *get area*, or `EOF` if no characters could be read.

**See Also:** `filebuf::underflow`, `stdiobuf::underflow`, `strstreambuf::underflow`

## ***strstream***

---

**Declared:** strstrea.h

**Derived from:** strstreambase, iostream

The `strstream` class is used to create and write to string stream objects.

The `strstream` class provides little of its own functionality. Derived from the `strstreambase` and `iostream` classes, its constructors and destructor provide simplified access to the appropriate equivalents in those base classes. The member functions provide specialized access to the string stream object.

Of the available I/O stream classes, creating a `strstream` object is the preferred method of performing read and write operations on a string stream.

### **Public Member Functions**

The following member functions are declared in the public interface:

```
strstream();
strstream(char *,
int,
ios::openmode = ios::in|ios::out);
strstream(signed char *,
int,
ios::openmode = ios::in|ios::out);
strstream(unsigned char *,
int,
ios::openmode = ios::in|ios::out);
~strstream();
char *str();
```

**See Also:** istrstream, ostrstream, strstreambase

**Synopsis:**

```
#include <strstrea.h>
public:
char *strstream::str();
```

**Semantics:** The `str` public member function creates a pointer to the buffer being used by the `strstream` object. If the `strstream` object was created without dynamic allocation (static mode), the pointer is the same as the buffer pointer passed in the constructor.

For `strstream` objects using dynamic allocation, the `str` public member function makes an implicit call to the `strstreambuf::freeze` member function. If nothing has been written to the `strstream` object, the returned pointer will be `NULL`.

Note that the buffer does not necessarily end with a null character. If the pointer returned by the `str` public member function is to be interpreted as a C string, it is the program's responsibility to ensure that the null character is present.

**Results:** The `str` public member function returns a pointer to the buffer being used by the `strstream` object.

**See Also:** `strstreambuf::str`, `strstreambuf::freeze`

## ***strstream::strstream()***

---

**Synopsis:**

```
#include <strstrea.h>
public:
 strstream::strstream();
```

**Semantics:** This form of the public `strstream` constructor creates an empty `strstream` object. Dynamic allocation is used. The inherited stream member functions can be used to access the `strstream` object. Note that the *get pointer* and *put pointer* are not necessarily pointing at the same location, so moving one pointer (e.g. by doing a write) does not affect the location of the other pointer.

**Results:** This form of the public `strstream` constructor creates an initialized, empty `strstream` object.

**See Also:** `~strstream`

**Synopsis:**

```
#include <strstrea.h>
public:
 strstream::strstream(char *str,
 int len,
 ios::openmode mode);
 strstream::strstream(signed char *str,
 int len,
 ios::openmode mode);
 strstream::strstream(unsigned char *str,
 int len,
 ios::openmode mode);
```

**Semantics:** These forms of the public `strstream` constructor create an initialized `strstream` object. Dynamic allocation is not used. The buffer is specified by the `str` and `len` parameters. If the `ios::append` or `ios::atend` bits are set in the `mode` parameter, the `str` parameter is assumed to contain a C string terminated by a null character, and writing commences at the null character. Otherwise, writing commences at `str`. Reading commences at `str`.

**Results:** This form of the public `strstream` constructor creates an initialized `strstream` object.

**See Also:** `~strstream`

## ***strstream::~strstream()***

---

**Synopsis:**

```
#include <strstrea.h>
public:
 strstream::~strstream();
```

**Semantics:** The public ~strstream destructor does not do anything explicit. The call to the public ~strstream destructor is inserted implicitly by the compiler at the point where the strstream object goes out of scope.

**Results:** The strstream object is destroyed.

**See Also:** strstream

**Declared:** strstrea.h

**Derived from:** ios

**Derived by:** istrstream, ostrstream, strstream

The **strstreambase** class is a base class that provides common functionality for the three string stream-based classes, **istrstream**, **ostrstream** and **strstream**. The **strstreambase** class is derived from the **ios** class which provides the stream state information. The **strstreambase** class provides constructors for string stream objects and one member function.

### **Protected Member Functions**

The following member functions are declared in the protected interface:

```
strstreambase();
strstreambase(char *, int, char * = 0);
~strstreambase();
```

### **Public Member Functions**

The following member function is declared in the public interface:

```
strstreambuf *rdbuf() const;
```

**See Also:** istrstream, ostrstream, strstream, strstreambuf

## *strstreambase::rdbuf()*

---

**Synopsis:**

```
#include <strstrea.h>
public:
 strstreambuf *strstreambase::rdbuf() const;
```

**Semantics:** The `rdbuf` public member function creates a pointer to the `strstreambuf` associated with the `strstreambase` object. Since the `strstreambuf` object is embedded within the `strstreambase` object, this function never returns `NULL`.

**Results:** The `rdbuf` public member function returns a pointer to the `strstreambuf` associated with the `strstreambase` object.

**Synopsis:**

```
#include <strstrea.h>
protected:
 strstreambase::strstreambase();
```

**Semantics:** This form of the protected `strstreambase` constructor creates a `strstreambase` object that is initialized, but empty. Dynamic allocation is used to store characters. No buffer is allocated. A buffer is allocated when data is first written to the `strstreambase` object.

This form of the protected `strstreambase` constructor is only used implicitly by the compiler when it generates a constructor for a derived class.

**Results:** The protected `strstreambase` constructor creates an initialized `strstreambase` object.

**See Also:** `~strstreambase`

## ***strstreambase::strstreambase()***

---

**Synopsis:**

```
#include <strstrea.h>
protected:
 strstreambase::strstreambase(char *str,
 int len,
 char *pstart);
```

**Semantics:** This form of the protected `strstreambase` constructor creates a `strstreambase` object that is initialized and uses the buffer specified by the `str` and `len` parameters as its *reserve area* within the associated `strstreambuf` object. Dynamic allocation is not used.

This form of the protected `strstreambase` constructor is unlikely to be explicitly used, except in the member initializer list for the constructor of a derived class.

The `str`, `len` and `pstart` parameters are interpreted as follows:

1. The buffer starts at `str`.
2. If `len` is positive, the buffer is `len` characters long.
3. If `len` is zero, `str` is a pointer to a C string which is terminated by a null character, and the length of the buffer is the length of the string.
4. If `len` is negative, the buffer is unbounded. This last form should be used with extreme caution, since no buffer is truly unlimited in size and it would be easy to write beyond the available space.
5. If the `pstart` parameter is NULL, the `strstreambase` object is read-only.
6. Otherwise, `pstart` divides the buffer into two regions. The *get area* starts at `str` and ends at `pstart-1`. The *put area* starts at `pstart` and goes to the end of the buffer.

**Results:** The protected `strstreambase` constructor creates an initialized `strstreambase` object.

**See Also:** `~strstreambase`

**Synopsis:**

```
#include <strstrea.h>
protected:
strstreambase::~strstreambase();
```

**Semantics:** The protected ~strstreambase destructor does not do anything explicit. The call to the protected ~strstreambase destructor is inserted implicitly by the compiler at the point where the strstreambase object goes out of scope.

**Results:** The strstreambase object is destroyed.

**See Also:** strstreambase

## ***strstreambuf***

---

**Declared:** strstrea.h

**Derived from:** streambuf

The `strstreambuf` class is derived from the `streambuf` class and provides additional functionality required to write characters to and read characters from a string buffer. Read and write operations can occur at different positions in the string buffer, since the *get pointer* and *put pointer* are not necessarily connected. Seek operations are also supported.

The *reserve area* used by the `strstreambuf` object may be either fixed in size or dynamic. Generally, input strings are of a fixed size, while output streams are dynamic, since the final size may not be predictable. For dynamic buffers, the `strstreambuf` object automatically grows the buffer when necessary.

The `strstreambuf` class differs quite markedly from the `filebuf` and `stdiobuf` classes. Since there is no actual source or destination for the characters in `strstream` objects, the buffer itself takes on that role. When writing is occurring and the *put area* is full, the `overflow` virtual member function reallocates the buffer to a larger size (if possible), the *put area* is extended and the writing continues. If reading is occurring and the *get area* is empty, the `underflow` virtual member function checks to see if the *put area* is present and not empty. If so, the *get area* is extended to overlap the *put area*.

C++ programmers who wish to use string streams without deriving new objects will probably never explicitly create or use a `strstreambuf` object.

### **Protected Member Functions**

The following member function is declared in the protected interface:

```
virtual int doallocate();
```

### **Public Member Functions**

The following member functions are declared in the public interface:

```
strstreambuf();
strstreambuf(int);
strstreambuf(void *(*)(long), void (*)(void *));
strstreambuf(char *, int, char * = 0);
~strstreambuf();
int alloc_size_increment(int);
void freeze(int = 1);
char *str();
virtual int overflow(int = EOF);
virtual int underflow();
virtual streambuf *setbuf(char *, int);
virtual streampos seekoff(streamoff,
ios::seekdir,
ios::openmode);
virtual int sync();
```

**See Also:** streambuf, strstreambase

**Synopsis:**

```
#include <strstrea.h>
public:
 int strstreambuf::alloc_size_increment(int increment);
```

**Semantics:**

The `alloc_size_increment` public member function modifies the allocation size used when the buffer is first allocated or reallocated by dynamic allocation. The *increment* parameter is added to the previous allocation size for future use.

This function is a WATCOM extension.

**Results:**

The `alloc_size_increment` public member function returns the previous value of the allocation size.

**See Also:**

`strstreambuf::doallocate`, `setbuf`

## *strstreambuf::doallocate()*

---

**Synopsis:**

```
#include <strstrea.h>
protected:
 virtual int strstreambuf::doallocate();
```

**Semantics:** The doallocate protected virtual member function is called by the allocate member function when it is determined that the *put area* is full and needs to be extended.

The doallocate protected virtual member function performs the following steps:

1. If dynamic allocation is not being used, the doallocate protected virtual member function fails.
2. A new size for the buffer is determined. If the allocation size is bigger than the current size, the allocation size is used. Otherwise, the buffer size is increased by DEFAULT\_MAINBUF\_SIZE, which is 512.
3. A new buffer is allocated. If an allocation function was specified in the constructor for the strstreambuf object, that allocation function is used, otherwise the operator new intrinsic function is used. If the allocation fails, the doallocate protected virtual member function fails.
4. If necessary, the contents of the *get area* are copied to the newly allocated buffer and the *get area* pointers are adjusted accordingly.
5. The contents of the *put area* are copied to the newly allocated buffer and the *put area* pointers are adjusted accordingly, extending the *put area* to the end of the new buffer.
6. The old buffer is freed. If a free function was specified in the constructor for the strstreambuf object, that free function is used, otherwise the operator delete intrinsic function is used.

**Results:** The doallocate protected virtual member function returns \_\_NOT\_EOF on success, otherwise EOF is returned.

**See Also:** strstreambuf::alloc\_size\_increment, setbuf

**Synopsis:**

```
#include <strstrea.h>
public:
void strstreambuf::freeze(int frozen = 1);
```

**Semantics:** The `freeze` public member function enables and disables automatic deletion of the *reserve area*. If the `freeze` public member function is called with no parameter or a non-zero parameter, the `strstreambuf` object is frozen. If the `freeze` public member function is called with a zero parameter, the `strstreambuf` object is unfrozen.

A frozen `strstreambuf` object does not free the *reserve area* in the destructor. If the `strstreambuf` object is destroyed while it is frozen, it is the program's responsibility to also free the *reserve area*.

If characters are written to the `strstreambuf` object while it is frozen, the effect is undefined since the *reserve area* may be reallocated and therefore may move. However, if the `strstreambuf` object is frozen and then unfrozen, characters may be written to it.

**Results:** The `freeze` public member function returns the previous frozen state.

**See Also:** `strstreambuf::str`, `~strstreambuf`

## ***strstreambuf::overflow()***

---

**Synopsis:**

```
#include <strstrea.h>
public:
 virtual int strstreambuf::overflow(int ch = EOF);
```

**Semantics:** The `overflow` public virtual member function provides the output communication between the `streambuf` member functions and the `strstreambuf` object. Member functions in the `streambuf` class call the `overflow` public virtual member function when the *put area* is full. The `overflow` public virtual member function attempts to grow the *put area* so that writing may continue.

The `overflow` public virtual member function performs the following steps:

1. If dynamic allocation is not being used, the *put area* cannot be extended, so the `overflow` public virtual member function fails.
2. If dynamic allocation is being used, a new buffer is allocated using the `doallocate` member function. It handles copying the contents of the old buffer to the new buffer and discarding the old buffer.
3. If the *ch* parameter is not EOF, it is added to the end of the extended *put area* and the *put pointer* is advanced.

**Results:** The `overflow` public virtual member function returns `__NOT_EOF` when it successfully extends the *put area*, otherwise EOF is returned.

**See Also:** `streambuf::overflow`  
`strstreambuf::underflow`

**Synopsis:** #include <strstrea.h>  
public:

```
virtual streampos strstreambuf::seekoff(streamoff offset,
ios::seekdir dir,
ios::openmode mode);
```

**Semantics:** The `seekoff` public virtual member function positions the *get pointer* and/or *put pointer* to the specified position in the *reserve area*. If the *get pointer* is moved, it is moved to a position relative to the start of the *reserve area* (which is also the start of the *get area*). If a position is specified that is beyond the end of the *get area* but is in the *put area*, the *get area* is extended to include the *put area*. If the *put pointer* is moved, it is moved to a position relative to the start of the *put area*, **not** relative to the start of the *reserve area*.

The `seekoff` public virtual member function seeks *offset* bytes from the position specified by the *dir* parameter.

The *mode* parameter may be `ios::in`, `ios::out`, or `ios::in|ios::out` and should be interpreted as follows, provided the interpretation is meaningful:

|                               |                                                                         |
|-------------------------------|-------------------------------------------------------------------------|
| <code>ios::in</code>          | the <i>get pointer</i> should be moved.                                 |
| <code>ios::out</code>         | the <i>put pointer</i> should be moved.                                 |
| <code>ios::in ios::out</code> | both the <i>get pointer</i> and the <i>put pointer</i> should be moved. |

If *mode* has any other value, the `seekoff` public virtual member function fails.  
`ios::in|ios::out` is not valid if the *dir* parameter is `ios::cur`.

The *dir* parameter may be `ios::beg`, `ios::cur`, or `ios::end` and is interpreted in conjunction with the *offset* parameter as follows:

|                       |                                                                                                                                   |
|-----------------------|-----------------------------------------------------------------------------------------------------------------------------------|
| <code>ios::beg</code> | the <i>offset</i> is relative to the start and should be a positive value.                                                        |
| <code>ios::cur</code> | the <i>offset</i> is relative to the current position and may be positive<br>(seek towards end) or negative (seek towards start). |
| <code>ios::end</code> | the <i>offset</i> is relative to the end and should be a negative value.                                                          |

If the *dir* parameter has any other value, or the *offset* parameter does not have an appropriate sign, the `seekoff` public virtual member function fails.

**Results:** The `seekoff` public virtual member function returns the new position in the file on success, otherwise EOF is returned. If both or `ios::in|ios::out` are specified and the *dir* parameter is `ios::cur` the returned position refers to the *put pointer*.

## ***strstreambuf::setbuf()***

---

**Synopsis:**

```
#include <strstrea.h>
public:
 virtual streambuf *strstreambuf::setbuf(char *, int size);
```

**Semantics:** The `setbuf` public virtual member function is used to control the size of the allocations when the `strstreambuf` object is using dynamic allocation. The first parameter is ignored. The next time an allocation is required, at least the number of characters specified in the `size` parameter is allocated. If the specified size is not sufficient, the allocation reverts to its default behavior, which is to extend the buffer by `DEFAULT_MAINBUF_SIZE`, which is 512 characters.

If a program is going to write a large number of characters to the `strstreambuf` object, it should call the `setbuf` public virtual member function to indicate the size of the next allocation, to prevent multiple allocations as the buffer gets larger.

**Results:** The `setbuf` public virtual member function returns a pointer to the `strstreambuf` object.

**See Also:** `strstreambuf::alloc_size_increment`, `doallocate`

**Synopsis:**

```
#include <strstrea.h>
public:
char *strstreambuf::str();
```

**Semantics:** The `str` public member function freezes the `strstreambuf` object and returns a pointer to the *reserve area*. This pointer remains valid after the `strstreambuf` object is destroyed provided the `strstreambuf` object remains frozen, since the destructor does not free the *reserve area* if it is frozen.

The returned pointer may be `NULL` if the `strstreambuf` object is using dynamic allocation but has not yet had anything written to it.

If the `strstreambuf` object is not using dynamic allocation, the pointer returned by the `str` public member function is the same buffer pointer provided to the constructor. For a `strstreambuf` object using dynamic allocation, the pointer points to a dynamically allocated area.

Note that the *reserve area* does not necessarily end with a null character. If the pointer returned by the `str` public member function is to be interpreted as a C string, it is the program's responsibility to ensure that the null character is present.

**Results:** The `str` public member function returns a pointer to the *reserve area* and freezes the `strstreambuf` object.

**See Also:** `strstreambuf::freeze`

## *strstreambuf::strstreambuf()*

---

**Synopsis:**

```
#include <strstrea.h>
public:
 strstreambuf::strstreambuf();
```

**Semantics:** This form of the public `strstreambuf` constructor creates an empty `strstreambuf` object that uses dynamic allocation. No *reserve area* is allocated to start. Whenever characters are written to extend the `strstreambuf` object, the *reserve area* is reallocated and copied as required. The size of allocation is determined by the `strstreambuf` object unless the `setbuf` or `alloc_size_increment` member functions are called to change the allocation size. The default allocation size is determined by the constant `DEFAULT_MAINBUF_SIZE`, which is 512.

**Results:** This form of the public `strstreambuf` constructor creates a `strstreambuf` object.

**See Also:** `strstreambuf::doallocate`, `~strstreambuf`

**Synopsis:**

```
#include <strstrea.h>
public:
 strstreambuf::strstreambuf(int alloc_size);
```

**Semantics:** This form of the public `strstreambuf` constructor creates an empty `strstreambuf` object that uses dynamic allocation. No buffer is allocated to start. Whenever characters are written to extend the `strstreambuf` object, the *reserve area* is reallocated and copied as required. The size of the first allocation is determined by the `alloc_size` parameter, unless changed by a call to the `setbuf` or `alloc_size_increment` member functions.

Note that the `alloc_size` parameter is the starting *reserve area* size. When the *reserve area* is reallocated, the `strstreambuf` object uses `DEFAULT_MAINBUF_SIZE` to increase the *reserve area* size, unless the `setbuf` or `alloc_size_increment` member functions have been called to specify a new allocation size.

**Results:** This form of the public `strstreambuf` constructor creates a `strstreambuf` object.

**See Also:** `strstreambuf::alloc_size_increment`, `doallocate`, `setbuf`, `~strstreambuf`

## ***strstreambuf::strstreambuf()***

---

**Synopsis:**

```
#include <strstrea.h>
public:
 strstreambuf::strstreambuf(void * (*alloc_fn)(long),
 void (*free_fn)(void *));
```

**Semantics:** This form of the public `strstreambuf` constructor creates an empty `strstreambuf` object that uses dynamic allocation. No buffer is allocated to start. Whenever characters are written to extend the `strstreambuf` object, the *reserve area* is reallocated and copied as required, using the specified `alloc_fn` and `free_fn` functions. The size of allocation is determined by the class unless the `setbuf` or `alloc_size_increment` member functions are called to change the allocation size. The default allocation size is determined by the constant `DEFAULT_MAINBUF_SIZE`, which is 512.

When a new *reserve area* is allocated, the function specified by the `alloc_fn` parameter is called with a `long` integer value indicating the number of bytes to allocate. If `alloc_fn` is `NULL`, the `operator new` intrinsic function is used. Likewise, when the *reserve area* is freed, the function specified by the `free_fn` parameter is called with the pointer returned by the `alloc_fn` function as the parameter. If `free_fn` is `NULL`, the `operator delete` intrinsic function is used.

**Results:** This form of the public `strstreambuf` constructor creates a `strstreambuf` object.

**See Also:** `strstreambuf::alloc_size_increment`, `doallocate`, `setbuf`, `~strstreambuf`

---

**Synopsis:**

```
#include <strstrea.h>
public:
 strstreambuf::strstreambuf(char *str,
 int len,
 char *pstart = NULL);
 strstreambuf::strstreambuf(signed char *str,
 int len,
 signed char *pstart = NULL);
 strstreambuf::strstreambuf(unsigned char *str,
 int len,
 unsigned char *pstart = NULL);
```

**Semantics:** This form of the public `strstreambuf` constructor creates a `strstreambuf` object that does not use dynamic allocation (unless `str` is `NULL`). The `strstreambuf` object is said to be using static allocation. The `str` and `len` parameters specify the bounds of the *reserve area*.

The `str`, `len` and `pstart` parameters are interpreted as follows:

1. The buffer starts at `str`.
2. If `len` is positive, the buffer is `len` characters long.
3. If `len` is zero, `str` is a pointer to a C string which is terminated by a null character, and the length of the buffer is the length of the string.
4. If `len` is negative, the buffer is unbounded. This last form should be used with extreme caution, since no buffer is truly unlimited in size and it would be easy to write beyond the available space.
5. If the `pstart` parameter is `NULL`, the `strstreambuf` object is read-only.
6. Otherwise, `pstart` divides the buffer into two regions. The *get area* starts at `str` and ends at `pstart-1`. The *put area* starts at `pstart` and goes to the end of the buffer.

If the *get area* is exhausted and characters have been written to the *put area*, the *get area* is extended to include the *put area*.

The *get pointer* and *put pointer* do not necessarily point at the same position in the *reserve area*, so a read followed by a write does not imply that the write stores following the last character read. The *get pointer* is positioned following the last read operation, and the *put pointer* is positioned following the last write operation, unless the `seekoff` member function has been used to reposition the pointer(s).

Note that if `str` is `NULL` the effect is to create an empty dynamic `strstreambuf` object.

**Results:** This form of the public `strstreambuf` constructor creates a `strstreambuf` object.

**See Also:** `~strstreambuf`

## ***strstreambuf::~strstreambuf()***

---

**Synopsis:**

```
#include <strstrea.h>
public:
 strstreambuf::~strstreambuf();
```

**Semantics:**

The public `~strstreambuf` destructor destroys the `strstreambuf` object after discarding the *reserve area*. The *reserve area* is discarded only if the `strstreambuf` object is using dynamic allocation and is not frozen. The *reserve area* is freed using the free function specified by the form of the constructor that allows specification of the allocate and free functions, or using the `operator delete` intrinsic function. If the `strstreambuf` object is frozen or using static allocation, the user of the `strstreambuf` object must have a pointer to the *reserve area* and is responsible for freeing it. The call to the public `~strstreambuf` destructor is inserted implicitly by the compiler at the point where the `strstreambuf` object goes out of scope.

**Results:** The `strstreambuf` object is destroyed.

**See Also:** `strstreambuf`

**Synopsis:**

```
#include <strstrea.h>
public:
 virtual int strstreambuf::sync();
```

**Semantics:** The sync public virtual member function does nothing because there is no external device with which to synchronize.

**Results:** The sync public virtual member function returns \_\_NOT\_EOF.

## ***strstreambuf::underflow()***

---

**Synopsis:**

```
#include <strstrea.h>
public:
 virtual int strstreambuf::underflow();
```

**Semantics:** The `underflow` public virtual member function provides the input communication between the `streambuf` member functions and the `strstreambuf` object. Member functions in the `streambuf` class call the `underflow` public virtual member function when the *get area* is empty.

If there is a non-empty *put area* present following the *get area*, the *get area* is extended to include the *put area*, allowing the input operation to continue using the *put area*. Otherwise the *get area* cannot be extended.

**Results:** The `underflow` public virtual member function returns the first available character in the *get area* on successful extension, otherwise EOF is returned.

**See Also:** `streambuf::underflow`  
`strstreambuf::overflow`

---

# **19 String Class**

This class is used to store arbitrarily long sequences of characters in memory. Objects of this type may be concatenated, substringed, compared and searched without the need for memory management by the user. Unlike a C string, this object has no delimiting character, so any character in the collating sequence, or character set, may be stored in an object.

The class documented here is the Open Watcom legacy string class. It is not related to the `std::basic_string` class template nor to its corresponding specialization `std::string`.

**Declared:** string.hpp

The `String` class is used to store arbitrarily long sequences of characters in memory. Objects of this type may be concatenated, substringed, compared and searched without the need for memory management by the user. Unlike a C string, a `String` object has no delimiting character, so any character in the collating sequence, or character set, may be stored in a `String` object.

## **Public Functions**

The following constructors and destructors are declared:

```
String();
String(size_t, capacity);
String(String const &, size_t = 0, size_t = NPOS);
String(char const *, size_t = NPOS);
String(char, size_t = 1);
~String();
```

The following member functions are declared:

```
operator char const *();
operator char() const;
String &operator =(String const &);
String &operator =(char const *);
String &operator +=(String const &);
String &operator +=(char const *);
String operator ()(size_t, size_t) const;
char &operator ()(size_t);
char const &operator [](size_t) const;
char &operator [](size_t);
int operator !() const;
size_t length() const;
char const &get_at(size_t) const;
void put_at(size_t, char);
int match(String const &) const;
int match(char const *) const;
int index(String const &, size_t = 0) const;
int index(char const *, size_t = 0) const;
String upper() const;
String lower() const;
int valid() const;
int alloc_mult_size() const;
int alloc_mult_size(int);
```

The following friend functions are declared:

```
friend int operator ==(String const &, String const &);
friend int operator ==(String const &, char const *);
friend int operator ==(char const *, String const &);
friend int operator ==(String const &, char);
friend int operator ==(char , String const &);
friend int operator !=(String const &, String const &);
friend int operator !=(String const &, char const *);
friend int operator !=(char const *, String const &);
friend int operator !=(String const &, char);
friend int operator !=(char , String const &);
friend int operator <(String const &, String const &);
```

```
friend int operator <(String const &, char const *);
friend int operator <(char const *, String const &);
friend int operator <(String const &, char);
friend int operator <(char , String const &);
friend int operator <=(String const &, String const &);
friend int operator <=(String const &, char const *);
friend int operator <=(char const *, String const &);
friend int operator <=(String const &, char);
friend int operator <=(char , String const &);
friend int operator >(String const &, String const &);
friend int operator >(String const &, char const *);
friend int operator >(char const *, String const &);
friend int operator >(String const &, char);
friend int operator >(char , String const &);
friend int operator >=(String const &, String const &);
friend int operator >=(String const &, char const *);
friend int operator >=(char const *, String const &);
friend int operator >=(String const &, char);
friend int operator >=(char , String const &);
friend String operator +(String &, String const &);
friend String operator +(String &, char const *);
friend String operator +(char const *, String const &);
friend String operator +(String &, char);
friend String operator +(char , String const &);
friend int valid(String const &);
```

The following I/O Stream inserter and extractor functions are declared:

```
friend istream &operator >>(istream &, String &);
friend ostream &operator <<(ostream &, String const &);
```

## *String::alloc\_mult\_size()*

---

**Synopsis:**

```
#include <string.hpp>
public:
 int String::alloc_mult_size() const;
 int String::alloc_mult_size(int mult);
```

**Semantics:** The `alloc_mult_size` public member function is used to query and/or change the allocation multiple size.

The first form of the `alloc_mult_size` public member function queries the current setting.

The second form of the `alloc_mult_size` public member function sets the value to a multiple of 8 based on the *mult* parameter. The value of *mult* is rounded down to a multiple of 8 characters. If *mult* is less than 8, the new multiple size is 1 and allocation sizes are exact.

The scheme used to store a `String` object allocates the memory for the characters in multiples of some size. By default, this size is 8 characters. A `String` object with a length of 10 actually has 16 characters of storage allocated for it. Concatenating more characters on the end of the `String` object only allocates a new storage block if more than 6 (16-10) characters are appended. This scheme tries to find a balance between reallocating frequently (multiples of a small value) and creating a large amount of unused space (multiples of a large value).

**Results:** The `alloc_mult_size` public member function returns the previous allocation multiple size.

**Synopsis:**

```
#include <string.hpp>
public:
 char const &String::get_at(size_t pos);
```

**Semantics:** The `get_at` public member function creates a `const` reference to the character at offset `pos` within the `String` object. This reference may not be used to modify that character. The first character of a `String` object is at position zero.

If `pos` is greater than or equal to the length of the `String` object, and the resulting reference is used, the behavior is undefined.

The reference is associated with the `String` object, and therefore has meaning only as long as the `String` object is not modified (or destroyed). If the `String` object has been modified and an old reference is used, the behavior is undefined.

**Results:** The `get_at` public member function returns a `const` reference to a character.

**See Also:** `String::put_at`, `operator []`, `operator ()`

## ***String::index()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 int String::index(String const &str, size_t pos = 0) const;
 int String::index(char const *pch, size_t pos = 0) const;
```

**Semantics:** The `index` public member function computes the offset at which a sequence of characters in the `String` object is found.

The first form searches the `String` object for the contents of the `str` `String` object.

The second form searches the `String` object for the sequence of characters pointed at by `pch`.

If `pos` is specified, the search begins at that offset from the start of the `String` object. Otherwise, the search begins at offset zero (the first character).

The `index` public member function treats upper and lower case letters as not equal.

**Results:** The `index` public member function returns the offset at which the sequence of characters is found. If the substring is not found, -1 is returned.

**See Also:** `String::lower`, `operator !=`, `operator ==`, `match`, `upper`

**Synopsis:**

```
#include <string.hpp>
public:
 size_t String::length() const;
```

**Semantics:** The `length` public member function computes the number of characters contained in the `String` object.

**Results:** The `length` public member function returns the number of characters contained in the `String` object

## *String::lower()*

---

**Synopsis:**

```
#include <string.hpp>
public:
 String String::lower() const;
```

**Semantics:** The `lower` public member function creates a `String` object whose value is the same as the original object's value, except that all upper-case letters have been converted to lower-case.

**Results:** The `lower` public member function returns a lower-case `String` object.

**See Also:** `String::upper`

**Synopsis:**

```
#include <string.hpp>
public:
 int String::match(String const &str) const;
 int String::match(char const *pch) const;
```

**Semantics:** The `match` public member function compares two character sequences to find the offset where they differ.

The first form compares the `String` object to the `str` `String` object.

The second form compares the `String` object to the `pch` C string.

The first character is at offset zero. The `match` public member function treats upper and lower case letters as not equal.

**Results:** The `match` public member function returns the offset at which the two character sequences differ. If the character sequences are equal, -1 is returned.

**See Also:** `String::index`, `lower`, `operator !=`, `operator ==`, `upper`

## *String::operator !()*

---

**Synopsis:**

```
#include <string.hpp>
public:
 int String::operator !() const;
```

**Semantics:** The operator ! public member function tests the validity of the `String` object.

**Results:** The operator ! public member function returns a non-zero value if the `String` object is invalid, otherwise zero is returned.

**See Also:** `String::valid`, `valid`

**Synopsis:**

```
#include <string.hpp>
public:
 friend int operator !=(String const &lft, String const &rht);
 friend int operator !=(String const &lft, char const *rht);
 friend int operator !=(char const *lft, String const &rht);
 friend int operator !=(String const &lft, char rht);
 friend int operator !=(char lft, String const &rht);
```

**Semantics:** The operator `!=` function compares two sequences of characters in terms of an *inequality* relationship.

A `String` object is different from another `String` object if the lengths are different or they contain different sequences of characters. A `String` object and a C string are different if their lengths are different or they contain a different sequence of characters. A C string is terminated by a null character. A `String` object and a character are different if the `String` object does not contain only the character. Upper-case and lower-case characters are considered different.

**Results:** The operator `!=` function returns a non-zero value if the lengths or sequences of characters in the *lft* and *rht* parameter are different, otherwise zero is returned.

**See Also:** `String::operator ==`, `operator <`, `operator <=`, `operator >`, `operator >=`

## *String::operator ()()*

---

**Synopsis:**

```
#include <string.hpp>
public:
 char &String::operator ()(size_t pos);
```

**Semantics:** The `operator ()` public member function creates a reference to the character at offset *pos* within the `String` object. This reference may be used to modify that character. The first character of a `String` object is at position zero.

If *pos* is greater than or equal to the length of the `String` object, and the resulting reference is used, the behavior is undefined.

If the reference is used to modify other characters within the `String` object, the behavior is undefined.

The reference is associated with the `String` object, and therefore has meaning only as long as the `String` object is not modified (or destroyed). If the `String` object has been modified and an old reference is used, the behavior is undefined.

**Results:** The `operator ()` public member function returns a reference to a character.

**See Also:** `String::operator []`, `operator char`, `operator char const *`

**Synopsis:**

```
#include <string.hpp>
public:
 String String::operator ()(size_t pos, size_t len) const;
```

**Semantics:** This form of the `operator ()` public member function extracts a sub-sequence of characters from the `String` object. A new `String` object is created that contains the sub-sequence of characters. The sub-sequence begins at offset `pos` within the `String` object and continues for `len` characters. The first character of a `String` object is at position zero.

If `pos` is greater than or equal to the length of the `String` object, the result is empty.

If `len` is such that `pos + len` exceeds the length of the object, the result is the sub-sequence of characters from the `String` object starting at offset `pos` and running to the end of the `String` object.

**Results:** The `operator ()` public member function returns a `String` object.

**See Also:** `String::operator []`, `operator char`, `operator char const *`

## ***String operator +()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 friend String operator +(String &lft, String const &rht);
 friend String operator +(String &lft, char const *rht);
 friend String operator +(char const *lft, String const &rht);
 friend String operator +(String &lft, char rht);
 friend String operator +(char lft, String const &rht);
```

**Semantics:** The `operator +` function concatenates two sequences of characters into a new `String` object. The new `String` object contains the sequence of characters from the *lft* parameter followed by the sequence of characters from the *rht* parameter.

A NULL pointer to a C string is treated as a pointer to an empty C string.

**Results:** The `operator +` function returns a new `String` object that contains the characters from the *lft* parameter followed by the characters from the *rht* parameter.

**See Also:** `String::operator +=`

**Synopsis:**

```
#include <string.hpp>
public:
 String &String::operator +=(String const &str);
 String &String::operator +=(char const *pch);
```

**Semantics:**

The `operator +=` public member function appends the contents of the parameter to the end of the `String` object.

The first form of the `operator +=` public member function appends the contents of the `str` `String` object to the `String` object.

The second form appends the null-terminated sequence of characters stored at `pch` to the `String` object. If the `pch` parameter is `NULL`, nothing is appended.

**Results:**

The `operator +=` public member function returns a reference to the `String` object that was the target of the assignment.

**See Also:**

`String::operator =`

## ***String operator <()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 friend int operator <(String const &lft, String const &rht);
 friend int operator <(String const &lft, char const *rht);
 friend int operator <(char const *lft, String const &rht);
 friend int operator <(String const &lft, char rht);
 friend int operator <(char lft, String const &rht);
```

**Semantics:** The operator `<` function compares two sequences of characters in terms of a *less-than* relationship.

*lft* is less-than *rht* if *lft* if the characters of *lft* occur before the characters of *rht* in the collating sequence. Upper-case and lower-case characters are considered different.

**Results:** The operator `<` function returns a non-zero value if the *lft* sequence of characters is less than the *rht* sequence, otherwise zero is returned.

**See Also:** `String::operator !=`, `operator ==`, `operator <=`, `operator >`, `operator >=`

**Synopsis:**

```
#include <string.hpp>
public:
 friend ostream &operator <<(ostream &strm, String const &str);
```

**Semantics:**

The operator `<<` function is used to write the sequence of characters in the `str` `String` object to the `strm` `ostream` object. Like C strings, the value of the `str` `String` object is written to `strm` without the addition of any characters. No special processing occurs for any characters in the `String` object that have special meaning for the `strm` object, such as carriage-returns.

The underlying implementation of the operator `<<` function uses the `ostream` write method, which writes unformatted characters to the output stream. If formatted output is required, then the programmer should make use of the classes accessor methods, such as `c_str()`, and pass the resulting data item to the stream using the appropriate insert operator.

**Results:**

The operator `<<` function returns a reference to the `strm` parameter.

**See Also:**

`ostream`

## ***String operator <=()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 friend int operator <=(String const &lft, String const &rht);
 friend int operator <=(String const &lft, char const *rht);
 friend int operator <=(char const *lft, String const &rht);
 friend int operator <=(String const &lft, char rht);
 friend int operator <=(char lft, String const &rht);
```

**Semantics:** The operator `<=` function compares two sequences of characters in terms of a *less-than or equal* relationship.

*lft* is less-than or equal to *rht* if the characters of *lft* are equal to or occur before the characters of *rht* in the collating sequence. Upper-case and lower-case characters are considered different.

**Results:** The operator `<=` function returns a non-zero value if the *lft* sequence of characters is less than or equal to the *rht* sequence, otherwise zero is returned.

**See Also:** `String::operator !=`, `operator ==`, `operator <`, `operator >`, `operator >=`

**Synopsis:**

```
#include <string.hpp>
public:
 String &String::operator =(String const &str);
 String &String::operator =(char const *pch);
```

**Semantics:** The `operator =` public member function sets the contents of the `String` object to be the same as the parameter.

The first form of the `operator =` public member function sets the value of the `String` object to be the same as the value of the `str` `String` object.

The second form sets the value of the `String` object to the null-terminated sequence of characters stored at `pch`. If the `pch` parameter is `NULL`, the `String` object is empty.

**Results:** The `operator =` public member function returns a reference to the `String` object that was the target of the assignment.

**See Also:** `String::operator +=`, `String`

## ***String operator ==()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 friend int operator ==(String const &lft, String const &rht);
 friend int operator ==(String const &lft, char const *rht);
 friend int operator ==(char const *lft, String const &rht);
 friend int operator ==(String const &lft, char rht);
 friend int operator ==(char lft, String const &rht);
```

**Semantics:** The `operator ==` function compares two sequences of characters in terms of an *equality* relationship.

A `String` object is equal to another `String` object if they have the same length and they contain the same sequence of characters. A `String` object and a C string are equal if their lengths are the same and they contain the same sequence of characters. The C string is terminated by a null character. A `String` object and a character are equal if the `String` object contains only that character. Upper-case and lower-case characters are considered different.

**Results:** The `operator ==` function returns a non-zero value if the lengths and sequences of characters in the *lft* and *rht* parameter are identical, otherwise zero is returned.

**See Also:** `String::operator !=`, `operator <`, `operator <=`, `operator >`, `operator >=`

**Synopsis:**

```
#include <string.hpp>
public:
 friend int operator >(String const &lft, String const &rht);
 friend int operator >(String const &lft, char const *rht);
 friend int operator >(char const *lft, String const &rht);
 friend int operator >(String const &lft, char rht);
 friend int operator >(char lft, String const &rht);
```

**Semantics:** The `operator >` function compares two sequences of characters in terms of a *greater-than* relationship.

*lft* is greater-than *rht* if the characters of *lft* occur after the characters of *rht* in the collating sequence. Upper-case and lower-case characters are considered different.

**Results:** The `operator >` function returns a non-zero value if the *lft* sequence of characters is greater than the *rht* sequence, otherwise zero is returned.

**See Also:** `String::operator !=, operator ==, operator <, operator <=, operator >=`

## ***String operator >=()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 friend int operator >=(String const &lft, String const &rht);
 friend int operator >=(String const &lft, char const *rht);
 friend int operator >=(char const *lft, String const &rht);
 friend int operator >=(String const &lft, char rht);
 friend int operator >=(char lft, String const &rht);
```

**Semantics:** The `operator >=` function compares two sequences of characters in terms of a *greater-than or equal* relationship.

*lft* is greater-than or equal to *rht* if the characters of *lft* are equal to or occur after the characters of *rht* in the collating sequence. Upper-case and lower-case characters are considered different.

**Results:** The `operator >=` function returns a non-zero value if the *lft* sequence of characters is greater than or equal to the *rht* sequence, otherwise zero is returned.

**See Also:** `String::operator !=`, `operator ==`, `operator <`, `operator <=`, `operator >`

**Synopsis:**

```
#include <string.hpp>
public:
 friend istream &operator >>(istream &strm, String &str);
```

**Semantics:**

The `operator >>` function is used to read a sequence of characters from the `strm` `istream` object into the `str` `String` object. Like C strings, the gathering of characters for a `str` `String` object ends at the first whitespace encountered, so that the last character placed in `str` is the character before the whitespace.

**Results:**

The `operator >>` function returns a reference to the `strm` parameter.

**See Also:**

`istream`

## *String::operator []()*

---

**Synopsis:**

```
#include <string.hpp>
public:
 char const &String::operator [](size_t pos) const;
 char &String::operator [](size_t pos);
```

**Semantics:** The operator `[]` public member function creates either a `const` or a non-`const` reference to the character at offset *pos* within the `String` object. The non-`const` reference may be used to modify that character. The first character of a `String` object is at position zero.

If *pos* is greater than or equal to the length of the `String` object, and the resulting reference is used, the behavior is undefined.

If the non-`const` reference is used to modify other characters within the `String` object, the behavior is undefined.

The reference is associated with the `String` object, and therefore has meaning only as long as the `String` object is not modified (or destroyed). If the `String` object has been modified and an old reference is used, the behavior is undefined.

**Results:** The operator `[]` public member function returns either a `const` or a non-`const` reference to a character.

**See Also:** `String::operator ()`, `operator char`, `operator char const *`

**Synopsis:**

```
#include <string.hpp>
public:
 String::operator char();
```

**Semantics:** The operator `char` public member function converts a `String` object into the first character it contains. If the `String` object is empty, the result is the null character.

**Results:** The operator `char` public member function returns the first character contained in the `String` object. If the `String` object is empty, the null character is returned.

**See Also:** `String::operator ()`, `operator []`, `operator char const *`

## *String::operator char const \*()*

---

**Synopsis:**

```
#include <string.hpp>
public:
 String::operator char const *();
```

**Semantics:** The `operator char const *` public member function converts a `String` object into a C string containing the same length and sequence of characters, terminated by a null character. If the `String` object contains a null character the resulting C string is terminated by that null character.

The returned pointer is associated with the `String` object, and therefore has meaning only as long as the `String` object is not modified. If the intention is to be able to refer to the C string after the `String` object has been modified, a copy of the string should be made, perhaps by using the C library `strdup` function.

The returned pointer is a pointer to a constant C string. If the pointer is used in some way to modify the C string, the behavior is undefined.

**Results:** The `operator char const *` public member function returns a pointer to a null-terminated constant C string that contains the same characters as the `String` object.

**See Also:** `String::operator ()`, `operator []`, `operator char`

**Synopsis:**

```
#include <string.hpp>
public:
void String::put_at(size_t pos, char chr);
```

**Semantics:** The `put_at` public member function modifies the character at offset *pos* within the `String` object. The character at the specified offset is set to the value of *chr*. If *pos* is greater than the number of characters within the `String` object, *chr* is appended to the `String` object.

**Results:** The `put_at` public member function has no return value.

**See Also:** `String::get_at`, `operator []`, `operator ()`, `operator +=`, `operator +`

## ***String::String()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 String::String();
```

**Semantics:** This form of the public `String` constructor creates a default `String` object containing no characters. The created `String` object has length zero.

**Results:** This form of the public `String` constructor produces a `String` object.

**See Also:** `String::operator =`, `operator +=`, `~String`

**Synopsis:**

```
#include <string.hpp>
public:
 String::String(size_t size, String::capacity cap);
```

**Semantics:** This form of the public `String` constructor creates a `String` object. The function constructs a `String` object of length `size` if `cap` is equal to the enumerated `default_size`. The function reserves `size` bytes of memory and sets the length of the `String` object to be zero if `cap` is equal to the enumerated `reserve`.

**Results:** This form of the public `String` constructor produces a `String` object of size `size`.

**See Also:** `String::operator =`, `~String`

## ***String::String()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 String::String(String const &str, size_t pos = 0, size_t num = NPOS
);
```

**Semantics:** This form of the public `String` constructor creates a `String` object which contains a sub-string of the `str` parameter. The sub-string starts at position `pos` within `str` and continues for `num` characters or until the end of the `str` parameter, whichever comes first.

**Results:** This form of the public `String` constructor produces a sub-string or duplicate of the `str` parameter.

**See Also:** `String::operator =`, `operator ()`, `operator []`, `~String`

**Synopsis:**

```
#include <string.hpp>
public:
 String::String(char const *pch, size_t num = NPOS);
```

**Semantics:** This form of the public `String` constructor creates a `String` object from a C string. The `String` object contains the sequence of characters located at the `pch` parameter. Characters are included up to `num` or the end of the C string pointed at by `pch`. Note that C strings are terminated by a null character and that the value of the created `String` object does not contain that character, nor any following it.

**Results:** This form of the public `String` constructor produces a `String` object of at most length `n` containing the characters in the C string starting at the `pch` parameter.

**See Also:** `String::operator =`, `operator char const *`, `operator ()`, `operator []`,  
`~String`

## ***String::String()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 String::String(char ch, size_t rep = 1);
```

**Semantics:** This form of the public `String` constructor creates a `String` object containing *rep* copies of the *ch* parameter.

**Results:** This form of the public `String` constructor produces a `String` object of length *rep* containing only the character specified by the *ch* parameter.

**See Also:** `String::operator =`, `operator char`, `~String`

**Synopsis:**

```
#include <string.hpp>
public:
String::~String();
```

**Semantics:** The public ~*String* destructor destroys the *String* object. The call to the public ~*String* destructor is inserted implicitly by the compiler at the point where the *String* object goes out of scope.

**Results:** The *String* object is destroyed.

**See Also:** *String*

## *String::upper()*

---

**Synopsis:**

```
#include <string.hpp>
public:
 String String::upper() const;
```

**Semantics:** The `upper` public member function creates a new `String` object whose value is the same as the original `String` object, except that all lower-case letters have been converted to upper-case.

**Results:** The `upper` public member function returns a new upper-case `String` object.

**See Also:** `String::lower`

**Synopsis:**

```
#include <string.hpp>
public:
 friend int valid(String const &str);
```

**Semantics:** The `valid` function tests the validity of the `str` `String` object.

**Results:** The `valid` function returns a non-zero value if the `str` `String` object is valid, otherwise zero is returned.

**See Also:** `String::operator !, valid`

## ***String::valid()***

---

**Synopsis:**

```
#include <string.hpp>
public:
 int String::valid() const;
```

**Semantics:** The `valid` public member function tests the validity of the `String` object.

**Results:** The `valid` public member function returns a non-zero value if the `String` object is valid, otherwise zero is returned.

**See Also:** `String::operator !, valid`



`__NOT_EOF` 7

## A

abs, related function  
     Complex 19-20  
 acos, related function  
     Complex 19, 21  
 acosh, related function  
     Complex 19, 22  
 adjustfield, member enumeration  
     ios 665  
 all\_fine, member enumeration  
     WCExcept 70  
     WCIterExcept 75  
 alloc\_mult\_size, member function  
     String 862, 864  
 alloc\_size\_increment, member function  
     strstreambuf 846-847  
 allocate, member function  
     streambuf 792, 794  
 allocator  
     function 259, 263, 286, 290, 416, 514  
 app, member enumeration  
     ios 675  
 append, member enumeration  
     ios 675  
 append, member function  
     WCIsvConstDListIter<Type> 308  
     WCIsvConstSListIter<Type> 308  
     WCIsvDList<Type> 233, 241  
     WCIsvDListIter<Type> 324, 332  
     WCIsvSList<Type> 233, 241  
     WCIsvSListIter<Type> 324, 332  
     WCPtrConstDListIter<Type> 343  
     WCPtrConstSListIter<Type> 343  
     WCPtrDList<Type> 256, 266  
     WCPtrDListIter<Type> 359, 367  
     WCPtrOrderedVector<Type> 525, 532  
     WCPtrSList<Type> 256, 266  
     WCPtrSListIter<Type> 359, 367  
     WCPtrSortedVector<Type> 525, 532  
     WCValConstDListIter<Type> 378  
     WCValConstSListIter<Type> 378  
     WCValDList<Type> 283, 293

WCValDListIter<Type> 394, 402  
 WCValOrderedVector<Type> 568, 576  
 WCValSList<Type> 283, 293  
 WCValSListIter<Type> 394, 402  
 WCValSortedVector<Type> 568, 576  
 arg, related function  
     Complex 19, 23  
 asin, related function  
     Complex 19, 24  
 asinh, related function  
     Complex 19, 25  
 atan, related function  
     Complex 19, 26  
 atanh, related function  
     Complex 19, 27  
 ate, member enumeration  
     ios 675  
 atend, member enumeration  
     ios 675  
 attach, member function  
     filebuf 610, 612  
     fstreambase 635-636

## B

bad, member function  
     ios 655, 657  
 badbit, member enumeration  
     ios 673  
 base, member function  
     streambuf 792, 795  
 basefield, member enumeration  
     ios 665  
 beg, member enumeration  
     ios 683  
 binary, member enumeration  
     ios 675  
 bitalloc, member function  
     ios 656, 658  
 bitHash, member function  
     WCPtrHashDict<Key,Value> 82, 88  
     WCPtrHashSet<Type> 106, 115  
     WCPtrHashTable<Type> 106, 115  
     WCValHashDict<Key,Value> 132, 137  
     WCValHashSet<Type> 154, 163  
     WCValHashTable<Type> 154, 163  
 blen, member function  
     streambuf 792, 796  
 buckets, member function  
     WCPtrHashDict<Key,Value> 82, 89

WCPtrHashSet<Type> 106, 116  
WCPtrHashTable<Type> 106, 116  
WCValHashDict<Key,Value> 132, 138  
WCValHashSet<Type> 154, 164  
WCValHashTable<Type> 154, 164

**C**

cerr 9  
check\_all, member enumeration  
    WCExcept 70  
    WCIterExcept 75  
check\_none, member enumeration  
    WCExcept 70  
    WCIterExcept 75  
cin 9  
clear, member function  
    ios 655, 659  
    WCIsvDList<Type> 233, 242  
    WCIsvSList<Type> 233, 242  
    WCPtrDList<Type> 256, 267  
    WCPtrHashDict<Key,Value> 83, 90  
    WCPtrHashSet<Type> 106, 117  
    WCPtrHashTable<Type> 106, 117  
    WCPtrOrderedVector<Type> 525, 533  
    WCPtrSkipList<Type> 446, 456  
    WCPtrSkipListDict<Key,Value> 426, 432  
    WCPtrSkipListSet<Type> 446, 456  
    WCPtrSList<Type> 256, 267  
    WCPtrSortedVector<Type> 525, 533  
    WCPtrVector<Type> 555, 560  
    WCQueue<Type,FType> 414, 418  
    WCStack<Type,FType> 512, 516  
    WCValDList<Type> 283, 294  
    WCValHashDict<Key,Value> 132, 139  
    WCValHashSet<Type> 154, 165  
    WCValHashTable<Type> 154, 165  
    WCValOrderedVector<Type> 568, 577  
    WCValSkipList<Type> 489, 498  
    WCValSkipListDict<Key,Value> 470, 475  
    WCValSkipListSet<Type> 489, 498  
    WCValSList<Type> 283, 294  
    WCValSortedVector<Type> 568, 577  
    WCValVector<Type> 598, 603  
clearAndDestroy, member function  
    WCIsvDList<Type> 233, 243  
    WCIsvSList<Type> 233, 243  
    WCPtrDList<Type> 256, 268  
    WCPtrHashDict<Key,Value> 83, 91  
    WCPtrHashSet<Type> 106, 118

WCPtrHashTable<Type> 106, 118  
WCPtrOrderedVector<Type> 525, 534  
WCPtrSkipList<Type> 446, 457  
WCPtrSkipListDict<Key,Value> 426, 433  
WCPtrSkipListSet<Type> 446, 457  
WCPtrSList<Type> 256, 268  
WCPtrSortedVector<Type> 525, 534  
WCPtrVector<Type> 555, 561  
WCValDList<Type> 283, 295  
WCValSList<Type> 283, 295

clog 9  
close, member function  
    filebuf 610, 613  
    fstreambase 635, 637  
common types 7  
Complex class 17  
Complex related functions  
    abs 19-20  
    acos 19, 21  
    acosh 19, 22  
    arg 19, 23  
    asin 19, 24  
    asinh 19, 25  
    atan 19, 26  
    atanh 19, 27  
    conj 19, 32  
    cos 19, 33  
    cosh 19, 34  
    exp 19, 35  
    imag 19, 37  
    log 19  
    log10 19, 39  
    norm 19, 40  
    num 38  
    operator != 19, 41  
    operator \* 18, 42  
    operator + 18, 45  
    operator - 18, 48  
    operator / 18, 50  
    operator << 18, 52  
    operator == 18-19, 54  
    operator >> 18, 55  
    polar 19, 56  
    pow 19, 57  
    real 19, 59  
    sin 19, 60  
    sinh 19, 61  
    sqrt 19, 62  
    tan 19, 63  
    tanh 19, 64

Complex::Complex 18, 28-30  
Complex::imag 18, 36  
Complex::operator \*= 18, 43  
Complex::operator + 18, 44

Complex::operator += 18, 46  
 Complex::operator - 18, 47  
 Complex::operator == 18, 49  
 Complex::operator /= 18, 51  
 Complex::operator = 18, 53  
 Complex::real 18, 58  
 Complex::~Complex 18, 31  
 conj, related function  
     Complex 19, 32  
 constructor  
     Complex 18, 28-30  
     filebuf 610, 615-617  
     fstream 628-632  
     fstreambase 635, 638-641  
     ifstream 648-652  
     ios 655, 670-671  
     iostream 691-694  
     istream 698, 710-712  
     istrstream 729-731  
     ofstream 748-752  
     ostream 755, 769-771  
     ostrstream 778-780  
     stdiobuf 784, 786-787  
     streambuf 792, 830-831  
     String 862, 888-892  
     strstream 836, 838-839  
     strstreambase 841, 843-844  
     strstreambuf 846, 854-857  
 WCDLink 230-231  
 WCExcept 66-67  
 WCIsvConstSListIter<Type> 308  
 WCIsvSList<Type> 233  
 WCIsvSListIter<Type> 324  
 WCIterExcept 71-72  
 WCPtrConstSListIter<Type> 343  
 WCPtrHashDict<Key,Value> 84-86  
 WCPtrHashDictIter<Key,Value> 180  
 WCPtrHashSetIter<Type> 202  
 WCPtrHashTable<Type> 107-109, 111-113  
 WCPtrSkipList<Type> 448-450, 452-454  
 WCPtrSkipListDict<Key,Value> 428-430  
 WCPtrSList<Type> 256  
 WCPtrSListIter<Type> 359  
 WCPtrSortedVector<Type> 526-527, 529-530  
 WCPtrVector<Type> 555-558  
 WCQueue<Type,FType> 414-416  
 WCSLink 280-281  
 WCStack<Type,FType> 512-514  
 WCValConstSListIter<Type> 378  
 WCValHashDict<Key,Value> 133-135  
 WCValHashDictIter<Key,Value> 191  
 WCValHashSetIter<Type> 215  
 WCValHashTable<Type> 155-157, 159-161  
 WCValSkipList<Type> 490-492, 494-496  
 WCValSkipListDict<Key,Value> 471-473  
 WCValSList<Type> 283  
 WCValSListIter<Type> 394  
 WCValSortedVector<Type> 570-571, 573-574  
 WCValVector<Type> 598-601  
 container, member function  
     WCIsvConstDListIter<Type> 308, 315  
     WCIsvConstSListIter<Type> 308, 315  
     WCIsvDListIter<Type> 324, 333  
     WCIsvSListIter<Type> 324, 333  
     WCPtrConstDListIter<Type> 343, 350  
     WCPtrConstSListIter<Type> 343, 350  
     WCPtrDListIter<Type> 359, 368  
     WCPtrHashDictIter<Key,Value> 180, 184  
     WCPtrHashSetIter<Type> 202, 209  
     WCPtrHashTableIter<Type> 202, 209  
     WCPtrSListIter<Type> 359, 368  
     WCValConstDListIter<Type> 378, 385  
     WCValConstSListIter<Type> 378, 385  
     WCValDListIter<Type> 394, 403  
     WCValHashDictIter<Key,Value> 191, 195  
     WCValHashSetIter<Type> 215, 222  
     WCValHashTableIter<Type> 215, 222  
     WCValSListIter<Type> 394, 403  
 contains, member function  
     WCIsvDList<Type> 233, 244  
     WCIsvSList<Type> 233, 244  
     WCPtrDList<Type> 256, 269  
     WCPtrHashDict<Key,Value> 83, 92  
     WCPtrHashSet<Type> 106, 119  
     WCPtrHashTable<Type> 106, 119  
     WCPtrOrderedVector<Type> 525, 535  
     WCPtrSkipList<Type> 447, 458  
     WCPtrSkipListDict<Key,Value> 426, 434  
     WCPtrSkipListSet<Type> 447, 458  
     WCPtrSList<Type> 256, 269  
     WCPtrSortedVector<Type> 525, 535  
     WCValDList<Type> 283, 296  
     WCValHashDict<Key,Value> 132, 140  
     WCValHashSet<Type> 154, 166  
     WCValHashTable<Type> 154, 166  
     WCValOrderedVector<Type> 568, 578  
     WCValSkipList<Type> 489, 499  
     WCValSkipListDict<Key,Value> 470, 476  
     WCValSkipListSet<Type> 489, 499  
     WCValSList<Type> 283, 296  
     WCValSortedVector<Type> 568, 578  
 cos, related function  
     Complex 19, 33  
 cosh, related function  
     Complex 19, 34  
 cout 9  
 cur, member enumeration  
     ios 683

current, member function  
  WCIsvConstDListIter<Type> 308, 316  
  WCIsvConstSListIter<Type> 308, 316  
  WCIsvDListIter<Type> 324, 334  
  WCIsvSListIter<Type> 324, 334  
  WCPtrConstDListIter<Type> 343, 351  
  WCPtrConstSListIter<Type> 343, 351  
  WCPtrDListIter<Type> 359, 369  
  WCPtrHashSetIter<Type> 202, 210  
  WCPtrHashTableIter<Type> 202, 210  
  WCPtrSListIter<Type> 359, 369  
  WCValConstDListIter<Type> 378, 386  
  WCValConstSListIter<Type> 378, 386  
  WCValDListIter<Type> 394, 404  
  WCValHashSetIter<Type> 215, 223  
  WCValHashTableIter<Type> 215, 223  
  WCValSListIter<Type> 394, 404

## D

dbp, member function  
  streambuf 793, 797  
deallocor  
  function 259, 263, 286, 290, 416, 514  
dec, manipulator 733-734  
dec, member enumeration  
  ios 665  
destructor  
  Complex 18, 31  
  filebuf 610, 618  
  fstream 628, 633  
  fstreambase 635, 642  
  ifstream 648, 653  
  ios 655, 672  
  iostream 691, 695  
  istream 698, 713  
  istrstream 729, 732  
  ofstream 748, 753  
  ostream 755, 772  
  ostream 778, 781  
  stdiobuf 784, 788  
  streambuf 792, 832  
  String 862, 893  
  strstream 836, 840  
  strstreambase 841, 845  
  strstreambuf 846, 858  
  WCDLink 230, 232  
  WCExcept 66, 68  
  WCIsvConstSListIter<Type> 308  
  WCIsvSListIter<Type> 233

WCIsvSListIter<Type> 324  
WCIterExcept 71, 73  
WCPtrConstSListIter<Type> 343  
WCPtrHashDict<Key,Value> 87  
WCPtrHashDictIter<Key,Value> 180  
WCPtrHashSetIter<Type> 202  
WCPtrHashTable<Type> 110, 114  
WCPtrSkipList<Type> 451, 455  
WCPtrSkipListDict<Key,Value> 431  
WCPtrSList<Type> 256  
WCPtrSListIter<Type> 359  
WCPtrSortedVector<Type> 528, 531  
WCPtrVector<Type> 555, 559  
WCQueue<Type,FType> 414, 417  
WCSLink 280, 282  
WCStack<Type,FType> 512, 515  
WCValConstSListIter<Type> 378  
WCValHashDict<Key,Value> 136  
WCValHashDictIter<Key,Value> 191  
WCValHashSetIter<Type> 215  
WCValHashTable<Type> 158, 162  
WCValSkipList<Type> 493, 497  
WCValSkipListDict<Key,Value> 474  
WCValSList<Type> 283  
WCValSListIter<Type> 394  
WCValSortedVector<Type> 572, 575  
WCValVector<Type> 598, 602  
do\_sgetn, member function  
  streambuf 793, 798  
do\_sputn, member function  
  streambuf 793, 799  
doallocate, member function  
  streambuf 792, 800  
  strstreambuf 846, 848

## E

eatwhite, member function  
  istream 698, 700  
eback, member function  
  streambuf 792, 801  
ebuf, member function  
  streambuf 792, 802  
egptr, member function  
  streambuf 792, 803  
empty\_container  
  exception 70, 246-247, 249, 271-272, 274, 298-299,  
    301, 420-421, 424, 519, 521, 538, 543, 545,  
    551-553, 563, 581, 586, 588, 594-596, 605  
empty\_container, member enumeration

WCExcept 70  
 end, member enumeration  
   ios 683  
 endl, manipulator 733, 735  
 ends, manipulator 733, 736  
 entries, member function  
   WCIsvDList<Type> 233, 245  
   WCIsvSList<Type> 233, 245  
   WCPtrDList<Type> 256, 270  
   WCPtrHashDict<Key,Value> 83, 93  
   WCPtrHashSet<Type> 106, 120  
   WCPtrHashTable<Type> 106, 120  
   WCPtrOrderedVector<Type> 525, 536  
   WCPtrSkipList<Type> 447, 459  
   WCPtrSkipListDict<Key,Value> 426, 435  
   WCPtrSkipListSet<Type> 447, 459  
   WCPtrSList<Type> 256, 270  
   WCPtrSortedVector<Type> 525, 536  
   WCQueue<Type,FType> 414, 419  
   WCStack<Type,FType> 512, 517  
   WCValDList<Type> 283, 297  
   WCValHashDict<Key,Value> 132, 141  
   WCValHashSet<Type> 154, 167  
   WCValHashTable<Type> 154, 167  
   WCValOrderedVector<Type> 568, 579  
   WCValSkipList<Type> 489, 500  
   WCValSkipListDict<Key,Value> 470, 477  
   WCValSkipListSet<Type> 489, 500  
   WCValSList<Type> 283, 297  
   WCValSortedVector<Type> 568, 579  
 EOF 7  
 eof, member function  
   ios 655, 660  
 eofbit, member enumeration  
   ios 673  
 eptr, member function  
   streambuf 792, 804  
 exception handling 3  
 exceptions 70  
   function 75  
 exceptions, member function  
   ios 655, 661  
   WCExcept 66, 69  
   WCIterExcept 71, 74  
 exp, related function  
   Complex 19, 35  
 extractor 11, 698



fail, member function  
   ios 655, 662  
 failbit, member enumeration  
   ios 673  
 fd, member function  
   filebuf 610, 614  
   fstreambase 635, 644  
 filebuf 791  
 filebuf::attach 610, 612  
 filebuf::close 610, 613  
 filebuf::fd 610, 614  
 filebuf::filebuf 610, 615-617  
 filebuf::is\_open 610, 619  
 filebuf::open 610, 620  
 filebuf::openprot 610, 621  
 filebuf::overflow 610, 622  
 filebuf::pbackfail 610, 623  
 filebuf::seekoff 611, 624  
 filebuf::setbuf 611, 625  
 filebuf::sync 611, 626  
 filebuf::underflow 610, 627  
 filebuf::~filebuf 610, 618  
 filedesc 7  
 fill character 663  
 fill, member function  
   ios 655, 663  
 find, member function  
   WCIsvDList<Type> 233, 246  
   WCIsvSList<Type> 233, 246  
   WCPtrDList<Type> 256, 271  
   WCPtrHashDict<Key,Value> 83, 94  
   WCPtrHashSet<Type> 106, 121  
   WCPtrHashTable<Type> 106, 121  
   WCPtrOrderedVector<Type> 525, 537  
   WCPtrSkipList<Type> 447, 460  
   WCPtrSkipListDict<Key,Value> 426, 436  
   WCPtrSkipListSet<Type> 447, 460  
   WCPtrSList<Type> 256, 271  
   WCPtrSortedVector<Type> 525, 537  
   WCValDList<Type> 283, 298  
   WCValHashDict<Key,Value> 132, 142  
   WCValHashSet<Type> 154, 168  
   WCValHashTable<Type> 154, 168  
   WCValOrderedVector<Type> 568, 580  
   WCValSkipList<Type> 489, 501  
   WCValSkipListDict<Key,Value> 470, 478  
   WCValSkipListSet<Type> 489, 501  
   WCValSList<Type> 283, 298  
   WCValSortedVector<Type> 568, 580

findKeyAndValue, member function  
  WCPtrHashDict<Key,Value> 83, 95  
  WCPtrSkipListDict<Key,Value> 426, 437  
  WCValHashDict<Key,Value> 132, 143  
  WCValSkipListDict<Key,Value> 470, 479  
findLast, member function  
  WCIsvDList<Type> 233, 247  
  WCIsvSList<Type> 233, 247  
  WCPtrDList<Type> 256, 272  
  WCPtrSList<Type> 256, 272  
  WCValDList<Type> 283, 299  
  WCValSList<Type> 283, 299  
first, member function  
  WCPtrOrderedVector<Type> 525, 538  
  WCPtrSortedVector<Type> 525, 538  
  WCQueue<Type,FType> 414, 420  
  WCValOrderedVector<Type> 568, 581  
  WCValSortedVector<Type> 568, 581  
fixed, member enumeration  
  ios 665  
flags, member function  
  ios 655, 664  
floatfield, member enumeration  
  ios 665  
flush, manipulator 733, 737  
flush, member function  
  ostream 755, 757  
fmtflags, member enumeration  
  ios 655, 665  
forall, member function  
  WCIsvDList<Type> 233, 248  
  WCIsvSList<Type> 233, 248  
  WCPtrDList<Type> 256, 273  
  WCPtrHashDict<Key,Value> 83, 96  
  WCPtrHashSet<Type> 106, 122  
  WCPtrHashTable<Type> 106, 122  
  WCPtrSkipList<Type> 447, 461  
  WCPtrSkipListDict<Key,Value> 426, 438  
  WCPtrSkipListSet<Type> 447, 461  
  WCPtrSList<Type> 256, 273  
  WCValDList<Type> 283, 300  
  WCValHashDict<Key,Value> 132, 144  
  WCValHashSet<Type> 154, 169  
  WCValHashTable<Type> 154, 169  
  WCValSkipList<Type> 489, 502  
  WCValSkipListDict<Key,Value> 470, 480  
  WCValSkipListSet<Type> 489, 502  
  WCValSList<Type> 283, 300  
format precision 679  
format width 689  
formatted input 11  
formatted output 13  
freeze, member function  
  strstreambuf 846, 849

fstream 635, 691  
fstream::fstream 628-632  
fstream::open 628, 634  
fstream::~fstream 628, 633  
fstreambase 628, 648, 748  
fstreambase::attach 635-636  
fstreambase::close 635, 637  
fstreambase::fd 635, 644  
fstreambase::fstreambase 635, 638-641  
fstreambase::is\_open 635, 643  
fstreambase::open 635, 645  
fstreambase::rdbuf 635, 646  
fstreambase::setbuf 635, 647  
fstreambase::~fstreambase 635, 642  
functions and types 15

## G

gbump, member function  
  streambuf 792, 805  
gcount, member function  
  istream 699, 701  
get area 791  
get pointer 806  
get, member function  
  istream 698, 702-705  
  WCIsvDList<Type> 233, 249  
  WCIsvSList<Type> 233, 249  
  WCPtrDList<Type> 256, 274  
  WCPtrSList<Type> 256, 274  
  WCQueue<Type,FType> 414, 421  
  WCValDList<Type> 283, 301  
  WCValSList<Type> 283, 301  
get\_at, member function  
  String 862, 865  
getline, member function  
  istream 698, 706  
good, member function  
  ios 655, 668  
goodbit, member enumeration  
  ios 673  
gptr, member function  
  streambuf 792, 806

## H

header files

algorithm 3  
 complex 3  
 exception 3  
 fstream 4  
 functional 3  
 generic 4  
 iomanip 4  
 ios 4  
 iosfwd 4  
 iostream 4  
 istream 4  
 iterator 4  
 limits 4  
 list 4  
 map 4  
 memory 4  
 new 5  
 numeric 5  
 ostream 5  
 set 5  
 stdiobuf 5  
 streambuf 5  
 string 5  
 strstream 5  
 vector 5  
 wcdefs 5  
 wclbase 5  
 wclcom 5  
 wclibase 5  
 wclist 5  
 wclistit 5  
 wcqueue 6  
 wcstack 6  
 hex, manipulator 733, 738  
 hex, member enumeration  
     ios 665

**I**

ifstream 635, 698  
 ifstream::ifstream 648-652  
 ifstream::open 648, 654  
 ifstream::~ifstream 648, 653  
 ignore, member function  
     istream 698, 707  
 imag, member function  
     Complex 18, 36  
 imag, related function  
     Complex 19, 37  
 in, member enumeration

ios 675  
 in\_avail, member function  
     streambuf 793, 807  
 index, member function  
     String 862, 866  
     WCIsvDList<Type> 233, 250-251  
     WCIsvSList<Type> 233, 250-251  
     WCPtrDList<Type> 256, 275  
     WCPtrOrderedVector<Type> 525, 539  
     WCPtrSList<Type> 256, 275  
     WCPtrSortedVector<Type> 525, 539  
     WCValDList<Type> 283, 302  
     WCValOrderedVector<Type> 568, 582  
     WCValSList<Type> 283, 302  
     WCValSortedVector<Type> 568, 582  
 index\_range  
     exception 70, 100, 148, 247, 272, 299, 420-421,  
         424, 442, 484, 519, 521, 538, 541, 543, 545,  
         563, 581, 584, 586, 588, 605  
 index\_range, member enumeration  
     WCExcept 70  
 init, member function  
     ios 655, 669  
 insert, member function  
     WCIsvConstDListIter<Type> 308  
     WCIsvConstSListIter<Type> 308  
     WCIsvDList<Type> 233, 252  
     WCIsvDListIter<Type> 324, 335  
     WCIsvSList<Type> 233, 252  
     WCIsvSListIter<Type> 324, 335  
     WCPtrConstDListIter<Type> 343  
     WCPtrConstSListIter<Type> 343  
     WCPtrDList<Type> 256, 276  
     WCPtrDListIter<Type> 359, 370  
     WCPtrHashDict<Key, Value> 83, 97  
     WCPtrHashSet<Type> 106, 123  
     WCPtrHashTable<Type> 106, 123  
     WCPtrOrderedVector<Type> 525, 540  
     WCPtrSkipList<Type> 447, 462  
     WCPtrSkipListDict<Key, Value> 426, 439  
     WCPtrSkipListSet<Type> 447, 462  
     WCPtrSList<Type> 256, 276  
     WCPtrSListIter<Type> 359, 370  
     WCPtrSortedVector<Type> 525, 540  
     WCQueue<Type, FType> 414, 422  
     WCValConstDListIter<Type> 378  
     WCValConstSListIter<Type> 378  
     WCValDList<Type> 283, 303  
     WCValDListIter<Type> 394, 405  
     WCValHashDict<Key, Value> 132, 145  
     WCValHashSet<Type> 154, 170  
     WCValHashTable<Type> 154, 170  
     WCValOrderedVector<Type> 568, 583  
     WCValSkipList<Type> 489, 503

WCValSkipListDict<Key,Value> 470, 481  
WCValSkipListSet<Type> 489, 503  
WCValSList<Type> 283, 303  
WCValSListIter<Type> 394, 405  
WCValSortedVector<Type> 568, 583  
insertAt, member function  
  WCPtrOrderedVector<Type> 525, 541  
  WCPtrSortedVector<Type> 525, 541  
  WCValOrderedVector<Type> 568, 584  
  WCValSortedVector<Type> 568, 584  
inserter 13, 755  
internal, member enumeration  
  ios 665  
intrusive  
  classes 233  
ios 635, 698, 755, 841  
ios::adjustfield 665  
ios::app 675  
ios::append 675  
ios::ate 675  
ios::atend 675  
ios::bad 655, 657  
ios::badbit 673  
ios::basefield 665  
ios::beg 683  
ios::binary 675  
ios::bitalloc 656, 658  
ios::clear 655, 659  
ios::cur 683  
ios::dec 665  
ios::end 683  
ios::eof 655, 660  
ios::eofbit 673  
ios::exceptions 655, 661  
ios::fail 655, 662  
ios::failbit 673  
ios::fill 655, 663  
ios::fixed 665  
ios::flags 655, 664  
ios::floatfield 665  
ios::fmtflags 655, 665  
ios::good 655, 668  
ios::goodbit 673  
ios::hex 665  
ios::in 675  
ios::init 655, 669  
ios::internal 665  
ios::ios 655, 670-671  
ios::iostate 655, 673  
ios::iword 656, 674  
ios::left 665  
ios::nocreate 675  
ios::noreplace 675  
ios::oct 665  
ios::openmode 655, 675  
ios::operator ! 656, 677  
ios::operator void \* 656, 678  
ios::out 675  
ios::precision 655, 679  
ios::pword 656, 680  
ios::rdbuf 655, 681  
ios::rdstate 655, 682  
ios::right 665  
ios::scientific 665  
ios::seekdir 655, 683  
ios::setf 655, 684  
ios::setstate 655, 685  
ios::showbase 665  
ios::showpoint 665  
ios::showpos 665  
ios::skipws 665  
ios::stdio 665  
ios::sync\_with\_stdio 656, 686  
ios::text 675  
ios::tie 655, 687  
ios::trunc 675  
ios::truncate 675  
ios::unitbuf 665  
ios::unsetf 655, 688  
ios::uppercase 665  
ios::width 655-656, 689  
ios::xalloc 656, 690  
ios::~ios 655, 672  
iostate, member enumeration  
  ios 655, 673  
iostream 628, 698, 755, 836  
iostream::iostream 691-694  
iostream::operator = 691, 696-697  
iostream::~iostream 691, 695  
ipfx, member function  
  istream 698, 708  
is\_open, member function  
  filebuf 610, 619  
  fstreambase 635, 643  
isEmpty, member function  
  WCIsvDList<Type> 233, 253  
  WCIsvSList<Type> 233, 253  
  WCPtrDList<Type> 256, 277  
  WCPtrHashDict<Key,Value> 83, 98  
  WCPtrHashSet<Type> 106, 124  
  WCPtrHashTable<Type> 106, 124  
  WCPtrOrderedVector<Type> 525, 542  
  WCPtrSkipList<Type> 447, 463  
  WCPtrSkipListDict<Key,Value> 426, 440  
  WCPtrSkipListSet<Type> 447, 463  
  WCPtrSList<Type> 256, 277  
  WCPtrSortedVector<Type> 525, 542  
WCQueue<Type,FType> 414, 423

WCStack<Type,FType> 512, 518  
 WCValDList<Type> 283, 304  
 WCValHashDict<Key,Value> 132, 146  
 WCValHashSet<Type> 154, 171  
 WCValHashTable<Type> 154, 171  
 WCValOrderedVector<Type> 568, 585  
 WCValSkipList<Type> 489, 504  
 WCValSkipListDict<Key,Value> 470, 482  
 WCValSkipListSet<Type> 489, 504  
 WCValSList<Type> 283, 304  
 WCValSortedVector<Type> 568, 585  
 isfx, member function  
     istream 698, 709  
 istream 648, 655, 691, 729  
 istream input 11  
 istream::eatwhite 698, 700  
 istream::gcount 699, 701  
 istream::get 698, 702-705  
 istream::getline 698, 706  
 istream::ignore 698, 707  
 istream::ipfx 698, 708  
 istream::isfx 698, 709  
 istream::istream 698, 710-712  
 istream::operator = 699, 714-715  
 istream::operator >> 699, 716-721  
 istream::peek 699, 722  
 istream::putback 698, 723  
 istream::read 698, 724  
 istream::seekg 698, 725-726  
 istream::sync 699, 727  
 istream::telli 698, 728  
 istream::~istream 698, 713  
 istrstream 698, 841  
 istrstream::istrstream 729-731  
 istrstream::~istrstream 729, 732  
 iter\_range  
     exception 75, 319, 321, 338, 340, 354, 356, 373,  
         375, 389, 391, 408, 410  
 iter\_range, member enumeration  
     WCIterExcept 75  
 iterator classes 5  
 iword, member function  
     ios 656, 674

L

last, member function  
     WCPtrOrderedVector<Type> 525, 543  
     WCPtrSortedVector<Type> 525, 543  
     WCQueue<Type,FType> 414, 424  
     WCValOrderedVector<Type> 568, 586  
     WCValSortedVector<Type> 568, 586  
 left, member enumeration  
     ios 665  
 length, member function  
     String 862, 867  
     WCPtrVector<Type> 555, 562  
     WCValVector<Type> 598, 604  
 list containers 5  
 log, related function  
     Complex 19  
 log10, related function  
     Complex 19, 39  
 lower, member function  
     String 862, 868

M

manipulator manipulators  
     dec 733-734  
     endl 733, 735  
     ends 733, 736  
     flush 733, 737  
     hex 733, 738  
     oct 733, 739  
     resetiosflags 733, 740  
     setbase 733, 741  
     setfill 733, 742  
     setiosflags 733, 743  
     setprecision 733, 744  
     setw 733, 745  
     setwidth 733, 746  
     ws 733, 747  
 manipulators  
     dec 733-734  
     endl 733, 735  
     ends 733, 736  
     flush 733, 737  
     hex 733, 738  
     oct 733, 739  
     resetiosflags 733, 740

K

key, member function  
     WCPtrHashDictIter<Key,Value> 180, 185  
     WCValHashDictIter<Key,Value> 191, 196

setbase 733, 741  
setfill 733, 742  
setiosflags 733, 743  
setprecision 733, 744  
setw 733, 745  
setwidth 733, 746  
ws 733, 747  
match, member function  
  String 862, 869

## N

nocreate, member enumeration  
  ios 675  
noreplace, member enumeration  
  ios 675  
norm, related function  
  Complex 19, 40  
not\_empty  
  exception 70, 87, 110, 114, 136, 158, 162, 237, 240,  
    261, 265, 288, 292, 417, 431, 451, 455, 474,  
    493, 497, 515, 528, 531, 559, 572, 575, 602  
not\_empty, member enumeration  
  WCExcept 70  
not\_unique  
  exception 70, 123, 170, 462, 503  
not\_unique, member enumeration  
  WCExcept 70  
num, related function  
  Complex 38

## O

occurrencesOf, member function  
  WCPtrHashSet<Type> 106, 125  
  WCPtrHashTable<Type> 106, 125  
  WCPtrOrderedVector<Type> 525, 544  
  WCPtrSkipList<Type> 447, 464  
  WCPtrSkipListSet<Type> 447, 464  
  WCPtrSortedVector<Type> 525, 544  
  WCValHashSet<Type> 154, 172  
  WCValHashTable<Type> 154, 172  
  WCValOrderedVector<Type> 568, 587  
  WCValSkipList<Type> 489, 505  
  WCValSkipListSet<Type> 489, 505  
  WCValSortedVector<Type> 568, 587  
oct, manipulator 733, 739

oct, member enumeration  
  ios 665  
ofstream 635, 755  
ofstream::ofstream 748-752  
ofstream::open 748, 754  
ofstream::~ofstream 748, 753  
open, member function  
  filebuf 610, 620  
  fstream 628, 634  
  fstreambase 635, 645  
  ifstream 648, 654  
  ofstream 748, 754  
openmode, member enumeration  
  ios 655, 675  
openprot, member data  
  filebuf 621  
openprot, member function  
  filebuf 610  
operator !=, member function  
  ios 656, 677  
  String 862, 870  
operator !=, related function  
  Complex 19, 41  
  String 862, 871  
operator (), member function  
  String 862, 872-873  
WCIsvConstDListIter<Type> 308, 317  
WCIsvConstSListIter<Type> 308, 317  
WCIsvDListIter<Type> 324, 336  
WCIsvSListIter<Type> 324, 336  
WCPtrConstDListIter<Type> 343, 352  
WCPtrConstSListIter<Type> 343, 352  
WCPtrDListIter<Type> 359, 371  
WCPtrHashDictIter<Key,Value> 180, 186  
WCPtrHashSetIter<Type> 202, 211  
WCPtrHashTableIter<Type> 202, 211  
WCPtrSListIter<Type> 359, 371  
WCValConstDListIter<Type> 378, 387  
WCValConstSListIter<Type> 378, 387  
WCValDListIter<Type> 394, 406  
WCValHashDictIter<Key,Value> 191, 197  
WCValHashSetIter<Type> 215, 224  
WCValHashTableIter<Type> 215, 224  
WCValSListIter<Type> 394, 406  
operator \*, related function  
  Complex 18, 42  
operator \*=, member function  
  Complex 18, 43  
operator ++, member function  
  WCIsvConstDListIter<Type> 308, 318  
  WCIsvConstSListIter<Type> 308, 318  
  WCIsvDListIter<Type> 324, 337  
  WCIsvSListIter<Type> 324, 337  
  WCPtrConstDListIter<Type> 343, 353

- WCPtrConstSListIter<Type> 343, 353  
 WCPtrDListIter<Type> 359, 372  
 WCPtrHashDictIter<Key, Value> 180, 187  
 WCPtrHashSetIter<Type> 202, 212  
 WCPtrHashTableIter<Type> 202, 212  
 WCPtrSListIter<Type> 359, 372  
 WCValConstDListIter<Type> 378, 388  
 WCValConstSListIter<Type> 378, 388  
 WCValDListIter<Type> 394, 407  
 WCValHashDictIter<Key, Value> 191, 198  
 WCValHashSetIter<Type> 215, 225  
 WCValHashTableIter<Type> 215, 225  
 WCValSListIter<Type> 394, 407
- operator +, member function  
 Complex 18, 44
- operator +, related function  
 Complex 18, 45  
 String 863, 874
- operator +=, member function  
 Complex 18, 46  
 String 862, 875
- WCIsvConstDListIter<Type> 308, 319  
 WCIsvConstSListIter<Type> 308, 319  
 WCIsvDListIter<Type> 324, 338  
 WCIsvSListIter<Type> 324, 338  
 WCPtrConstDListIter<Type> 343, 354  
 WCPtrConstSListIter<Type> 343, 354  
 WCPtrDListIter<Type> 359, 373  
 WCPtrSListIter<Type> 359, 373  
 WCValConstDListIter<Type> 378, 389  
 WCValConstSListIter<Type> 378, 389  
 WCValDListIter<Type> 394, 408  
 WCValSListIter<Type> 394, 408
- operator -, member function  
 Complex 18, 47
- operator -, related function  
 Complex 18, 48
- operator --, member function  
 WCIsvConstDListIter<Type> 308, 320  
 WCIsvConstSListIter<Type> 308, 320  
 WCIsvDListIter<Type> 324-325, 339  
 WCIsvSListIter<Type> 324-325, 339  
 WCPtrConstDListIter<Type> 343, 355  
 WCPtrConstSListIter<Type> 343, 355  
 WCPtrDListIter<Type> 359-360, 374  
 WCPtrSListIter<Type> 359-360, 374  
 WCValConstDListIter<Type> 378, 390  
 WCValConstSListIter<Type> 378, 390  
 WCValDListIter<Type> 394-395, 409  
 WCValSListIter<Type> 394-395, 409
- operator ==, member function  
 Complex 18, 49
- WCIsvConstDListIter<Type> 308, 321  
 WCIsvConstSListIter<Type> 308, 321
- WCIsvDListIter<Type> 324-325, 340  
 WCIsvSListIter<Type> 324-325, 340  
 WCPtrConstDListIter<Type> 343, 356  
 WCPtrConstSListIter<Type> 343, 356  
 WCPtrDListIter<Type> 359-360, 375  
 WCPtrSListIter<Type> 359-360, 375  
 WCValConstDListIter<Type> 378, 391  
 WCValConstSListIter<Type> 378, 391  
 WCValDListIter<Type> 394-395, 410  
 WCValSListIter<Type> 394-395, 410
- operator /, related function  
 Complex 18, 50
- operator /=, member function  
 Complex 18, 51
- operator <, related function  
 String 862-863, 876
- operator <<, member function  
 ostream 755-756, 758-764
- operator <<, related function  
 Complex 18, 52  
 String 863, 877
- operator <=, related function  
 String 863, 878
- operator =, member function  
 Complex 18, 53  
 iostream 691, 696-697  
 istream 699, 714-715  
 ostream 755, 765-766  
 String 862, 879
- WCIsvDList<Type> 233, 254  
 WCIsvSList<Type> 233, 254  
 WCPtrDList<Type> 256, 278  
 WCPtrHashDict<Key, Value> 83, 101  
 WCPtrHashSet<Type> 106, 126  
 WCPtrHashTable<Type> 106, 126  
 WCPtrOrderedVector<Type> 525, 546  
 WCPtrSkipList<Type> 447, 465  
 WCPtrSkipListDict<Key, Value> 427, 443  
 WCPtrSkipListSet<Type> 447, 465  
 WCPtrSList<Type> 256, 278  
 WCPtrSortedVector<Type> 525, 546  
 WCPtrVector<Type> 555, 564  
 WCValDList<Type> 284, 305  
 WCValHashDict<Key, Value> 132, 149  
 WCValHashSet<Type> 154, 173  
 WCValHashTable<Type> 154, 173  
 WCValOrderedVector<Type> 569, 589  
 WCValSkipList<Type> 489, 506  
 WCValSkipListDict<Key, Value> 470, 485  
 WCValSkipListSet<Type> 489, 506  
 WCValSList<Type> 284, 305  
 WCValSortedVector<Type> 569, 589  
 WCValVector<Type> 598, 606
- operator ==, member function

WCIsvDList<Type> 234, 255  
WCIsvSList<Type> 234, 255  
WCPtrDList<Type> 256, 279  
WCPtrHashDict<Key,Value> 83, 102  
WCPtrHashSet<Type> 106, 127  
WCPtrHashTable<Type> 106, 127  
WCPtrOrderedVector<Type> 525, 547  
WCPtrSkipList<Type> 447, 466  
WCPtrSkipListDict<Key,Value> 427, 444  
WCPtrSkipListSet<Type> 447, 466  
WCPtrSList<Type> 256, 279  
WCPtrSortedVector<Type> 525, 547  
WCPtrVector<Type> 555, 565  
WCValDList<Type> 284, 306  
WCValHashDict<Key,Value> 132, 150  
WCValHashSet<Type> 154, 174  
WCValHashTable<Type> 154, 174  
WCValOrderedVector<Type> 569, 590  
WCValSkipList<Type> 489, 507  
WCValSkipListDict<Key,Value> 470, 486  
WCValSkipListSet<Type> 489, 507  
WCValSList<Type> 284, 306  
WCValSortedVector<Type> 569, 590  
WCValVector<Type> 598, 607  
operator ==, related function  
    Complex 18-19, 54  
    String 862, 880  
operator >, related function  
    String 863, 881  
operator >=, related function  
    String 863, 882  
operator >>, member function  
    istream 699, 716-721  
operator >>, related function  
    Complex 18, 55  
    String 863, 883  
operator [], member function  
    String 862, 884  
    WCPtrHashDict<Key,Value> 83, 99-100  
    WCPtrOrderedVector<Type> 525, 545  
    WCPtrSkipListDict<Key,Value> 427, 441-442  
    WCPtrSortedVector<Type> 525, 545  
    WCPtrVector<Type> 555, 563  
    WCValHashDict<Key,Value> 132, 147-148  
    WCValOrderedVector<Type> 568, 588  
    WCValSkipListDict<Key,Value> 470, 483-484  
    WCValSortedVector<Type> 568, 588  
    WCValVector<Type> 598, 605  
operator char const \*, member function  
    String 862, 886  
operator char, member function  
    String 862, 885  
operator void \*, member function  
    ios 656, 678  
opfx, member function  
    ostream 755, 767  
osfx, member function  
    ostream 755, 768  
ostream 655, 691, 748, 778  
ostream output 13  
ostream::flush 755, 757  
ostream::operator << 755-756, 758-764  
ostream::operator = 755, 765-766  
ostream::opfx 755, 767  
ostream::osfx 755, 768  
ostream::ostream 755, 769-771  
ostream::put 755, 773  
ostream::seekp 755, 774-775  
ostream::tellp 755, 776  
ostream::write 755, 777  
ostream::~ostream 755, 772  
ostrstream 755, 841  
ostrstream::ostrstream 778-780  
ostrstream::pcount 778, 782  
ostrstream::str 778, 783  
ostrstream::~ostrstream 778, 781  
out, member enumeration  
    ios 675  
out\_of\_memory 367, 370, 402, 405  
exception 70, 84, 86, 97, 99, 101, 104, 107, 109,  
    111, 113, 123, 126, 130, 133, 135, 145, 147,  
    149, 152, 155, 157, 159, 161, 170, 173, 177,  
    260, 264, 266, 276, 278, 287, 291, 293, 303,  
    305, 422, 428, 430, 439, 441, 443, 448, 450,  
    452, 454, 462, 465, 471, 473, 481, 483, 485,  
    490, 492, 494, 496, 503, 506, 520, 527, 530,  
    532, 540-541, 546, 548, 554, 558, 563-564,  
    566, 571, 574, 576, 583-584, 589, 591, 597,  
    601, 605-606, 608  
out\_of\_memory, member enumeration  
    WCExcept 70  
out\_waiting, member function  
    streambuf 793, 808  
overflow, member function  
    filebuf 610, 622  
    stdiobuf 784-785  
    streambuf 793, 809  
    strstreambuf 846, 850



pbackfail, member function  
    filebuf 610, 623  
    streambuf 793, 810

pbase, member function  
     streambuf 792, 811  
 pbump, member function  
     streambuf 792, 812  
 pcount, member function  
     ostrstream 778, 782  
 peek, member function  
     istream 699, 722  
 pointer  
     lists 229  
 polar, related function  
     Complex 19, 56  
 pop, member function  
     WCStack<Type,FType> 512, 519  
 pow, related function  
     Complex 19, 57  
 pptr, member function  
     streambuf 792, 813  
 precision, member function  
     ios 655, 679  
 predefined objects 9  
 prepend, member function  
     WCPtrOrderedVector<Type> 525, 548  
     WCPtrSortedVector<Type> 525, 548  
     WCValOrderedVector<Type> 568, 591  
     WCValSortedVector<Type> 568, 591  
 push, member function  
     WCStack<Type,FType> 512, 520  
 put area 791  
 put pointer 813  
 put, member function  
     ostream 755, 773  
 put\_at, member function  
     String 862, 887  
 putback, member function  
     istream 698, 723  
 pword, member function  
     ios 656, 680

**R**

rdbuf, member function  
     fstreambase 635, 646  
     ios 655, 681  
     strstreambase 841-842  
 rdstate, member function  
     ios 655, 682  
 read, member function  
     istream 698, 724  
 real, member function  
     Complex 18, 58  
 real, related function  
     Complex 19, 59  
 remove, member function  
     WCPtrHashDict<Key,Value> 83, 103  
     WCPtrHashSet<Type> 106, 128  
     WCPtrHashTable<Type> 106, 128  
     WCPtrOrderedVector<Type> 525, 549  
     WCPtrSkipList<Type> 447, 467  
     WCPtrSkipListDict<Key,Value> 426, 445  
     WCPtrSkipListSet<Type> 447, 467  
     WCPtrSortedVector<Type> 525, 549  
     WCValHashDict<Key,Value> 132, 151  
     WCValHashSet<Type> 154, 175  
     WCValHashTable<Type> 154, 175  
     WCValOrderedVector<Type> 568, 592  
     WCValSkipList<Type> 489, 508  
     WCValSkipListDict<Key,Value> 470, 487  
     WCValSkipListSet<Type> 489, 508  
     WCValSortedVector<Type> 568, 592  
 removeAll, member function  
     WCPtrHashSet<Type> 106, 129  
     WCPtrHashTable<Type> 106, 129  
     WCPtrOrderedVector<Type> 525, 550  
     WCPtrSkipList<Type> 447, 468  
     WCPtrSkipListSet<Type> 447, 468  
     WCPtrSortedVector<Type> 525, 550  
     WCValHashSet<Type> 154, 176  
     WCValHashTable<Type> 154, 176  
     WCValOrderedVector<Type> 568, 593  
     WCValSkipList<Type> 489, 509  
     WCValSkipListSet<Type> 489, 509  
     WCValSortedVector<Type> 568, 593  
 removeAt, member function  
     WCPtrOrderedVector<Type> 525, 551  
     WCPtrSortedVector<Type> 525, 551  
     WCValOrderedVector<Type> 568, 594  
     WCValSortedVector<Type> 568, 594  
 removeFirst, member function  
     WCPtrOrderedVector<Type> 525, 552  
     WCPtrSortedVector<Type> 525, 552  
     WCValOrderedVector<Type> 568, 595  
     WCValSortedVector<Type> 568, 595  
 removeLast, member function  
     WCPtrOrderedVector<Type> 525, 553  
     WCPtrSortedVector<Type> 525, 553  
     WCValOrderedVector<Type> 568, 596  
     WCValSortedVector<Type> 568, 596  
 reserve area 791  
 reset, member function  
     WCIsvConstDListIter<Type> 308, 322-323  
     WCIsvConstSListIter<Type> 308, 322-323  
     WCIsvDListIter<Type> 324, 341-342  
     WCIsvSListIter<Type> 324, 341-342

WCPtrConstDListIter<Type> 343, 357-358  
WCPtrConstSListIter<Type> 343, 357-358  
WCPtrDListIter<Type> 359, 376-377  
WCPtrHashDictIter<Key,Value> 180, 188-189  
WCPtrHashSetIter<Type> 202, 213-214  
WCPtrHashTableIter<Type> 202, 213-214  
WCPtrSListIter<Type> 359, 376-377  
WCValConstDListIter<Type> 378, 392-393  
WCValConstSListIter<Type> 378, 392-393  
WCValDListIter<Type> 394, 411-412  
WCValHashDictIter<Key,Value> 191, 199-200  
WCValHashSetIter<Type> 215, 226-227  
WCValHashTableIter<Type> 215, 226-227  
WCValSListIter<Type> 394, 411-412  
resetiosflags, manipulator 733, 740  
resize, member function  
    WCPtrHashDict<Key,Value> 83, 104  
    WCPtrHashSet<Type> 106, 130  
    WCPtrHashTable<Type> 106, 130  
    WCPtrOrderedVector<Type> 525, 554  
    WCPtrSortedVector<Type> 525, 554  
    WCPtrVector<Type> 555, 566  
    WCValHashDict<Key,Value> 132, 152  
    WCValHashSet<Type> 154, 177  
    WCValHashTable<Type> 154, 177  
    WCValOrderedVector<Type> 568, 597  
    WCValSortedVector<Type> 568, 597  
    WCValVector<Type> 598, 608  
resize\_required  
    exception 70, 524, 526, 529, 532, 540-541, 548,  
        563, 567, 570, 573, 576, 583-584, 591, 605  
resize\_required, member enumeration  
    WCExcept 70  
right, member enumeration  
    ios 665

## S

sbumpc, member function  
    streambuf 793, 814  
scientific, member enumeration  
    ios 665  
seekdir, member enumeration  
    ios 655, 683  
seekg, member function  
    istream 698, 725-726  
seekoff, member function  
    filebuf 611, 624  
    streambuf 793, 815  
    strstreambuf 846, 851

seekp, member function  
    ostream 755, 774-775  
seekpos, member function  
    streambuf 793, 816  
setb, member function  
    streambuf 792, 817  
setbase, manipulator 733, 741  
setbuf, member function  
    filebuf 611, 625  
    fstreambase 635, 647  
    streambuf 793, 818  
    strstreambuf 846, 852  
setf, member function  
    ios 655, 684  
setfill, manipulator 733, 742  
setg, member function  
    streambuf 792, 819  
setiosflags, manipulator 733, 743  
setp, member function  
    streambuf 792, 820  
setprecision, manipulator 733, 744  
setstate, member function  
    ios 655, 685  
setw, manipulator 733, 745  
setwidth, manipulator 733, 746  
sgetc, member function  
    streambuf 793, 821  
sgetchar, member function  
    streambuf 793, 822  
sgetn, member function  
    streambuf 793, 823  
showbase, member enumeration  
    ios 665  
showpoint, member enumeration  
    ios 665  
showpos, member enumeration  
    ios 665  
sin, related function  
    Complex 19, 60  
sinh, related function  
    Complex 19, 61  
skipws, member enumeration  
    ios 665  
snextc, member function  
    streambuf 793, 824  
speekc, member function  
    streambuf 793, 825  
sputbackc, member function  
    streambuf 793, 826  
sputc, member function  
    streambuf 793, 827  
sputn, member function  
    streambuf 793, 828  
sqrt, related function

Complex 19, 62  
 stdio, member enumeration  
     ios 665  
 stdiobuf 791  
 stdiobuf::overflow 784-785  
 stdiobuf::stdiobuf 784, 786-787  
 stdiobuf::sync 784, 789  
 stdiobuf::underflow 784, 790  
 stdiobuf::~stdiobuf 784, 788  
 stossc, member function  
     streambuf 793, 829  
 str, member function  
     ostrstream 778, 783  
     strstream 836-837  
     strstrembuf 846, 853  
 streambuf 610, 784, 846  
 streambuf::allocate 792, 794  
 streambuf::base 792, 795  
 streambuf::blen 792, 796  
 streambuf::dbp 793, 797  
 streambuf::do\_sgetn 793, 798  
 streambuf::do\_sputn 793, 799  
 streambuf::doallocate 792, 800  
 streambuf::eback 792, 801  
 streambuf::ebuf 792, 802  
 streambuf::egptr 792, 803  
 streambuf::epptr 792, 804  
 streambuf::gbump 792, 805  
 streambuf::gptr 792, 806  
 streambuf::in\_avail 793, 807  
 streambuf::out\_waiting 793, 808  
 streambuf::overflow 793, 809  
 streambuf::pbackfail 793, 810  
 streambuf::pbase 792, 811  
 streambuf::pbump 792, 812  
 streambuf::pptr 792, 813  
 streambuf::sbumpc 793, 814  
 streambuf::seekoff 793, 815  
 streambuf::seekpos 793, 816  
 streambuf::setb 792, 817  
 streambuf::setbuf 793, 818  
 streambuf::setg 792, 819  
 streambuf::setp 792, 820  
 streambuf::sgetc 793, 821  
 streambuf::sgetchar 793, 822  
 streambuf::sgetn 793, 823  
 streambuf::snextc 793, 824  
 streambuf::speekc 793, 825  
 streambuf::sputbackc 793, 826  
 streambuf::sputc 793, 827  
 streambuf::sputn 793, 828  
 streambuf::stossc 793, 829  
 streambuf::streambuf 792, 830-831  
 streambuf::sync 793, 833  
 streambuf::unbuffered 792, 834  
 streambuf::underflow 793, 835  
 streambuf::~streambuf 792, 832  
 streamoff 7  
 strempos 7  
 String related functions  
     operator != 862, 871  
     operator + 863, 874  
     operator < 862-863, 876  
     operator << 863, 877  
     operator <= 863, 878  
     operator == 862, 880  
     operator > 863, 881  
     operator >= 863, 882  
     operator >> 863, 883  
     valid 863, 895  
 String::alloc\_mult\_size 862, 864  
 String::get\_at 862, 865  
 String::index 862, 866  
 String::length 862, 867  
 String::lower 862, 868  
 String::match 862, 869  
 String::operator ! 862, 870  
 String::operator () 862, 872-873  
 String::operator += 862, 875  
 String::operator = 862, 879  
 String::operator [] 862, 884  
 String::operator char 862, 885  
 String::operator char const \* 862, 886  
 String::put\_at 862, 887  
 String::String 862, 888-892  
 String::upper 862, 894  
 String::valid 862, 896  
 String::~String 862, 893  
 strstream 691, 841  
 strstrembuf::str 836-837  
 strstrembuf::strstream 836, 838-839  
 strstrembuf::~strstream 836, 840  
 strstrembase 729, 778, 836  
 strstrembase::rdbuf 841-842  
 strstrembase::strstreambase 841, 843-844  
 strstrembase::~strstreambase 841, 845  
 strstrembuf 791  
 strstrembuf::alloc\_size\_increment 846-847  
 strstrembuf::doallocate 846, 848  
 strstrembuf::freeze 846, 849  
 strstrembuf::overflow 846, 850  
 strstrembuf::seekoff 846, 851  
 strstrembuf::setbuf 846, 852  
 strstrembuf::str 846, 853  
 strstrembuf::strstreambuf 846, 854-857  
 strstrembuf::sync 846, 859  
 strstrembuf::underflow 846, 860  
 strstrembuf::~strstreambuf 846, 858

sync, member function  
  filebuf 611, 626  
  istream 699, 727  
  stdiobuf 784, 789  
  streambuf 793, 833  
  strstreambuf 846, 859  
sync\_with\_stdio, member function  
  ios 656, 686

## T

tan, related function  
  Complex 19, 63  
tanh, related function  
  Complex 19, 64  
tellg, member function  
  istream 698, 728  
tellp, member function  
  ostream 755, 776  
text, member enumeration  
  ios 675  
tie, member function  
  ios 655, 687  
top, member function  
  WCStack<Type,FType> 512, 521  
trunc, member enumeration  
  ios 675  
truncate, member enumeration  
  ios 675

## U

unbuffered, member function  
  streambuf 792, 834  
undef\_item 185, 190, 196, 201, 210, 223, 316, 334,  
  351, 369, 386, 404  
  exception 75  
undef\_item, member enumeration  
  WCIterExcept 75  
undef\_iter  
  exception 75, 184, 186-187, 195, 197-198, 209,  
    211-212, 222, 224-225, 315, 317-321,  
    332-333, 335-340, 350, 352-356, 367-368,  
    370-375, 385, 387-391, 402-403, 405-410  
undef\_iter, member enumeration  
  WCIterExcept 75  
underflow, member function

filebuf 610, 627  
stdiobuf 784, 790  
streambuf 793, 835  
strstreambuf 846, 860  
undex\_iter  
  exception 179, 307  
unformatted input 11  
unformatted output 13  
unitbuf, member enumeration  
  ios 665  
unsetf, member function  
  ios 655, 688  
upper, member function  
  String 862, 894  
uppercase, member enumeration  
  ios 665

## V

valid, member function  
  String 862, 896  
valid, related function  
  String 863, 895  
value  
  lists 229  
value, member function  
  WCPtrHashDictIter<Key,Value> 180, 190  
  WCValHashDictIter<Key,Value> 191, 201

## W

wc\_state, member enumeration  
  WCExcept 66, 70  
WCDLink 280  
WCDLink::WCDLink 230-231  
WCDLink::~WCDLink 230, 232  
WCExcept::all\_fine 70  
WCExcept::check\_all 70  
WCExcept::check\_none 70  
WCExcept::empty\_container 70  
WCExcept::exceptions 66, 69  
WCExcept::index\_range 70  
WCExcept::not\_empty 70  
WCExcept::not\_unique 70  
WCExcept::out\_of\_memory 70  
WCExcept::resize\_required 70  
WCExcept::wc\_state 66, 70

WCExcept::WCExcept 66-67  
 WCExcept::zero\_buckets 70  
 WCExcept::~WCExcept 66, 68  
 WCIsvConstDListIter, member function  
     WCIsvConstDListIter<Type> 312-313  
     WCIsvConstSListIter<Type> 312-313  
 WCIsvConstDListIter<Type>::append 308  
 WCIsvConstDListIter<Type>::container 308, 315  
 WCIsvConstDListIter<Type>::current 308, 316  
 WCIsvConstDListIter<Type>::insert 308  
 WCIsvConstDListIter<Type>::operator () 308, 317  
 WCIsvConstDListIter<Type>::operator ++ 308, 318  
 WCIsvConstDListIter<Type>::operator += 308, 319  
 WCIsvConstDListIter<Type>::operator -- 308, 320  
 WCIsvConstDListIter<Type>::operator -= 308, 321  
 WCIsvConstDListIter<Type>::reset 308, 322-323  
 WCIsvConstDListIter<Type>::WCIsvConstDListIter  
    312-313  
 WCIsvConstDListIter<Type>::WCIsvConstSListIter  
    309-310  
 WCIsvConstDListIter<Type>::~WCIsvConstDListIter  
    314  
 WCIsvConstDListIter<Type>::~WCIsvConstSListIter  
    311  
 WCIsvConstSListIter, member function  
     WCIsvConstDListIter<Type> 309-310  
     WCIsvConstSListIter<Type> 309-310  
 WCIsvConstSListIter<Type>::append 308  
 WCIsvConstSListIter<Type>::container 308, 315  
 WCIsvConstSListIter<Type>::current 308, 316  
 WCIsvConstSListIter<Type>::insert 308  
 WCIsvConstSListIter<Type>::operator () 308, 317  
 WCIsvConstSListIter<Type>::operator ++ 308, 318  
 WCIsvConstSListIter<Type>::operator += 308, 319  
 WCIsvConstSListIter<Type>::operator -- 308, 320  
 WCIsvConstSListIter<Type>::operator -= 308, 321  
 WCIsvConstSListIter<Type>::reset 308, 322-323  
 WCIsvConstSListIter<Type>::WCIsvConstDListIter  
    312-313  
 WCIsvConstSListIter<Type>::WCIsvConstSListIter  
    309-310  
 WCIsvConstSListIter<Type>::WCIsvConstSListIter<Type>  
    308  
 WCIsvConstSListIter<Type>::~WCIsvConstDListIter  
    314  
 WCIsvConstSListIter<Type>::~WCIsvConstSListIter  
    311  
 WCIsvConstSListIter<Type>::~WCIsvConstSListIter<Type>  
    308  
 WCIsvDList, member function  
     WCIsvDList<Type> 233, 236, 238-240  
     WCIsvSList<Type> 233, 236, 238-240  
 WCIsvDList<Type>::append 233, 241  
 WCIsvDList<Type>::clear 233, 242  
 WCIsvDList<Type>::clearAndDestroy 233, 243  
 WCIsvDList<Type>::contains 233, 244  
 WCIsvDList<Type>::entries 233, 245  
 WCIsvDList<Type>::find 233, 246  
 WCIsvDList<Type>::findLast 233, 247  
 WCIsvDList<Type>::forAll 233, 248  
 WCIsvDList<Type>::get 233, 249  
 WCIsvDList<Type>::index 233, 250-251  
 WCIsvDList<Type>::insert 233, 252  
 WCIsvDList<Type>::isEmpty 233, 253  
 WCIsvDList<Type>::operator = 233, 254  
 WCIsvDList<Type>::operator == 234, 255  
 WCIsvDList<Type>::WCIsvDList 233, 236, 238-240  
 WCIsvDList<Type>::WCIsvSList 233, 235, 237  
 WCIsvDListIter, member function  
     WCIsvDListIter<Type> 329-330  
     WCIsvSListIter<Type> 329-330  
 WCIsvDListIter<Type>::append 324, 332  
 WCIsvDListIter<Type>::container 324, 333  
 WCIsvDListIter<Type>::current 324, 334  
 WCIsvDListIter<Type>::insert 324, 335  
 WCIsvDListIter<Type>::operator () 324, 336  
 WCIsvDListIter<Type>::operator ++ 324, 337  
 WCIsvDListIter<Type>::operator += 324, 338  
 WCIsvDListIter<Type>::operator -- 324-325, 339  
 WCIsvDListIter<Type>::operator -= 324-325, 340  
 WCIsvDListIter<Type>::reset 324, 341-342  
 WCIsvDListIter<Type>::WCIsvDListIter 329-330  
 WCIsvDListIter<Type>::WCIsvSListIter 326-327  
 WCIsvDListIter<Type>::~WCIsvDListIter 331  
 WCIsvDListIter<Type>::~WCIsvSListIter 328  
 WCIsvSList, member function  
     WCIsvDList<Type> 233, 235, 237  
     WCIsvSList<Type> 233, 235, 237  
 WCIsvSList<Type>::append 233, 241  
 WCIsvSList<Type>::clear 233, 242  
 WCIsvSList<Type>::clearAndDestroy 233, 243  
 WCIsvSList<Type>::contains 233, 244  
 WCIsvSList<Type>::entries 233, 245  
 WCIsvSList<Type>::find 233, 246  
 WCIsvSList<Type>::findLast 233, 247  
 WCIsvSList<Type>::forAll 233, 248  
 WCIsvSList<Type>::get 233, 249  
 WCIsvSList<Type>::index 233, 250-251  
 WCIsvSList<Type>::insert 233, 252  
 WCIsvSList<Type>::isEmpty 233, 253  
 WCIsvSList<Type>::operator = 233, 254  
 WCIsvSList<Type>::operator == 234, 255  
 WCIsvSList<Type>::WCIsvDList 233, 236, 238-240  
 WCIsvSList<Type>::WCIsvSList 233, 235, 237  
 WCIsvSList<Type>::WCIsvSList<Type> 233  
 WCIsvSList<Type>::~WCIsvSList<Type> 233  
 WCIsvSListIter, member function  
     WCIsvDListIter<Type> 326-327

WCIsvSListIter<Type> 326-327  
WCIsvSListIter<Type>::append 324, 332  
WCIsvSListIter<Type>::container 324, 333  
WCIsvSListIter<Type>::current 324, 334  
WCIsvSListIter<Type>::insert 324, 335  
WCIsvSListIter<Type>::operator () 324, 336  
WCIsvSListIter<Type>::operator ++ 324, 337  
WCIsvSListIter<Type>::operator += 324, 338  
WCIsvSListIter<Type>::operator -- 324-325, 339  
WCIsvSListIter<Type>::operator -= 324-325, 340  
WCIsvSListIter<Type>::reset 324, 341-342  
WCIsvSListIter<Type>::WCIsvDListIter 329-330  
WCIsvSListIter<Type>::WCIsvSListIter 326-327  
WCIsvSListIter<Type>::WCIsvSListIter<Type> 324  
WCIsvSListIter<Type>::~WCIsvDListIter 331  
WCIsvSListIter<Type>::~WCIsvSListIter 328  
WCIsvSListIter<Type>::~WCIsvSListIter<Type> 324  
wciter\_state, member enumeration  
    WCIterExcept 71, 75  
WCIterExcept::all\_fine 75  
WCIterExcept::check\_all 75  
WCIterExcept::check\_none 75  
WCIterExcept::exceptions 71, 74  
WCIterExcept::iter\_range 75  
WCIterExcept::undef\_item 75  
WCIterExcept::undef\_iter 75  
WCIterExcept::wciter\_state 71, 75  
WCIterExcept::WCIterExcept 71-72  
WCIterExcept::~WCIterExcept 71, 73  
WCLListExcept  
    class 66  
WCPtrConstDListIter, member function  
    WCPtrConstDListIter<Type> 347-348  
    WCPtrConstSListIter<Type> 347-348  
WCPtrConstDListIter<Type>::append 343  
WCPtrConstDListIter<Type>::container 343, 350  
WCPtrConstDListIter<Type>::current 343, 351  
WCPtrConstDListIter<Type>::insert 343  
WCPtrConstDListIter<Type>::operator () 343, 352  
WCPtrConstDListIter<Type>::operator ++ 343, 353  
WCPtrConstDListIter<Type>::operator += 343, 354  
WCPtrConstDListIter<Type>::operator -- 343, 355  
WCPtrConstDListIter<Type>::operator -= 343, 356  
WCPtrConstDListIter<Type>::reset 343, 357-358  
WCPtrConstDListIter<Type>::WCPtrConstDListIter  
    347-348  
WCPtrConstDListIter<Type>::WCPtrConstSListIter  
    344-345  
WCPtrConstDListIter<Type>::~WCPtrConstDListIter  
    349  
WCPtrConstDListIter<Type>::~WCPtrConstSListIter  
    346  
WCPtrConstSListIter, member function  
    WCPtrConstDListIter<Type> 344-345  
    WCPtrConstSListIter<Type> 344-345  
    WCPtrConstSListIter<Type>::append 343  
    WCPtrConstSListIter<Type>::container 343, 350  
    WCPtrConstSListIter<Type>::current 343, 351  
    WCPtrConstSListIter<Type>::insert 343  
    WCPtrConstSListIter<Type>::operator () 343, 352  
    WCPtrConstSListIter<Type>::operator ++ 343, 353  
    WCPtrConstSListIter<Type>::operator += 343, 354  
    WCPtrConstSListIter<Type>::operator -- 343, 355  
    WCPtrConstSListIter<Type>::operator -= 343, 356  
    WCPtrConstSListIter<Type>::reset 343, 357-358  
    WCPtrConstSListIter<Type>::WCPtrConstDListIter  
        347-348  
    WCPtrConstSListIter<Type>::WCPtrConstSListIter  
        344-345  
    WCPtrConstSListIter<Type>::WCPtrConstSListIter<T  
        ype> 343  
    WCPtrConstSListIter<Type>::~WCPtrConstDListIter  
        349  
    WCPtrConstSListIter<Type>::~WCPtrConstSListIter  
        346  
    WCPtrConstSListIter<Type>::~WCPtrConstSListIter<  
        Type> 343  
    WCPtrDList, member function  
        WCPtrDList<Type> 260, 262-265  
        WCPtrSList<Type> 260, 262-265  
    WCPtrDList<Type>::append 256, 266  
    WCPtrDList<Type>::clear 256, 267  
    WCPtrDList<Type>::clearAndDestroy 256, 268  
    WCPtrDList<Type>::contains 256, 269  
    WCPtrDList<Type>::entries 256, 270  
    WCPtrDList<Type>::find 256, 271  
    WCPtrDList<Type>::findLast 256, 272  
    WCPtrDList<Type>::forAll 256, 273  
    WCPtrDList<Type>::get 256, 274  
    WCPtrDList<Type>::index 256, 275  
    WCPtrDList<Type>::insert 256, 276  
    WCPtrDList<Type>::isEmpty 256, 277  
    WCPtrDList<Type>::operator = 256, 278  
    WCPtrDList<Type>::operator == 256, 279  
    WCPtrDList<Type>::WCPtrDList 260, 262-265  
    WCPtrDList<Type>::WCPtrSList 258-259, 261  
    WCPtrDListIter, member function  
        WCPtrDListIter<Type> 364-365  
        WCPtrSListIter<Type> 364-365  
    WCPtrDListIter<Type>::append 359, 367  
    WCPtrDListIter<Type>::container 359, 368  
    WCPtrDListIter<Type>::current 359, 369  
    WCPtrDListIter<Type>::insert 359, 370  
    WCPtrDListIter<Type>::operator () 359, 371  
    WCPtrDListIter<Type>::operator ++ 359, 372  
    WCPtrDListIter<Type>::operator += 359, 373  
    WCPtrDListIter<Type>::operator -- 359-360, 374  
    WCPtrDListIter<Type>::operator -= 359-360, 375

WCPtrDListIter<Type>::reset 359, 376-377  
 WCPtrDListIter<Type>::WCPtrDListIter 364-365  
 WCPtrDListIter<Type>::WCPtrSListIter 361-362  
 WCPtrDListIter<Type>::~WCPtrDListIter 366  
 WCPtrDListIter<Type>::~WCPtrSListIter 363  
 WCPtrHashDict, member function  
     WCPtrHashDict<Key,Value> 82  
 WCPtrHashDict<Key,Value>::bitHash 82, 88  
 WCPtrHashDict<Key,Value>::buckets 82, 89  
 WCPtrHashDict<Key,Value>::clear 83, 90  
 WCPtrHashDict<Key,Value>::clearAndDestroy 83, 91  
     WCPtrHashDict<Key,Value>::contains 83, 92  
     WCPtrHashDict<Key,Value>::entries 83, 93  
     WCPtrHashDict<Key,Value>::find 83, 94  
     WCPtrHashDict<Key,Value>::findKeyAndValue 83, 95  
     WCPtrHashDict<Key,Value>::forall 83, 96  
     WCPtrHashDict<Key,Value>::insert 83, 97  
     WCPtrHashDict<Key,Value>::isEmpty 83, 98  
     WCPtrHashDict<Key,Value>::operator = 83, 101  
     WCPtrHashDict<Key,Value>::operator == 83, 102  
     WCPtrHashDict<Key,Value>::operator [] 83, 99-100  
     WCPtrHashDict<Key,Value>::remove 83, 103  
     WCPtrHashDict<Key,Value>::resize 83, 104  
     WCPtrHashDict<Key,Value>::WCPtrHashDict 82  
     WCPtrHashDict<Key,Value>::WCPtrHashDict<Key,Value> 84-86  
     WCPtrHashDict<Key,Value>::~WCPtrHashDict 82  
     WCPtrHashDict<Key,Value>::~WCPtrHashDict<Key,Value> 87  
 WCPtrHashDictIter, member function  
     WCPtrHashDictIter<Key,Value> 181-182  
 WCPtrHashDictIter<Key,Value>::container 180, 184  
 WCPtrHashDictIter<Key,Value>::key 180, 185  
 WCPtrHashDictIter<Key,Value>::operator () 180, 186  
 WCPtrHashDictIter<Key,Value>::operator ++ 180, 187  
 WCPtrHashDictIter<Key,Value>::reset 180, 188-189  
 WCPtrHashDictIter<Key,Value>::value 180, 190  
 WCPtrHashDictIter<Key,Value>::WCPtrHashDictIter 181-182  
 WCPtrHashDictIter<Key,Value>::WCPtrHashDictIter<Key,Value> 180  
 WCPtrHashDictIter<Key,Value>::~WCPtrHashDictIter 183  
 WCPtrHashDictIter<Key,Value>::~WCPtrHashDictIter<Key,Value> 180  
 WCPtrHashSet, member function  
     WCPtrHashSet<Type> 105  
     WCPtrHashTable<Type> 105  
 WCPtrHashSet<Type>::bitHash 106, 115  
 WCPtrHashSet<Type>::buckets 106, 116  
 WCPtrHashSet<Type>::clear 106, 117  
 WCPtrHashSet<Type>::clearAndDestroy 106, 118  
 WCPtrHashSet<Type>::contains 106, 119  
 WCPtrHashSet<Type>::entries 106, 120  
 WCPtrHashSet<Type>::find 106, 121  
 WCPtrHashSet<Type>::forall 106, 122  
 WCPtrHashSet<Type>::insert 106, 123  
 WCPtrHashSet<Type>::isEmpty 106, 124  
 WCPtrHashSet<Type>::occurrencesOf 106, 125  
 WCPtrHashSet<Type>::operator = 106, 126  
 WCPtrHashSet<Type>::operator == 106, 127  
 WCPtrHashSet<Type>::remove 106, 128  
 WCPtrHashSet<Type>::removeAll 106, 129  
 WCPtrHashSet<Type>::resize 106, 130  
 WCPtrHashSet<Type>::WCPtrHashSet 105  
 WCPtrHashSet<Type>::WCPtrHashTable 105  
 WCPtrHashSet<Type>::~WCPtrHashSet 105  
 WCPtrHashSet<Type>::~WCPtrHashTable 106  
 WCPtrHashSetIter, member function  
     WCPtrHashSetIter<Type> 203-204  
     WCPtrHashTableIter<Type> 203-204  
 WCPtrHashSetIter<Type>::container 202, 209  
 WCPtrHashSetIter<Type>::current 202, 210  
 WCPtrHashSetIter<Type>::operator () 202, 211  
 WCPtrHashSetIter<Type>::operator ++ 202, 212  
 WCPtrHashSetIter<Type>::reset 202, 213-214  
 WCPtrHashSetIter<Type>::WCPtrHashSetIter 203-204  
 WCPtrHashSetIter<Type>::WCPtrHashSetIter<Type> 202  
 WCPtrHashSetIter<Type>::WCPtrHashTableIter 206-207  
 WCPtrHashSetIter<Type>::~WCPtrHashSetIter 205  
 WCPtrHashSetIter<Type>::~WCPtrHashSetIter<Type> 202  
 WCPtrHashSetIter<Type>::~WCPtrHashTableIter 208  
 WCPtrHashTable, member function  
     WCPtrHashSet<Type> 105  
     WCPtrHashTable<Type> 105  
 WCPtrHashTable<Type>::bitHash 106, 115  
 WCPtrHashTable<Type>::buckets 106, 116  
 WCPtrHashTable<Type>::clear 106, 117  
 WCPtrHashTable<Type>::clearAndDestroy 106, 118  
 WCPtrHashTable<Type>::contains 106, 119  
 WCPtrHashTable<Type>::entries 106, 120  
 WCPtrHashTable<Type>::find 106, 121  
 WCPtrHashTable<Type>::forall 106, 122  
 WCPtrHashTable<Type>::insert 106, 123  
 WCPtrHashTable<Type>::isEmpty 106, 124  
 WCPtrHashTable<Type>::occurrencesOf 106, 125  
 WCPtrHashTable<Type>::operator = 106, 126  
 WCPtrHashTable<Type>::operator == 106, 127  
 WCPtrHashTable<Type>::remove 106, 128  
 WCPtrHashTable<Type>::removeAll 106, 129  
 WCPtrHashTable<Type>::resize 106, 130

WCPtrHashTable<Type>::WCPtrHashSet 105  
WCPtrHashTable<Type>::WCPtrHashTable 105  
WCPtrHashTable<Type>::WCPtrHashTable<Type>  
    107-109, 111-113  
WCPtrHashTable<Type>::~WCPtrHashSet 105  
WCPtrHashTable<Type>::~WCPtrHashTable 106  
WCPtrHashTable<Type>::~WCPtrHashTable<Type>  
    110, 114  
WCPtrHashTableIter, member function  
    WCPtrHashSetIter<Type> 206-207  
    WCPtrHashTableIter<Type> 206-207  
WCPtrHashTableIter<Type>::container 202, 209  
WCPtrHashTableIter<Type>::current 202, 210  
WCPtrHashTableIter<Type>::operator () 202, 211  
WCPtrHashTableIter<Type>::operator ++ 202, 212  
WCPtrHashTableIter<Type>::reset 202, 213-214  
WCPtrHashTableIter<Type>::WCPtrHashSetIter  
    203-204  
WCPtrHashTableIter<Type>::WCPtrHashTableIter  
    206-207  
WCPtrHashTableIter<Type>::~WCPtrHashSetIter 205  
WCPtrHashTableIter<Type>::~WCPtrHashTableIter  
    208  
WCPtrOrderedVector, member function  
    WCPtrOrderedVector<Type> 525  
    WCPtrSortedVector<Type> 525  
WCPtrOrderedVector<Type>::append 525, 532  
WCPtrOrderedVector<Type>::clear 525, 533  
WCPtrOrderedVector<Type>::clearAndDestroy 525,  
    534  
WCPtrOrderedVector<Type>::contains 525, 535  
WCPtrOrderedVector<Type>::entries 525, 536  
WCPtrOrderedVector<Type>::find 525, 537  
WCPtrOrderedVector<Type>::first 525, 538  
WCPtrOrderedVector<Type>::index 525, 539  
WCPtrOrderedVector<Type>::insert 525, 540  
WCPtrOrderedVector<Type>::insertAt 525, 541  
WCPtrOrderedVector<Type>::isEmpty 525, 542  
WCPtrOrderedVector<Type>::last 525, 543  
WCPtrOrderedVector<Type>::occurrencesOf 525,  
    544  
WCPtrOrderedVector<Type>::operator = 525, 546  
WCPtrOrderedVector<Type>::operator == 525, 547  
WCPtrOrderedVector<Type>::operator [] 525, 545  
WCPtrOrderedVector<Type>::prepend 525, 548  
WCPtrOrderedVector<Type>::remove 525, 549  
WCPtrOrderedVector<Type>::removeAll 525, 550  
WCPtrOrderedVector<Type>::removeAt 525, 551  
WCPtrOrderedVector<Type>::removeFirst 525, 552  
WCPtrOrderedVector<Type>::removeLast 525, 553  
WCPtrOrderedVector<Type>::resize 525, 554  
WCPtrOrderedVector<Type>::WCPtrOrderedVector  
    525

WCPtrOrderedVector<Type>::WCPtrSortedVector  
    525  
WCPtrOrderedVector<Type>::~WCPtrOrderedVector  
    525  
WCPtrOrderedVector<Type>::~WCPtrSortedVector  
    525  
WCPtrSkipList, member function  
    WCPtrSkipList<Type> 446  
    WCPtrSkipListSet<Type> 446  
WCPtrSkipList<Type>::clear 446, 456  
WCPtrSkipList<Type>::clearAndDestroy 446, 457  
WCPtrSkipList<Type>::contains 447, 458  
WCPtrSkipList<Type>::entries 447, 459  
WCPtrSkipList<Type>::find 447, 460  
WCPtrSkipList<Type>::forall 447, 461  
WCPtrSkipList<Type>::insert 447, 462  
WCPtrSkipList<Type>::isEmpty 447, 463  
WCPtrSkipList<Type>::occurrencesOf 447, 464  
WCPtrSkipList<Type>::operator = 447, 465  
WCPtrSkipList<Type>::operator == 447, 466  
WCPtrSkipList<Type>::remove 447, 467  
WCPtrSkipList<Type>::removeAll 447, 468  
WCPtrSkipList<Type>::WCPtrSkipList 446  
WCPtrSkipList<Type>::WCPtrSkipList<Type>  
    448-450, 452-454  
WCPtrSkipList<Type>::WCPtrSkipListSet 446  
WCPtrSkipList<Type>::~WCPtrSkipList 446  
WCPtrSkipList<Type>::~WCPtrSkipList<Type> 451,  
    455  
WCPtrSkipList<Type>::~WCPtrSkipListSet 446  
WCPtrSkipListDict, member function  
    WCPtrSkipListDict<Key,Value> 426  
WCPtrSkipListDict<Key,Value>::clear 426, 432  
WCPtrSkipListDict<Key,Value>::clearAndDestroy  
    426, 433  
WCPtrSkipListDict<Key,Value>::contains 426, 434  
WCPtrSkipListDict<Key,Value>::entries 426, 435  
WCPtrSkipListDict<Key,Value>::find 426, 436  
WCPtrSkipListDict<Key,Value>::findKeyAndValue  
    426, 437  
WCPtrSkipListDict<Key,Value>::forall 426, 438  
WCPtrSkipListDict<Key,Value>::insert 426, 439  
WCPtrSkipListDict<Key,Value>::isEmpty 426, 440  
WCPtrSkipListDict<Key,Value>::operator = 427, 443  
WCPtrSkipListDict<Key,Value>::operator == 427,  
    444  
WCPtrSkipListDict<Key,Value>::operator [] 427,  
    441-442  
WCPtrSkipListDict<Key,Value>::remove 426, 445  
WCPtrSkipListDict<Key,Value>::WCPtrSkipListDict  
    426  
WCPtrSkipListDict<Key,Value>::WCPtrSkipListDict<  
    Key,Value> 428-430

WCPtrSkipListDict<Key,Value>::~WCPtrSkipListDict  
     426  
 WCPtrSkipListDict<Key,Value>::~WCPtrSkipListDict  
     <Key,Value> 431  
 WCPtrSkipListSet, member function  
     WCPtrSkipList<Type> 446  
     WCPtrSkipListSet<Type> 446  
 WCPtrSkipListSet<Type>::clear 446, 456  
 WCPtrSkipListSet<Type>::clearAndDestroy 446, 457  
 WCPtrSkipListSet<Type>::contains 447, 458  
 WCPtrSkipListSet<Type>::entries 447, 459  
 WCPtrSkipListSet<Type>::find 447, 460  
 WCPtrSkipListSet<Type>::forall 447, 461  
 WCPtrSkipListSet<Type>::insert 447, 462  
 WCPtrSkipListSet<Type>::isEmpty 447, 463  
 WCPtrSkipListSet<Type>::occurrencesOf 447, 464  
 WCPtrSkipListSet<Type>::operator = 447, 465  
 WCPtrSkipListSet<Type>::operator == 447, 466  
 WCPtrSkipListSet<Type>::remove 447, 467  
 WCPtrSkipListSet<Type>::removeAll 447, 468  
 WCPtrSkipListSet<Type>::WCPtrSkipList 446  
 WCPtrSkipListSet<Type>::WCPtrSkipListSet 446  
 WCPtrSkipListSet<Type>::~WCPtrSkipList 446  
 WCPtrSkipListSet<Type>::~WCPtrSkipListSet 446  
 WCPtrSList, member function  
     WCPtrDList<Type> 258-259, 261  
     WCPtrSList<Type> 258-259, 261  
 WCPtrSList<Type>::append 256, 266  
 WCPtrSList<Type>::clear 256, 267  
 WCPtrSList<Type>::clearAndDestroy 256, 268  
 WCPtrSList<Type>::contains 256, 269  
 WCPtrSList<Type>::entries 256, 270  
 WCPtrSList<Type>::find 256, 271  
 WCPtrSList<Type>::findLast 256, 272  
 WCPtrSList<Type>::forAll 256, 273  
 WCPtrSList<Type>::get 256, 274  
 WCPtrSList<Type>::index 256, 275  
 WCPtrSList<Type>::insert 256, 276  
 WCPtrSList<Type>::isEmpty 256, 277  
 WCPtrSList<Type>::operator = 256, 278  
 WCPtrSList<Type>::operator == 256, 279  
 WCPtrSList<Type>::WCPtrDList 260, 262-265  
 WCPtrSList<Type>::WCPtrSList 258-259, 261  
 WCPtrSList<Type>::WCPtrSList<Type> 256  
 WCPtrSList<Type>::~WCPtrSList<Type> 256  
 WCPtrSListItemSize  
     macro 416, 514  
 WCPtrSListIter, member function  
     WCPtrDListIter<Type> 361-362  
     WCPtrSListIter<Type> 361-362  
 WCPtrSListIter<Type>::append 359, 367  
 WCPtrSListIter<Type>::container 359, 368  
 WCPtrSListIter<Type>::current 359, 369  
 WCPtrSListIter<Type>::insert 359, 370  
 WCPtrSListIter<Type>::operator () 359, 371  
 WCPtrSListIter<Type>::operator ++ 359, 372  
 WCPtrSListIter<Type>::operator += 359, 373  
 WCPtrSListIter<Type>::operator -- 359-360, 374  
 WCPtrSListIter<Type>::operator -= 359-360, 375  
 WCPtrSListIter<Type>::reset 359, 376-377  
 WCPtrSListIter<Type>::WCPtrDListIter 364-365  
 WCPtrSListIter<Type>::WCPtrSListIter 361-362  
 WCPtrSListIter<Type>::WCPtrSListIter<Type> 359  
 WCPtrSListIter<Type>::~WCPtrDListIter 366  
 WCPtrSListIter<Type>::~WCPtrSListIter 363  
 WCPtrSListIter<Type>::~WCPtrSListIter<Type> 359  
 WCPtrSortedVector, member function  
     WCPtrOrderedVector<Type> 525  
     WCPtrSortedVector<Type> 525  
 WCPtrSortedVector<Type>::append 525, 532  
 WCPtrSortedVector<Type>::clear 525, 533  
 WCPtrSortedVector<Type>::clearAndDestroy 525,  
     534  
 WCPtrSortedVector<Type>::contains 525, 535  
 WCPtrSortedVector<Type>::entries 525, 536  
 WCPtrSortedVector<Type>::find 525, 537  
 WCPtrSortedVector<Type>::first 525, 538  
 WCPtrSortedVector<Type>::index 525, 539  
 WCPtrSortedVector<Type>::insert 525, 540  
 WCPtrSortedVector<Type>::insertAt 525, 541  
 WCPtrSortedVector<Type>::isEmpty 525, 542  
 WCPtrSortedVector<Type>::last 525, 543  
 WCPtrSortedVector<Type>::occurrencesOf 525, 544  
 WCPtrSortedVector<Type>::operator = 525, 546  
 WCPtrSortedVector<Type>::operator == 525, 547  
 WCPtrSortedVector<Type>::operator [] 525, 545  
 WCPtrSortedVector<Type>::prepend 525, 548  
 WCPtrSortedVector<Type>::remove 525, 549  
 WCPtrSortedVector<Type>::removeAll 525, 550  
 WCPtrSortedVector<Type>::removeAt 525, 551  
 WCPtrSortedVector<Type>::removeFirst 525, 552  
 WCPtrSortedVector<Type>::removeLast 525, 553  
 WCPtrSortedVector<Type>::resize 525, 554  
 WCPtrSortedVector<Type>::WCPtrOrderedVector  
     525  
 WCPtrSortedVector<Type>::WCPtrSortedVector 525  
 WCPtrSortedVector<Type>::WCPtrSortedVector<Typ  
     e> 526-527, 529-530  
 WCPtrSortedVector<Type>::~WCPtrOrderedVector  
     525  
 WCPtrSortedVector<Type>::~WCPtrSortedVector  
     525  
 WCPtrSortedVector<Type>::~WCPtrSortedVector<Ty  
     pe> 528, 531  
 WCPtrVector<Type>::clear 555, 560  
 WCPtrVector<Type>::clearAndDestroy 555, 561  
 WCPtrVector<Type>::length 555, 562  
 WCPtrVector<Type>::operator = 555, 564

WCPtrVector<Type>::operator == 555, 565  
WCPtrVector<Type>::operator [] 555, 563  
WCPtrVector<Type>::resize 555, 566  
WCPtrVector<Type>::WCPtrVector<Type> 555-558  
WCPtrVector<Type>::~WCPtrVector<Type> 555,  
    559  
WCQueue<Type,FType>::clear 414, 418  
WCQueue<Type,FType>::entries 414, 419  
WCQueue<Type,FType>::first 414, 420  
WCQueue<Type,FType>::get 414, 421  
WCQueue<Type,FType>::insert 414, 422  
WCQueue<Type,FType>::isEmpty 414, 423  
WCQueue<Type,FType>::last 414, 424  
WCQueue<Type,FType>::WCQueue<Type,FType>  
    414-416  
WCQueue<Type,FType>::~WCQueue<Type,FType>  
    414, 417  
WCSLink 230  
WCSLink::WCSLink 280-281  
WCSLink::~WCSLink 280, 282  
WCStack<Type,FType>::clear 512, 516  
WCStack<Type,FType>::entries 512, 517  
WCStack<Type,FType>::isEmpty 512, 518  
WCStack<Type,FType>::pop 512, 519  
WCStack<Type,FType>::push 512, 520  
WCStack<Type,FType>::top 512, 521  
WCStack<Type,FType>::WCStack<Type,FType>  
    512-514  
WCStack<Type,FType>::~WCStack<Type,FType>  
    512, 515  
WCValConstDListIter, member function  
    WCValConstDListIter<Type> 382-383  
    WCValConstSListIter<Type> 382-383  
WCValConstDListIter<Type>::append 378  
WCValConstDListIter<Type>::container 378, 385  
WCValConstDListIter<Type>::current 378, 386  
WCValConstDListIter<Type>::insert 378  
WCValConstDListIter<Type>::operator () 378, 387  
WCValConstDListIter<Type>::operator ++ 378, 388  
WCValConstDListIter<Type>::operator += 378, 389  
WCValConstDListIter<Type>::operator -- 378, 390  
WCValConstDListIter<Type>::operator -= 378, 391  
WCValConstDListIter<Type>::reset 378, 392-393  
WCValConstDListIter<Type>::WCValConstDListIter  
    382-383  
WCValConstDListIter<Type>::WCValConstSListIter  
    379-380  
WCValConstDListIter<Type>::~WCValConstDListIter  
    384  
WCValConstDListIter<Type>::~WCValConstSListIter  
    381  
WCValConstSListIter, member function  
    WCValConstDListIter<Type> 379-380  
    WCValConstSListIter<Type> 379-380  
WCValConstSListIter<Type>::append 378  
WCValConstSListIter<Type>::container 378, 385  
WCValConstSListIter<Type>::current 378, 386  
WCValConstSListIter<Type>::insert 378  
WCValConstSListIter<Type>::operator () 378, 387  
WCValConstSListIter<Type>::operator ++ 378, 388  
WCValConstSListIter<Type>::operator += 378, 389  
WCValConstSListIter<Type>::operator -- 378, 390  
WCValConstSListIter<Type>::operator -= 378, 391  
WCValConstSListIter<Type>::reset 378, 392-393  
WCValConstSListIter<Type>::WCValConstDListIter  
    382-383  
WCValConstSListIter<Type>::WCValConstSListIter  
    379-380  
WCValConstSListIter<Type>::WCValConstSListIter<  
    Type> 378  
WCValConstSListIter<Type>::~WCValConstDListIter  
    384  
WCValConstSListIter<Type>::~WCValConstSListIter  
    381  
WCValConstSListIter<Type>::~WCValConstSListIter  
    378  
WCValDList, member function  
    WCValDList<Type> 287, 289-292  
    WCValSList<Type> 287, 289-292  
WCValDList<Type>::append 283, 293  
WCValDList<Type>::clear 283, 294  
WCValDList<Type>::clearAndDestroy 283, 295  
WCValDList<Type>::contains 283, 296  
WCValDList<Type>::entries 283, 297  
WCValDList<Type>::find 283, 298  
WCValDList<Type>::findLast 283, 299  
WCValDList<Type>::forAll 283, 300  
WCValDList<Type>::get 283, 301  
WCValDList<Type>::index 283, 302  
WCValDList<Type>::insert 283, 303  
WCValDList<Type>::isEmpty 283, 304  
WCValDList<Type>::operator = 284, 305  
WCValDList<Type>::operator == 284, 306  
WCValDList<Type>::WCValDList 287, 289-292  
WCValDList<Type>::WCValSList 285-286, 288  
WCValDListItemSize  
    macro 263, 290  
WCValDListIter, member function  
    WCValDListIter<Type> 399-400  
    WCValSListIter<Type> 399-400  
WCValDListIter<Type>::append 394, 402  
WCValDListIter<Type>::container 394, 403  
WCValDListIter<Type>::current 394, 404  
WCValDListIter<Type>::insert 394, 405  
WCValDListIter<Type>::operator () 394, 406  
WCValDListIter<Type>::operator ++ 394, 407  
WCValDListIter<Type>::operator += 394, 408  
WCValDListIter<Type>::operator -- 394-395, 409

WCValDListIter<Type>::operator -= 394-395, 410  
 WCValDListIter<Type>::reset 394, 411-412  
 WCValDListIter<Type>::WCValDListIter 399-400  
 WCValDListIter<Type>::WCValSListIter 396-397  
 WCValDListIter<Type>::~WCValDListIter 401  
 WCValDListIter<Type>::~WCValSListIter 398  
 WCValHashDict, member function  
   WCValHashDict<Key, Value> 132  
 WCValHashDict<Key, Value>::bitHash 132, 137  
 WCValHashDict<Key, Value>::buckets 132, 138  
 WCValHashDict<Key, Value>::clear 132, 139  
 WCValHashDict<Key, Value>::contains 132, 140  
 WCValHashDict<Key, Value>::entries 132, 141  
 WCValHashDict<Key, Value>::find 132, 142  
 WCValHashDict<Key, Value>::findKeyAndValue  
   132, 143  
 WCValHashDict<Key, Value>::forall 132, 144  
 WCValHashDict<Key, Value>::insert 132, 145  
 WCValHashDict<Key, Value>::isEmpty 132, 146  
 WCValHashDict<Key, Value>::operator = 132, 149  
 WCValHashDict<Key, Value>::operator == 132, 150  
 WCValHashDict<Key, Value>::operator [] 132,  
   147-148  
 WCValHashDict<Key, Value>::remove 132, 151  
 WCValHashDict<Key, Value>::resize 132, 152  
 WCValHashDict<Key, Value>::WCValHashDict 132  
 WCValHashDict<Key, Value>::WCValHashDict<Key,  
   Value> 133-135  
 WCValHashDict<Key, Value>::~WCValHashDict 132  
 WCValHashDict<Key, Value>::~WCValHashDict<Ke  
   y, Value> 136  
 WCValHashDictIter, member function  
   WCValHashDictIter<Key, Value> 192-193  
 WCValHashDictIter<Key, Value>::container 191, 195  
 WCValHashDictIter<Key, Value>::key 191, 196  
 WCValHashDictIter<Key, Value>::operator () 191,  
   197  
 WCValHashDictIter<Key, Value>::operator ++ 191,  
   198  
 WCValHashDictIter<Key, Value>::reset 191, 199-200  
 WCValHashDictIter<Key, Value>::value 191, 201  
 WCValHashDictIter<Key, Value>::WCValHashDictIt  
   er 192-193  
 WCValHashDictIter<Key, Value>::WCValHashDictIt  
   er<Key, Value> 191  
 WCValHashDictIter<Key, Value>::~WCValHashDictIt  
   er 194  
 WCValHashDictIter<Key, Value>::~WCValHashDictIt  
   er<Key, Value> 191  
 WCValHashSet, member function  
   WCValHashSet<Type> 153  
   WCValHashTable<Type> 153  
 WCValHashSet<Type>::bitHash 154, 163  
 WCValHashSet<Type>::buckets 154, 164  
 WCValHashSet<Type>::clear 154, 165  
 WCValHashSet<Type>::contains 154, 166  
 WCValHashSet<Type>::entries 154, 167  
 WCValHashSet<Type>::find 154, 168  
 WCValHashSet<Type>::forall 154, 169  
 WCValHashSet<Type>::insert 154, 170  
 WCValHashSet<Type>::isEmpty 154, 171  
 WCValHashSet<Type>::occurrencesOf 154, 172  
 WCValHashSet<Type>::operator = 154, 173  
 WCValHashSet<Type>::operator == 154, 174  
 WCValHashSet<Type>::remove 154, 175  
 WCValHashSet<Type>::removeAll 154, 176  
 WCValHashSet<Type>::resize 154, 177  
 WCValHashSet<Type>::WCValHashSet 153  
 WCValHashSet<Type>::WCValHashTable 154  
 WCValHashSet<Type>::~WCValHashSet 154  
 WCValHashSet<Type>::~WCValHashTable 154  
 WCValHashSetIter, member function  
   WCValHashSetIter<Type> 216-217  
   WCValHashTableIter<Type> 216-217  
 WCValHashSetIter<Type>::container 215, 222  
 WCValHashSetIter<Type>::current 215, 223  
 WCValHashSetIter<Type>::operator () 215, 224  
 WCValHashSetIter<Type>::operator ++ 215, 225  
 WCValHashSetIter<Type>::reset 215, 226-227  
 WCValHashSetIter<Type>::WCValHashSetIter  
   216-217  
 WCValHashSetIter<Type>::WCValHashSetIter<Type  
   > 215  
 WCValHashSetIter<Type>::WCValHashTableIter  
   219-220  
 WCValHashSetIter<Type>::~WCValHashSetIter 218  
 WCValHashSetIter<Type>::~WCValHashSetIter<Typ  
   e> 215  
 WCValHashSetIter<Type>::~WCValHashTableIter  
   221  
 WCValHashTable, member function  
   WCValHashSet<Type> 154  
   WCValHashTable<Type> 154  
 WCValHashTable<Type>::bitHash 154, 163  
 WCValHashTable<Type>::buckets 154, 164  
 WCValHashTable<Type>::clear 154, 165  
 WCValHashTable<Type>::contains 154, 166  
 WCValHashTable<Type>::entries 154, 167  
 WCValHashTable<Type>::find 154, 168  
 WCValHashTable<Type>::forall 154, 169  
 WCValHashTable<Type>::insert 154, 170  
 WCValHashTable<Type>::isEmpty 154, 171  
 WCValHashTable<Type>::occurrencesOf 154, 172  
 WCValHashTable<Type>::operator = 154, 173  
 WCValHashTable<Type>::operator == 154, 174  
 WCValHashTable<Type>::remove 154, 175  
 WCValHashTable<Type>::removeAll 154, 176  
 WCValHashTable<Type>::resize 154, 177

WCValHashTable<Type>::WCValHashSet 153  
WCValHashTable<Type>::WCValHashTable 154  
WCValHashTable<Type>::WCValHashTable<Type>  
    155-157, 159-161  
WCValHashTable<Type>::~WCValHashSet 154  
WCValHashTable<Type>::~WCValHashTable 154  
WCValHashTable<Type>::~WCValHashTable<Type>  
    158, 162  
WCValHashTableIter, member function  
    WCValHashSetIter<Type> 219-220  
    WCValHashTableIter<Type> 219-220  
WCValHashTableIter<Type>::container 215, 222  
WCValHashTableIter<Type>::current 215, 223  
WCValHashTableIter<Type>::operator () 215, 224  
WCValHashTableIter<Type>::operator ++ 215, 225  
WCValHashTableIter<Type>::reset 215, 226-227  
WCValHashTableIter<Type>::WCValHashSetIter  
    216-217  
WCValHashTableIter<Type>::WCValHashTableIter  
    219-220  
WCValHashTableIter<Type>::~WCValHashSetIter  
    218  
WCValHashTableIter<Type>::~WCValHashTableIter  
    221  
WCValOrderedVector, member function  
    WCValOrderedVector<Type> 568  
    WCValSortedVector<Type> 568  
WCValOrderedVector<Type>::append 568, 576  
WCValOrderedVector<Type>::clear 568, 577  
WCValOrderedVector<Type>::contains 568, 578  
WCValOrderedVector<Type>::entries 568, 579  
WCValOrderedVector<Type>::find 568, 580  
WCValOrderedVector<Type>::first 568, 581  
WCValOrderedVector<Type>::index 568, 582  
WCValOrderedVector<Type>::insert 568, 583  
WCValOrderedVector<Type>::insertAt 568, 584  
WCValOrderedVector<Type>::isEmpty 568, 585  
WCValOrderedVector<Type>::last 568, 586  
WCValOrderedVector<Type>::occurrencesOf 568,  
    587  
WCValOrderedVector<Type>::operator = 569, 589  
WCValOrderedVector<Type>::operator == 569, 590  
WCValOrderedVector<Type>::operator [] 568, 588  
WCValOrderedVector<Type>::prepend 568, 591  
WCValOrderedVector<Type>::remove 568, 592  
WCValOrderedVector<Type>::removeAll 568, 593  
WCValOrderedVector<Type>::removeAt 568, 594  
WCValOrderedVector<Type>::removeFirst 568, 595  
WCValOrderedVector<Type>::removeLast 568, 596  
WCValOrderedVector<Type>::resize 568, 597  
WCValOrderedVector<Type>::WCValOrderedVector  
    568  
WCValOrderedVector<Type>::WCValSortedVector  
    568

WCValOrderedVector<Type>::~WCValOrderedVecto  
    r 568  
WCValOrderedVector<Type>::~WCValSortedVector  
    568  
WCValSkipList, member function  
    WCValSkipList<Type> 488  
    WCValSkipListSet<Type> 488  
WCValSkipList<Type>::clear 489, 498  
WCValSkipList<Type>::contains 489, 499  
WCValSkipList<Type>::entries 489, 500  
WCValSkipList<Type>::find 489, 501  
WCValSkipList<Type>::forall 489, 502  
WCValSkipList<Type>::insert 489, 503  
WCValSkipList<Type>::isEmpty 489, 504  
WCValSkipList<Type>::occurrencesOf 489, 505  
WCValSkipList<Type>::operator = 489, 506  
WCValSkipList<Type>::operator == 489, 507  
WCValSkipList<Type>::remove 489, 508  
WCValSkipList<Type>::removeAll 489, 509  
WCValSkipList<Type>::WCValSkipList 488  
WCValSkipList<Type>::WCValSkipList<Type>  
    490-492, 494-496  
WCValSkipList<Type>::WCValSkipListSet 488-489  
WCValSkipList<Type>::~WCValSkipList 488  
WCValSkipList<Type>::~WCValSkipList<Type>  
    493, 497  
WCValSkipList<Type>::~WCValSkipListSet 489  
WCValSkipListDict, member function  
    WCValSkipListDict<Key, Value> 470  
WCValSkipListDict<Key, Value>::clear 470, 475  
WCValSkipListDict<Key, Value>::contains 470, 476  
WCValSkipListDict<Key, Value>::entries 470, 477  
WCValSkipListDict<Key, Value>::find 470, 478  
WCValSkipListDict<Key, Value>::findKeyAndValue  
    470, 479  
WCValSkipListDict<Key, Value>::forall 470, 480  
WCValSkipListDict<Key, Value>::insert 470, 481  
WCValSkipListDict<Key, Value>::isEmpty 470, 482  
WCValSkipListDict<Key, Value>::operator = 470, 483  
WCValSkipListDict<Key, Value>::operator == 470,  
    486  
WCValSkipListDict<Key, Value>::operator [] 470,  
    483-484  
WCValSkipListDict<Key, Value>::remove 470, 487  
WCValSkipListDict<Key, Value>::WCValSkipListDict  
    470  
WCValSkipListDict<Key, Value>::WCValSkipListDict  
    <Key, Value> 471-473  
WCValSkipListDict<Key, Value>::~WCValSkipListDi  
    ct 470  
WCValSkipListDict<Key, Value>::~WCValSkipListDi  
    ct<Key, Value> 474  
WCValSkipListSet, member function  
    WCValSkipList<Type> 488-489

- WCValSkipListSet<Type> 488-489  
 WCValSkipListSet<Type>::clear 489, 498  
 WCValSkipListSet<Type>::contains 489, 499  
 WCValSkipListSet<Type>::entries 489, 500  
 WCValSkipListSet<Type>::find 489, 501  
 WCValSkipListSet<Type>::forall 489, 502  
 WCValSkipListSet<Type>::insert 489, 503  
 WCValSkipListSet<Type>::isEmpty 489, 504  
 WCValSkipListSet<Type>::occurrencesOf 489, 505  
 WCValSkipListSet<Type>::operator = 489, 506  
 WCValSkipListSet<Type>::operator == 489, 507  
 WCValSkipListSet<Type>::remove 489, 508  
 WCValSkipListSet<Type>::removeAll 489, 509  
 WCValSkipListSet<Type>::WCValSkipList 488  
 WCValSkipListSet<Type>::WCValSkipListSet 488-489  
 WCValSkipListSet<Type>::~WCValSkipList 488  
 WCValSkipListSet<Type>::~WCValSkipListSet 489  
 WCValSList, member function  
   WCValDList<Type> 285-286, 288  
   WCValSList<Type> 285-286, 288  
 WCValSList<Type>::append 283, 293  
 WCValSList<Type>::clear 283, 294  
 WCValSList<Type>::clearAndDestroy 283, 295  
 WCValSList<Type>::contains 283, 296  
 WCValSList<Type>::entries 283, 297  
 WCValSList<Type>::find 283, 298  
 WCValSList<Type>::findLast 283, 299  
 WCValSList<Type>::forAll 283, 300  
 WCValSList<Type>::get 283, 301  
 WCValSList<Type>::index 283, 302  
 WCValSList<Type>::insert 283, 303  
 WCValSList<Type>::isEmpty 283, 304  
 WCValSList<Type>::operator = 284, 305  
 WCValSList<Type>::operator == 284, 306  
 WCValSList<Type>::WCValDList 287, 289-292  
 WCValSList<Type>::WCValSList 285-286, 288  
 WCValSList<Type>::WCValSList<Type> 283  
 WCValSList<Type>::~WCValSList<Type> 283  
 WCValSListItemSize  
   macro 259, 286, 416, 514  
 WCValSListIter, member function  
   WCValDListIter<Type> 396-397  
   WCValSListIter<Type> 396-397  
 WCValSListIter<Type>::append 394, 402  
 WCValSListIter<Type>::container 394, 403  
 WCValSListIter<Type>::current 394, 404  
 WCValSListIter<Type>::insert 394, 405  
 WCValSListIter<Type>::operator () 394, 406  
 WCValSListIter<Type>::operator ++ 394, 407  
 WCValSListIter<Type>::operator += 394, 408  
 WCValSListIter<Type>::operator -- 394-395, 409  
 WCValSListIter<Type>::operator -= 394-395, 410  
 WCValSListIter<Type>::reset 394, 411-412  
 WCValSListIter<Type>::WCValDListIter 399-400  
 WCValSListIter<Type>::WCValSListIter 396-397  
 WCValSListIter<Type>::WCValSListIter<Type> 394  
 WCValSListIter<Type>::~WCValDListIter 401  
 WCValSListIter<Type>::~WCValSListIter 398  
 WCValSListIter<Type>::~WCValSListIter<Type> 394  
 WCValSortedVector, member function  
   WCValOrderedVector<Type> 568  
   WCValSortedVector<Type> 568  
 WCValSortedVector<Type>::append 568, 576  
 WCValSortedVector<Type>::clear 568, 577  
 WCValSortedVector<Type>::contains 568, 578  
 WCValSortedVector<Type>::entries 568, 579  
 WCValSortedVector<Type>::find 568, 580  
 WCValSortedVector<Type>::first 568, 581  
 WCValSortedVector<Type>::index 568, 582  
 WCValSortedVector<Type>::insert 568, 583  
 WCValSortedVector<Type>::insertAt 568, 584  
 WCValSortedVector<Type>::isEmpty 568, 585  
 WCValSortedVector<Type>::last 568, 586  
 WCValSortedVector<Type>::occurrencesOf 568, 587  
 WCValSortedVector<Type>::operator = 569, 589  
 WCValSortedVector<Type>::operator == 569, 590  
 WCValSortedVector<Type>::operator [] 568, 588  
 WCValSortedVector<Type>::prepend 568, 591  
 WCValSortedVector<Type>::remove 568, 592  
 WCValSortedVector<Type>::removeAll 568, 593  
 WCValSortedVector<Type>::removeAt 568, 594  
 WCValSortedVector<Type>::removeFirst 568, 595  
 WCValSortedVector<Type>::removeLast 568, 596  
 WCValSortedVector<Type>::resize 568, 597  
 WCValSortedVector<Type>::WCValOrderedVector 568  
 WCValSortedVector<Type>::WCValSortedVector 568  
 WCValSortedVector<Type>::WCValSortedVector<Type> 570-571, 573-574  
 WCValSortedVector<Type>::~WCValOrderedVector 568  
 WCValSortedVector<Type>::~WCValSortedVector 568  
 WCValSortedVector<Type>::~WCValSortedVector<Type> 572, 575  
 WCValVector<Type>::clear 598, 603  
 WCValVector<Type>::length 598, 604  
 WCValVector<Type>::operator = 598, 606  
 WCValVector<Type>::operator == 598, 607  
 WCValVector<Type>::operator [] 598, 605  
 WCValVector<Type>::resize 598, 608  
 WCValVector<Type>::WCValVector<Type> 598-601  
 WCValVector<Type>::~WCValVector<Type> 598, 602  
 width, member function

ios 655-656, 689  
write, member function  
    ostream 755, 777  
ws, manipulator 733, 747

## X

xalloc, member function  
    ios 656, 690

## Z

zero\_buckets  
    exception 70, 104, 130, 152, 177  
zero\_buckets, member enumeration  
    WCExcept 70

## ~

~WCIsvConstDListIter, member function  
    WCIsvConstDListIter<Type> 314  
    WCIsvConstSListIter<Type> 314  
~WCIsvConstSListIter, member function  
    WCIsvConstDListIter<Type> 311  
    WCIsvConstSListIter<Type> 311  
~WCIsvDListIter, member function  
    WCIsvDListIter<Type> 331  
    WCIsvSListIter<Type> 331  
~WCIsvSListIter, member function  
    WCIsvDListIter<Type> 328  
    WCIsvSListIter<Type> 328  
~WCPtrConstDListIter, member function  
    WCPtrConstDListIter<Type> 349  
    WCPtrConstSListIter<Type> 349  
~WCPtrConstSListIter, member function  
    WCPtrConstDListIter<Type> 346  
    WCPtrConstSListIter<Type> 346  
~WCPtrDListIter, member function  
    WCPtrDListIter<Type> 366  
    WCPtrSListIter<Type> 366  
~WCPtrHashDict, member function  
    WCPtrHashDict<Key,Value> 82  
~WCPtrHashDictIter, member function  
    WCPtrHashDictIter<Key,Value> 183  
~WCPtrHashSet, member function  
    WCPtrHashSet<Type> 105  
    WCPtrHashTable<Type> 105  
~WCPtrHashSetIter, member function  
    WCPtrHashSetIter<Type> 205  
    WCPtrHashTableIter<Type> 205  
~WCPtrHashTable, member function  
    WCPtrHashSet<Type> 106  
    WCPtrHashTable<Type> 106  
~WCPtrHashTableIter, member function  
    WCPtrHashSetIter<Type> 208  
    WCPtrHashTableIter<Type> 208  
~WCPtrOrderedVector, member function  
    WCPtrOrderedVector<Type> 525  
    WCPtrSortedVector<Type> 525  
~WCPtrSkipList, member function  
    WCPtrSkipList<Type> 446  
    WCPtrSkipListSet<Type> 446  
~WCPtrSkipListDict, member function  
    WCPtrSkipListDict<Key,Value> 426  
~WCPtrSkipListSet, member function  
    WCPtrSkipList<Type> 446  
    WCPtrSkipListSet<Type> 446  
~WCPtrSListIter, member function  
    WCPtrDListIter<Type> 363  
    WCPtrSListIter<Type> 363  
~WCPtrSortedVector, member function  
    WCPtrOrderedVector<Type> 525  
    WCPtrSortedVector<Type> 525  
~WCValConstDListIter, member function  
    WCValConstDListIter<Type> 384  
    WCValConstSListIter<Type> 384  
~WCValConstSListIter, member function  
    WCValConstDListIter<Type> 381  
    WCValConstSListIter<Type> 381  
~WCValDListIter, member function  
    WCValDListIter<Type> 401  
    WCValSListIter<Type> 401  
~WCValHashDict, member function  
    WCValHashDict<Key,Value> 132  
~WCValHashDictIter, member function  
    WCValHashDictIter<Key,Value> 194  
~WCValHashSet, member function  
    WCValHashSet<Type> 154  
    WCValHashTable<Type> 154  
~WCValHashSetIter, member function  
    WCValHashSetIter<Type> 218  
    WCValHashTableIter<Type> 218  
~WCValHashTable, member function  
    WCValHashSet<Type> 154  
    WCValHashTable<Type> 154  
~WCValHashTableIter, member function  
    WCValHashSetIter<Type> 221

WCValHashTableIter<Type> 221  
~WCValOrderedVector, member function  
  WCValOrderedVector<Type> 568  
  WCValSortedVector<Type> 568  
~WCValSkipList, member function  
  WCValSkipList<Type> 488  
  WCValSkipListSet<Type> 488  
~WCValSkipListDict, member function  
  WCValSkipListDict<Key,Value> 470  
~WCValSkipListSet, member function  
  WCValSkipList<Type> 489  
  WCValSkipListSet<Type> 489  
~WCValSListIter, member function  
  WCValDListIter<Type> 398  
  WCValSListIter<Type> 398  
~WCValSortedVector, member function  
  WCValOrderedVector<Type> 568  
  WCValSortedVector<Type> 568