MAX FOR LIVE · ABLETON LIVE 11 / 12

Tuple

Every chord in your key, one click away.

A chord-grid instrument for Ableton Live: explore, perform and record harmony in real time — triads, sevenths, ninths, borrowed chords and secondary dominants, all voiced and voice-led.



DOCUMENT
User Manual

VERSION
v1.7.0

EDITION
2026 · EN

ONLINE
tuple.live

One screen, all your harmony.

Tuple lays out **every valid chord** in your key as a playable grid — always visible, never hidden behind a menu — and lets you **place those chords in time** on a progression of up to 32 bars, then write the result to a clip.

Pick a key and a scale: Tuple instantly generates the full grid of diatonic chords, column by column, from degree `I` to degree `VII`. **Borrowed chords** and **secondary dominants** stay inside the same grid — no wizard, no separate page.

Click a cell (or hit a pad on the Push 2): the chord plays at once, already voiced and voice-led from the previous one. Your hands stay on the music.

KEY IDEA


Tuple outputs **the chord only** — every voicing stays a coherent chord you can play with one hand.

01 Installation & requirements p.3
02 Quick start p.5
03 Interface overview p.6
04 Harmony — Key · Scale · Sync p.12
05 Voicing — Voicing · Leading · Octave p.14
06 The grid & borrowed chords p.17
07 Color logics (Layout) p.19
08 Smart Chords p.20
09 Voicing reference p.22
10 Chord-family reference p.24
11 Monitor & dual window p.25
12 Progression → Clip p.26
13 Push 2 integration p.30
14 Recording p.32
15 Automatic updates p.33
16 Tips, troubleshooting & credits p.34
★ Glossary p.35
★ What's new in 1.7 p.36

Getting Tuple onto a track.

Requirements

- **Ableton Live 11 or 12**, Suite edition — or Standard/Intro with the **Max for Live** add-on.
- About **50 MB** of disk space.
- **Push 2** — optional, to play the grid on the pads.
- An **instrument** (synth, piano…) on the same track to hear the chords.



CHAIN ORDER. TUPLE → INSTRUMENT, ON THE SAME MIDI TRACK.

IMPORTANT

Do not rename or move the files shipped alongside the device: the interface loads from the folder. Keep the bundle intact.

DID YOU KNOW

Tuple outputs the chord only, leaving the rest of your arrangement on its own tracks — you keep full control of the low register.

Installation

Choose the method for your OS:

Windows

01 Download `Tuple-Installer.exe` from tuple.live and run it.

02 The installer places the Tuple folder in your **User Library › Presets › Max MIDI Effect** automatically.

03 Restart Ableton — Tuple appears under Max MIDI Effect in the browser.

macOS

01 Download `tuple.zip` from tuple.live and unzip it.

02 Double-click `Install Tuple.command`. If macOS blocks it, right-click → **Open** first.

03 Pick your **User Library › Presets › Max MIDI Effect** folder when prompted.

04 Restart Ableton — Tuple appears under Max MIDI Effect.

Manual (all platforms)

01 Unzip `tuple.zip` and **keep all files in the same folder**.

02 In Live, drag `tuple.amxd` onto a **MIDI track**.

03 Place Tuple **before the instrument** in the MIDI effect chain.

04 Arm the track: the chords you play feed the instrument.

Your first progression in 60 seconds.

01 **Set the harmony.** Click **KEY** and **SCALE**, or press **SYNC** to import Live's current scale.

02 **Open the grid.** Click **OPEN** to reveal the full window with every chord.

03 **Play a chord.** Click a cell in column `I` — it sounds and its notes appear in the Monitor.

04 **Move on.** Jump to columns `IV`, `V`, `VI`... With **Voice Leading** on, transitions stay smooth.

05 **Record.** Arm the track, hit record, and perform the grid live.

A PROGRESSION TO START WITH

In **C MAJOR**, try the classic `I - V - vi - IV`:

`C` → `G` → `Am` → `F`

Then move down one row to switch to sevenths (`CM7 · G7 · Am7 · FM7`): the grid stacks richness vertically, from simplest to most colorful.

PERFORMANCE TIP

The **BORROWED column** (far right) adds color and tension without leaving the key: drop a `bVII` or a `V/vi` into the middle of a diatonic progression.

SHORTCUT

Instead of setting KEY/SCALE by hand, put Tuple on a track whose Live scale is already defined, then press `SYNC`.

The control strip.

Inside Live's rack, Tuple sits in a compact strip: controls on the left, Monitor on the right. The full grid opens in a second window.




FIGURE 3.1 — THE COMPACT STRIP IN LIVE'S DEVICE RACK, AT ITS REAL SIZE.

1. **Tuple** — about, version, updates
2. **KEY** — the root
3. **SCALE** — the mode
4. **SYNC** — follow key & scale from Live
5. **VOICING** — the spacing
6. **LEADING** — Off / Anchor / Follow
7. **OCTAVE** — −2 to +2
8. **The Monitor** — degree, chord name, notes, keyboard
9. **OPEN** — lifts the full window

LEFT — SIX FIELDS SHAPE THE CHORD

- **Key · Scale** — the tonal centre and mode the whole grid is built from. ↳ Ch. 4
- **Sync** — follow the key & scale straight from Live's own scale setting.
- **Voicing** — how the notes are spread: eight spacings, `Default` to `Rootless`. ↳ Ch. 5
- **Leading** — smooth the motion from one chord to the next: `Off · Anchor · Follow`.
- **Octave** — shift the whole chord up or down, `-2` to `+2`.

RIGHT — THE MONITOR

- **Monitor** — the chord you're playing, its note names and a mini-keyboard, on the same screen as the fields.
- **Open** — the key at the top right unfolds the full chord grid in its own window (Fig. 3.2).

Tuple, in the flesh.

The same device, unfolded: the top screen, the whole grid, and the progression screen underneath, between its keys.



FIGURE 3.2 — THE FULL WINDOW IN C MAJOR, AT ITS REAL SIZE OF 1200 × 734.

1. **The top screen** — every setting, one click away
2. **The grid** — I to VII, plus Borrowed
3. **The progression screen** — cards, then clip

TOP — THE TOP SCREEN

Four groups of fields: **HARMONY** (Key, Scale, Sync), **VOICING** (Voicing, Leading, Octave, Smart), **PLAY** (Expression, Push) and **SYSTEM** (Settings). Everything that shapes the chord is one press away. A list opens inside the screen, and ‹ takes you back; Expression shows its faders there (Strum, Curve, Ramp, Humanize, Velocity).

CENTRE — THE GRID

Every valid chord for the key, color-coded by degree: seven columns `I`–`VII` plus a Borrowed column. The **screen** at the bottom carries the progression — fields, bar ruler and cards, always visible — and the **Monitor** lives on it. Physical keys sit on both sides: Capture, Play, Stop on the left; Create clip, Re-voice all, Clear on the right.

SETTINGS

The Settings field opens the once-in-a-while fields in the top screen: **Layout**, **Notation**, **Extended**, **Avoid notes**, **MIDI out**, **On top** and **Theme** — Tuple ships in its **Night** look, one press for Day — plus **About** and **Manual**. The window itself is resizable: the whole face scales as one, nothing reflows or truncates.

The full window (grid).

One click on **OPEN** unfolds the whole grid: seven degree columns and the BORROWED column. Nothing shares the space with them — the settings are on the top screen, the progression on the screen below.




FIGURE 3.3 — THE GRID IN C MAJOR: SEVEN DEGREE COLUMNS I–VII + BORROWED, EVERY VALID CHORD FOR THE KEY. THE CHORD BEING PLAYED STANDS OUT; BORROWED CHORDS SIT IN THE LAST COLUMN.

THE EIGHTH COLUMN



THE BORROWED COLUMN. SAME SHAPE AS THE SEVEN DEGREES, ONE COLOUR APART — VIOLET IN EVERY LAYOUT, SO A BORROWED CHORD NEVER PASSES FOR A DIATONIC ONE.


READING THE GRID

- **Columns** = the seven degrees, from `I` (tonic) to `VII` (leading tone).
- **Rows** = chord families, ordered from simplest (triad) to most colorful (extensions).
- **Right column** = borrowed chords & secondary dominants.

BEYOND THE GRID

- **Push** (top screen) — grabs the Push 2 pad grid.
- **Settings** — Layout (the degree color logic), Notation, Extended, Avoid notes, MIDI out, On top, Theme (Night / Day), About, Manual.
- **Logo** — click the logo (top-left) to open About: version, links, and the update panel when a new version is available.

A CELL, UP CLOSE



ONE CELL, CLOSE UP. THE HEAD CARRIES THE ROMAN NUMERAL AND THE DEGREE NAME; EVERY CELL IN THE COLUMN REPEATS ITS COLOUR AS A DOT ON THE RIGHT, SO YOU CAN FIND A COLUMN WITHOUT READING A SINGLE WORD.

The top screen, field by field.

Ten fields, four groups, one row. Every one of them carries its own label, so nothing here needs to be memorised — this page only says what each one changes. Hover a field and a small chevron shows it responds.




FIGURE 3.4 — THE TOP SCREEN AT ITS REAL SIZE, 1036 × 80.

FIELD	WHAT IT CHANGES	CHAPTER
Key	The root the whole grid is built from.	04
Scale	The mode. Changing it rebuilds every column at once.	04
Sync	Follows key and scale from Live's own scale setting. It reads `Live` and its lamp stays lit while it follows.	04
Voicing	Chord spacing — eight styles, from `Default` to `Rootless`.	09
Leading	Voice leading: `Off`, `Anchor`, `Follow`.	05
Octave	Shifts the whole chord, `-2` to `+2`.	05
Smart	Suggestions: `Off`, `Function`, `Leading` (voice-leading). Each press moves to the next.	08
Expression	Opens the faders in the screen: Strum, Curve, Ramp, Humanize, Velocity. Also sent out as `CC 20–25`.	05
Push	Grabs the Push 2 pad grid. The lamp says whether it holds it.	13
Settings	Opens the settings in the screen — what you set once and forget.	–

Settings — set once, forget.




FIGURE 3.5 — SETTINGS, OPEN IN THE TOP SCREEN. ‹ COMES BACK TO THE MAIN PAGE.

FIELD	WHAT IT DOES
Layout	The degree colour logic: Spectrum, Function, Tension, Fifths, Quality. ↳ Ch. 7
Notation	Flat or sharp spelling for every name on the grid.
Extended	Enriches the borrowed chords from what you play. The diatonic grid never changes. ↳ Ch. 6
Avoid notes	Filters the tensions that clash with the chord. Switchable, because some styles want them.
MIDI out	Sends the chords to another track: lists this track's `MIDI To` outputs from Live, and Live saves your choice with the set. With an instrument after Tuple on the track it reads `Instrument` and does nothing.
On top	Keeps the full window above Live.
Theme	Night or Day. Tuple opens in `Night`, and this manual is shot in it.
About	Version, links, and the update panel when a new build is out. ↳ Ch. 15
Manual	Opens this manual on `tuple.live`.

WHY SO FEW

Everything that shapes a chord lives on the top screen, in the open. Settings only holds what you decide once: how the grid is coloured, how notes are spelled, which window sits on top.

Key · Scale · Sync.

Change the root or the scale and the whole grid follows.

Key — the root

Twelve roots, laid out like a keyboard: the tonal center of the degrees `I-VII`.

Scale — the mode

It sets the color of the degrees and the chords. Pick a family tab, then a mode:

SCALE	CHARACTER	TYPICAL DEGREE I
Major	Bright, stable — the tonal reference	`I maj`
Minor	Dark, natural minor (Aeolian)	`i m`
Dorian	Minor with a major sixth — jazz, modal	`i m`
Phrygian	Tense minor, minor second — Spanish color	`i m`
Lydian	Dreamy major, augmented fourth	`I maj`
Mixolydian	Major with a minor seventh — groove, blues	`I 7`
Harmonic Minor	Dramatic minor, raised leading tone	`i m`
Melodic Minor	Minor with a raised 6th & 7th — jazz minor	`i m`
Locrian	Diminished tonic, ♭2 & ♭5 — unstable, dark	`i°`
Lydian Dominant	Lydian with a ♭7 — the ♯11 dominant color	`I 7`
Major Pentatonic	Five notes, no semitone tension — open	`I maj`
Minor Pentatonic	Five-note minor — riffs, blues, lo-fi	`i m`

18 more modes complete three mode families:

Melodic minor	`Dorian b2 · Lyd. Aug · Mixo b6 · Locrian #2 · Altered`
Harmonic minor	`Locrian #6 · Ionian #5 · Dorian #4 · Phryg. Dom · Lydian #2 · Ultraloc.`
Harmonic major	`Harm.Maj · Dorian b5 · Phryg. b4 · Lydian b3 · Mixo b2 · Lyd.Aug #2 · Locr. bb7`

Every scale has borrowed chords. Pentatonics use their parent scale's table; the 18 added modes compute theirs: the major and minor triads of the parallel scale (natural minor if the tonic has a major third, else major) that the mode lacks, nearest the tonic first, four at most.

Sync & notation

On load, Tuple imports Live's key & scale automatically — the grid starts matched to your project, nothing to set up. A set that holds a saved progression keeps its own key instead.

The **SYNC** field then keeps Tuple on Live: press it and it imports the key and scale, reads `Live`, and follows every change made in Live. While it follows, KEY and SCALE are locked. Press it again to set them by hand.

NOTATION — FLAT OR SHARP

The **NOTATION** field, in **SETTINGS**, moves all chord names between **flat** and **sharp** notation — grid, screen and menus update at once. The preference is saved and restored across sessions.

Flats ♭	E♭, A♭, B♭ — common in jazz, pop, brass arrangements.
Sharps ♯	D#, G#, A# — common in guitar-centric contexts.


WORKFLOW

Set the scale in Live once, then turn on Sync in all your Tuple devices. Change the key in Live and they all follow, which transposes a whole session.

SYNC IS ON THE STRIP

`SYNC` is one of the six fields on the compact strip — no need to open the full window to follow Live's scale. Notation, being a set-once choice, lives in `Settings` in the full window.

THE SYNC LAMP



THE HARMONY GROUP, FOLLOWING LIVE. THE LAMP BESIDE SYNC STAYS LIT AND THE FIELD READS LIVE WHILE TUPLE FOLLOWS LIVE'S SCALE. PRESS IT AGAIN AND THE LAMP GOES OUT.

Voicing · Leading · Octave.

The Voicing group, in this order: how the notes are spread, how they move from one chord to the next, and the register. Smart, the last field of the group, has its own chapter (↳ Ch. 8).

Octave

Transposes the whole chord, from `-2` to `+2` octaves. The field reads `◂ 0 ▸`: click an arrow to step, or scroll on the field. Handy to seat chords in the right register within your arrangement.

Voicing

Defines how the chord's notes are spread across the register. The list holds eight spacings — `Default`, `Closed`, `Clear`, `Open`, `Section`, `Chord Melody`, `Two Hands` and `Rootless` — each described in the ↳ voicing reference. `Default` is the neutral one: no voicing at all, every chord tone at its default position, and voice leading never moves it.

DESIGN RULE

Every spacing is playable with one hand, root included — except `Rootless`, which leaves the root to the bass. Only `Two Hands` is deliberately two-handed (low root + right-hand chord).

Extended

The **EXTENDED** field, in **SETTINGS**, enriches the **borrowed chords** from what you play: Borrowed and Mediants take the extension that fits after your last chord, and tritone subs become `7#11`. The diatonic grid never changes — for the 9ths, 11ths and 13ths of a degree, open the `Ext` page of the Borrowed column. Turn it off for the plain borrowed chords. ↳ Ch. 6

Voice Leading

When on, **Voice Leading** pulls each new chord close to the previous one: the voices move as little as possible, so transitions become smooth and musical instead of jumpy.

ONE CONTROL, THREE POSITIONS

Off	Chords stay exactly as the voicing built them.
Anchor	Anchors the voices around a fixed register — stable and predictable.
Follow	Minimal movement from the previous chord — the smoothest, most legato.

IN PRACTICE

For legato pads, set LEADING to `Follow`. For repeated rhythmic stabs, set it to `Off` so every chord lands in the same place each time.

WHICH SPACINGS RESPOND

Voice leading reshapes seven of the eight. `Default` is the exception: it produces a single candidate, so there is nothing for Anchor or Follow to choose between — measured, it stays put on all 91 cells while `Closed` moves on most of them under Anchor. That is what makes it a neutral reference rather than a style.

EXPRESSION (FULL WINDOW)

The Expression field, in the PLAY group of the full window, opens five performance controls in the screen. Drag or scroll each; `center / 0` = off.

Strum	Spreads the chord over time. Left = down (high→low), right = up (low→high); larger values turn the chord into an arpeggio.	`±250 ms`
Curve	Shape of the strum spacing: Linear, Accelerate or Decelerate.	`3 shapes`
Ramp	Velocity ramp across the strummed notes. Left = fade (first note loudest), right = build.	`±100`
Humanize	Subtle, random velocity & timing variation for a less mechanical feel.	`0 = off`
Velocity	Clamps the output velocity between its two handles, after Ramp and Humanize.	`1–127`

EXPRESSION AS MIDI CC

Each control also goes out as a MIDI controller when you move it — `CC 20` Strum, `CC 21` Ramp, `CC 22` Curve, `CC 23` Humanize, `CC 24` and `CC 25` the Velocity handles (bipolar controls sit at 64 when centred). Map them in the instrument after Tuple, or record them: they are sent on change only, never on load.

VELOCITY RANGE

The two Velocity handles are also Live parameters, `Vel Min` and `Vel Max` (1–127, in the device's automation list). They clamp Tuple's output velocity at the very end of the chain, after Ramp and Humanize. The defaults, 1 and 127, leave the sound untouched.

WHERE THE CONTROLS LIVE




EXPRESSION, OPEN IN THE TOP SCREEN. STRUM, RAMP, HUMANIZE AND VELOCITY ARE LIVE PARAMETERS, AND EVERY CONTROL ALSO LEAVES ON A MIDI CONTROLLER — DRAG, OR SCROLL ON THE VALUE.

What Voice Leading changes.

Voice Leading is the craft of moving between chords with the **least** motion: keep the notes two chords share in place, and let the rest step to the nearest note instead of jumping. It makes a progression sound connected and legato rather than blocky — and Tuple applies it automatically, re-laying each chord to sit close to the one before.

WITHOUT VOICE LEADING


Each chord plays in root position, in a fixed register. The whole hand jumps from one chord to the next — fine for rhythmic stabs, but disconnected for sustained parts.



C → F: THE HAND "JUMPS" TO THE RIGHT.

WITH VOICE LEADING

The target chord is rearranged to sit near the previous one — shared notes hold, the rest glide by a step. The fingers barely move and the progression flows. One control, three positions, read left to right as manual → automatic: **Off** leaves the voicing untouched, **Anchor** keeps a stable register, **Follow** chases the smoothest path (↳ Ch. 5).



C → F: C IS SHARED, ONLY TWO VOICES GLIDE BY A STEP.

BY EAR

Voice Leading doesn't change **which** chord you play — only **how** it's laid out. The harmonic function stays identical; what changes is the smoothness of the transition.

Every valid chord, never hidden.

Tuple's principle: show the maximum number of valid chords for the chosen scale, and keep borrowed chords inside the same grid.

The diatonic degrees

Each column is a degree of the scale, named by its function:

I	Tonic — rest
II	Supertonic
III	Mediant
IV	Subdominant — the lift
V	Dominant — the tension
VI	Submediant — the relative
VII	Leading tone — instability

The rows stack the degree's chord families, from triad to extensions. A column stops where the scale no longer yields a valid chord — hence the uneven column heights.

The Borrowed column

The last column gathers **borrowed chords** (modal interchange) and **secondary dominants** — colors from elsewhere that enrich the key without leaving it.

IN MAJOR	ROLE
♭III ♭VI ♭VII	Borrowed from the parallel minor
iv	Minor subdominant
V/V V/ii V/vi	Secondary dominants

INSTANT COLOR

A minor `iv` right before returning to the `I` is one of the most moving borrowings in pop.

MORE PAGES — TRITONE, MEDIANTS & EXT

The column header holds four small screens, one per page: `♭` (`Borrowed`, the table above), `TRI` (`Tritone`), `MED` (`Mediants`, chromatic mediants) and `EXT` (`Ext`). The page you are on glows violet; **click any other screen** to switch straight to that page. `MED` exists in major and minor only: elsewhere it stays dimmed and does nothing, and switching to such a scale while on `Mediants` falls back to page 1. The page is also a Live parameter (`Borrowed Page`), automatable and saved with your set.

`Tritone` follows your playing: after each chord, it offers tritone substitutes (a dominant seventh a half step above the target) leading to the chords most likely to come next, ranked like Smart. Each cell names its target — `D♭7 → C`, always first before you play. A tritone sub counts as its target: after `D♭7` the page reads as after `C`, and never offers the one you just played. `Ext` shows what the column of the last diatonic chord you played does **not** have: on the ii of C major, `Dm11 D7sus4 D6sus2 Dmadd11…`, from your scale, minus avoid notes, closest first; when nothing is new, it stays empty. Both work in every scale. With **EXTENDED** on, each tritone sub becomes a `7♯11`; the Ext page does not change.



FIGURE 6.1 — WITH **EXTENDED** ON, HERE AFTER C, THE SEVEN DIATONIC COLUMNS STAY EXACTLY AS THEY ARE; ONLY THE BORROWED COLUMN TAKES ITS COLOR: D♯ADD9, FM6, G♯6…

THE BORROWED COLUMN, ENRICHED



THE BORROWED COLUMN, EXTENDED ON. THE SAME CHORDS, EACH WITH THE EXTENSION THAT FITS AFTER YOUR LAST CHORD. AFTER DM7, FM6 BECOMES FM9.

With EXTENDED on, Borrowed and Mediants follow your playing too. The chords stay the same — same roots, same qualities, same order — but each one takes the extension that fits **after the chord you just played**: a new color the previous chord did not already have, one note richer, sevenths after sevenths and sixths/add chords after triads. In C major, after `C` the `iv` reads `Fm6`; after `Dm7` it reads `Fm9`. The cell you just played keeps its name while you hold it; the others move. A captured card keeps exactly what you heard. Changing key or scale starts again from the tonic. With **EXTENDED** off, the column shows the plain chords, as before.

Layout — reading the grid in color.


The **LAYOUT** field, in **SETTINGS**, opens a list of five color logics in the screen — or scroll on it to cycle. The grid stays the same; only the way you read it changes.

I	II	III	IV	V	VI	VII

LOGIC	WHAT THE COLOR ENCODES	USE IT TO…
Spectrum	A distinct hue per degree, rainbow-style (the bar above).	spot the column instantly.
Function	tonic · subdominant · dominant.	think in tension/rest.
Tension	home → tense, by dissonance.	pace the color of a progression.
Fifths	near → far on the circle of fifths.	compose by fifth motion.
Quality	major · minor · dim · aug.	sort chords by type.

In every logic, **borrowed** chords stay violet.

THE HEADS OF THE EIGHT COLUMNS



THE EIGHT HEADS, IN SPECTRUM. EACH CARRIES ITS ROMAN NUMERAL ON THE DEGREE'S OWN COLOUR, AND EVERY CELL BELOW REPEATS THAT COLOUR AS A DOT. CHANGE THE LOGIC AND ONLY THESE COLOURS MOVE — THE CHORDS STAY WHERE THEY ARE.



FIGURE 7.1 — THE SAME GRID READ IN FUNCTION: TONIC (BLUE), SUBDOMINANT (GREEN), DOMINANT (RED), BORROWED (VIOLET).

ADVICE

Start in **Spectrum** to memorize where the degrees are, then switch to **Function** once you think in tonic / subdominant / dominant.

Where to go next.

Turn **SMART** on and, as you play, Tuple lights up the chords that follow naturally from the one you just played. It's a guide laid over the grid — every chord stays playable; nothing is hidden or forced.

How to read it

The **hue** is always the degree color of your current Layout, so the grid still reads the same. The **brightness** carries the suggestion: **brighter = stronger**. Empty cells stay dark, and the chord you just played stays highlighted as the anchor.




FIGURE 8.1 — SMART IN FUNCTION MODE AFTER PLAYING THE I: THE STRONGEST FOLLOW-UPS GLOW, GROUPED ACROSS FUNCTIONS.

MODE	WHAT BRIGHTNESS MEANS	USE IT TO…
Function	Harmonic strength — how strongly a chord wants to follow, by function (resolutions, dominants, set-ups, surprises, color).	find the convincing next move.
Voice leading	Smoothness — how little the notes move to get there, measured on your **current voicing & octave**.	keep the motion seamless.

Each press on the **SMART** field moves through **Off → Function → Voice leading**. Suggestions are grouped by harmonic function, so you always see a spread of options — a few resolutions, a few tension moves, a few colors — never a whole row lit at once.

GOOD TO KNOW

Smart works in **any** Layout — it's a mode, not a color scheme. And because Voice leading reads your actual voicing, changing the **VOICING** re-ranks the suggestions: the same progression can light up differently in Closed vs. Open.

WHAT A SUGGESTION LOOKS LIKE



THREE COLUMNS UNDER SMART. A LIT CELL IS A CHORD WORTH PLAYING NEXT; THE BRIGHTER IT IS, THE STRONGER THE PULL. THE HUE STAYS THE DEGREE'S OWN, SO A SUGGESTION NEVER HIDES WHICH COLUMN IT BELONGS TO.

Eight spacings, one axis.

The voicing decides how a chord's notes are spread across the register. There are eight, and they read as one axis — from no voicing at all to the widest grip. Every one is playable with one hand, root included (except `Rootless`, which leaves the root out); only `Two Hands` is deliberately two-handed.




FIGURE 9.1 — THE VOICING LIST, OPEN IN THE TOP SCREEN.

SPACING	WHAT IT DOES
Default	No voicing at all: every chord tone at its default position, in order — root, 3rd, 5th, 7th, then the extensions. Voice leading never moves it, so it is the reference to compare the others against.
Closed	True close position: from the bass up, each note sits as low as it can above the one before. No chord tone can slip into a gap.
Clear	Closed, with no seconds down low — each chord stands apart.
Open	The root stays at the bottom and the chord opens just above it. Air between the voices, clarity for pads.
Section	Drop 2 — the horn-section voicing. The second voice from the top drops an octave: the muddy middle clears and the top note gets air.
Chord Melody	Drop 3 — the solo-guitar voicing. The third voice from the top drops instead. Needs four notes; on a triad the cell plays an open triad.
Two Hands	The bass note alone, the rest of the chord about an octave above it. The only one that asks for two hands, and the only one that reaches below C3.
Rootless	No root — leave it to the bass. Thirds, sevenths and ninths, the jazz-piano way.

ONE RULE HOLDS ACROSS ALL EIGHT

Tuple plays **the chord**, not a bass part. No spacing drops a voice below the chord to fake a bassline — that is doubling, not voicing, and it belongs on its own track. `Two Hands` is the documented exception, and it still keeps its floor at C2.

What happened to the old styles.

Tuple used to ship twenty-nine voicings: six of the spacings above, plus twenty-three genre grips — House, Trance, Funk, Jazz, the Rootless family, Quartal, Soul, Rave and the rest. They were removed in v1.5.0. Here is what that means for a set you already have.

One parameter

`Voice Spacing` is the Live parameter that holds the style: eight positions, from `Closed` to `Clear`, automatable and MIDI-mappable. `Rootless` and `Clear` were added at the end of the list in v1.7.0: none of the earlier positions moved. v1.5.0 also kept the old `Voicing` parameter, with all twenty-nine of its entries, so that an old set could reopen on the nearest surviving spacing. That bridge is gone now.

What an old set sounds like now

- A set saved before this version **reopens on `Closed`**, whatever style it used. Open it, listen, and pick the spacing that fits.
- An automation lane on `Voice Spacing` written with v1.5.0 is **one step off**: that version had an extra entry, `(from Voicing)`, at the top of the list. Redraw the lane, or shift its values down by one.
- `Closed` itself changed in v1.5.0 — it is genuinely close position now. A set that used it on a ninth chord or richer will sound different too.

IF YOU NEED THE OLD SOUND BACK

Open the set, listen, and pick the spacing that fits. `Default` is the closest thing to the old default: it matches what `Closed` played in v1.4.2 on 83 of the 91 cells. Only the add9 chords and one 6/9 sit differently.

The chord families.

Each column stacks these families, in the priority order below. The engine only shows a family when the scale makes it valid for that degree.

FAMILY	EXAMPLE LABELS	DESCRIPTION
Triad	`maj · m · dim · aug`	The three-note chord — always available.
Seventh	`M7 · m7 · 7 · dim7 · ø7`	Adds the 7th — depth and direction.
Ninth	`M9 · m9 · 9`	Extends to the major 9th.
mMaj7	`mMaj7`	Minor with major 7th — dramatic color.
Sus4	`sus4 · 7sus4`	Fourth instead of the third — suspension.
Sus2	`sus2`	Second instead of the third — open.
Add9	`add9 · madd9`	Triad + 9th, no 7th — bright.
Sixth	`6 · m6`	Soft color, without seventh tension.
Six/Nine	`6/9 · m6/9`	Sixth + ninth — rich and stable.
7♭9 / 7♯9	`7b9 · 7#9`	Altered dominants — strong tension.

ENGINE LOGIC

Tuple detects the real quality of each chord from the scale: the same degree will sound `M7`, `m7` or `7` depending on context, automatically.

See & organize.

Monitor

The Monitor lives on the **screen** — the strip's screen in the rack, the progression screen in the full window. It shows the **notes of the current chord** in real time and highlights them on a **mini-keyboard**, in the color of the degree. It's instant visual feedback — useful to learn voicings or check the register.

It also reacts before you play: **highlight or hover a chord cell** in the grid and the Monitor previews that cell's notes, so you can read a chord with your eyes before committing it.

The dual-window workflow

Tuple splits performance into two surfaces:

- The **compact strip** in the rack — controls and Monitor always in view.
- The **full window** with the entire grid, opened via **OPEN**, one click away.

The grid is never shrunk: the rack's limited height would hide it, so it lives in its own window — full access stays immediate.

ON TOP & SIZING

Keep the grid window in front while you work in Live: enable **ON TOP** in **SETTINGS**. The window is resizable — the whole face scales as one, so nothing reflows or truncates at any size.



FIGURE 10.1 — THE FULL WINDOW: THE TOP SCREEN, THE WHOLE GRID, AND THE PROGRESSION SCREEN BETWEEN ITS KEYS.




FIGURE 10.2 — THE COMPACT STRIP: SIX FIELDS AND THE MONITOR STAY IN VIEW INSIDE LIVE'S RACK.

RECOMMENDED SETUP

Grid window "always on top" on one side of the screen, Live underneath: you compose at the grid while keeping the arrangement visible.

Build it, then bounce it.

Lay chords out in time inside Tuple, on one continuous progression of up to 32 bars, then write the whole thing straight to a MIDI clip — no re-playing your chords into a record track.





FIGURE 12.1 — A CAPTURED PROGRESSION (I · VI · IV · V): EACH CHORD IS A CARD UNDER THE BAR RULER, ITS WIDTH IS ITS LENGTH. CM7 LASTS TWO BARS, THE V WAS DROPPED ON BAR 7 AND LEAVES A GAP, THE IV IS INVERTED AND PINNED, AND THE SELECTED CARD FILLS WITH ITS COLOR AND SHOWS ITS **PENCIL**. THE LOOP FIELD IS SET TO 8 BARS.

THE KEYS ON EITHER SIDE



CAPTURE · PLAY · STOP. THE LAMP ON CAPTURE SAYS WHETHER THE NEXT CHORD YOU PLAY LANDS ON THE PROGRESSION. PLAY AND STOP DRIVE LIVE'S OWN TRANSPORT — TUPLE DOES NOT HAVE ONE OF ITS OWN. SPACE DOES THE SAME FROM TUPLE'S WINDOW: IT STARTS LIVE, OR STOPS IT, EVEN WHILE THE WINDOW HAS THE FOCUS.

Create clip, **Re-voice all** and **Clear** sit on the right of the screen. All three act on the whole progression, and they stay dimmed while the progression is empty.

During playback, the Monitor, the grid highlight and Smart follow the card that plays. A linked clip follows your edits as you make them, even while you stretch a card.

The loop, in blocks of four

In the full window, the bottom of Tuple is a hardware-style **screen**: a row of fields, an overview strip, the bar ruler and your chords as cards beneath it. The progression is one continuous loop of up to **32 bars**, counted in **blocks** of four. A bar is always four beats, and a card is at least an eighth of a bar. Each card has its own length and its own position on the ruler, and a card can sit across the line between two blocks.

The `Loop` field sets the length of the **loop**, and of the clip Tuple writes: ‹ › add or remove a block, from 4 to 32 bars. It grows to every block your chords reach. Shorten it below them and the cards past the end stay, dimmed, silent and out of the clip; lengthen it and they return. Gaps and the rest of the loop are silence.

MOVING ALONG THE LOOP

The screen shows a view of 2 bars up to the whole loop, 4 by default; the overview strip above the ruler always shows all of it. The gestures are Live's: drag sideways on the ruler or the strip to scroll, up or down to zoom. The wheel scrolls, `ctrl`+wheel zooms toward the pointer. Double-click the strip for the whole loop, the ruler for the selected card. With `Follow play` on, the view jumps along with the playhead.

Adding chords

01 Press the **CAPTURE** key.

02 Click (or play) chords on the grid. Each one flies from its cell to the progression, right **after the selected card** — or after the last card when none is selected — and becomes the selection, so the next chord follows it.

03 Press **CAPTURE** again when you are done.

You can also **drag a cell** from the grid onto the progression, capture on or off: a card comes out of the cell and lands where you drop it. Dragging never captures; only a click does. When the progression is full, the cell pulses red and nothing is added.

Free placement

A card lands **where you drop it**, to the eighth of a bar, and empty bars stay empty. Drop it **onto** another card and it goes before or after that card, depending on which half you aim at; the cards it then overlaps are pushed later. While you drag, the card lifts, a dotted outline shows where it will land and its neighbours make room. If the push would run past bar 32, the outline turns red with `no room` and the card goes back.

LENGTH — EITHER EDGE

Hover a card and a handle appears on its edges: drag one. The right edge moves its end, the left edge moves its start. The length you are setting follows the right edge (`2 bars 3/8`), and it snaps to the eighth of a bar when you let go. Like a clip in Live, a longer card replaces what it covers: a card fully covered disappears, a card partly covered keeps what sticks out, and nothing else moves. At the end of the progression the edge resists, the length turns red and the card settles on the space left. It never goes below an eighth of a bar. A card too narrow for its name shows it vertically.

LISTENING

Hover a card to preview its notes in the Monitor, without sound; press and hold it to hear it. While Live plays, an amber **playhead** runs across the progression and Tuple plays the card under it — no clip needed. It loops over the length of the loop, counted from bar 1 of the set.

The edit bar

Click a card to select it and hear it. The **pencil**, on the selected card or on the one you hover, opens the **edit bar** above it. Every change plays the card briefly, so you judge it by ear. Click elsewhere or press `Esc` to close it, and `Esc` again to deselect; it also steps aside while you drag.

- **Style** — the eight voicings, one click each. It sets the voicing for **that chord only**; the rest of the progression keeps yours.
- **Inversion** — ◂ ▸ step it down or up from `Root`. Changing it pins the card.
- **Pin** — a pinned card keeps the shape you gave it, and voice leading leaves it alone; a pin shows on the card. Click `Pin` again, or the pin on the card, to hand it back to voice leading.
- **Octave** — ◂ ▸ shift **that chord** ±2 octaves; its tensions and the next card's voice leading follow.
- **Tensions** — seven chips: `♭9 9 ♯9 11 ♯11 ♭13 13`. A chip filled with the card's color is on the chord; a struck-out one clashes with the chord type (the tooltip says why); a plain dim one is already part of the type; a dotted one lies outside the scale; a dotted one in the card's color is set, but this voicing has no room for it. A tension stacks **above** the chord; the voicing underneath never re-shuffles. Change key or scale and each tension follows to the new scale's color.
- **The bin** — at the end of the bar, removes the card. Its place becomes a gap; nothing else moves.

The AVOID NOTES field (in SETTINGS) is what strikes out the clashing tensions.

Several cards at once

Drag a rectangle from an empty spot of the progression, as on a desktop: every card it touches is selected (hold `ctrl` to add to the selection). `ctrl`-click adds or removes one card, `shift`-click takes the range. Drag any selected card and the **whole group moves**, gaps kept; hold `ctrl` as you drop and it is **duplicated** there instead.

The edit bar then sets the whole group: a value they don't share reads `mixed`, and the bin says how many cards go.

Re-voice all

A captured chord keeps the voicing it had when you played it. The RE-VOICE ALL key leads the cards again from left to right, each one from the card before it. Pinned cards stay as they are, and guide the card after them.

Undo

After a delete or a CLEAR, the screen offers `Undo`: click it and the cards come back where they were. It stays until your next change. CLEAR asks first.



FIGURE 12.2 — TWO CARDS SELECTED: THE INVERSION READS MIXED, THE BIN COUNTS TWO.

Write to a clip — and keep it live

Pick the destination with the `Target` field (the `Clip Target` Live parameter): **Session** writes at the highlighted clip slot, **Arrangement** writes at the playhead position. Then press **CREATE CLIP**: on an empty spot, Tuple creates the clip and writes the whole progression, as long as the loop, gaps left silent. Where a clip already sits, the key reads **APPLY TO CLIP** instead, and writes into that one. The two gestures are separate on purpose: nothing is ever replaced by a button that meant “create”.

The clip Tuple just made is now the one it **edits**. Every change to the progression — add, move, remove, re-voice, invert, resize, undo — is rewritten into it as you work. The `Clip` field names it, beside a lit LED; its × detaches: the editing stops and the clip stays in Live exactly as it is.

Follow — turn the field on and the clip you **select in Live** becomes the one the progression edits; click another clip and Tuple follows. Attaching alone changes nothing: the first time your edit would write into a clip Tuple did not create and that already has notes, the Clip field shows **REPLACE**, once. Press it and that clip is yours — Tuple keeps writing to it without asking again. Leave it unanswered and nothing is written. Nothing you made is ever overwritten silently.

GOOD TO KNOW


Each card stores the chord exactly as you captured it — already voiced and voice-led — so the clip sounds like what you heard. Change `KEY` or `SCALE` and the whole progression follows — names, numerals and notes are re-derived in the new key. Your `STRUM`, `RAMP`, `CURVE` and `HUMANIZE` settings are written into the clip too — deterministically, so editing one card never re-rolls the feel of the others. All four at zero gives clean block chords.

And when you **launch** the linked clip, it becomes the only voice: Tuple passes its notes through untouched and its own playback stays silent — stop the clip and the cards take over again.

A FULL-WINDOW FEATURE

Writing to an Ableton clip needs Live, so **CREATE CLIP** and **FOLLOW** are device-only. You can still build, re-order and audition progressions in the browser demo (there it exports a MIDI file instead).

THE FIELD ROW



THE FIELD ROW. EVERY FIELD WORKS WITH ONE CLICK. IN BLUE, LOOP AND FOLLOW PLAY; IN ORANGE, CLIP, FOLLOW AND TARGET; IN MAUVE, PROG AND MODE, WHICH DRIVE THE PUSH (↳ CH. 13). WHEN NO CLIP IS ATTACHED THE CLIP FIELD SAYS SO, RATHER THAN LEAVING YOU TO GUESS.

The grid, under your fingers.

With a Push 2, play the chord grid straight on the pads — one chord per pad, the colors mirroring the screen. A Launchpad X takes the pad grid too, when no Push is connected.

Enable

01 Connect the Push 2 and open Tuple's full window.

02 Click **PUSH** on the top screen, or turn **PUSH MODE**, a Live parameter, on the first encoder of the device on Push: Tuple grabs the pad grid. Its lamp says whether it holds it. The encoders follow the device Push is pointing at, in three banks: Chords, Feel and Clip.

03 The pads light up according to the current color logic (Layout).

04 Hit a pad: the chord plays, voiced and voice-led, just like on screen.

Push **extends** the grid, it doesn't replace it: columns = degrees `I-VII` + Borrowed, rows = chord families.



FIGURE 13.1 — TUPLE ON PUSH 2: ONE CHORD PER PAD, THE COLORS MIRRORING THE GRID, AND THE PAD YOU HOLD OUTLINED. THE PUSH SCREEN STAYS LIVE'S — TUPLE LIGHTS THE PADS AND NOTHING ELSE.

PADS & MIDI

A pressed pad lights up brighter while held. Tuple exposes **15 controls** as Live parameters — `Push Mode`, `Octave`, `Voice Spacing`, `Voice Leading`, `VL Mode`, `Layout`, `Borrowed Page`, `Strum`, `Strum Ramp`, `Humanize`, `Vel Min`, `Vel Max`, `Capture`, `Write Clip` and `Clip Target` — MIDI-mappable (`Cmd/Ctrl+M`), automatable, saved with your set. Push is optional; everything works via the mouse too.

Build a progression on the pads.

Turn on the **PROG** field and the Push becomes a progression companion: the bottom row holds your progression, and the rows above develop the step you select — substitutes, what comes next, or a fresh voicing.

The layout

The **bottom row** is your progression, one chord per pad, left to right — a window of **eight cards** that follows the selected card. In this mode ◄ ► shift the window by one card, so every chord stays in reach. Select a step and the **column above it** fills with options for that step — a blank row separates the progression from the options. Every step keeps its own column, so you read each one straight up.

Three modes MODE

Substitutes	Chords that can replace the step at the same harmonic slot — function siblings (I ↔ iii ↔ vi…), quality variants, then a borrowed one: the tritone sub of a dominant (G7 → D♭7) or the parallel chord (IV → iv). A borrowed step offers its diatonic counterpart, its close neighbours and the borrowed chords that share its function; a tritone sub offers its dominant back and, when a card follows, other dominants to the same target. Within each group, the closest chord sits lowest.
Suite	Where to go next — the same Smart suggestions, offered as a chord to follow this one.
Voicings	Every voicing the engine can produce, to re-voice this step in place.



FIGURE 13.2 — THE PROGRESSION SCREEN DRIVES IT: PROG TURNS THE PUSH COMPANION ON, MODE CYCLES SUBS · SUITE · VOIC.

EDITING IS GATED BY CAPTURE

With **CAPTURE** on, picking an option edits the progression: **Substitutes** and **Voicings** replace the step, **Suite** inserts a new step after it. With Capture off, the options simply **audition** — you hear them without changing anything.

READING THE COLORS

Options start neutral; a pad takes its chord's degree color the moment you press it, so you always see what you're about to commit.


Capture the take.

For a fixed progression, the linked clip is the fastest route: build your chords as cards and let **Progression → Clip** (Ch. 12) write and rewrite the clip as you edit — voicing, order, duration and expression stay editable after the fact. To capture a **free live performance** instead, record Tuple's output onto a second track, as follows.

Record a live performance

To capture a free performance (especially on Push), record Tuple's MIDI output onto a second track: add a MIDI track, set **MIDI FROM** to Tuple's track / **POST FX**, set **MONITOR** to **IN** (the step most people miss), arm and record. In Push mode, also set the record track's **MIDI TO** to **NO OUTPUT** so notes aren't echoed and doubled. For playback, give that track its own instrument and mute Tuple's.

WHAT YOU ARE RECORDING



THE SCREEN, WHILE YOU PLAY. DEGREE, CHORD NAME, THE NOTES GOING OUT, AND THE SAME NOTES ON THE KEYBOARD. IT IS WHAT LANDS IN THE CLIP — NOTHING ELSE IS ADDED ON THE WAY.

Staying current, from inside Ableton.

About panel

Click the **logo** (top-left of the window), or **ABOUT** in **SETTINGS**, to open the About panel. It shows the current version, creator contact, Discord and website links, and a **Replay guide tour** button to restart the onboarding overlay.

When Tuple detects a newer version on startup, a small pill appears next to the logo: `↑ v1.X.X`. Click the logo to switch the About panel to **Update mode**.

Update panel

The panel shows the new version number and a brief changelog. Two paths, depending on the release:

- **Install** — downloads the update and replaces the Tuple folder in place. When it finishes, close and reopen the device in Ableton to activate the new files.
- **Download** — used when the `.amxd` itself has changed (Ableton locks it while it is loaded). On Windows it launches the installer; on macOS it opens the releases page in your browser so you can install manually.

Later dismisses the overlay for the session. **Ignore this version** hides it until the next one.

KEEP THE FOLDER INTACT

In-place updates write directly to the Tuple folder next to your `.amxd`. If you moved the files after installing, use the **Download** path instead.

How it works

01 At startup Tuple fetches a small `version.json` from GitHub. No analytics — just a version number and a reinstall flag.

02 If a new version exists, the badge pill appears on the logo. The device keeps working normally — nothing changes until you click Install.

03 Install downloads the ZIP and extracts it next to the `.amxd`. The download runs in a background Node process; progress is shown in the panel.

04 Close and reopen the device in Ableton to load the updated files. Your project settings (key, scale, voicing…) are preserved.

NO INTERNET CONNECTION?

The badge simply never appears — the device starts normally. To update manually, download the latest zip from tuple.live and replace the Tuple folder.

Going further.

WORKFLOW TIPS

- Compose at the grid, record the MIDI, then edit the notes — Tuple seeds the ideas.
- Mix 2–3 borrowings into a diatonic progression for a chorus that "lifts off".
- Change voicing between verse and chorus without changing the chords.
- Duplicate the track with a different voicing to double / layer textures.

TROUBLESHOOTING

No sound	Tuple must be **before** the instrument, track armed.
Blank interface	Files moved — keep the folder intact, reload the device.
Sync does nothing	Define a scale in Live first, then press SYNC.
Chords sound muddy	Raise the Octave, or move to **Open** — it puts air between the voices.
A note won't stop	Disarm then re-arm the track, or stop the transport.
Push pads stay dark	Toggle **PUSH** in the device; Push 2 must be connected.
Several Tuples at once	Fine — each instance is independent. One per track for different keys / voicings.

FAQ

Is Tuple a sequencer?
It sequences **chords** — lay them out in time, leave silences, loop, write a clip. Tuple plays the cards itself while Live runs. Not a step or note sequencer: no piano roll, no melody line.

Do I need a Push 2?
No, it's optional. Everything plays via the mouse or MIDI.

Does it follow my song key?
Yes — Tuple imports Live's key & scale automatically when it loads.

Can I record what I play?
Yes — Tuple sends real MIDI notes. Arm the track, record, then edit the notes like any MIDI clip.

Are the controls automatable?
Yes — 15 controls are Live parameters: automate them, MIDI-map them, saved with your set.

Privacy (Version checks). Tuple checks for updates by making an unauthenticated GET request to the GitHub API. This reveals your IP address and that Tuple is running — no other data is transmitted.

CREATOR
c0re

COMPATIBILITY
Live 11 / 12 · Max for Live

LICENSE
MIT · free

CONTACT
c0re_m4l@proton.me

COMMUNITY
discord.gg/skn5Np6DdP

WEB & DEMO
tuple.live

SMART DATA
Suggestion order checked against the RS 200 corpus (de Clercq & Temperley, CC BY 4.0) and McGill Billboard (Burgoyne, Wild & Fujinaga, CC0)

Tuple

Every chord in your key, one click away. Try the demo in your browser before installing.

User Manual · 2026 Edition
tuple.live

Key terms, in one place.

A quick reference for the words used throughout this manual.

Diatonic	Chords built only from the notes of the current key & scale.
Degree (I–VII)	A chord's position in the scale, in Roman numerals (I = tonic, V = dominant…).
Tonic · Subdominant · Dominant	The three harmonic functions: rest, lift, tension.
Borrowed chord	A chord taken from a parallel mode (modal interchange) for color — kept inside the grid.
Voicing	How a chord's notes are arranged and spaced (which note sits on top, the gaps between voices).
Voice leading	Moving each voice the smallest distance from one chord to the next, for smooth transitions.
Off / Anchor / Follow	The three positions of Tuple's LEADING field: untouched, fixed register, minimal movement.
Inversion	The same chord with a note other than the root at the bottom.
Rootless voicing	A voicing that omits the root, leaving it to the bass instrument. Tuple's `Rootless` spacing does exactly that; every other spacing keeps the root.
Drop voicing	One inner voice dropped an octave (Drop 2 / Drop 3) for a wider, open sound.
Octave	Shifts the whole chord up or down in register.
Layout	The color logic used to read the grid (Spectrum, Function, Tension…).
Smart Chords	A guide overlay: as you play, the grid lights likely next chords — by function (strength) or voice leading (smoothness).
Strum	Spreads a chord's notes over time (down or up), up to an arpeggio.
Humanize	Small random velocity & timing variation for a less mechanical feel.
Tension	A color note (9th, 11th or 13th family) stacked above a progression card as an upper structure — the chord underneath keeps its shape.
Avoid notes	Tensions the tonal tradition avoids on a given chord type (the 11 on a major chord…). Tuple strikes them out; Avoid notes in Settings turns the filter off.
Progression	Chords placed in time: up to 32 bars, a card per chord, gaps allowed.
Block	Four bars of the progression. The loop and the clip are counted in blocks.

New in 1.7.

Progression

- A free track of up to 32 bars, gaps included.
- Cards placed to the eighth of a bar, stretched from either edge.
- Edit bar, box-select, group moves, Undo.
- Zoomable timeline, a loop shorter than your cards.
- Saved with your Live set.

Playing

- Monitor, grid and Smart follow playback.
- Space starts and stops Live.
- A linked clip follows every edit.
- MIDI out to another track.

Harmony & voicing

- Rootless and Clear voicings.
- Better voice leading, reworked Two Hands.
- Smart tables corrected against a chord corpus.

Push & Launchpad

- Launchpad X pad grid.
- Push Mode on an encoder, three parameter banks.
- Eight-card window in progression mode.

Look

- A new facade: screens, group colors, physical keys.
- Scale in two steps, Settings on the top screen.