

Re-Entrant Corner Flow of an Upper Convected Maxwell Fluid

TFR Transfer Talk

Christian Jones



October 5, 2022

Motivation

- Many materials we encounter have **viscoelastic** properties.
 - Viscosity: measure of resistance to flow.
 - Elasticity: ability of a material to return to its original state after removal of deforming forces.
- Due to polymer processing applications, modelling is incredibly important!



Sesame Workshop, 2017.




Cabrera, X., 2020




Kempner, J., 2022

Properties of Viscoelastic Fluids


Shear Thinning:




Stress Relaxation:



Creep:



Normal Stress Effects:



Tanner, R. I., 2000

Viscoelastic Modelling

Overview

Q. How can we model these materials?

A. Use **conservation laws**.

1 Mass:

$$\nabla \cdot \mathbf{u} = 0.$$

2 Momentum:

$$\rho \left(\frac{\partial \mathbf{u}}{\partial t} + (\mathbf{u} \cdot \nabla) \mathbf{u} \right) = -\nabla p + \nabla \cdot \mathbf{T}, \quad \mathbf{T}^T = \mathbf{T}.$$

We still need to specify \mathbf{T} !

Viscoelastic Modelling

Overview

Q. How can we model these materials?

A. Use **conservation laws**.

1 Mass:

$$\nabla \cdot \mathbf{u} = 0.$$

2 Momentum:

$$\rho \left(\frac{\partial \mathbf{u}}{\partial t} + (\mathbf{u} \cdot \nabla) \mathbf{u} \right) = -\nabla p + \nabla \cdot \mathbf{T}, \quad \mathbf{T}^T = \mathbf{T}.$$

We still need to specify \mathbf{T} !

Could try $\mathbf{T} = \eta \left(\nabla \mathbf{u} + \nabla \mathbf{u}^T \right) =: 2\eta \mathbf{D} \dots$

Viscoelastic Modelling

Overview

Q. How can we model these materials?

A. Use **conservation laws**.

1 Mass:

$$\nabla \cdot \mathbf{u} = 0.$$

2 Momentum:

$$\rho \left(\frac{\partial \mathbf{u}}{\partial t} + (\mathbf{u} \cdot \nabla) \mathbf{u} \right) = -\nabla p + \nabla \cdot \mathbf{T}, \quad \mathbf{T}^T = \mathbf{T}.$$

We still need to specify \mathbf{T} !

Could try $\mathbf{T} = \eta \left(\nabla \mathbf{u} + \nabla \mathbf{u}^T \right) =: 2\eta \mathbf{D}$... but this doesn't help us!

Viscoelastic Modelling

Constitutive Equations

Can we do better?

Viscoelastic Modelling

Constitutive Equations

Can we do better?

- Acierno et. al.
- Chang et. al.
- Chilcott-Rallison
- Corotational Jeffreys
- Corotational Maxwell
- Curtiss-Bird
- Doi-Edwards
- Elastic Dumbbell
- Extended Pom-Pom
- Extended WM
- FENE
- FENE-P
- Giesekus
- Green-Tobolsky
- Jeffreys
- Johnson-Segelman
- Kaye-BKZ
- Kelvin-Voigt
- Leonov
- Lodge
- Maxwell
- Maxwell-Wiechert
- Modified UCM
- Oldroyd 8 Constant
- Oldroyd-B
- Phan-Thien-Tanner
- Pom-Pom
- Rolie-Poly
- Rouse
- Tanner-Simmons
- Upper Convected Maxwell
- White-Metzner
- Yamamoto

Viscoelastic Modelling

Constitutive Equations

Can we do better?

- Acierno et. al.
- Chang et. al.
- Chilcott-Rallison
- Corotational Jeffreys
- Corotational Maxwell
- Curtiss-Bird
- Doi-Edwards
- Elastic Dumbbell
- Extended Pom-Pom
- Extended WM
- FENE
- FENE-P
- Giesekus
- Green-Tobolsky
- Jeffreys
- Johnson-Segelman
- Kaye-BKZ
- Kelvin-Voigt
- Leonov
- Lodge
- Maxwell
- Maxwell-Wiechert
- Modified UCM
- Oldroyd 8 Constant
- Oldroyd-B
- Phan-Thien-Tanner
- Pom-Pom
- Rolie-Poly
- Rouse
- Tanner-Simmons
- **Upper Convected Maxwell**
- White-Metzner
- Yamamoto


Upper Convected Maxwell (UCM) Model

$$\underbrace{\tau \left(\frac{\partial \boldsymbol{T}}{\partial t} + (\mathbf{u} \cdot \nabla) \boldsymbol{T} - (\nabla \mathbf{u}) \boldsymbol{T} - \boldsymbol{T} (\nabla \mathbf{u})^T \right)}_{\nabla \boldsymbol{T}} + \boldsymbol{T} = 2\eta \boldsymbol{D}$$

- First term captures elastic behaviour; remaining terms capture viscous behaviour.
- Introduced a *relaxation time* τ and viscosity parameter η .
- Relaxation time quantifies material ‘memory’.

Problem Setup

Planar, steady flow around corner of angle $\theta = \pi/\alpha$. ($1/2 \leq \alpha < 1$)



Mathematics due to Hinch (1993), Renardy (1995), Rallison and Hinch (2004) and Evans (2008).

Equations?

Dimensionless equations:

$$\nabla \cdot \mathbf{u} = 0,$$

$$\text{Re}(\mathbf{u} \cdot \nabla) \mathbf{u} = -\nabla p + \nabla \cdot \boldsymbol{\mathcal{T}},$$

$$\text{Wi} \frac{\nabla}{\boldsymbol{\mathcal{T}}} + \boldsymbol{\mathcal{T}} = 2\boldsymbol{\mathcal{D}}.$$

Obtain Reynolds (Re) and Weissenberg (Wi) numbers:

$$\text{Re} = \frac{[\text{inertial forces}]}{[\text{viscous forces}]}; \quad \text{Wi} = \frac{[\text{elastic forces}]}{[\text{viscous forces}]}.$$

Useful: incompressibility condition gives a *streamfunction* ψ with

$$\mathbf{u} = \nabla \wedge \psi \mathbf{k}.$$

These equations are complicated!

Step 1: Outer Solution

Governing Equations

- Assume elasticity drives the flow, and inertia is subdominant.
- Find at leading order as $r \rightarrow 0$:

$$\nabla \cdot \boldsymbol{T} = 0, \quad \nabla p = \nabla \cdot \boldsymbol{T}.$$

- First equation solved by $\boldsymbol{T} = \lambda(\psi) \mathbf{u} \mathbf{u}^T$.
- Setting $\mathbf{v} = \lambda^{1/2} \mathbf{u}$, obtain

$$(\mathbf{v} \cdot \nabla) \mathbf{v} = \nabla p, \quad \nabla \cdot \mathbf{v} = 0.$$

- Outer solution governed by the Euler equations!

Step 1: Outer Solution

Finding the Streamfunction

$$(\mathbf{v} \cdot \nabla) \mathbf{v} = \nabla p, \quad \nabla \cdot \mathbf{v} = 0.$$

- Incompressibility: $\mathbf{v} = \nabla \wedge \psi^* \mathbf{k}$.
- Planar flow: $\nabla^2 \psi^* = 0$.
- Applying no-slip conditions: $\psi^* \sim Cr^\alpha \sin(\alpha\theta)$.
- As \mathbf{u} is parallel to \mathbf{v} , $\psi^* = h(\psi)$, with $\lambda^{1/2}(\psi) = h'(\psi)$
- Since we are local to the corner, take

$$\psi^* \propto \psi^{1/n},$$

with n to be determined.

Step 1: Outer Solution

Summary

Consequently, near the corner apex:

$$\psi \sim C_0(r^\alpha \sin(\alpha\theta))^n,$$

$$\lambda \sim C_1 C_0^{2(\frac{1}{n}-1)} (r^\alpha \sin(\alpha\theta))^{2(1-n)},$$

$$\mathbf{T} \sim \lambda(\psi) \mathbf{u} \mathbf{u}^T,$$

$$p \sim \frac{1}{2} \lambda \|\mathbf{u}\|^2,$$

for unknown C_0 , C_1 and n .

To neglect inertia, we also find that $n > 1$.

Are we done?

Look near the wall. In this region:


$$\psi \sim \frac{1}{2} \underbrace{\frac{\partial^2 \psi}{\partial y^2}(x, 0)}_{\dot{\gamma}} y^2 \quad \text{as} \quad y \rightarrow 0 \quad (x > 0),$$

from which $T_{11} \sim 2Wi\dot{\gamma}^2$, $T_{12} \sim \dot{\gamma}$, $T_{22} = o(1)$.

However, from the outer solution, as $y \rightarrow 0$ with $x > 0$:

$$r \sim x, \quad \theta \sim y/x, \quad T_{12} \sim \text{constant}.x^{2(\alpha-1)-1}y.$$

These don't agree, so we need boundary layers.



Step 2: Inner Solution

Rescaling

To find the boundary layer equations, we only need to focus on the upstream wall.

- 1 Rescale (Cartesian) independent variables:

$$x = \epsilon \hat{x}, \quad y = \delta(\epsilon) \hat{y}$$

with $0 < \epsilon \ll 1$ and $\delta \ll \epsilon$.

- 2 Using outer solution, rescale remaining variables:

$$\begin{aligned} \psi &= \epsilon^{n(\alpha-1)} \delta^n \hat{\psi}, & p &= \epsilon^{2(\alpha-1)} \hat{p}, & T_{11} &= \epsilon^{2(\alpha-1)} \hat{T}_{11}, \\ T_{12} &= \epsilon^{2(\alpha-1)-1} \delta \hat{T}_{12}, & T_{22} &= \epsilon^{2(\alpha-2)} \delta^2 \hat{T}_{22}. \end{aligned}$$

- 3 Inserting into UCM (Wi $\nabla \cdot \mathbf{T} + \mathbf{T} = 2\mathbf{D}$), dominant balance gives


$$n = 3 - \alpha \text{ and } \delta = \epsilon^{2-\alpha}.$$

Step 2: Inner Solution

What do we learn?

- 1 Boundary layers of thickness $O(\epsilon^{2-\alpha})$ exist at walls.
- 2 Layers separated by an outer region solved for in Step 1.
- 3 Layers governed by leading order UCM equations and momentum equation

$$\frac{\partial \hat{T}_{11}}{\partial \hat{x}} + \frac{\partial \hat{T}_{12}}{\partial \hat{y}} = \frac{\partial \hat{p}}{\partial \hat{x}}.$$



Step 2: Inner Solution

Boundary layer UCM equations:

$$\hat{T}_{11} + \text{Wi} \left[\hat{u} \frac{\partial \hat{T}_{11}}{\partial \hat{x}} + \hat{v} \frac{\partial \hat{T}_{11}}{\partial \hat{y}} - 2 \frac{\partial \hat{u}}{\partial \hat{x}} \hat{T}_{11} - 2 \frac{\partial \hat{u}}{\partial \hat{y}} \hat{T}_{12} \right] = 0,$$

$$\hat{T}_{12} + \text{Wi} \left[\hat{u} \frac{\partial \hat{T}_{12}}{\partial \hat{x}} + \hat{v} \frac{\partial \hat{T}_{12}}{\partial \hat{y}} - \frac{\partial \hat{v}}{\partial \hat{x}} \hat{T}_{11} - \left(\frac{\partial \hat{u}}{\partial \hat{x}} + \frac{\partial \hat{v}}{\partial \hat{y}} \right) \hat{T}_{12} - \frac{\partial \hat{u}}{\partial \hat{y}} \hat{T}_{22} \right] = \frac{\partial \hat{u}}{\partial \hat{y}},$$

$$\hat{T}_{22} + \text{Wi} \left[\hat{u} \frac{\partial \hat{T}_{22}}{\partial \hat{x}} + \hat{v} \frac{\partial \hat{T}_{22}}{\partial \hat{y}} - 2 \frac{\partial \hat{v}}{\partial \hat{x}} \hat{T}_{12} - 2 \frac{\partial \hat{u}}{\partial \hat{y}} \hat{T}_{22} \right] = 2 \frac{\partial \hat{v}}{\partial \hat{y}}.$$

We can still do more with these!

Step 3: Similarity Solution

- Seek a solution in the layer of the form

$$\hat{\psi} = \hat{x}^{3-\alpha} f(\xi), \quad \hat{T}_{11} = \hat{x}^{2(\alpha-1)} t_{11}(\xi), \quad \hat{T}_{12} = \hat{x}^{\alpha-1} t_{12}(\xi), \quad \hat{T}_{22} = t_{22}(\xi).$$

- Similarity variable:

$$\xi = \frac{\hat{y}}{\hat{x}^{2-\alpha}}$$

- Substitution into layer equations reduces the PDE system to four ODEs.
- Furthermore, we find that $\frac{\partial \hat{p}}{\partial \hat{x}} =: G$ is constant.

Step 3: Similarity Solution

UCM equations:

$$t_{11} + \text{Wi} \{ 2(\alpha - 2)f't_{11} - (3 - \alpha)ft'_{11} + 2(2 - \alpha)\xi f''t_{11} - 2f''t_{12} \} = 0$$

$$\begin{aligned} t_{12} + \text{Wi} \left\{ (\alpha - 1)f't_{12} - (3 - \alpha)ft'_{12} - f''t_{22} + (2 - \alpha)(3 - \alpha)ft_{11} \right. \\ \left. - (2 - \alpha)(3 - \alpha)\xi f't_{11} + (2 - \alpha)^2\xi^2 f''t_{11} \right\} = f'' \end{aligned}$$

$$\begin{aligned} t_{22} + \text{Wi} \left\{ - (3 - \alpha)ft'_{22} + 2(2 - \alpha)(3 - \alpha)ft_{12} - 2(2 - \alpha)(3 - \alpha)f'\xi t_{12} \right. \\ \left. + 2(2 - \alpha)^2\xi^2 f''t_{12} + 2f't_{22} - 2(2 - \alpha)\xi f''t_{22} \right\} = -2f' + 2(2 - \alpha)\xi f''. \end{aligned}$$

Momentum equation:

$$2(\alpha - 1)t_{11} - (2 - \alpha)\xi t'_{11} + t'_{12} = G.$$

Can We Solve This?

- Wall Conditions: $f(0) = 0 = f'(0)$.
- Matching: As $\xi \rightarrow \infty$

$$f \sim \pm f_0 \xi^{3-\alpha}, \quad t_{11} \sim t_0,$$

$$t_{12} \sim t_0(1-\alpha)\xi, \quad t_{22} \sim t_0(\alpha-1)^2\xi^2,$$

with $f_0 := C_0 \alpha^{3-\alpha}$ and $t_0 := G/(\alpha-1)$.

- Upstream problem: formulate as IVP and integrate away from wall.
- Downstream problem: IVP unstable, need to formulate as a BVP.
- Issue: Lost stress information in the outer region — need a *natural stress formulation!*

Natural Stress Formulation?

- Realign the stress tensor basis with the flow direction:

$$\begin{aligned}\mathbf{T} &= T_{11}\mathbf{i} \otimes \mathbf{i} + T_{12}(\mathbf{i} \otimes \mathbf{j} + \mathbf{j} \otimes \mathbf{i}) + T_{22}\mathbf{j} \otimes \mathbf{j}, \\ &= \lambda(\psi)\mathbf{u} \otimes \mathbf{u} + \mu(\psi)(\mathbf{u} \otimes \mathbf{w} + \mathbf{w} \otimes \mathbf{u}) + \nu(\psi)\mathbf{w} \otimes \mathbf{w}.\end{aligned}$$

- In Cartesian co-ordinates,

$$\mathbf{u} = (u, v, 0)^T, \quad \mathbf{w} = \left(-\frac{v}{u^2 + v^2}, \frac{u}{u^2 + v^2}, 0 \right)^T.$$

- Already found λ in the outer region; posit $\mu \sim C_2 \psi^{n_2}$, $\nu \sim C_3 \psi^{n_3}$.
- In the boundary layers, we seek a similarity solution of the form

$$\lambda = x^{2(\alpha-2)} \tilde{\lambda}(\xi), \quad \mu = x^{\alpha-1} \tilde{\mu}(\xi), \quad \nu = x^2 \tilde{\nu}(\xi),$$

Now Can We Solve This?

- We can show (in the BL):

$$\tilde{\lambda} = t_{11}(f')^2,$$

$$\tilde{\mu} = t_{12} - \frac{t_{11}}{f'} \left[-(3-\alpha)f + (2-\alpha)\xi f' \right],$$

$$\tilde{\nu} = (f')^2 t_{22} + t_{11} \left[-(3-\alpha)f + (2-\alpha)\xi f' \right]^2 - 2f' t_{12} \left[-(3-\alpha)f + (2-\alpha)\xi f' \right].$$

- Matching gives $n_2 = \frac{\alpha-1}{3-\alpha}$ and $n_3 = \frac{2}{3-\alpha}$.
- New matching conditions: As $\xi \rightarrow \infty$

$$\tilde{\lambda} \sim C_1 f_0^{2(\frac{1}{n}-1)} \xi^{2(\alpha-2)}, \quad \tilde{\mu} \sim \pm C_2 f_0^{n_2} \xi^{\alpha-1}, \quad \tilde{\nu} \sim C_3 f_0^{n_3} \xi^2.$$

- This time, we don't lose any stress information!

Summary

In this presentation, we have

- Presented the geometry for viscoelastic re-entrant corner flow.
- Demonstrated a leading order description of the flow using matched asymptotics.
- Highlighted the benefits of using natural stress variables for solving the problem.

Where Next?

Ultimate aim: *Apply these techniques to other viscoelastic flows.*


This could be via:

1 Different viscoelastic models:


- Including shear thinning (White-Metzner/Modified UCM)
- Newtonian solvent inclusion.

2 Different geometries:


Stick-slip



Die Swell



Squeeze Flow



Thank you for listening!



References

LFT:

Kempner, J., 2022. Female hand holding Coronavirus lateral flow antigen self test kit showing positive result with grey plain background [Online]. Shutterstock. Available from: <https://www.shutterstock.com/image-photo/uk-london-2022-january-13-female-2105486615> [Accessed 02-10-22]

Lego:

Cabrera, X., 2020. 'Lego bricks' [Online]. Unsplash. Available from: <https://unsplash.com/photos/kn-UmDZQDjM> [Accessed 04-10-22].

Cookies:

Sesame Workshop, 2017. *Cookie Monster looking at cookies* [Online]. Available from: <https://www.foodandwine.com/news/sesame-street-cookie-monster-cooking-show> [Accessed 01-10-22].

Shear diagram:

Østergård., A. L., 2020. 'Why Shear Rate Matters in Process Control' [Online]. Fluidan. Available from: <https://fluidan.com/why-shear-rate-matters-in-process-control/> [Accessed 04-10-22].

Weissenberg Effect:

R. I. Tanner. Engineering Rheology. 2nd ed. New York, N.Y.: Oxford University Press, 2000, p.6.

References

Hinch 1993:

E. J. Hinch. "The flow of an Oldroyd fluid round a sharp corner". In: *J. Non-Newtonian Fluid Mech.* 50 (1993), pp. 161–171.

Renardy 1995:

M. Renardy. "A matched solution for corner flow of the upper convected Maxwell fluid". In: *J. Non-Newtonian Fluid Mech.* 58 (1995), pp. 83–89.

Rallison and Hinch 2004:

J. M. Rallison and E. J. Hinch. "The flow of an Oldroyd fluid past a reentrant corner: the downstream boundary layer". In: *J. Non-Newtonian Fluid Mech.* 116 (2004), pp. 141–162.

Evans 2008(1):

J. D. Evans. "Re-entrant corner flows of UCM fluids: The Cartesian stress basis". In: *J. Non-Newtonian Fluid Mech.* 150.2 (2008), pp. 116–138.

Evans 2008(2):

J. D. Evans. "Re-entrant corner flows of UCM fluids: The natural stress basis". In: *J. Non-Newtonian Fluid Mech.* 150.2 (2008), pp. 139–153.