CALIBER MINING AND LOGISTICS LIMITED · PULSE-II · MANPOWER & OT

Shift Performance

Operating manual

For site in-charges, MIS staff and reviewers · Matches the system as of 10 November 2026

1. What this report shows

Shows the work of each employee shift by shift: the doors worked, HMR hours, completed trips and kilometres from the saved VLB and ELB cards, with the scheduled shift start and end from the Shift Master. A site in-charge or MIS clerk uses it to check one driver's or operator's shift and to find duties whose meter or trip figures need review.

> **One row.** One row is one employee at one site on one duty date in one shift, that is, one duty. All cards and vehicles of that employee in the same shift stay in the same row.

2. Open the report and choose what to see

In the left menu open **Reports** → **Manpower & OT** → **Shift Performance**. Then set the selectors described below.

Selector or button	What it does
From / To	First and last duty date of the report. From opens on the 1st of the current month and To on today's date. A date before 1 November 2026 cannot be chosen, To cannot be earlier than From, and the range can cover at most 31 days. Outside these limits nothing loads and the screen says "Choose a valid range of up to 31 days, starting on or after 1 November 2026."
Site	Keeps only the duties of one site. "All" means every site assigned to your login. Changing the site sets Saved batch and Door / equipment back to "All".
Shift	Keeps only the duties of one shift. The list shows the shift codes found in the loaded records, for example S1, S2, S3.
Saved batch	Shows the duties that have at least one card in the chosen batch. The row still shows every card of that duty, also the cards outside the batch.
Employee	Shows the duties of one employee. Each entry reads Employee ID · name, for example "CMPL90001 · SAMPLE DRIVER 01".
Door / equipment	Shows the duties that have at least one card on the chosen door number, for example V9001. The row still shows the other doors the employee worked in that shift.
Today	Button. Sets From and To to today's date. The other selections stay.
Clear selections	Button. Sets Site, Shift, Saved batch, Employee and Door / equipment back to "All". The dates stay.

Auto-hide filters	Tick box. When ticked, the selectors are tucked away and only a bar with the current dates, site and shift stays on screen. Move the mouse over the bar, or press it, to open the selectors; they close when the mouse leaves. The choice is remembered in this browser.
Refresh reports	Button at the top right. Reads the saved records again with the same selections. It cannot be pressed while a load is running.

3. What is on the screen

On the screen	What it shows
REPORTS / MANPOWER & OT	The page heading, with the title “Shift Performance” under it. The next line reads “Saved duties, clear assignments and shift-by-shift performance.”
Manpower by Category · Manpower by Category Reconciliation · Shift Performance · Shift Attendance Equipment Wise · OT & Multiple Duties	The tab row. Press a name to open that view. The dates and selections stay the same when you move between these five tabs.
Bar above the selectors	Shows the From and To dates in use, the site (or “All assigned sites”), the shift (or “All shifts”) and how many of Saved batch, Employee and Door / equipment are set, for example “2 more selections”. The bar can be pressed only when “Auto-hide filters” is ticked.
Loading saved records and checking shift patterns…	Shown while the report is being read. The table appears when the reading is over.
Error message	If the report cannot be read, the reason is shown in place of the table. For example, when the chosen dates hold more than 50,000 saved cards the screen says “This range contains too many saved cards. Select a shorter date range.”
Line under the selectors	Repeats the dates, site and shift in use, then “Saved records only” and “Updated … IST”, the time at which this report was read.
Distinct assets	Count card. Number of different machines on the saved cards that match the selections. A machine is one door number at one site. Cards left out of totals, and cards whose door number does not fit exactly one machine in the Equipment master, are not counted.
Distinct employees	Count card. Number of different employees matched on the saved cards that match the selections.
Employee shift duties	Count card. Number of rows in the “Shift Performance” table below.
Review items	Count card. Number of rows in the “Manpower Data Review” table at the bottom.

One row per employee, site, date and shift. Changing vehicles within a shift remains one duty. Vehicle and batch selections show the complete matching duty.	The notice above the table. It states what one row stands for and that a Door / equipment or Saved batch selection still shows the whole duty.
Shift Performance	The table. The line under its title repeats the selections and adds “Each shift is separate; HMR is machine performance”. If nothing matches it says “No saved duties with a resolved employee identity match these selections.”
Manpower Data Review	The table at the bottom. It lists every problem found on the selected cards, one row for each problem, so that it can be corrected. If there is none it says “No card needs correction in these selections.”
Sources and calculation rules	Press to open the written rules the report follows. The last line says that manpower requirements, shortages and relief availability are reserved for a later phase.

4. The columns

Column	Meaning
Shift Performance · Duty date	Book date of the duty, written as year-month-day.
Shift Performance · Site	Site of the duty.
Shift Performance · Shift	Shift code of the duty, for example S1, S2 or S3.
Shift Performance · Employee ID	Employee ID from the employee master. Only matched employees are listed.
Shift Performance · Caliber ID	Caliber ID mapped to that employee in the master.
Shift Performance · Driver / operator	Name from the employee master, for example SAMPLE DRIVER 01.
Shift Performance · Doors worked	Door numbers of all cards of the duty, separated by “;”.
Shift Performance · Equipment / make / model	For each card: door number, then equipment group / make / model from the Equipment master, for example “V9001: group / make / model”.
Shift Performance · HMR performance HRS	Closing HMR minus opening HMR of each card, added for the duty. It shows “—” when a card of the duty fails a check: HMR reading missing, closing lower than opening, hours more than the scheduled shift, HMR overlapping another card of the same machine and shift, differing saved copies of the same scan, or wrong trip or kilometre figures on a VLB card. It also shows “—” when the cards together are more than the scheduled shift hours. These are machine hours, not attendance or payable OT.
Shift Performance · Completed trips	Completed trips of the VLB cards of the duty, added. A trip is counted on the card that carries its loading time; a row that records only the unloading of a trip loaded in the earlier shift is not counted again. Shows “—” when the duty has no VLB card or a VLB card of the duty fails a check.

Shift Performance · Kilometres	Closing KMR minus opening KMR of each VLB card, added for the duty. Shows “—” when the duty has no VLB card or a VLB card of the duty fails a check.
Shift Performance · Scheduled start (IST)	Date and time at which the shift starts, from the Shift Master in force for that site and date. Blank when the Shift Master timing is missing or unclear, or when the shift start saved on a card differs from the Shift Master.
Shift Performance · Scheduled end (IST)	Date and time at which the shift ends, from the same Shift Master record. A shift that crosses midnight shows the next date. Blank in the same cases as the start.
Shift Performance · Source batches	Names of the batches in which the cards of the duty were saved. Blank when they are in no batch.
Shift Performance · Saved cards	Book numbers of the cards of the duty, separated by “;”.
Shift Performance · Remarks / review	Every review reason found on the cards of the duty, separated by “;”. Blank when no problem was found.
Manpower Data Review · Duty date	Book date of the card that has the problem.
Manpower Data Review · Site	Site of that card.
Manpower Data Review · Shift	Shift code of that card.
Manpower Data Review · Door / equipment	Door number of that card.
Manpower Data Review · Employee ID	Matched Employee ID, or the ID saved on the card when it was not matched.
Manpower Data Review · Driver / operator	Name of the driver or operator on that card.
Manpower Data Review · Saved card	Book number of the card. Use it to find the card.
Manpower Data Review · Log book	VLB or ELB. LMV items are shown only on OT & Multiple Duties.
Manpower Data Review · Source batches	Names of the batches holding the card, or “Saved VLB (no site batch)” / “Saved ELB (no site batch)”.
Manpower Data Review · What to correct	The problem in words. Examples: “Invalid or excessive HMR hours; performance totals unavailable.”, “Missing or invalid kilometre / completed-trip values; performance totals unavailable.”, “Overlapping HMR intervals on this asset/shift; performance totals unavailable.”, “Effective site shift schedule is missing or ambiguous; timing requires review.”

5. Keep in mind

- Only saved VLB and ELB log books dated 1 November 2026 or later are read. Pending scans and deleted records are excluded. LMV log books are used only by OT & Multiple Duties.

- HMR performance HRS is the running of the machine as read from the meter. It is not the employee's attendance time and not payable OT. Clock-in and clock-out times are not in the log books.
- Each shift is its own row and hours are never added across shifts on this tab. The scheduled start and end come from the Shift Master in force for that site and date.
- When a card fails a check, the total shows "—" instead of a doubtful number. The reason is written in Remarks / review and in Manpower Data Review.
- Only duties whose Employee ID was matched to the employee master are listed. A card with a missing or unmatched ID, a shift that cannot be read, or a date or site that disagrees with the log book is not in this table; look for it in Manpower Data Review.
- A repeated record or a possible repeated scan/card is counted once. The extra copy is listed in Manpower Data Review.

6. Download, print and search

- Tables on this page have a **Generate** button: **Download as PDF**, **Download as Excel** or **Smart Print**. The file contains the whole table, not only the rows visible on screen.
- Type in **Search this report** to find a door number, driver or card inside a table.
- Press a column heading to sort by that column.
- If the page looks old after an update, press **Ctrl + F5** once.

7. Review checklist

Step	Do this
1	Set From, To and Site, and confirm them in the line under the selectors. Press "Refresh reports" if cards were saved after the "Updated" time.
2	Choose the person in Employee, or type the Employee ID in the search box, and read one row for each shift worked.
3	Compare Doors worked and Saved cards with the paper cards of that shift.
4	Where HMR performance HRS, Completed trips or Kilometres shows "—", read Remarks / review, then open the cards named in Saved cards and check the opening and closing readings.
5	Check Scheduled start (IST) and Scheduled end (IST). A blank means the Shift Master timing for that site, date and shift needs checking.
6	Open "Manpower Data Review" to see the cards that were left out of this table.

> **This manual shows how to read and verify the report.** What action to take on its findings is as instructed by management.

8. Common questions

Question	Answer
A driver used two vehicles in one shift. Why is there only one row?	One duty is one employee, site, date and shift. Both door numbers are in Doors worked, both cards are in Saved cards, and the hours, trips and kilometres of the cards are added.

Why does HMR performance HRS show “—”?	At least one card of the duty failed a check, or the cards together are more than the scheduled shift hours. The report then shows no total rather than a doubtful one. Remarks / review names the reason and Saved cards names the cards to open.
I chose one door number but the row shows other doors too. Why?	Door / equipment and Saved batch pick the duty. The complete duty is always shown, with every card of that shift.
Why are Completed trips and Kilometres “—” for an equipment operator?	Trips and kilometres are read from VLB cards only. A duty with only ELB cards shows HMR hours, and “—” in these two columns.