CALIBER MINING AND LOGISTICS LIMITED · PULSE-II · UTILISATION & EXCEPTIONS

Meter Reading Exceptions

Operating manual

For site in-charges, MIS staff and reviewers · Matches the system as of 9 November 2026 · The picture uses sample data, not real records

1. What this report shows

Lists saved VLB and ELB log books whose HMR or KMR readings look wrong: a reading is missing, closing is below opening, the difference is too large, or the opening does not match the previous log book of the same door. A site in-charge or MIS clerk uses it to find the log books whose meter readings should be checked against the card.


> **One row.** One row is one saved log book that has at least one meter problem. Log books with no problem are not listed.

2. Open the report and choose what to see

In the left menu open **Reports** → **Utilisation & Exceptions** → **Meter Reading Exceptions**. Then set the selectors described below.

Selector or button	What it does
From	First book date to include. It opens on the 1st of the current month (India time). Dates before 1 November 2026 are not accepted. Continuity is checked only from this date onwards.
To	Last book date to include. It cannot be earlier than From, and From to To can cover at most 366 days. If the dates are not valid the screen shows "Choose a valid date range of at most 366 days." and no report is shown. Keep in mind: Actions → Reset table also puts From back to the 1st of the current month and To back to today.
Site	Keeps only log books of that site. "All" means every site assigned to your login. Once a site is chosen, the Shift, Vehicle / equipment, Driver / operator and Work order lists show only that site's entries.
Shift	Keeps only log books saved against that shift. The continuity check then compares only log books of that shift with each other.
Vehicle / equipment	Keeps only log books of that door number.
Driver / operator	Keeps only log books of that person. The continuity check then compares only that person's log books with each other. The list holds only people found on log books or scan cards in the chosen dates.
Work order	Keeps only log books saved against that work order. The continuity check then compares only those log books with each other.

3. What is on the screen



Picture 1. The report screen: selectors, totals and the table. *Sample data.*

On the screen	What it shows
Report	Picker at the top of the screen. It lists all reports under their groups; choosing a name opens that report.
Refresh	Loads the saved records for the chosen dates again. Press it after log books have been saved or corrected. Changing Site, Shift or the other selectors does not need Refresh.
Filters:	One line showing what is selected in Site, Shift, Vehicle / equipment, Driver / operator and Work order, written as "site: …", "shift: …", "asset: …", "employee: …" and "workOrder: …". With nothing selected it reads "All sites, assets, shifts and employees". Site and Work order appear by name; Shift, Vehicle / equipment and Driver / operator appear as the system's internal number.
logbooks	Number of saved VLB and ELB log books that match the dates and selectors. All of these are checked.
assets	Number of different doors on those log books.
trips	Total trips on those log books.
report rows	Number of log books that have at least one exception. This is the number of rows in the table below.

Continuity is checked within the selected range. KMR is limited to 250 km per shift.	Notice shown above the table on this report. It states the two fixed rules of the check.

4. The columns

Column	Meaning
Date	Book date of the log book.
Site	Site saved on the log book.
Book NO	Book number of the saved log book.
Door NO	Door number of the vehicle or equipment.
Caliber ID	Employee ID of the driver or operator on the log book.
Employee	Name of the driver or operator on the log book.
Shift	Shift name saved on the log book.
Exception	The problems found on this log book, separated by ";". "Missing HMR": opening or closing HMR is not saved. "Closing HMR below opening": closing HMR is less than opening HMR. "HMR exceeds shift hours": the HMR difference is more than the shift hours on the log book. "Missing KMR": a VLB log book without opening or closing KMR. "Closing KMR below opening": closing KMR is less than opening KMR. "KMR exceeds 250 km": the KM run is more than 250. "HMR discontinuity" and "KMR discontinuity": the opening reading is not the same as the closing reading of the previous log book of the same door.

5. Keep in mind

- Continuity compares each log book with the previous log book of the same door among the log books now loaded, taken in order of date and shift start time. The first log book of a door in the chosen dates is not compared with anything earlier.
- Choosing a Shift, Driver / operator or Work order removes the log books in between, so the report may show a discontinuity that is not real. Keep these on "All" when checking continuity.
- The readings must match exactly. Any difference between the previous closing reading and this opening reading is reported, however small.
- The 250 km limit and the shift-hours limit are fixed in this report and are applied to each log book.
- A separate Meter Continuity Report is available under Reports → Trips & Productivity. It runs on the server with its own date range and tolerance.
- Only saved VLB and ELB log books of sites assigned to your login are read. LMV log books, deleted log books and dates before 1 November 2026 are not included.

6. Download, print and search

- Tables on this page have a **Generate** button: **Download as PDF**, **Download as Excel** or **Smart Print**. The file contains the whole table, not only the rows visible on screen.
- Type in **Search this report** to find a door number, driver or card inside a table.
- Press a column heading to sort by that column.

- If the page looks old after an update, press **Ctrl + F5** once.

7. Review checklist

Step	Do this
1	Set From one day before the period you want to check, so that the first shift has a previous log book to compare with.
2	Choose the Site and keep Shift, Driver / operator and Work order on "All".
3	Read the Exception column. Use Search this report to find one kind, for example "Missing".
4	For a discontinuity, open the Vehicle Logbook Register or Equipment Logbook Register for the same door and compare this log book's opening reading with the closing reading of the log book before it.
5	For "exceeds" and "below opening" rows, compare the saved readings with the Trip Card or Job Card.
6	After corrections are saved, press Refresh and confirm that the row is gone.

> **This manual shows how to read and verify the report.** What action to take on its findings is as instructed by management.

8. Common questions

Question	Answer
The readings on this log book are correct. Why does it show a discontinuity?	Its opening reading is not equal to the closing reading of the previous log book of the same door. The previous log book may be wrong, or a log book in between may be missing or left out by a selector.
Why is the first log book of a door never shown with a discontinuity?	Continuity is checked only within the chosen dates, so the first log book has nothing before it to compare with.
A door is not in the list. Is something missing?	No. Only log books with at least one exception are listed.
Can the 250 km limit be changed on the screen?	No. It is fixed in the report.