CALIBER MINING AND LOGISTICS LIMITED · PULSE-II · TRIPS & PRODUCTIVITY

Loading Equipment-wise Report

Operating manual

For site in-charges, MIS staff and reviewers · Matches the system as of 9 November 2026 · The picture uses sample data, not real records

1. What this report shows

Shows how many trips each loading equipment loaded, and how many different vehicles it loaded, at each site in the chosen dates. The figures come from the trip rows of Vehicle Log Books.


> **One row.** One row is one loading equipment at one site. The trips of every Vehicle Log Book trip row that names this equipment are added up in it.

2. Open the report and choose what to see

In the left menu open **Reports** → **Trips & Productivity** → **Loading Equipment-wise Report**. Then set the selectors described below.

Selector or button	What it does
From / To	First and last date to include, by the Book Date of the log book. From starts on the 1st of the current month and To on today's date. Dates before 01-11-2026 cannot be chosen, From must not be after To, and the range can be at most 366 days. If the dates are not valid, the screen shows "Choose a valid date range of at most 366 days." and no data is loaded. Changing a date loads the data again.
Site	Keeps only the log books of one site. "All" keeps every site your login can see. Once a site is chosen, the Shift, Vehicle / equipment, Driver / operator and Work order lists show only that site's entries.
Shift	Keeps only the log books of the chosen shift. Every shift in the list belongs to one site, so shifts of the same name at two sites appear as separate entries. Choose Site first, then Shift.
Vehicle / equipment	Keeps only the log books of the chosen vehicle. It does not choose the loading equipment; use Loading equipment for that.
Driver / operator	Keeps only the log books saved in the name of the chosen person. The list has only the people found on the log books and scan cards of the chosen dates.
Work order	Keeps only the log books saved against the chosen work order. The list has only the work orders found on the log books and scan cards of the chosen dates.
Loading equipment	Keeps only the trip rows loaded by the chosen loading equipment. It changes the table and the "report rows" count only; the logbooks, assets and trips counts above the table do not change.

3. What is on the screen



Picture 1. The report screen: selectors, totals and the table. *Sample data.*

On the screen	What it shows
Report	Drop-down at the top with every report, listed under its group. Choosing a name opens that report.
Saved operational records	Line under the report name. It repeats the From and To dates in use.
Refresh	Loads the saved log books again for the same dates. Press it when log books were saved or corrected after the report was opened. While data is loading the button cannot be pressed and "Loading complete report data…" is shown.
Filters:	One line listing the selectors that are set. With none set it reads "All sites, assets, shifts and employees". The line uses short names: site, shift, asset (Vehicle / equipment), employee (Driver / operator), workOrder and loading. For shift, asset and employee it shows the record number of the choice, not its name.
logbooks	Number of saved log books, VLB and ELB together, that match the dates and filters.
assets	Number of different vehicles and equipment on those log books.
trips	Total trips on those log books.
report rows	Number of rows in the table below.

No matching records or exceptions found.	Shown inside the table when nothing matches the dates and filters.

4. The columns

Column	Meaning
Site	Site of the Vehicle Log Books that hold the trip rows.
Equipment	Loading equipment written in the trip rows, for example TPC901.
Trips	Total trips loaded by this equipment: the counted trips of all its trip rows, added up.
Vehicles	Number of different vehicles that have a trip row with this equipment.

5. Keep in mind

- The report is built from the trip rows of Vehicle Log Books, not from the loading equipment's own Equipment Log Book. An equipment appears only if a vehicle trip row names it.
- An equipment named in log books of two sites gets one row for each site.
- Trip rows saved without a loading equipment name are added up in a row whose Equipment is blank.
- A trip is counted on the log book that has its loading time. A trip row with only an unloading time (a load taken over from the previous driver) is not counted again.
- The counts "logbooks", "assets" and "trips" above the table take all matching log books, VLB and ELB together. They do not change with Loading equipment.
- A Vehicle Log Book that was not entered adds nothing here, so the Trips of its loading equipment come out lower.

6. Download, print and search

- Tables on this page have a **Generate** button: **Download as PDF**, **Download as Excel** or **Smart Print**. The file contains the whole table, not only the rows visible on screen.
- Type in **Search this report** to find a door number, driver or card inside a table.
- Press a column heading to sort by that column.
- If the page looks old after an update, press **Ctrl + F5** once.

7. Review checklist

Step	Do this
1	Set From and To to the period and choose Site.
2	Check that every loading equipment that worked has a row, and that no row has a blank Equipment.
3	Compare the Trips of each equipment with the site's own loading count for the period.
4	With Loading equipment at All, check that the Trips column adds up to the "trips" count above the table.
5	For a doubtful equipment, open Trip Timing & Gap Report and choose it in Loading equipment there to see each trip row.

> **This manual shows how to read and verify the report.** What action to take on its findings is as instructed by management.

8. Common questions

Question	Answer
Why is an equipment missing from the table?	No Vehicle Log Book trip row of the chosen dates names it. Its own Equipment Log Book does not add it here.
Why does the same equipment have two rows?	It is named in Vehicle Log Books of two sites. Each site gets its own row.
Does Vehicle / equipment choose the loading equipment?	No. It chooses the vehicle of the log book. Use Loading equipment to choose the loader.