

Chp 30: Inductance - (I)

Goals for Chapter 30

- To learn how current in one coil can induce an emf in another unconnected coil
- To relate the induced emf to the rate of change of the current
- To calculate the energy in a magnetic field
- To analyze circuits containing resistors and inductors
- To describe electrical oscillations in circuits and why the oscillations decay

Introduction




- How does a coil induce a current in a neighboring coil.
- A sensor triggers the traffic light to change when a car arrives at an intersection. How does it do this?
- Why does a coil of metal behave very differently from a straight wire of the same metal?
- We'll learn how circuits can be coupled without being connected together.



Introduction




- How does a coil induce a current in a neighboring coil.
- A sensor triggers the traffic light to change when a car arrives at an intersection. How does it do this?
- Why does a coil of metal behave very differently from a straight wire of the same metal?
- We'll learn how circuits can be coupled without being connected together.



A changing current in a coil induces an emf in an adjacent coil.
The coupling between the coils is described by their *mutual inductance*.
A changing current in a coil also induces an emf in that same coil.
Such a coil is called an *inductor*, and the relationship of current to emf is described by the *inductance* (also called *self-inductance*) of the coil.

Mutual inductance: If the current in coil 1 is changing, the changing flux through coil 2 induces an emf in coil 2.




Mutual inductance

If the current in coil 1 changes, the flux through coil 2 changes as well

→according to Faraday's law, this induces an emf in coil 2.

$$\mathcal{E}_2 = -N_2 \frac{d\Phi_{B2}}{dt}$$

Mutual inductance: If the current in coil 1 is changing, the changing flux through coil 2 induces an emf in coil 2.



Mutual inductance


If the current in coil 1 changes, the flux through coil 2 changes as well

→ according to Faraday's law, this induces an emf in coil 2.

$$\mathcal{E}_2 = -N_2 \frac{d\Phi_{B2}}{dt}$$

the magnetic flux through *each turn* of coil 2, caused by the current i_1 in coil 1, as Φ_{B2}

Mutual inductance: If the current in coil 1 is changing, the changing flux through coil 2 induces an emf in coil 2.



Mutual inductance

If the current in coil 1 changes, the flux through coil 2 changes as well


→ according to Faraday's law, this induces an emf in coil 2.

$$\mathcal{E}_2 = -N_2 \frac{d\Phi_{B2}}{dt}$$

the magnetic flux through *each turn* of coil 2, caused by the current i_1 in coil 1, as Φ_{B2}

$$\rightarrow \Phi_{B2} = (\text{constant}) \times (i_1)$$

Mutual inductance: If the current in coil 1 is changing, the changing flux through coil 2 induces an emf in coil 2.



Mutual inductance

If the current in coil 1 changes, the flux through coil 2 changes as well

→ according to Faraday's law, this induces an emf in coil 2.

$$\mathcal{E}_2 = -N_2 \frac{d\Phi_{B2}}{dt}$$


the magnetic flux through each turn of coil 2, caused by the current i_1 in coil 1, as Φ_{B2}

$$\rightarrow \Phi_{B2} = (\text{constant}) \times (i_1)$$

$$\rightarrow N_2 \Phi_{B2} = M_{21} i_1$$

↑
mutual inductance

Mutual inductance: If the current in coil 1 is changing, the changing flux through coil 2 induces an emf in coil 2.



Mutual inductance

If the current in coil 1 changes, the flux through coil 2 changes as well

→ according to Faraday's law, this induces an emf in coil 2.

$$\mathcal{E}_2 = -N_2 \frac{d\Phi_{B2}}{dt}$$

the magnetic flux through *each turn* of coil 2, caused by the current i_1 in coil 1, as Φ_{B2}


$$\rightarrow \Phi_{B2} = (\text{constant}) \times (i_1)$$

$$\rightarrow N_2 \Phi_{B2} = M_{21} i_1$$

\uparrow
mutual inductance

$$\rightarrow N_2 \frac{d\Phi_{B2}}{dt} = M_{21} \frac{di_1}{dt}$$

Mutual inductance: If the current in coil 1 is changing, the changing flux through coil 2 induces an emf in coil 2.



Mutual inductance

If the current in coil 1 changes, the flux through coil 2 changes as well

→ according to Faraday's law, this induces an emf in coil 2.

$$\mathcal{E}_2 = -N_2 \frac{d\Phi_{B2}}{dt}$$

the magnetic flux through each turn of coil 2, caused by the current i_1 in coil 1, as Φ_{B2}

$$\rightarrow \Phi_{B2} = (\text{constant}) \times (i_1)$$


$$\rightarrow N_2 \Phi_{B2} = M_{21} i_1$$

↑
mutual inductance

$$\rightarrow N_2 \frac{d\Phi_{B2}}{dt} = M_{21} \frac{di_1}{dt} \rightarrow \mathcal{E}_2 = -M_{21} \frac{di_1}{dt}$$

$$M_{21} = \frac{N_2 \Phi_{B2}}{i_1}$$

Mutual inductance: If the current in coil 1 is changing, the changing flux through coil 2 induces an emf in coil 2.



Mutual inductance

If the current in coil 1 changes, the flux through coil 2 changes as well

→ according to Faraday's law, this induces an emf in coil 2.

$$\mathcal{E}_2 = -N_2 \frac{d\Phi_{B2}}{dt}$$

the magnetic flux through *each turn* of coil 2, caused by the current i_1 in coil 1, as Φ_{B2}

$$\rightarrow \Phi_{B2} = (\text{constant}) \times (i_1)$$

$$N_2 \Phi_{B2} = M_{21} i_1$$

↑
mutual inductance

$$\rightarrow N_2 \frac{d\Phi_{B2}}{dt} = M_{21} \frac{di_1}{dt} \rightarrow \mathcal{E}_2 = -M_{21} \frac{di_1}{dt}$$


$$M_{21} = \frac{N_2 \Phi_{B2}}{i_1}$$

$$\mathcal{E}_2 = -M \frac{di_1}{dt} \quad \text{and} \quad \mathcal{E}_1 = -M \frac{di_2}{dt}$$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_1 \Phi_{B1}}{i_2} \quad (\text{mutual inductance})$$

$$1 \text{ H} = 1 \text{ Wb/A} = 1 \text{ V} \cdot \text{s/A} = 1 \text{ } \Omega \cdot \text{s} = 1 \text{ J/A}^2$$


Mutual inductance examples



$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$

the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

Mutual inductance examples




$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$

the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_2 B_1 A}{i_1}$$

Mutual inductance examples




$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$

the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_2 B_1 A}{i_1} = \frac{N_2}{i_1} \frac{\mu_0 N_1 i_1}{l} A$$

Mutual inductance examples




$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$

the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_2 B_1 A}{i_1} = \frac{N_2}{i_1} \frac{\mu_0 N_1 i_1}{l} A = \frac{\mu_0 A N_1 N_2}{l}$$

Mutual inductance examples



$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$


the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_2 B_1 A}{i_1} = \frac{N_2}{i_1} \frac{\mu_0 N_1 i_1}{l} A = \frac{\mu_0 A N_1 N_2}{l}$$

Suppose $l=0.50\text{m}$, $A=10\text{cm}^2=110^{-3}\text{ m}^2$, $N_1=1000$ turns, and $N_2 = 10$ turns.

→
$$M = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(1.0 \times 10^{-3} \text{ m}^2)(1000)(10)}{0.50 \text{ m}} = 25 \times 10^{-6} \text{ Wb/A} = 25 \times 10^{-6} \text{ H} = 25 \mu\text{H}$$

Mutual inductance examples



$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$

the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_2 B_1 A}{i_1} = \frac{N_2}{i_1} \frac{\mu_0 N_1 i_1}{l} A = \frac{\mu_0 A N_1 N_2}{l}$$

Suppose $l=0.50\text{m}$, $A=10\text{cm}^2=10^{-3}\text{ m}^2$, $N_1=1000$ turns, and $N_2 = 10$ turns.


→
$$M = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(1.0 \times 10^{-3} \text{ m}^2)(1000)(10)}{0.50 \text{ m}} = 25 \times 10^{-6} \text{ Wb/A} = 25 \times 10^{-6} \text{ H} = 25 \mu\text{H}$$

suppose the current i_2 in the outer coil is given by $i_2 = 12.0 \times 10^6 \text{ A/s} \cdot t$.

(a) At $t = 3.0 \mu\text{s}$, what is the average magnetic flux through each turn of the solenoid (coil 1) due to the current in the outer coil? (b) What is the induced emf in the solenoid?

(a)

Mutual inductance examples



$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$

the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_2 B_1 A}{i_1} = \frac{N_2}{i_1} \frac{\mu_0 N_1 i_1}{l} A = \frac{\mu_0 A N_1 N_2}{l}$$

Suppose $l=0.50\text{m}$, $A=10\text{cm}^2=10^{-3}\text{ m}^2$, $N_1=1000$ turns, and $N_2 = 10$ turns.


→
$$M = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(1.0 \times 10^{-3} \text{ m}^2)(1000)(10)}{0.50 \text{ m}} = 25 \times 10^{-6} \text{ Wb/A} = 25 \times 10^{-6} \text{ H} = 25 \mu\text{H}$$

suppose the current i_2 in the outer coil is given by $i_2 = (2.0 \times 10^6 \text{ A/s})t$.

(a) At $t = 3.0 \mu\text{s}$, what is the average magnetic flux through each turn of the solenoid (coil 1) due to the current in the outer coil? (b) What is the induced emf in the solenoid?

(a) $i_2 = (2.0 \times 10^6 \text{ A/s})(3.0 \times 10^{-6} \text{ s})$

Mutual inductance examples



$$B_1 = \mu_0 n_1 i_1 = \frac{\mu_0 N_1 i_1}{l}$$

the number of turns per unit length, which for solenoid (1) is $n_1 = N_1/L$

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_2 B_1 A}{i_1} = \frac{N_2}{i_1} \frac{\mu_0 N_1 i_1}{l} A = \frac{\mu_0 A N_1 N_2}{l}$$

Suppose $l=0.50\text{m}$, $A=10\text{cm}^2=10^{-3}\text{ m}^2$, $N_1=1000$ turns, and $N_2 = 10$ turns.

→ $M = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(1.0 \times 10^{-3} \text{ m}^2)(1000)(10)}{0.50 \text{ m}} = 25 \times 10^{-6} \text{ Wb/A} = 25 \times 10^{-6} \text{ H} = 25 \mu\text{H}$

suppose the current i_2 in the outer coil is given by $i_2 = (2.0 \times 10^6 \text{ A/s})t$.

(a) At $t = 3.0 \mu\text{s}$, what is the average magnetic flux through each turn of the solenoid (coil 1) due to the current in the outer coil? (b) What is the induced emf in the solenoid?


(a) $i_2 = (2.0 \times 10^6 \text{ A/s})(3.0 \times 10^{-6} \text{ s}) \rightarrow \Phi_{B1} = \frac{Mi_2}{N_1} = \frac{(25 \times 10^{-6} \text{ H})(6.0 \text{ A})}{1000} = 1.5 \times 10^{-7} \text{ Wb}$

(b) $di_2/dt = 2 \times 10^6 \text{ A/s}$

→ $\mathcal{E}_1 = -M \frac{di_2}{dt} = -(25 \times 10^{-6} \text{ H})(2.0 \times 10^6 \text{ A/s}) = -50 \text{ V}$

Self-inductance


Self-inductance: If the current i in the coil is changing, the changing flux through the coil induces an emf in the coil.



consider only a *single isolated circuit*.
When a current is present in a circuit, it sets up a magnetic field that causes a magnetic flux through the *same circuit*;
If the current changes → this flux changes
→ Thus any circuit that carries a varying current has an emf induced in it by the variation in *its own* magnetic field.

Self-inductance

Self-inductance: If the current i in the coil is changing, the changing flux through the coil induces an emf in the coil.




consider only a *single* isolated circuit.
When a current is present in a circuit, it sets up a magnetic field that causes a magnetic flux through the *same* circuit;
If the current changes → this flux changes
→ Thus any circuit that carries a varying current has an emf induced in it by the variation in *its own* magnetic field.

Define self inductance
(or simply inductance) as:

$$L = \frac{N\Phi_B}{i}$$

Self-inductance

Self-inductance: If the current i in the coil is changing, the changing flux through the coil induces an emf in the coil.



consider only a *single* isolated circuit.
When a current is present in a circuit, it sets up a magnetic field that causes a magnetic flux through the *same* circuit;
If the current changes → this flux changes
→ Thus any circuit that carries a varying current has an emf induced in it by the variation in *its own* magnetic field.


Define self inductance
(or simply inductance) as:

$$L = \frac{N\Phi_B}{i}$$

$$\rightarrow N \frac{d\Phi_B}{dt} = L \frac{di}{dt}$$

Self-inductance

Self-inductance: If the current i in the coil is changing, the changing flux through the coil induces an emf in the coil.



consider only a *single* isolated circuit.
When a current is present in a circuit, it sets up a magnetic field that causes a magnetic flux through the *same* circuit;
If the current changes → this flux changes
→ Thus any circuit that carries a varying current has an emf induced in it by the variation in *its own* magnetic field.

Define self inductance
(or simply **inductance**) as:

$$L = \frac{N\Phi_B}{i}$$


$$\rightarrow N \frac{d\Phi_B}{dt} = L \frac{di}{dt}$$



$$\mathcal{E} = -L \frac{di}{dt} \quad (\text{self-induced emf})$$

Self-inductance

Self-inductance: If the current i in the coil is changing, the changing flux through the coil induces an emf in the coil.



consider only a *single* isolated circuit.
When a current is present in a circuit, it sets up a magnetic field that causes a magnetic flux through the *same* circuit;
If the current changes → this flux changes
→ Thus any circuit that carries a varying current has an emf induced in it by the variation in *its own* magnetic field.

Define self inductance
(or simply **inductance**) as:


$$L = \frac{N\Phi_B}{i}$$

$$\Rightarrow N \frac{d\Phi_B}{dt} = L \frac{di}{dt} \quad \Rightarrow \quad \mathcal{E} = -L \frac{di}{dt} \quad (\text{self-induced emf})$$

As stated in Lenz's law; the self- induced emf in a circuit opposes any change in the current in that circuit.

Self-inductance

Self-inductance: If the current i in the coil is changing, the changing flux through the coil induces an emf in the coil.



consider only a *single* isolated circuit.
When a current is present in a circuit, it sets up a magnetic field that causes a magnetic flux through the *same* circuit;
If the current changes → this flux changes
→ Thus any circuit that carries a varying current has an **emf induced in it by the variation in its own magnetic field.**


Define self inductance
(or simply **inductance**) as:

$$L = \frac{N\Phi_B}{i}$$

$$\Rightarrow N \frac{d\Phi_B}{dt} = L \frac{di}{dt} \quad \Rightarrow \quad \mathcal{E} = -L \frac{di}{dt} \quad (\text{self-induced emf})$$

As stated in Lenz's law; the self- induced emf in a circuit opposes any change in the current in that circuit.

Inductors As Circuit Elements




A circuit device that is designed to have a particular inductance is called an **inductor**, or a **choke**. The usual circuit symbol for an inductor is




Potential across an inductor


- (a) Resistor with current i flowing from a to b : potential drops from a to b .




- (b) Inductor with *constant* current i flowing from a to b : no potential difference.



- (c) Inductor with *increasing* current i flowing from a to b : potential drops from a to b .



- (d) Inductor with *decreasing* current i flowing from a to b : potential increases from a to b .




The potential across an inductor depends on the rate of change of the current through it.


The self-induced emf does *not* oppose current, but opposes a *change* in the current.

Potential across an inductor


- (a) Resistor with current i flowing from a to b : potential drops from a to b .




- (b) Inductor with *constant* current i flowing from a to b : no potential difference.



- (c) Inductor with *increasing* current i flowing from a to b : potential drops from a to b .



- (d) Inductor with *decreasing* current i flowing from a to b : potential increases from a to b .




The potential across an inductor depends on the rate of change of the current through it.

The self-induced emf does *not* oppose current, but opposes a *change* in the current.


going around a conducting loop, measuring potential differences across circuit elements, the algebraic sum of these differences around any closed loop must be zero because the electric field produced by charges distributed around the circuit is *conservative* $E_c = 0$

Potential across an inductor


- (a) Resistor with current i flowing from a to b : potential drops from a to b .




- (b) Inductor with *constant* current i flowing from a to b : no potential difference.



- (c) Inductor with *increasing* current i flowing from a to b : potential drops from a to b .




- (d) Inductor with *decreasing* current i flowing from a to b : potential increases from a to b .



The potential across an inductor depends on the rate of change of the current through it.

The self-induced emf does *not* oppose current, but opposes a *change* in the current.


going around a conducting loop, measuring potential differences across circuit elements, the algebraic sum of these differences around any closed loop must be zero because the electric field produced by charges distributed around the circuit is *conservative* $E_c = 0$




When an inductor is included the magnetically induced electric field within the coils of the inductor is *not* conservative $\rightarrow \vec{E}_c + \vec{E}_n = \mathbf{0}$

Potential across an inductor


- (a) Resistor with current i flowing from a to b : potential drops from a to b .




- (b) Inductor with *constant* current i flowing from a to b : no potential difference.



- (c) Inductor with *increasing* current i flowing from a to b : potential drops from a to b .




- (d) Inductor with *decreasing* current i flowing from a to b : potential increases from a to b .



The potential across an inductor depends on the rate of change of the current through it.

The self-induced emf does *not* oppose current, but opposes a *change* in the current.

going around a conducting loop, measuring potential differences across circuit elements, the algebraic sum of these differences around any closed loop must be zero because the electric field produced by charges distributed around the circuit is *conservative* $E_c = 0$




When an inductor is included the magnetically induced electric field within the coils of the inductor is *not* conservative $\rightarrow \vec{E}_c + \vec{E}_n = \mathbf{0}$

Faraday's Law: line integral of E_n = negative of the change of the rate of flux


$$\oint \vec{E}_n \cdot d\vec{l} = -L \frac{di}{dt}$$

Potential across an inductor


- (a) Resistor with current i flowing from a to b : potential drops from a to b .




- (b) Inductor with *constant* current i flowing from a to b : no potential difference.



- (c) Inductor with *increasing* current i flowing from a to b : potential drops from a to b .




- (d) Inductor with *decreasing* current i flowing from a to b : potential increases from a to b .



The potential across an inductor depends on the rate of change of the current through it.

The self-induced emf does *not* oppose current, but opposes a *change* in the current.

going around a conducting loop, measuring potential differences across circuit elements, the algebraic sum of these differences around any closed loop must be zero because the electric field produced by charges distributed around the circuit is *conservative* $E_c = 0$



When an inductor is included the magnetically induced electric field within the coils of the inductor is *not* conservative $\rightarrow \vec{E}_c + \vec{E}_n = \mathbf{0}$

Faraday's Law: line integral of \vec{E}_n = negative of the change of the rate of flux


$$\oint \vec{E}_n \cdot d\vec{l} = -L \frac{di}{dt}$$

$$\int_a^b \vec{E}_n \cdot d\vec{l} = -L \frac{di}{dt}$$


$$\int_a^b \vec{E}_c \cdot d\vec{l} = L \frac{di}{dt}$$

Potential across an inductor


- (a) Resistor with current i flowing from a to b : potential drops from a to b .




- (b) Inductor with *constant* current i flowing from a to b : no potential difference.



- (c) Inductor with *increasing* current i flowing from a to b : potential drops from a to b .




- (d) Inductor with *decreasing* current i flowing from a to b : potential increases from a to b .



The potential across an inductor depends on the rate of change of the current through it.

The self-induced emf does *not* oppose current, but opposes a *change* in the current.

going around a conducting loop, measuring potential differences across circuit elements, the algebraic sum of these differences around any closed loop must be zero because the electric field produced by charges distributed around the circuit is *conservative* $E_c = 0$



When an inductor is included the magnetically induced electric field within the coils of the inductor is *not* conservative $\rightarrow \vec{E}_c + \vec{E}_n = \mathbf{0}$

Faraday's Law: line integral of \vec{E}_n = negative of the change of the rate of flux


$$\oint \vec{E}_n \cdot d\vec{l} = -L \frac{di}{dt}$$

$$\int_a^b \vec{E}_n \cdot d\vec{l} = -L \frac{di}{dt}$$

$$\int_a^b \vec{E}_c \cdot d\vec{l} = L \frac{di}{dt}$$


$$V_{ab} = V_a - V_b = L \frac{di}{dt}$$

Applications of Inductors



$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$


Applications of Inductors



$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$

$$\Phi_B = BA = \frac{\mu_0 NiA}{2\pi r} \quad \rightarrow \quad L = \frac{N\Phi_B}{i} = \frac{\mu_0 N^2 A}{2\pi r}$$

Applications of Inductors




$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$

$$\Phi_B = BA = \frac{\mu_0 NiA}{2\pi r} \quad \rightarrow \quad L = \frac{N\Phi_B}{i} = \frac{\mu_0 N^2 A}{2\pi r}$$

Suppose $N = 200$ turns, $A = 5.0 \text{ cm}^2 = 5.0 \times 10^{-4} \text{ m}^2$, and $r = 0.10 \text{ m}$

$$\rightarrow L = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(200)^2(5.0 \times 10^{-4} \text{ m}^2)}{2\pi(0.10 \text{ m})} = 40 \times 10^{-6} \text{ H} = 40 \mu\text{H}$$

Applications of Inductors



$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$


$$\Phi_B = BA = \frac{\mu_0 NiA}{2\pi r} \quad \rightarrow \quad L = \frac{N\Phi_B}{i} = \frac{\mu_0 N^2 A}{2\pi r}$$

Suppose $N = 200$ turns, $A = 5.0 \text{ cm}^2 = 5.0 \times 10^{-4} \text{ m}^2$, and $r = 0.10 \text{ m}$

$$\rightarrow L = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(200)^2(5.0 \times 10^{-4} \text{ m}^2)}{2\pi(0.10 \text{ m})} = 40 \times 10^{-6} \text{ H} = 40 \mu\text{H}$$

If the current in the toroidal solenoid in the example increases uniformly from 0 to 6.0 A in 3.0 μs , find the magnitude and direction of the self-induced emf.

Applications of Inductors



$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$

$$\Phi_B = BA = \frac{\mu_0 NiA}{2\pi r} \quad \rightarrow \quad L = \frac{N\Phi_B}{i} = \frac{\mu_0 N^2 A}{2\pi r}$$


Suppose $N = 200$ turns, $A = 5.0 \text{ cm}^2 = 5.0 \times 10^{-4} \text{ m}^2$, and $r = 0.10 \text{ m}$

$$\rightarrow L = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(200)^2(5.0 \times 10^{-4} \text{ m}^2)}{2\pi(0.10 \text{ m})} = 40 \times 10^{-6} \text{ H} = 40 \mu\text{H}$$

If the current in the toroidal solenoid in the example increases uniformly from 0 to 6.0 A in 3.0 μs , find the magnitude and direction of the self-induced emf.

$$|\mathcal{E}| = L \left| \frac{di}{dt} \right| \quad di/dt = ?$$

Applications of Inductors



$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$

$$\Phi_B = BA = \frac{\mu_0 NiA}{2\pi r} \quad \rightarrow \quad L = \frac{N\Phi_B}{i} = \frac{\mu_0 N^2 A}{2\pi r}$$

Suppose $N = 200$ turns, $A = 5.0 \text{ cm}^2 = 5.0 \times 10^{-4} \text{ m}^2$, and $r = 0.10 \text{ m}$


$$\rightarrow L = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(200)^2(5.0 \times 10^{-4} \text{ m}^2)}{2\pi(0.10 \text{ m})} = 40 \times 10^{-6} \text{ H} = 40 \mu\text{H}$$

If the current in the toroidal solenoid in the example increases uniformly from 0 to 6.0 A in 3.0 μs , find the magnitude and direction of the self-induced emf.

$$|\mathcal{E}| = L \left| \frac{di}{dt} \right| \quad di/dt = ?$$

$$\rightarrow di/dt = \Delta i/\Delta t = (6.0 - 0.0) \text{ A} / 3.0 \times 10^{-6} \text{ s} = 2 \times 10^6 \text{ A/s}$$

Applications of Inductors



$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$

$$\Phi_B = BA = \frac{\mu_0 NiA}{2\pi r} \quad \rightarrow \quad L = \frac{N\Phi_B}{i} = \frac{\mu_0 N^2 A}{2\pi r}$$

Suppose $N = 200$ turns, $A = 5.0 \text{ cm}^2 = 5.0 \times 10^{-4} \text{ m}^2$, and $r = 0.10 \text{ m}$

$$\rightarrow L = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(200)^2(5.0 \times 10^{-4} \text{ m}^2)}{2\pi(0.10 \text{ m})} = 40 \times 10^{-6} \text{ H} = 40 \mu\text{H}$$


If the current in the toroidal solenoid in the example increases uniformly from 0 to 6.0 A in 3.0 μs , find the magnitude and direction of the self-induced emf.

$$|\mathcal{E}| = L \left| \frac{di}{dt} \right| \quad di/dt = ?$$

$$\rightarrow di/dt = \Delta i/\Delta t = (6.0 - 0.0) \text{ A} / 3.0 \times 10^{-6} \text{ s} = 2 \times 10^6 \text{ A/s}$$

$$|\mathcal{E}| = L \left| \frac{di}{dt} \right| = (40 \times 10^{-6} \text{ H})(2.0 \times 10^6 \text{ A/s}) = 80 \text{ V}$$

Applications of Inductors



$$L = N\Phi_B/i \quad B = \mu_0 Ni/2\pi r$$

$$\Phi_B = BA = \frac{\mu_0 NiA}{2\pi r} \quad \rightarrow \quad L = \frac{N\Phi_B}{i} = \frac{\mu_0 N^2 A}{2\pi r}$$

Suppose $N = 200$ turns, $A = 5.0 \text{ cm}^2 = 5.0 \times 10^{-4} \text{ m}^2$, and $r = 0.10 \text{ m}$

$$\rightarrow L = \frac{(4\pi \times 10^{-7} \text{ Wb/A} \cdot \text{m})(200)^2(5.0 \times 10^{-4} \text{ m}^2)}{2\pi(0.10 \text{ m})} = 40 \times 10^{-6} \text{ H} = 40 \mu\text{H}$$

If the current in the toroidal solenoid in the example increases uniformly from 0 to 6.0 A in $3.0 \mu\text{s}$, find the magnitude and direction of the self-induced emf.

$$|\mathcal{E}| = L \left| \frac{di}{dt} \right| \quad di/dt = ?$$

$$\rightarrow di/dt = \Delta i / \Delta t = (6.0 - 0.0) \text{ A} / 3.0 \times 10^{-6} \text{ s} = 2 \times 10^6 \text{ A/s}$$

$$|\mathcal{E}| = L \left| \frac{di}{dt} \right| = (40 \times 10^{-6} \text{ H})(2.0 \times 10^6 \text{ A/s}) = 80 \text{ V}$$

The current is increasing, so according to Lenz's law the direction of the emf is opposite to that of the current.

This corresponds to the situation in fig. the emf is in the direction from b to a , like a battery with a as the + terminal and b the - terminal, tending to oppose the current increase from the external circuit.

(c) Inductor with increasing current i flowing from a to b : potential drops from a to b .

