



Day by day — HST 0 to 41

Netted Kirin melon · matches the SOP book and the four pre-weighed bag sets

GROW

FLOWER

SIZING

RIPEN

HST	BAG SET	EC MS	TDS PPM	SOP /1000 L	WATER PER POLYBAG ML	PULSES	WATERING TIMES	JOB FOR THE DAY
0	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	TRANSPLANT + Trichoderma cup drench
1	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	
2	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	
3	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	
4	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	
5	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	
6	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	
7	GROW	2100	1050	—	500	3 × 5m	8am · 12pm · 4pm	Start removing side shoots, every 2–3 days
8	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	Silicon drench — 2 pulses only today · TIMER CHANGE — 4 pulses from tomorrow
9	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
10	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
11	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
12	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
13	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
14	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	Trichoderma cup drench
15	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	Silicon drench — 2 pulses only today
16	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
17	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
18	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
19	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
20	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	Node 8 reached — stop removing shoots
21	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
22	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	Silicon drench — 2 pulses only today
23	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	
24	GROW	2100	1050	—	800	4 × 6m	8 · 11am · 2 · 5pm	Mix the new FLOWER stock TONIGHT
25	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	CHANGE TO FLOWER MIX · start SOP · hand-pollinate 8–10 am
26	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
27	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
28	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
29	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	Silicon drench — 2 pulses only today
30	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
31	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
32	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
33	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
34	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
35	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	Trichoderma cup drench
36	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	Silicon drench — 2 pulses only today
37	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
38	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	Select ONE fruit per plant, remove the rest
39	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
40	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	
41	FLOWER	2400	1200	310 g	1167	5 × 7m	8 · 10 · 12 · 2 · 4	Mix the new SIZING stock TONIGHT

pH 5.8 – 6.3 every single day, every stage. · Dripper 2 L/hr, one per polybag, two plants share it — every water figure here is **per polybag**, not per plant. · On a silicon day run only the two afternoon pulses; the three silicon runs already water the bags. · SOP goes straight into the 1000 L tank, never into a bag. · Check run-off 15–20%, two or three times a week, never on a silicon day.



Day by day — HST 42 to 75

Netted Kirin melon · matches the SOP book and the four pre-weighed bag sets

GROW

FLOWER

SIZING

RIPEN

HST	BAG SET	EC MS	TDS PPM	SOP /1000 L	WATER PER POLYBAG ML	PULSES	WATERING TIMES	JOB FOR THE DAY
42	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
43	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	Silicon drench — 2 pulses only today
44	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
45	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	Netting starts — no leaf spray from here
46	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
47	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
48	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
49	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
50	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	Silicon drench — 2 pulses only today
51	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
52	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
53	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
54	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
55	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
56	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	Trichoderma cup drench
57	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	Silicon drench — 2 pulses only today
58	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	
59	SIZING	2550	1275	535 g	1600	6 × 8m	7 · 9 · 11 · 1 · 3 · 5	Mix the new RIPEN stock TONIGHT
60	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	CHANGE TO RIPEN MIX · STOP silicon
61	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
62	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
63	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
64	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
65	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
66	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
67	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
68	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
69	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
70	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
71	RIPEN	2700	1350	645 g	800	4 × 6m	8 · 11am · 2 · 5pm	
72	WATER ONLY	—	plain water	—	600	3 × 6m	8am · 12pm · 4pm	Plain water only to finish · harvest window
73	WATER ONLY	—	plain water	—	600	3 × 6m	8am · 12pm · 4pm	
74	WATER ONLY	—	plain water	—	600	3 × 6m	8am · 12pm · 4pm	
75	WATER ONLY	—	plain water	—	600	3 × 6m	8am · 12pm · 4pm	

pH 5.8 – 6.3 every single day, every stage. · Dripper 2 L/hr, one per polybag, two plants share it — every water figure here is **per polybag**, not per plant. · On a silicon day run only the two afternoon pulses; the three silicon runs already water the bags. · SOP goes straight into the 1000 L tank, never into a bag. · Check run-off 15–20%, two or three times a week, never on a silicon day.